Application ::RouteOutput () Step in packet sending process Socket::Send (), 1. The Application has previously created a socket (here, a UDPSocket) [pv4RoutingProtocol UdpSocketImpI It calls Socket::Send(). Either real data or dummy data is passed at the API. 2. Socket::Send forwards to UdpSocketImpI::DoSend() and later to ::Send () UdpSocketImpl::DoSendTo(). These functions set the proper source and destination addresses, handle socket calls. such as bind() and connect() and then the UdpL4Protocol::Send() function is called. As in a UdpL4Protocol) real implementation, the socket must guery the lpv4 routing system to find the right source address to match the destination address (m downTarget() callback) 3. UdpL4Protocol is where the socket-independent protocol logic for UDP is implemented. The Send() method adds the UDP header, initializes the checksum, and sends the packet to the lov4 laver. Ipv4L3Protocol The packet is not sent directly to the lpv4 layer but via a callback called m downTarget. In this example, the downtarget is [pv4L3Protocol, but it could be some other shim layer in general, ::Send () 4. [pv4L3Protoco] adds the IP header and sends the packet to an ::Lookup() appropriate Ipv4Interface instance, based on the route that was passed Arpipv4Interface ArpL3Protocol down from the UDP layer. In this example, the device is one that supports Arp. ..Send () Ipv4Interface looks up the MAC address if Arp is supported on this NetDevice technology, and if there is a cache hit, it sends the packet to the NetDevice, or else it first initiates an Arp request and waits for a reply. NetDevice