2.2. Electric flux & electric potential



This chapter starts with Gauss's law, a more general form of Coulomb's law, and the introduction of electric flux. Subsequently, we will discuss electric potential, i.e. dealing with energy in the context of electricity.

2.2.1. Electric flux

For a uniform electric field, the electric flux Φ_E of the field $\vec{\mathbf{E}}$ through an area A is given by:

$$\Phi_E = \vec{\mathbf{E}} \vec{\mathbf{A}}$$

with $ec{\mathbf{A}}$ as the vector perpendicular to the surface of A and a magnitude of A

Using $\cos\theta$ as the angle between $\vec{\bf E}$ & $\vec{\bf A}$, the equation can be rewritten as:

$$\Phi_E = EA\cos heta = E_\perp A = EA_\perp$$

Depending on the interpretation, either the field component perpendicular to the area, or the projection of A perpendicular to E is considered.

Most importantly, the electric flux relates to the field lines, i.e. the strength of the electric field being represented by the density of field lines. Or framed differently, the number of field lines N passing through an area perpendicular to the field is proportional to the electric flux:

$$N \propto E A_{\perp} = \Phi_E$$

interactive(children=(FloatSlider(value=1.0, description='Size', max=2.0, min=0.5), FloatSlid
er(value=0.0, des...

Integral form of electric flux over a closed surface

For an arbitrary surface \vec{A} , we can decompose the surface into into infinitesimal small areas $d\vec{A}$. For each $d\vec{A}$, the electric field within the area element is considered uniform and the area itself can be considered flat. This yields:

$$\Phi_E = \int ec{f E} dec{f A}$$

For Gauss's law, we need to consider the *total flux through a closed surface*. Hence, we use the integral of a closed surface \oint and get:

$$\Phi_E = \oint ec{f E} dec{f A}$$

Conventions for the electric flux over a closed surface

By convention the following is defined:

- $d\vec{\mathbf{A}}$ points outwards from the surface of enclosed volume
- flux leaving the surface is positive
- flux entering the surface is negative

Therefore:

- if Φ_E is positive, there is a net flux is out of the volume
- if Φ_E is negative, there is a net flux is into the volume
- if $\Phi_E=0$, there is no net flux

interactive(children=(FloatSlider(value=1.0, description='q_mag', max=1.0, min=-1.0), FloatSl
ider(value=0.0, d...

<function __main__.plot_e_field(q_mag, q_x, q_y, surface_size)>

2.2.2. Gauss's law

Named after Karl Friedrich Gauss (1777-1855), the law states that the electric flux through a closed surface is equal to the net charge enclosed in the surface Q_{enc} divided by the permittivity of free space ϵ_0 :

$$\oint ec{\mathbf{E}} dec{\mathbf{A}} = rac{Q_{enc}}{\epsilon_0}$$

Note that the flux through the surface is independent of:

- the distribution of the enclosed charged within the surface/volume
- charges outside the surface which might affect the position of the electric field lines through the surface, but not the number of field lines

Relation to Coulomb's law (thought experiment)

- imaging a spherical surface with a single enclosed charge Q_{enc} in the center of the sphere (radius r)
- ullet the f E field will oriented radially w.r.t. enclosed charge
- the field line will penetrate the spherical surface perpendicular and, therefore, will be parallel to the vector $d\vec{\mathbf{A}}$
- the field will have the same magnitude throughout the surface, since the charge is centered inside
 the sphere and, therefore, the surface having the distance r to the charge everywhere
- the area of the spherical surface is $\oint dA = 4\pi r^2$

$$rac{Q_{enc}}{\epsilon_0} = \oint ec{f E} dec{f A} = \oint E dA = E \oint dA = 4\pi r^2 E$$

With, $Q_{enc}=Q$, we obtain Coulomb's law in the electric field form:

$$E=rac{1}{4\pi\epsilon_0}rac{Q}{r^2}$$

While a spherical surface was convenient in the above thought experiment, any surface could have been used, providing the identical solution. As long as the same charge distribution is enclosed, the choice of surface will not affect the number of field lines passing through the surface. Hence, the electric flux will be the same regardless if a spherical surface A_1 or an arbitrarily shaped surface A_2 is considered:

$$\oint_{A1} ec{\mathbf{E}} dec{\mathbf{A}} = \oint_{A2} ec{\mathbf{E}} dec{\mathbf{A}} = rac{Q_{enc}}{\epsilon_0}$$

Coulomb's law and Gauss's law can be applied to electrics fields produced by static electric charges. Beyond that, i.e. studying electric field due to changing magnetic fields, only Gauss's law is applicable, hence, Gauss's law is considered to be more general description of electric fields.

Superposition & Gauss's law

Confirmed by experiments, the principle of superposition is applicable to the Gauss's law. Therefore, the enclosed charges and their net electric flux can be determined by considering portions of the enclosed charges individually and integrating over the sum of their respective fluxes:

$$\oint \vec{\mathbf{E}} d\vec{\mathbf{A}} = \oint (\sum_i \vec{\mathbf{E}}_i) d\vec{\mathbf{A}} = rac{\sum_i Q_i}{\epsilon_0} = rac{Q_{enc}}{\epsilon_0}$$

Applications of Gauss's law

- point charge: $E=rac{1}{4\pi\epsilon_0}rac{Q}{r^2}$
- charged spherical conducting shell:
 - outside: $E=rac{1}{4\pi\epsilon_0}rac{Q}{r^2}$
 - lacksquare inside: E=0
- solid charged non-conducting sphere:
 - lacksquare outside: $E=rac{1}{4\pi\epsilon_0}rac{Q}{r^2}$
 - \blacksquare inside: $E=rac{1}{4\pi\epsilon_0}rac{Q}{r_0^3}r$
- long uniform line of charge: $E=rac{1}{2\pi\epsilon_0}rac{\lambda}{R}$ with λ as the charge per unit length
- infinite plane of charge: $E=rac{\sigma}{2\epsilon_0}$ with σ as the charge per unit area
- near any conducting surface (can be imagined as side of a plane, thus field appears only on one side): $E=rac{\sigma}{\epsilon_0}$
- ullet between two closely spaced oppositely charged, parallel plates: $E=rac{\sigma}{\epsilon_0}$

Reminder: There cannot be any net charge within the conductor, only on its surface. Otherwise forces within the conductor would act on the electrons.

2.2.2. Electric potential

In line with for example mechanics, the concept of conservation of energy applied to electricity. So when in doubt about the ramifications of energy in electricity, try to think about a similar problem in mechanics, i.e. think about gravitation, but keep in mind that gravitation only causes attraction, while in electricity attraction and repulsion occur.

We start by introducing some general terms and concept before piecing it all together.

Electric potential energy

Similar to other types of potential energy, there is *electric potential energy* and it is defined (like all potential energies) for a conservative force, i.e. the electrostatic force ($F=k\frac{Q_1Q_2}{r^2}$). Note the similarity to potential energy due to gravitation, e.g. the $1/r^2$ dependency. Further, the change in energy is independent of the path taken.

In a homogeneous electric field, the work W required to move a test charge q from point A to point B depends on the distance d between $A \otimes B$ and the required force F. Since the electric field E is defined as the force per unit charge $E = \frac{F}{q}$, we obtain:

$$W = Fd = qEd$$

Because the change in potential energy ΔU is equal in magnitude but opposite in sign to the work, we get:

$$\Delta U = U_B - U_A = -W \quad ext{in [J]}$$

In line with mechanics, potential energy is transformed into kinetic energy K while the total amount of energy is conserved. However, there is a conceptional difference to gravitation which we need to consider: While mass is positive, charge can be negative and positive. This has consequences for where the electric potential energy is minimal. Imagine oppositely charged plates generating a uniform electric field:

- for a positive charge, the highest electric potential energy is at positive plate
- for a negative charge, the highest electric potential energy is at negative plate The closer a particle is to the plate of the same polarity, the higher the electrostatic force.

When the electric force does positive work on a charge, i.e. it moves the charge towards the oppositely charged plate, the kinetic energy increases while the potential energy decreases (total energy is conserved).

Voltage: The difference in electric potential

The electric potential V is defined as electric potential energy per unit charge. Note how electric potential is formulated analogously to the electric field (force per unit charge). The potential at point A depends on the electric potential energy at that point divided by the charge:

$$V_A=rac{U_A}{q}$$

Like in mechanics, the potential energy at a point in space alone is not very informative, only differences in potential energy can be measured. Following the analogy with mechanics, we can chose the point of zero electrical potential energy arbitrarily. Commonly the Earth, i.e. ground, or a distance at infinity, i.e. $V_x=0$ at $r_x=\infty$, are used.

In general, the potential difference between point A and B is :

$$V_{BA} = V_B - V_A$$
 in $[J/C] = [V]$

Acknowledging Alessandro Volta's (1745-1827, inventor of the electric battery) contribution to the field, we refer to Joules per Coulomb J/C as volt~V and, consequently, the potential difference as voltage.

To summarize:

- electric potential is defined for a single point in space, i.e. V_A .
- we can only measure potential difference, i.e. voltage,
- we can define arbitrarily a reference point with zero electric potential, typically using ground
- the voltage V_{BA} between A and B is the potential difference $V_{BA} = V_B V_A$.

Putting it all together

We can combine the following into one equation:

- voltage is the difference in electric potential
- electric potential is electric potential energy over unit charge
- changes in electric potential energy are equal in magnitude but opposite in sign to the performed work

$$V_{BA}=V_B-V_A=rac{U_B-U_A}{a}=rac{\Delta U_{BA}}{a}=-rac{W_{BA}}{a}$$

This gives us the following insides:

- the electric potential difference, i.e. voltage, causes a charge to move from A to B which causes a difference in potential energy of the charge equal to: $\Delta U_{BA} = qV_{BA}$
- as acquired energy directly relates to work, voltage is a measure of how much work a charge "can do"

Therefore, the work as well as electric potential energy will depend on the charge and voltage $W_{BA}=-qV_{BA}$. This is similar to gravitation. Instead of a height h, we have a difference in electric

potential V_{BA} , and instead of a mass m, we have a charge q (q can be positive or negative, but m only be positive)

As electric sources, such as batteries and generators, are designed to maintain a potential difference, the work they can perform will scale with the charge. As the amount of charge flowing through e.g. a wire depends on the time interval, the work generated scales with time itself. More on that topic in a later chapter.

2.2.3. Relating electric potential & electric field

The electric potential of a charge configuration is directly related to the associated electric field. While the field is a vector, the potential is a scalar. Therefore, it can be handy to work with the potential if possible. Let's investigate the relation between electric potential and electric field by first revisiting mechanics and subsequently apply our knowledge about electrics. We will see that we can express the relation by integration or by derivatives, two complementary views of the same underlying dependency.

Relation via integration

From mechanics, we know that the change in potential energy from point A to B is related to the force and the path $\vec{\bf l}$ between the points by:

$$\Delta U_{BA} = -\int_A^B ec{\mathbf{F}} dec{\mathbf{I}}$$

The difference in electric potential, i.e. the voltage V_{BA} , is related to the electric potential energy by $V_{BA}=rac{\Delta U_{BA}}{q}$. Further, the electric field is related to the force by $\vec{\mathbf{E}}=rac{\vec{\mathbf{F}}}{q}$. Hence, we obtain:

$$V_{BA} = -\int_A^B ec{\mathbf{E}} dec{\mathbf{l}}$$

Expressing the voltage as a function of the electric field can by very handy.

In a *uniform* electric field, i.e. the idealized field between two oppositely charged plates, the integral simplifies to:

$$V_{BA} = -Ed$$
 for uniform E-field

with d being the distance between A and B and parallel to the field lines. Further, only a path along the electrical field lines changes the voltage, i.e. $\vec{E} \parallel d\vec{I}$, and the potential is decreasing in the direction the electric field points. W.r.t. units, the electric field can be expressed in [N/C] (as used so far) or in [V/m] (motivated by the relation of field and potential).

For a *point charge* the electric potential can be expressed using the following steps:

• for the integral and a positive charge, we consider paths oriented radially away from the charge in the symmetrical electrical field, i.e. the path $d\vec{\bf l}$ becomes dr

- the distance for point A & B are $r_A \& r_B$, respectively
- the electric field due to a point charge is $E=rac{1}{4\pi\epsilon_0}rac{Q}{r^2}$ (Coulomb's law in electric field form)

$$V_{BA} = -\int_{A}^{B} ec{\mathbf{E}} dec{\mathbf{I}} = -rac{Q}{4\pi\epsilon_{0}} \int_{r_{A}}^{r_{B}} rac{1}{r^{2}} dr = -rac{1}{4\pi\epsilon_{0}} (rac{Q}{r_{B}} - rac{Q}{r_{A}})$$

The two terms represent V_B and V_A , respectively. If we set the electric potential zero at infinity: $V_B=0$ at $r_B=\infty$, we obtain the voltage V at the distance r of a point charge:

$$V=rac{1}{4\pi\epsilon_0}rac{Q}{r}$$
 for a point charge with $V=0$ at $r=\infty$

This expression is also called the *Coulomb potential* as it originates from Coulomb's law. The potential is zero at infinity and increase (decreases) linearly towards the positive (negative)charge.

As before, we can apply the principle of *superposition* to compute the potential due an *arbitrary charge distribution* by computing first the potential for each charge individually and, subsequently, obtain the total potential by integrating over the potentials of all individual charges:

$$V = rac{1}{4\pi\epsilon_0} \int rac{dq}{r}$$

with dq being a infinitesimal small portion of the charge and r its distance of the point where V should be determined.

Relation via derivative

Since we know the relation of potential and field by integration, we can derive the differential form of the relation for an infinitesimal small voltage dV as:

$$V_{BA} = -\int_A^B ec{\mathbf{E}} dec{\mathbf{I}} \quad \leftrightarrow \quad dV = -ec{\mathbf{E}} dec{\mathbf{I}}$$

Given that the electric field $\vec{\mathbf{E}}$ is a vector, we can express the solution for each axis individually:

$$E_x = rac{\delta V}{\delta x}; \quad E_y = rac{\delta V}{\delta y} \quad E_z = rac{\delta V}{\delta z}$$

This mathematical relation is a partial derivative also called the gradient of V. Using the gradient operator $\vec{\nabla}$ (also called nabla operator or del operator), obtain the solution as

$$\vec{\mathbf{E}} = -\mathrm{grad}V = -\vec{\nabla}V$$

In essence, it tells us that the electric field is proportional to the negative rate of change (a.k.a. slope) of V along each dimension.

Electrostatic potential energy

The change in electrostatic potential energy ΔU_{AB} a test charge q experiences as it moves from point A to B is:

$$\Delta U_{AB} = U_B - U_A = q(V_B - V_A)$$

Suppose we have only a *single* charge, no electric force is exerted on it, hence, the electric potential energy is zero.

Suppose we have a system of *two* point charges Q_1 and Q_2 with their distance r_{12} . If Q_1 remains stationary and Q_2 is brought closer, the voltage at the position of Q_2 and induced by the charge Q_1 will be:

$$V=rac{1}{4\pi\epsilon_0}\intrac{Q_1}{r_{12}}$$

Setting the voltage at infinity to zero, the potential energy is:

$$U=rac{1}{4\pi\epsilon_0}\intrac{Q_1Q_2}{r_{12}}$$

This idea can be extended to systems with more point charges by considering the interactions between each pair of point charges.

The electron volt

While not a SI-unit, the *electron volt* (eV) is often used when dealing with energies of particles, atoms, or molecules. It simply relies on the idea of relating the energy to the magnitude of charge of an electron q=e. Therefore, an electron volt describes the energy required to move an electron moving through a potential difference of 1V.

$$1 \mathrm{eV} \approx 1.60 \times 10^{-19} J$$

Equipotential lines & surfaces

We saw that changes in electric potential occur only if the path is parallel to the electric field $\vec{\mathbf{E}} + d\vec{\mathbf{l}}$. Therefore, movement perpendicular to the field, i.e. $\vec{\mathbf{E}} \perp d\vec{\mathbf{l}}$, does not require any work and there is no difference in electric potential. These configurations of zero change in potential are called equipotential line and equipotential surfaces for 2D and 3D, respectively.

Electric dipoles

By combining two charges with the same magnitude but opposite sign, +Q & -Q and separated by a distance l, we introduce the concept of an *electric dipole*. An electric dipole is associated with a *dipole moment* $\vec{\mathbf{p}}$:

$$\vec{\mathbf{p}} = Q\vec{\mathbf{l}}$$

with \vec{l} pointing from negative to positive charge. We refer to molecules with an non-zero dipole moment to as *polar molecules*. Within an uniform, external electric field \vec{E} , the associated torque $\vec{\tau}$ is:

$$ec{ au}=ec{\mathbf{p}} imesec{\mathbf{E}}$$

The potential energy of a electric dipole is:

$$U=-W=-\int au d heta=pE\int \sin heta d heta=-pE\cos heta=-ec{f p}ec{f E}$$

interactive(children=(FloatSlider(value=1.0, description='distance', max=4.0, min=0.5), Float Slider(value=1.0,...

<function __main__.plot_potential(distance, width, n_contours=25)>