Data Size

ICS312 Machine-Level and Systems Programming


Henri Casanova (henric@hawaii.edu)

Size of Data

- In .data and .bss segments, a label merely declares an address
- No data size that would be used by the program is enforced in the declaration
 - 2 dw's can be later used as 4 db's or 1 dd
- Instead, the size of data is inferred based on the source or destination register
 - □ mov eax, [L] ; loads 32 bits
 - mov al, [L] ; loads 8 bits
 - □ mov [L], eax ; stores 32 bits
 - □ mov [L], ax ; stores 16 bits
- This is why it's really important to know the names of the x86 registers

Size Reduction (aka Type Narrowing)

- Sometimes one needs to decrease the data size
- For instance, you have a 4-byte integer, but you needs to use it as a 1-byte integer for some purpose
 - e.g., you did a read_int, but you know the number is between 0 and 128 and is in fact a 1-byte ASCII code
- We can simply use the the fact that we can access lower bits of some registers independently
- Example:
 - □ mov ax, [L] ; load 16 bits in ax
 - mov bl, al ; take the lower 8 bits of ax and puts them in bl



.

Size Reduction (aka Type Narrowing)

- When doing a size reduction, one loses information
- So the "conversion to integers" may or may not work
- Example that "works":

```
\square mov ax, 000A2h ; ax = 162 decimal
```

□ mov bl, al; ; bl = 162 decimal

- □ Decimal 162 is *encodable* on 8 bits (because it's < 256)
- Example that "doesn't work":

```
mov ax, 00101h ; ax = 257 decimal
```

□ mov bl, al; ; bl = 1 decimal

□ Decimal 257 is *not encodable* on 8 bits because > 255

Size Reduction and Sign

- Consider a 2-byte quantity: FFF4
- If we interpret this quantity as unsigned it is decimal 65,524
 - The computer does not know whether the content of registers/ memory corresponds to signed or unsigned quantities
 - Once again it's the responsibility of the programmer to do the right thing, using the right instructions (more on this later)
- In this case size reduction "does not work", meaning that reduction to a 1-byte quantity will not be interpreted as decimal 65,524 (which is way over 255!), but instead as decimal 244 (F4h)
- If instead FFF4 is a signed quantity (using 2's complement), then it corresponds to -000C (000B + 1), that is to decimal -12
- In this case, size reduction works!
 - 1-byte value F4 is decimal value -12

Size Reduction and Sign

- The previous examples do **not** mean that size reduction always works for signed quantities
- For instance, consider signed FF32h, which is a negative number equal to -00CEh, that is, decimal -206
- A size reduction into a 1-byte quantity leads to 32h, which is decimal +50!
- This is because -206 is not encodable on 1 byte
 - The range of signed 1-byte quantities is between decimal
 -128 and decimal +127
- So, size reduction may work or not work for signed or unsigned quantities!
- In other words, there will always be "bad" cases

High-Level Languages

- All that we said in the previous slides applies to high-level languages
- For instance, in C/C++

No compiler warning

High-Level Languages (2)

Other languages are a bit more conservative, e.g., Java

 Other languages automatically adjust data size based on values, e.g., Python3



Two Rules to Remember

For unsigned numbers: size reduction works if all removed bits are 0

- For signed numbers: size reduction works if all removed bits are all 0's or all removed bits are all 1's, AND if the highest bit not removed is equal to the removed bits
 - This highest remaining bit is the new sign bit, and thus must be the same as the original sign bit

$$a = 0 \text{ or } 1$$

×

Size Increase (aka Type Widening)

- Size increase for unsigned quantities is simple: just add 0's to the left of it
- Size increase for signed quantities requires sign extension: the sign bit must be extended, that is, replicated
 - Consider the signed 1-byte number 5A. This is a positive number (decimal 90), and so its 2-byte version would be 005A
 - Consider the signed 1-byte number 8A. This is a negative number (decimal -118), and so its 2-byte version would be FF8A

м.


Unsigned size increase

- Say we want to size increase an unsigned 1byte number to be a 2-byte unsigned number
- This can be done in a few easy steps, for instance:
 - Put the 1-byte number into al
 - Set all bits of ah to 0
 - Access the number as ax
- Example

```
mov al, OEDh mov ah, O mov ..., ax
```

Unsigned size increase

- How about increasing the size of a 2-byte quantity to 4 byte?
- This cannot be done in the same manner because there is no way to access the 16 highest bit of register eax separately!



- Therefore, there is an instruction called movzx (Zero eXtend), which takes two operands:
 - Destination: 16- or 32-bit register
 - Source: 8- or 16-bit register, or 1 byte in memory, or 1 word in memory
 - The destination must be larger than the source!

Using movzx

- movzx eax, ax ; zero extends ax into eax
 movzx eax, al ; zero extends al into eax
 movzx ax, al ; zero extends al into ax
- movzx ebx, ax ; zero extends ax into ebx
- movzx ebx, [L] ; leads to a "size not specified" error
- movzx ebx, byte [L] ; zero extends 1byte value at address L into ebx
- movzx eax, word [L] ; zero extends 2byte value at address L into eax

v

Signed Size Increase

- There is no way to use mov or movzx instructions to increase the size of signed numbers, because of the needed sign extension
 - Sometimes we want to add 0's (like movzx), but sometimes we want to add 1's
- For this reason, we have a new instruction: movsx
 - Works just like MOVZX, but does sign extension
- Let's see an example..

.

Example

mov al, 0A7h ; as a programmer, I view this

; as an unsigned, 1-byte quantity

; (decimal 167)

mov bl, 0A7h ; as a programmer, I view this

; as a signed 1-byte

; quantity (decimal -89)

movzx eax, al; ; extend to a 4-byte value

; (00000A7)

movsx ebx, bl; ; extend to a 4-byte value

; (FFFFFA7)

In-class Exercise

Consider the following code

```
mov al, OB2h
movsx eax, al
mov bx, ax
movzx ebx, bx
```

- What's the final value of eax?
- What's the final value of ebx?

(poll)

In-class Exercise Solution

EAX EBX al, OB2h ?? | ?? | B2 mov FF FF FF B2 eax, al movsx FF FF FF B2 bx, ax mov FF | FF | FF | B2 ebx, bx movzx

Signed/Unsigned in C

- In C/C++ one can declare variables as signed or unsigned
 - In Java you don't have unsigned data types, but there are methods that treat signed data types as unsigned
 - which a LOT of people hate with a passion, with pretty good reasons
 - the rationale is likely that Java should be "easy for the average developer"
- Why would I like a language that supports signed/unsigned?
 - If I know that a variable never needs to be negative, I can extend its range by declaring it unsigned
 - Often one doesn't do this, and in fact one often uses 4-byte values (int) when 1byte values would suffice
 - □ e.g., for loop counters, which wastes bytes, and thus CPU cycles
 - □ When dealing with various binary data formats, it's really convenient to know exactly what the data means and manipulate it without extra bits
 - If I make a mistake (like setting an unsigned variable to a negative value) I want to compiler to complain!
- Let's look at a small C-code example

Signed/Unsigned in C/C++

Declarations:

```
unsigned char uchar = 0xFF;
signed char schar = 0xFF; // "char"="signed char"
```

- I declared these variables as 1-byte numbers, or chars, because I know I don't need to store large numbers
 - Often used to store ASCII codes, but can be used for anything

```
for (char x=0; x<30; x++) { ... }
```

- Let's say now that I have to call a function that requires a 4-byte int as argument (by default "int" = "signed int" in C/C++)
- We need to extend 1-byte values to 4-byte values
- This is done in C with a "cast"

```
int a = (int) uchar; // the compiler will use MOVZX to do this int b = (int) schar; // the compiler will use MOVSX to do this
```

Signed/Unsigned in C

```
unsigned char uchar = 0xFF;
signed char schar = 0xFF;
int a = (int)uchar;
int b = (int)schar;
printf("a = %d\n",a);
printf("b = %d\n",b);
```

What does this program print?

Signed/Unsigned in C

```
unsigned char uchar = 0xFF;
signed char schar = 0xFF;
int a = (int)uchar;
int b = (int)schar;
printf("a = %d\n",a);
printf("b = %d\n",b);
```

Prints out:

```
a = 255 (a = 0x000000FF)

b = -1 (b = 0xFFFFFFFF)
```

M

printf in C

- So, by declaring variables as "signed" or "unsigned" you define which of movsx or movzx will be used when you have a cast in C
- Printf can print signed or unsigned interpretation of numbers, regardless of how they were declared:
 - "%d": signed decimal
 - □ "%u": unsigned decimal
- Arguments to printf are automatically extended to 4-byte integers! (using movzx or movsx internally)
 - Unless you specify "short" as in "%hd" or "%hu"
- Good luck understanding this if you have never studied assembly at all...
- Let's try a simple example

Understanding printf

```
unsigned short us = 259; // 0x0103 signed short ss = -45; // 0xFFD3 printf("%d %d\n",us, ss); printf("%u %u\n",us, ss);
```

Let's together try to understand what will be printed before we look at the answer...

.

Understanding printf

```
unsigned short us = 259; // 0x0103 signed short ss = -45; // 0xFFD3 printf("%d %d\n",us, ss); printf("%u %u\n",us, ss);
```

259 -45259 4294967251

A "kitchen sink" example

```
unsigned short ushort; // 2-byte quantity signed char schar; // 1-byte quantity int integer; // 4-byte quantity schar = 0xAF; integer = (int) schar; integer++; ushort = integer; printf("ushort = %d\n",ushort);
```

- What does this code print?
 - Or what's the hex value of the value it prints?
- Let's do this together...

M

A "kitchen sink" example

```
unsigned short
                     ushort;
signed char
                     schar;
                     integer;
int
schar = 0xAF;
integer = (int) schar;
integer++;
ushort = integer;
printf("ushort = %d\n",ushort);
```

```
integer FF FF FF B0

ushort FF B0
```

Because printf doesn't specify "h" ushort is size augmented to 4-bytes using movzx (because declared as unsigned): 00 00 FF B0 The number is then printed as a signed integer ("%d"): 65456



More Signed/Unsigned in C

- On page 32 of the textbook there is an interesting example about the use of the fgetc() function
 - fgetc reads a 1-byte character from a file but returns it as a 4-byte quantity!
- This is a good example of how understanding low-level details can be necessary to understand high-level constructs
- Let's go through the example...

The Trouble with fgetc()

- The fgetc() function in the standard C I/O library takes as argument a file opened for reading, and returns a character, i.e., an ASCII code
- This function is often used to read in all characters of the file
- The prototype of the function is:

int fgetc(FILE *)

- One may have expected for fgetc() to return a char rather than an int
- But if the end of the file is reached, fgetc() returns a special value called EOF (End Of File)
 - □ Typically defined to be -1 (#define EOF -1)
- So fgetc() returns either
 - □ A character zero-extended into a 4-byte int (i.e., 000000xx), or
 - □ Integer -1 (i.e., FFFFFFF)

M

The Trouble with fgetc()

Buggy code to compute the sum of ASCII codes in a text file:

```
char c;
while ( (c = fgetc(file)) != EOF) {
     sum += c;
}
```

- In this code we have mistakenly declared c as a char
- C being C (and not Java), it thinks we know what we're doing and does a size-reduction of a 4-byte int into a 1-byte char when doing the assignment into c
- Let's say we just read in a character with ASCII code FF (decimal 255, "ÿ")
- fgetc() returned 000000FF, but it was truncated into 1-byte integer c=FF
 - □ FF is -1 in decimal
- So we then compare 1-byte value FF to 4-byte value FFFFFFFF
 - C allows comparing signed integer values of different byte sizes, for convenience, by internally sign-extending the shorter value
 - int x=-1; char y=-1; // (x == y) returns TRUE
 - So FF is sign-extended into FFFFFFF
- Therefore, the above code will "miss" all characters after ASCII code FF and mistake them for an end of file
- Solution: declare c as an int (which may seem counter-intuitive)

Example Type Widening Bug

- If you search around, you'll find bug reports about type widening pretty frequently
- For instance, https://unspecified.wordpress.com/ 2011/08/08/integer-conversions-in-c/
- Last paragraph is particularly illuminating
 - There's an implicit type widening of a signed char, that then can add a bunch of 1's when the intent was to always add a bunch of 0's
- This bug is for a popular password encryption library, which weakens its security
 - □ "This can result in passwords being even easier to crack than expected. This is due to a char signedness bug in crypt_blowfish."

M

Should you care?

- It all depends of what kind of work you do and what kind of software you deal with
 - Some codes will have stuff like that all over with signed/ unsigned declarations and casts galore
 - Some codes will have none of that ever
- If all you do is JavaScript Web app development, you likely will rarely care
- If you do lower-level development, you may care every single day
 - □ Or rather, if you don't know all this, your life will be very difficult
- Overall, it's pretty rare to completely avoid it for your entire life
 - Often due to binary data formats used all over the place

M

Conclusion

- Being aware of data sizes and of data size extension/reduction behaviors is important when doing low-level development
 - □ Assembly, C, C++, etc.
- Unfortunately, almost every developer at some point is confronted with data size issues and having studied a bit of assembly is the only way to solve mysteries
 - Important to know that a cast isn't magical, and can do the "wrong" thing