# Chapter 3: Internet transport protocols

#### Our goals:

- understand principles behind transport layer services:
  - multiplexing/demultiplexing
  - o reliable data transfer
  - flow control
  - congestion control

- learn about transport layer protocols in the Internet:
  - UDP: connectionless transport
  - TCP: connection-oriented transport
  - TCP congestion control


# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - o segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
  - send side: breaks app messages into segments, passes to network layer
  - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
  - Internet: TCP and UDP



# Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
  - relies on, enhances, network layer services

#### Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

## Internet transport-layer protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer


- 3.5 Connection-oriented transport: TCP
  - o segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Multiplexing/demultiplexing

#### <u>Demultiplexing at rcv host:</u>


delivering received segments to correct socket

= socket




#### Multiplexing at send host:

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



## How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries 1 transport-layer segment
  - each segment has source, destination port number (recall: well-known port numbers for specific applications)
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

# Connectionless demultiplexing

Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
  DatagramSocket(99111);
```

DatagramSocket mySocket2 = new
 DatagramSocket(99222);


UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
  - checks destination port number in segment
  - directs UDP segment to socket with that port number
- □ IP datagrams with different source IP addresses and/or source port numbers directed to same socket

# Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket (6428);




SP provides "return address"

## Connection-oriented demux


- TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - o dest IP address
  - dest port number
- recv host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
  - non-persistent HTTP will have different socket for each request

# Connection-oriented demux (cont)



# Connection-oriented demux: Threaded Web Server



# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - o segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out of order to app

#### connectionless:

- no handshaking between
   UDP sender, receiver
- each UDP segment handled independently of others

#### Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

## UDP: more

- often used for streaming multimedia apps
  - loss tolerant
  - o rate sensitive
- other UDP uses
  - o DNS
  - SNMP
- reliable transfer over UDP:
   add reliability at
   application layer
  - application-specific error recovery!

UDP segment format

(message)

32 bits -

## UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

#### Sender:

- □ treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field


#### Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected.
     But maybe errors
     nonetheless? More later

...

# Internet Checksum Example

- Note
  - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers




# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


## Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Reliable data transfer: getting started



### Reliable data transfer: getting started

#### We'll:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver
   event causing state transition

state: when in this "state" next state uniquely determined by next event



### Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - o no bit errors
  - no loss of packets
- □ separate FSMs for sender, receiver:
  - o sender sends data into underlying channel
  - o receiver read data from underlying channel




sender

receiver


### Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- the question: how to recover from errors:
  - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - o sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
  - error detection
  - o receiver feedback: control msgs (ACK,NAK) rcvr->sender

## rdt2.0: operation with no errors



### rdt2.0: error scenario



## rdt2.0 has a fatal flaw!

# What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


#### Handling duplicates:

- sender adds sequence number to each pkt
- sender retransmits current pkt if ACK/NAK garbled
- receiver discards (doesn't deliver up) duplicate pkt

#### stop and wait

Sender sends one packet, then waits for receiver response

### rdt2.1: sender, handles garbled ACK/NAKs



### rdt2.1: receiver, handles garbled ACK/NAKs

rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq0(rcvpkt) extract(rcvpkt,data) deliver data(data) sndpkt = make pkt(ACK, chksum) udt send(sndpkt) rdt rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make pkt(NAK, chksum) udt send(sndpkt) Wait for Wait foi 0 from rdt rcv(rcvpkt) && 1 from below, not corrupt(rcvpkt) && below. has seq1(rcvpkt) sndpkt = make pkt(ACK, chksum) udt send(sndpkt) rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq1(rcvpkt) extract(rcvpkt,data) deliver data(data) sndpkt = make pkt(ACK, chksum)

udt send(sndpkt)

rdt\_rcv(rcvpkt) && (corrupt(rcvpkt)
sndpkt = make\_pkt(NAK, chksum)
udt send(sndpkt)

rdt\_rcv(rcvpkt) &&
 not corrupt(rcvpkt) &&
 has\_seq0(rcvpkt)

sndpkt = make\_pkt(ACK, chksum)
udt\_send(sndpkt)

## rdt2.1: discussion

#### Sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "current" pkt has 0 or 1 seq. #


#### Receiver:

- must check if received packet is duplicate
  - state indicates whether0 or 1 is expected pktseq #
- note: receiver can not know if its last ACK/NAK received OK at sender

## rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - o receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

### rdt2.2: sender, receiver fragments




#### rdt3.0: channels with errors and loss


#### New assumption:

- underlying channel can also lose packets (data or ACKs)
  - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- <u>Approach:</u> sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but use of seq. #'s already handles this
  - receiver must specify seq# of pkt being ACKed
- requires countdown timer


## rdt3.0 sender




## rdt3.0 in action



(a) operation with no loss



## rdt3.0 in action



#### Performance of rdt3.0


- rdt3.0 works, but performance stinks
- □ example: 1 Gbps link, 15 ms e-e prop. delay, 1KB packet:

$$T_{\text{transmit}} = \frac{L \text{ (packet length in bits)}}{R \text{ (transmission rate, bps)}} = \frac{8kb/pkt}{10**9 \text{ b/sec}} = 8 \text{ microsec}$$

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- O U sender: utilization fraction of time sender busy sending
- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!

#### rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

# Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- o range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat


# Pipelining: increased utilization



# Go-Back-N

#### Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
  - o may deceive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- $\Box$  timeout(n): retransmit pkt n and all higher seq # pkts in window

#### GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextsegnum])
                          if (base == nextseqnum)
                           start timer
                          nextseqnum++
                       else
                        refuse data(data)
   base=1
   nextseqnum=1
                                           timeout
                                          start timer
                             Wait
                                          udt send(sndpkt[base])
                                          udt_send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                          udt send(sndpkt[nextseanum-1])
                         rdt rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start timer
```


#### GBN: receiver extended FSM



# ACK-only: always send ACK for correctly-received pkt with highest in-order seq #

- may generate duplicate ACKs
- o need only remember expectedseqnum
- out-of-order pkt:
  - discard (don't buffer) -> no receiver buffering!
  - Re-ACK pkt with highest in-order seq #


# GBN in action



# Selective Repeat

- receiver individually acknowledges all correctly received pkts
  - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
  - sender timer for each unACKed pkt
- sender window
  - N consecutive seq #'s
  - o again limits seq #s of sent, unACKed pkts

#### Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

# Selective repeat

#### -sender

#### data from above:

if next available seq # in window, send pkt

#### timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase, sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

#### receiver

pkt n in [rcvbase, rcvbase+N-1]

- $\Box$  send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

 $\Box$  ACK(n)

otherwise:

ignore


#### Selective repeat in action



# Selective repeat: dilemma

#### Example:

- seq #'s: 0, 1, 2, 3
- □ window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - o no "message boundaries"
- pipelined:
  - TCP congestion and flow control set window size
- send & receive buffers

- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- connection-oriented:
  - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver



## TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting
by bytes
of data
(not segments!)

# bytes rcvr willing to accept


# TCP seq. #'s and ACKs

#### <u>Seq. #'s:</u>

byte stream
 "number" of first
 byte in segment's
 data

#### ACKs:

- seq # of next byte expected from other side
- o cumulative ACK
- Q: how receiver handles out-of-order segments
  - A: TCP spec doesn't say, - up to implementor



simple telnet scenario

#### TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- Ionger than RTT
  - but RTT varies
- too short: premature timeout
  - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT


## TCP Round Trip Time and Timeout

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- $\Box$  typical value:  $\alpha = 0.125$

## Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



#### TCP Round Trip Time and Timeout

#### Setting the timeout

- EstimtedRTT plus "safety margin"
  - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

#### Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- Pipelined segments
- Cumulative acks
- TCP uses single retransmission timer

- Retransmissions are triggered by:
  - o timeout events
  - duplicate acks
- Initially consider simplified TCP sender:
  - ignore duplicate acks
  - ignore flow control, congestion control

## TCP sender events:

#### data rcvd from app:

- Create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- TimeOutInterval

#### timeout:

- retransmit segment that caused timeout
- restart timer

#### Ack rcvd:

- If acknowledges previously unacked segments
  - update what is known to be acked
  - start timer if there are outstanding segments

```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSegNum
      if (timer currently not running)
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
      start timer
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```


# TCP sender (simplified)

#### Comment:


 SendBase-1: last cumulatively ack'ed byte Example:

SendBase-1 = 71;
y= 73, so the rcvr
wants 73+;
y > SendBase, so
that new data is
acked

#### TCP: retransmission scenarios



## TCP retransmission scenarios (more)



Cumulative ACK scenario

# TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment startsat lower end of gap

## Fast Retransmit

- Time-out period often relatively long:
  - long delay before resending lost packet
- Detect lost segments via duplicate ACKs.
  - Sender often sends many segments back-toback
  - If segment is lost, there will likely be many duplicate ACKs.

- ☐ If sender receives 3
  ACKs for the same
  data, it supposes that
  segment after ACKed
  data was lost:
  - <u>fast retransmit:</u> resend segment before timer expires

# Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
    if (y > SendBase) {
        SendBase = y
        if (there are currently not-yet-acknowledged segments)
            start timer
        }
        else {
            increment count of dup ACKs received for y
            if (count of dup ACKs received for y = 3) {
                resend segment with sequence number y
            }
        }
}
```

a duplicate ACK for already ACKed segment

fast retransmit


# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP Flow Control

receive side of TCP connection has a receive buffer:




app process may be slow at reading from buffer

#### flow control

sender won't overflow receiver's buffer by transmitting too much, too fast

speed-matching service: matching the send rate to the receiving app's drain rate

# TCP Flow control: how it works



(Suppose TCP receiver discards out-of-order segments)

- spare room in buffer
- = RcvWindow

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
  - guarantees receive buffer doesn't overflow

# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

#### TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
  - o seq. #s
  - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator
  Socket clientSocket = new
  Socket("hostname", "port
  number");
- Server: contacted by client
  Socket connectionSocket =
  welcomeSocket.accept();

#### Three way handshake:

- Step 1: client host sends TCP
  SYN segment to server
  - specifies initial seq #
  - o no data
- Step 2: server host receives SYN, replies with SYNACK segment
  - server allocates buffers
  - specifies server initial seq. #
- <u>Step 3:</u> client receives SYNACK, replies with ACK segment, which may contain data


#### TCP Connection Management (cont.)

#### Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




### TCP Connection Management (cont.)

<u>Step 3:</u> client receives FIN, replies with ACK.


 Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



### TCP Connection Management (cont)



# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer


- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


# Principles of Congestion Control


### Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- □ a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delayswhen congested
- maximum achievable throughput

- one router, finite buffers
- sender retransmission of lost packet




- $\square$  always:  $\lambda_{in} = \lambda_{out}$  (goodput)
- "perfect" retransmission only when loss:  $\lambda' > \lambda$  out out retransmission of delayed (not lost) packet makes  $\lambda'$  in
- retransmission of delayed (not lost) packet makes  $\lambda_{\text{in}}$  larger (than perfect case) for same  $\lambda_{\text{out}}$




- "costs" of congestion:
- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as  $\lambda_{in}$  and  $\lambda_{in}'$  increase ?





### Another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

### Approaches towards congestion control

#### Two broad approaches towards congestion control:

# End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

# Network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate sender should send at

### Case study: ATM ABR congestion control


#### ABR: available bit rate:

- "elastic service"
- if sender's path
  "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

# RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - NI bit: no increase in rate (mild congestion)
  - CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

### Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
  - o congested switch may lower ER value in cell
  - sender' send rate thus minimum supportable rate on path
- □ EFCI bit in data cells: set to 1 in congested switch
  - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

# Chapter 3: Internet transport protocols

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP Congestion Control

- end-end control (no network assistance)
- sender limits transmission:

  LastByteSent-LastByteAcked

  ≤ CongWin
- Roughly,

rate = 
$$\frac{CongWin}{RTT}$$
 Bytes/sec

 CongWin is dynamic, function of perceived network congestion

# How does sender perceive congestion?


- loss event = timeout or3 duplicate acks
- TCP sender reduces rate (CongWin) after loss event

#### three mechanisms:

- O AIMD
- slow start
- conservative after timeout events

# TCP AIMD

multiplicative decrease: cut CongWin in half after loss event



additive increase:

increase Congwin by

1 MSS every RTT in

Long-lived TCP connection


# TCP Slow Start

- □ When connection begins, CongWin = 1 MSS
  - Example: MSS = 500bytes & RTT = 200 msec
  - o initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
  - desirable to quickly ramp up to respectable rate

 When connection begins, increase rate exponentially fast until first loss event

# TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
  - double CongWin every RTT
  - done by incrementing CongWin for every ACK received
- Summary: initial rate is slow but ramps up exponentially fast



# Refinement


- ☐ After 3 dup ACKs:
  - CongWin is cut in half
  - window then grows linearly
- But after timeout event:
  - CongWin instead set to 1 MSS;
  - window then grows exponentially
  - to a threshold, then grows linearly

#### Philosophy:

- 3 dup ACKs indicates network capable of delivering some segments
- timeout before 3 dup
   ACKs is "more alarming"

# Refinement (more)

- Q: When should the exponential increase switch to linear?
- A: When CongWin gets to 1/2 of its value before timeout.



### Implementation:

- Variable Threshold
- ☐ At loss event, Threshold is set to 1/2 of CongWin just before loss event

### Summary: TCP Congestion Control

- When CongWin is below Threshold, sender in slow-start phase, window grows exponentially.
- When Congwin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- □ When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

# TCP sender congestion control

Event	State	TCP Sender Action	Commentary
ACK receipt for previously unacked data	Slow Start (SS)	CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance"	Resulting in a doubling of CongWin every RTT
ACK receipt for previously unacked data	Congestion Avoidance (CA)	CongWin = CongWin+MSS * (MSS/CongWin)	Additive increase, resulting in increase of CongWin by 1 MSS every RTT
Loss event detected by triple duplicate ACK	SS or CA	Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance"	Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS.
Timeout	SS or CA	Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start"	Enter slow start
Duplicate ACK	SS or CA	Increment duplicate ACK count for segment being acked	CongWin and Threshold not changed

# TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
  - Ignore slow start
- □ Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- □ Just after loss, window drops to W/2, throughput to W/2RTT.
- □ Average throughout: .75 W/RTT

# TCP Futures


- Example: 1500 byte segments, 100ms RTT, want 10
   Gbps throughput
- Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT\sqrt{L}}$$

- $\Box$   $\rightarrow$  L = 2.10<sup>-10</sup> Wow
- New versions of TCP for high-speed needed!

# TCP Fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



# Why is TCP fair?

#### Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



# Fairness (more)

#### Fairness and UDP

- Multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- Instead use UDP:
  - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

# Fairness and parallel TCP connections

- nothing prevents app from opening parallel cactions between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 cnctions;
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2!

# Delay modeling

Q: How long does it take to receive an object from a Web server after sending a request?

# Ignoring congestion, delay is influenced by:

- TCP connection establishment
- data transmission delay
- slow start

#### Notation, assumptions:

- Assume one link between client and server of rate R
- ☐ S: MSS (bits)
- O: object size (bits)
- no retransmissions (no loss, no corruption)

#### Window size:


- First assume: fixed congestion window, W segments
- Then dynamic window, modeling slow start

# Fixed congestion window (1)

#### First case:

WS/R > RTT + S/R: ACK fo first segment in window returns before window's worth of data sent

delay = 2RTT + O/R




# Fixed congestion window (2)

#### Second case:

WS/R < RTT + S/R: wait for ACK after sending window's worth of data sent

delay = 2RTT + O/R+ (K-1)[S/R + RTT - WS/R]



### TCP Delay Modeling: Slow Start (1)

#### Now suppose window grows according to slow start

Will show that the delay for one object is:

$$Latency = 2RTT + \frac{O}{R} + P \left[ RTT + \frac{S}{R} \right] - (2^{P} - 1) \frac{S}{R}$$

where P is the number of times TCP idles at server:

$$P = \min\{Q, K-1\}$$

- where Q is the number of times the server idles if the object were of infinite size.
- and K is the number of windows that cover the object.

### TCP Delay Modeling: Slow Start (2)

#### Delay components:


- 2 RTT for connection estab and request
- O/R to transmit object
- time server idles due to slow start

Server idles: P = min{K-1,Q} times

#### Example:

- $\cdot$  0/S = 15 segments
- K = 4 windows
- Q = 2
- $P = min\{K-1,Q\} = 2$

Server idles P=2 times



### TCP Delay Modeling (3)

 $\frac{S}{R}$  + RTT = time from when server starts to send segment


until server receives acknowledgement

initiate TCP

$$2^{k-1} \frac{S}{R} = \text{time to transmit the kth window}$$

$$\left[\frac{S}{R} + RTT - 2^{k-1} \frac{S}{R}\right]^{+} = \text{idle time after the } k\text{th window}$$

delay = 
$$\frac{O}{R} + 2RTT + \sum_{p=1}^{P} idleTime_{p}$$
  
=  $\frac{O}{R} + 2RTT + \sum_{k=1}^{P} \left[ \frac{S}{R} + RTT - 2^{k-1} \frac{S}{R} \right]$   
=  $\frac{O}{R} + 2RTT + P[RTT + \frac{S}{R}] - (2^{P} - 1) \frac{S}{R}$ 



# TCP Delay Modeling (4)

Recall K = number of windows that cover object

How do we calculate K?

$$K = \min\{k : 2^{0}S + 2^{1}S + \dots + 2^{k-1}S \ge O\}$$

$$= \min\{k : 2^{0} + 2^{1} + \dots + 2^{k-1} \ge O/S\}$$

$$= \min\{k : 2^{k} - 1 \ge \frac{O}{S}\}$$

$$= \min\{k : k \ge \log_{2}(\frac{O}{S} + 1)\}$$

$$= \left\lceil \log_{2}(\frac{O}{S} + 1) \right\rceil$$


Calculation of Q, number of idles for infinite-size object, is similar (see HW).

# HTTP Modeling

- Assume Web page consists of:
  - 1 base HTML page (of size O bits)
  - M images (each of size O bits)
- Non-persistent HTTP:
  - M+1 TCP connections in series
  - O Response time = (M+1)O/R + (M+1)2RTT + sum of idle times
- Persistent HTTP:
  - 2 RTT to request and receive base HTML file
  - 1 RTT to request and receive M images
  - $\bigcirc$  Response time = (M+1)O/R + 3RTT + sum of idle times
- Non-persistent HTTP with X parallel connections
  - Suppose M/X integer.
  - 1 TCP connection for base file
  - M/X sets of parallel connections for images.
  - O Response time = (M+1)O/R + (M/X + 1)2RTT + sum of idle times

## HTTP Response time (in seconds)

RTT = 100 msec, O = 5 Kbytes, M=10 and X=5




For low bandwidth, connection & response time dominated by transmission time.

Persistent connections only give minor improvement over parallel connections.

### HTTP Response time (in seconds)

RTT = 1 sec, O = 5 Kbytes, M = 10 and X = 5



For larger RTT, response time dominated by TCP establishment & slow start delays. Persistent connections now give important improvement: particularly in high delay•bandwidth networks.

# Chapter 3: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - o reliable data transfer
  - o flow control
  - congestion control
- instantiation and implementation in the Internet
  - O UDP
  - O TCP