

# 13.4 — Overloading the I/O operators

▲ ALEX SEPTEMBER 13, 2021

For classes that have multiple member variables, printing each of the individual variables on the screen can get tiresome fast. For example, consider the following class:

```
class Point
2
3
   private:
       double m_x{};
       double m_y{};
5
       double m_z{};
       Point(double x=0.0, double y=0.0, double
   z=0.0)
8
         : m_x{x}, m_y{y}, m_z{z}
       double getX() const { return m_x; }
       double getY() const { return m_y; }
       double getZ() const { return m_z; }
   };
```

If you wanted to print an instance of this class to the screen, you'd have to do something like this:

Of course, it makes more sense to do this as a reusable function. And in previous examples, you've seen us create print() functions that work like this:

```
class Point
1
2
    {
3
    private:
        double m_x{};
4
        double m_y{};
5
        double m_z{};
    public:
6
        Point(double x=0.0, double y=0.0, double z=0.0)
          : m_x{x}, m_y{y}, m_z{z}
8
9
        double getX() const { return m_x; }
        double getY() const { return m_y; }
        double getZ() const { return m_z; }
        void print() const
        {
            std::cout << "Point(" << m_x << ", " << m_y << ", " << m_z <<
    ')';
11
    };
12
```

While this is much better, it still has some downsides. Because print() returns void, it can't be called in the middle of an output statement. Instead, you have to do this:

```
1    int main()
2    {
3         const Point point{5.0, 6.0, 7.0};

         std::cout << "My point is: ";
         point.print();
         std::cout << " in Cartesian
         space.\n";
        }
</pre>
```

It would be much easier if you could simply type:

```
1 | Point point{5.0, 6.0, 7.0};
cout << "My point is: " << point << " in Cartesian
space.\n";
```

and get the same result. There would be no breaking up output across multiple statements, and no having to remember what you named the print function.

Fortunately, by overloading the << operator, you can!

Overloading operator<<

Overloading operator<< is similar to overloading operator+ (they are both binary operators), except that the parameter types are different.

Consider the expression std::cout << point . If the operator is <<, what are the operands? The left operand is the std::cout object, and the right operand is your Point class object. std::cout is actually an object of type std::ostream. Therefore, our overloaded function will look like this:

Implementation of operator<< for our Point class is fairly straightforward -- because C++ already knows how to output doubles using operator<<, and our members are all doubles, we can simply use operator<< to output the member variables of our Point. Here is the above Point class with the overloaded operator<<.

```
1
    #include <iostream>
2
    class Point
3
4
    private:
5
         double m_x{};
        double m_y{};
6
        double m_z{};
    public:
         Point(double x=0.0, double y=0.0, double z=0.0)
8
           : m_x{x}, m_y{y}, m_z{z}
9
10
11
         friend std::ostream& operator<< (std::ostream& out, const Point& point);</pre>
    };
    std::ostream& operator<< (std::ostream& out, const Point& point)</pre>
12
        // Since operator<< is a friend of the Point class, we can access Point's members directly.
        out << "Point(" << point.m_x << ", " << point.m_y << ", " << point.m_z << ')'; // actual output done
13
    here
14
15
        return out; // return std::ostream so we can chain calls to operator<<
16
    }
    int main()
    {
        const Point point1{2.0, 3.0, 4.0};
17
        std::cout << point1 << '\n';</pre>
18
19
         return 0;
    }
```

This is pretty straightforward -- note how similar our output line is to the line in the print() function we wrote previously. The most notable difference is that std::cout has become parameter out (which will be a reference to std::cout when the function is called).

The trickiest part here is the return type. With the arithmetic operators, we calculated and returned a single answer by value (because we were creating and returning a new result). However, if you try to return std::ostream by value, you'll get a compiler error. This happens because std::ostream specifically disallows being copied.

In this case, we return the left hand parameter as a reference. This not only prevents a copy of std::ostream from being made, it also allows us to "chain" output commands together, such as std::cout << point << std::endl;

You might have initially thought that since operator<< doesn't return a value to the caller, we should define the function as returning void. But consider what would happen if our operator<< returned void. When the compiler evaluates <code>std::cout << point << '\n', due to the precedence/associativity rules, it evaluates this expression as (std::cout << point) << '\n'; . std::cout << point) would call our void-returning overloaded operator<< function, which returns void. Then the partially evaluated expression becomes: void << '\n'; , which makes no sense!</code>

By returning the out parameter as the return type instead, (std::cout<< point) returns std::cout. Then our partially evaluated expression becomes: std::cout << '\n'; , which then gets evaluated itself!

Any time we want our overloaded binary operators to be chainable in such a manner, the left operand should be returned (by reference). Returning the left-hand parameter by reference is okay in this case -- since the left-hand parameter was passed in by the calling function, it must still exist when the called function returns. Therefore, we don't have to worry about referencing something that will go out of scope and get destroyed when the operator returns.

Just to prove it works, consider the following example, which uses the Point class with the overloaded operator<< we wrote above:

```
#include <iostream>
2
    class Point
3
4
    private:
5
        double m_x{};
6
        double m_y{};
        double m_z{};
    public:
8
        Point(double x=0.0, double y=0.0, double z=0.0)
          : m_x\{x\}, m_y\{y\}, m_z\{z\}
9
10
11
        friend std::ostream& operator<< (std::ostream& out, const Point& point);</pre>
    };
    std::ostream& operator<< (std::ostream& out, const Point& point)</pre>
12
        // Since operator<< is a friend of the Point class, we can access Point's members
    directly.
13
        out << "Point(" << point.m_x << ", " << point.m_y << ", " << point.m_z << ')';
14
15
        return out;
16
    }
    int main()
    {
        Point point1{2.0, 3.5, 4.0};
        Point point2{6.0, 7.5, 8.0};
17
        std::cout << point1 << ' ' << point2 << '\n';
18
19
        return 0;
   }
```

#### This produces the following result:

```
Point(2, 3.5, 4) Point(6, 7.5, 8)
```

## Overloading operator>>

It is also possible to overload the input operator. This is done in a manner analogous to overloading the output operator. The key thing you need to know is that std::cin is an object of type std::istream. Here's our Point class with an overloaded operator>>:

```
#include <iostream>
1
2
    class Point
3
4
    private:
5
        double m_x{};
6
        double m_y{};
        double m_z{};
    public:
        Point(double x=0.0, double y=0.0, double z=0.0)
8
          : m_x{x}, m_y{y}, m_z{z}
9
10
11
        friend std::ostream& operator<< (std::ostream& out, const Point& point);</pre>
        friend std::istream& operator>> (std::istream& in, Point& point);
    };
12
    std::ostream& operator<< (std::ostream& out, const Point& point)</pre>
        // Since operator<< is a friend of the Point class, we can access Point's members directly.
13
        out << "Point(" << point.m_x << ", " << point.m_y << ", " << point.m_z << ')';
14
15
        return out;
    }
    std::istream& operator>> (std::istream& in, Point& point)
        // Since operator>> is a friend of the Point class, we can access Point's members directly.
        // note that parameter point must be non-const so we can modify the class members with the input
17
    values
        in >> point.m_x;
        in >> point.m_y;
        in >> point.m_z;
        return in;
18 }
```

Here's a sample program using both the overloaded operator<< and operator>>:

```
1    int main()
{
2        std::cout << "Enter a point: ";
        Point point;
        std::cin >> point;

        std::cout << "You entered: " << point <<

'\n';
        return 0;
6    }
</pre>
```

Assuming the user enters 3.0 4.5 7.26 as input, the program produces the following result:

```
You entered: Point(3, 4.5, 7.26)
```

## Conclusion

Overloading operator<< and operator>> make it extremely easy to output your class to screen and accept user input from the console.

## Quiz time

Take the Fraction class we wrote in the previous quiz (listed below) and add an overloaded operator<< and operator>> to it.

The following program should compile:

```
int main()
{
    Fraction f1;
    std::cout << "Enter fraction 1: ";
    std::cin >> f1;

Fraction f2;
    std::cout << "Enter fraction 2: ";
    std::cin >> f2;

std::cin >> f2;

std::cout << f1 << " * " << f2 << " is " << f1 * f2 << '\n'; // note: The result of f1 * f2 is an r-value

return 0;
}</pre>
```

## And produce the result:


```
Enter fraction 1: 2/3
Enter fraction 2: 3/8
2/3 * 3/8 is 1/4
```

#### Here's the Fraction class:

```
#include <iostream>
    #include <numeric> // for std::gcd
3
    class Fraction
4
5
    private:
     int m_numerator{};
    int m_denominator{};
8
9
    public:
10
     Fraction(int numerator=0, int denominator=1):
      m_numerator{numerator}, m_denominator{denominator}
11
12
      // We put reduce() in the constructor to ensure any new fractions we make get
    reduced!
13
      // Any fractions that are overwritten will need to be re-reduced
14
      reduce();
     }
     void reduce()
15
      int gcd{ std::gcd(m_numerator, m_denominator) };
16
17
       m_numerator /= gcd;
       m_denominator /= gcd;
18
19
      }
20
21
     friend Fraction operator*(const Fraction& f1, const Fraction& f2);
     friend Fraction operator*(const Fraction& f1, int value);
     friend Fraction operator*(int value, const Fraction& f1);
22
23
24
     void print() const
25
      std::cout << m_numerator << '/' << m_denominator << '\n';
26
27
28
    };
29
    Fraction operator*(const Fraction& f1, const Fraction& f2)
30
     return Fraction(f1.m_numerator * f2.m_numerator, f1.m_denominator *
    f2.m_denominator);
31
    Fraction operator*(const Fraction& f1, int value)
32
     return Fraction(f1.m_numerator * value, f1.m_denominator);
33
    Fraction operator*(int value, const Fraction& f1)
     return Fraction(f1.m_numerator * value, f1.m_denominator);
```

If you're on a pre-C++17 compiler, you can replace std::gcd with this function:

**Show Solution** 





**298 COMMENTS** 



Leave a comment... (use [code]your code here[/code] for syntax highlighting)

Name\*

Parall\*

Avatars from https://gravatar.com/ are connected to your provided email address.

Newest -

©2021 Learn C++



