Test of problems from SuiteSparse Matrix Collection

This package provides implementations of comparing BICGSTAB, GMRES, DQGMRES, FOM, DIOM, SCG, SWI, RGMRES, RFOM, RSCG, and DSWI for solving the linear system

$$Ax = b$$
,

where the matrix A from the SuiteSparse Matrix Collection and set b so that the solution is $x_{\star} = (1, 1, \dots, 1)$.

Contents

- BICGSTAB
- REGMRES
- DQGMRES
- REFOM
- DIOM(m)
- RESCG
- SWI(*m*)
- DYNSWIWP
- Test

BICGSTAB

Using Matlabs function "bicgstab" directly.

REGMRES

REGMRES (Restarted GMRES): Algorithm 6.11 in Yousef Saad's "Iterative Methods for Sparse Linear System (2nd Edition)"

function [x, k, res, resvec] = regmres(A, b, restart, tol, x0, maxit)

- \bullet [x] = regmres(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- \bullet [x] = regmres(A, b, restart) specifies the restarted number. If restart is [] then resgmres uses the default, n
- [x] = regmres(A, b, restart, tol) specifies the tolerance of the method. If tol is [] then resgmres uses the default, 1e-6.
- \bullet [x] = regmres(A, b, restart, tol, x0) specifies the initial guess. If x0 is [] then resgmres uses the default, an all zero vector.
- \bullet [x] = regmres(A, b, restart, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then regmres uses the default, 10000.

- [x, k] = regmres(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$.
- [x, k, res] = regmres(A, b, ...) also returns the last relative residual norm ||b Ax|| / ||b||.
- [x, k, res, resvec] = regmres(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

GMRES: set restart= n in the function "regmres".

DQGMRES

DQGMRES (Direct Quasi-GMRES): Algorithms 6.6 and 6.13 in Yousef Saad's "Iterative Methods for Sparse Linear System (2nd Edition)"

```
function [x, k, res, resvec] = dqgmres(A, b, m, tol, x0, maxit)
```

- [x] = dqgmres(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- \bullet [x] = dqgmres(A, b, m) specifies the number of the sliding window. If m is [] then dqgmres uses the default, n.
- \bullet [x] = dqgmres(A, b, m, tol) specifies the tolerance of the method. If tol is [] then dqgmres uses the default, 1e-6.
- \bullet [x] = dqgmres(A, b, m, tol, x0) specifies the initial guess. If x0 is [] then dqgmres uses the default, an all zero vector.
- \bullet [x] = dqgmres(A, b, m, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then dqgmres uses the default, 10000.
- [x, k] = dqgmres(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$.
- [x, k, res] = dqgmres(A, b, ...) also returns the last relative residual norm ||b Ax|| / ||b||.
- [x, k, res, resvec] = dqgmres(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

REFOM

REFOM (Restarted FOM): Algorithm 6.5 in Yousef Saad's "Iterative Methods for Sparse Linear System (2nd Edition)"

```
function [x, k, res, resvec] = refom(A, b, restart, tol, x0, maxit)
```

• [x] = refom(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.

- \bullet [x] = refom (A, b, restart) specifies the restarted number. If restart is [] then refom uses the default, n
- \bullet [x] = refom(A, b, restart, tol) specifies the tolerance of the method. If tol is [] then refom uses the default, 1e-6.
- \bullet [x] = refom(A, b, restart, tol, x0) specifies the initial guess. If x0 is [] then refom uses the default, an all zero vector.
- \bullet [x] = refom(A, b, restart, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then refom uses the default, 10000.
- [x, k] = refom(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$.
- [x, k, res] = refom(A, b, ...) also returns the last relative residual norm ||b Ax|| / ||b||.
- [x, k, res, resvec] = refom(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

FOM: set restart=n in the function "refom".

DIOM(m)

DIOM (Direct Incomplete Orthogonalization Method): Algorithms 6.6 and 6.8 in Yousef Saad's "Iterative Methods for Sparse Linear System (2nd Edition)"

function [x, k, res, resvec] = diom(A, b, mk, tol, x0, maxit)

- [x] = diom(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- $\bullet \left[x\right]=\operatorname{diom}(A,\,b,\,m)$ specifies the number of the sliding window. If m is [] then diom uses the default, n.
- \bullet [x] = diom(A, b, m, tol) specifies the tolerance of the method. If tol is [] then diom uses the default, 1e-6.
- \bullet [x] = diom(A, b, m, tol, x0) specifies the initial guess. If x0 is [] then diom uses the default, an all zero vector.
- \bullet [x] = diom(A, b, m, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then diom uses the default, 10000.
- [x, k] = diom(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le maxit$.
- [x, k, res] = diom(A, b, ...) also returns the last relative residual norm ||b Ax|| / ||b||.
- [x, k, res, resvec] = diom(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

RESCG

RESCG (Restarted SCG): Restarted semi-conjugate gradient method

function [x, k, res, resvec] = rescg(A, b, restart, tol, x0, maxit)

- [x] = rescg(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- \bullet [x] = rescg(A, b, restart) specifies the restarted number. If restart is [] then rescg uses the default, n
- \bullet [x] = rescg(A, b, restart, tol) specifies the tolerance of the method. If tol is [] then rescg uses the default, 1e-6.
- \bullet [x] = rescg(A, b, restart, tol, x0) specifies the initial guess. If x0 is [] then rescg uses the default, an all zero vector.
- \bullet [x] = rescg(A, b, restart, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then rescg uses the default, 10000.
- [x, k] = rescg(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$.
- [x, k, res] = rescg(A, b, ...) also returns the last relative residual norm ||b Ax||/||b||.
- [x, k, res, resvec] = $\operatorname{rescg}(A, b, ...)$ also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

SCG: set restart=n in the function "rescg".

SWI(m)

SWI: Sliding window implementation with pre-allocated memory

```
[x, k, res, resvec] = swi(A, b, m, tol, x0, maxit)
```

- [x] = swi(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- \bullet [x] = swi(A, b, m) specifies the number of the sliding window. If m is [] then swi uses the default, n.
- \bullet [x] = swi(A, b, m, tol) specifies the tolerance of the method. If tol is [] then swi uses the default, 1e-6.
- \bullet [x] = swi(A, b, m, tol, x0) specifies the initial guess. If x0 is [] then swi uses the default, an all zero vector.
- \bullet [x] = swi(A, b, m, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then swi uses the default, 10000.
- [x, k] = swi(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$
- [x, k, res] = swi(A, b, ...) also returns the last relative residual norm ||b Ax||/||b||.
- [x, k, res, resvec] = swi(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

DYNSWIWP

DYNSWIWP: Sliding window implementation with choosing m dynamically

The approach to choose m dynamically is as follows:

$$m = \begin{cases} \max\{[0.8m], 2\}, & \text{if } ||r_k|| < 0.9 ||r_{k-1}||; \\ \min\{2m, n\}, & \text{if } ||r_k|| > 2 ||r_{k-1}||; \\ m, & \text{otherwise.} \end{cases}$$

[x, k, res, resvec] = dynswiwp(A, b, m, tol, x0, maxit)

- [x] = dynswiwp(A, b) attempts to find a solution x to the system of linear equations Ax = b. The n-by-n coefficient matrix A must be positive definite but need not be symmetric. The right hand side column vector b must have length n.
- \bullet [x] = dynswiwp(A, b, m) specifies the number of the sliding window. If m is [] then dynswiwp uses the default, n.
- \bullet [x] = dynswiwp(A, b, m, tol) specifies the tolerance of the method. If tol is [] then dynswiwp uses the default, 1e-6.
- \bullet [x] = dynswiwp(A, b, m, tol, x0) specifies the initial guess. If x0 is [] then dynswiwp uses the default, an all zero vector.
- \bullet [x] = dynswiwp(A, b, m, tol, x0, maxit) specifies the maximum number of iterations. If maxit is [] then dynswiwp uses the default, 10000.
- [x, k] = dynswiwp(A, b, ...) returns the iteration number at which x was computed: $1 \le k \le \text{maxit}$
- [x, k, res] = dynswiwp(A, b, ...) also returns the last relative residual norm ||b Ax|| / ||b||.
- [x, k, res, resvec] = dynswiwp(A, b, ...) also returns a vector of estimates of the residual norms at each iteration, including ||b Ax||.

Test

- 1. Download the files: diom.m, dqgmres.m, swi.m, swiwp.m, cage12.mat, test_suitesparse.m, and testproblem.txt;
- 2. Run the function "test_suite sparse" directly, i.e., $\ \,$
 - >> test_suitesparse
- 3. The test results are saved in "TestResult" file.