Displaying page layout variables

Kent McPherson a.o.*

2000/09/25

1 Introduction

This LaTeX 2ε package is a reimplementation of `layout.sty` by Kent McPherson. It defines the command `\layout` which produces an overview of the layout of the current document. The command `\layout*` recomputes the values it uses to produce the overview.

The figure on the next page shows the output of the `\layout` command for this document.

2 The implementation

This package prints a figure to illustrate the layout that is implemented by the document class. In the figure several words appear. They are stored in control sequences to be able to select a different language.

```
1 ⟨*package⟩
2 \DeclareOption{dutch}{%
3   \def\Headertext{Kopregel}
4   \def\Bodytext{Broodtekst}
5   \def\Footertext{Voetregel}
6   \def\MarginNotestext{Marge\\Notities}
7   \def\oneinchtext{een inch}
8   \def\notshown{niet getoond}
9   }
10 \DeclareOption{german}{%
11   \def\Headertext{Kopfzeile}
12   \def\Bodytext{Haupttext}
13   \def\Footertext{Fu{\ss}zeile}
14   \def\MarginNotestext{Rand-\\ notizen}
15   \def\oneinchtext{ein Zoll}
16   \def\notshown{ohne Abbildung}
17   }
18 \DeclareOption{ngerman}{\ExecuteOptions{german}}
```

*Converted for LaTeX 2ε by Johannes Braams and modified by Hideo Umeki



1	one inch + \hoffset	2	one inch + \voffset
3	\oddsidemargin = 82pt	4	\topmargin = 16pt
5	\headheight = 12pt	6	\headsep = 25pt
7	\textheight = 550pt	8	\textwidth = 355pt
9	\marginparsep = 11pt	10	\marginparwidth = 126pt
11	\footskip = 30pt		\marginparpush = 0pt (not shown)
	\hoffset = 0pt		\voffset = 0pt
	\paperwidth = 614pt		\paperheight = 794pt

```
\DeclareOption{english}{%
  \def\Headertext{Header}
  \def\Bodytext{Body}
  \def\Footertext{Footer}
  \def\MarginNotestext{Margin\\Notes}
  \def\oneinchtext{one inch}
  \def\notshown{not shown}
  }
\DeclareOption{french}{%
  \def\Headertext{Ent\^{e}te}
  \def\Bodytext{Corps}
  \def\Footertext{Pied de page}
  \def\MarginNotestext{Marge\\Notes}
  \def\oneinchtext{un pouce}
  \def\notshown{non affich\'{e}}
  }
\DeclareOption{francais}{\ExecuteOptions{french}}
\DeclareOption{spanish}{%
  \def\Headertext{Encabezamiento}
  \def\Bodytext{Cuerpo}
  \def\Footertext{Pie de p\'agina}
  \def\MarginNotestext{Notas\\ Marginales}
  \def\oneinchtext{una pulgada}
  \def\notshown{no mostradas}
  }
\DeclareOption{portuguese}{%
  \def\Headertext{Cabe\c{c}alho}
  \def\Bodytext{Corpo}
  \def\Footertext{Rodap\'e}
  \def\MarginNotestext{Notas\\ Marginais}
  \def\oneinchtext{uma polegada}
  \def\notshown{n\~ao mostradas}
  }
\DeclareOption{brazilian}{%
  \def\Headertext{Cabe\c{c}alho}
  \def\Bodytext{Corpo}
  \def\Footertext{Rodap\'e}
  \def\MarginNotestext{Notas\\ Marginais}
  \def\oneinchtext{uma polegada}
  \def\notshown{n\~ao mostradas}
  }
\DeclareOption{italian}{%
  \def\Headertext{Testatina}
  \def\Bodytext{Corpo}
  \def\Footertext{Piedino}
  \def\MarginNotestext{Note\\ Marginali}
  \def\oneinchtext{un pollice}
  \def\notshown{non mostrato}
  }
```

This package has an option verbose. Using it will make the command `\layout` type some of the parameters on the terminal.

```
\DeclareOption{verbose}{\let\LayOuttype\typeout}
\DeclareOption{silent}{\let\LayOuttype\@gobble}
```

The normal behaviour of this package when showing the values of the parameters is to truncate them. However, if you want to see the real parameter values you can use the option reals to get that effect.

```
\def\lay@value{}
\DeclareOption{integers}{%
  \renewcommand*{\lay@value}[2]{%
    \expandafter\number\csname #1@#2\endcsname pt}}
\DeclareOption{reals}{%
  \renewcommand*{\lay@value}[2]{\the\csname #2\endcsname}}
```

The default language is English, the default mode is silent and the default way of showing parameter values is to use integers.

```
\ExecuteOptions{english,silent,integers}
\ProcessOptions
```

`\LayOutbs` Define `\LayOutbs` to produce a backslash. We use a definition which also works with OT1 fonts.

```
\newcommand\LayOutbs{}
\chardef\LayOutbs`\\
```

`\ConvertToCount` This macro stores the value of a *length* register in a *count* register.

```
\def\ConvertToCount#1#2{%
```

First copy the value

```
  #1=#2
```

Then divide it by 65536.

```
  \divide #1 by 65536}
```

The result of this is that the *count* register holds the value of the *length* register in points.

`\SetToHalf` `\SetToQuart` Small macros used in computing positions.

```
\def\SetToHalf#1#2{#1=#2\relax\divide#1by\tw@}
\def\SetToQuart#1#2{#1=#2\relax\divide#1by4}
```

`\Identify` A small macro used in identifying dimensions.

```
\def\Identify#1{%
  \put(\PositionX,\PositionY){\circle{20}}
  \put(\PositionX,\PositionY){\makebox(0,0){\tiny #1}}
}
```

`\InsideHArrow` This macro is used to produce two horizontal arrows inside a box. The argument gives the width of the box.

```
\def\InsideHArrow#1{{%
```

```
  \ArrowLength = #1
  \divide\ArrowLength by \tw@
  \advance\ArrowLength by -10
  \advance\PositionX by -10
  \ifnum\ArrowLength<\z@
    \put(\PositionX,\PositionY){\vector(1,0){-\ArrowLength}}
    \advance\PositionX by 20
    \put(\PositionX,\PositionY){\vector(-1,0){-\ArrowLength}}
  \else
    \put(\PositionX,\PositionY){\vector(-1,0){\ArrowLength}}
    \advance\PositionX by 20
    \put(\PositionX,\PositionY){\vector(+1,0){\ArrowLength}}
  \fi
}}
```

`\InsideVArrow` This macro is used to produce two vertical arrows inside a box. The argument gives the height of the box.

```
\def\InsideVArrow#1{{%
  \ArrowLength = #1
  \divide\ArrowLength by \tw@
  \advance\ArrowLength by -10
  \advance\PositionY by -10
  \put(\PositionX,\PositionY){\vector(0,-1){\ArrowLength}}
  \advance\PositionY by 20
  \put(\PositionX,\PositionY){\vector(0,+1){\ArrowLength}}
}}
```

`\OutsideHArrow` This macro is used to produce two horizontal arrows to delimit a length. The first argument is the position for the right arrow, the second argument gives the length and the third specifies the length of the arrows.

```
\def\OutsideHArrow#1#2#3{{%
  \PositionX = #1
  \advance\PositionX by #3
  \put(\PositionX,\PositionY){\vector(-1,0){#3}}
  \PositionX = #1 \advance\PositionX-#2
  \advance\PositionX by -#3
  \put(\PositionX,\PositionY){\vector(+1,0){#3}}
}}
```

`\OutsideVArrow` This macro is used to produce two vertical arrows to delimit a length. The first argument is the position for the lower arrow, the second argument gives the length and the third and fourth specify the lenghts of the lower and upper arrow.

```
\def\OutsideVArrow#1#2#3#4{{%
  \PositionY = #1
  \advance\PositionY by -#3
  \put(\PositionX,\PositionY){\vector(0,+1){#3}}
  \PositionY = #1
  \advance\PositionY#2
  \advance\PositionY#4
```

```
  \put(\PositionX,\PositionY){\vector(0,-1){#4}}
}}
```

`\Show` Macro used in the table that shows the setting of the parameters.

```
\def\Show#1#2{\LayOutbs #2 = \lay@value{#1}{#2}}
```

`\Type` Macro used to show a setting of a parameter on the terminal.

```
\def\Type#1#2{%
  \LayOuttype{#2 = \lay@value{#1}{#2}}}
```

`\oneinch` A constant, giving the length of an inch in points (approximately)

```
\newcount\oneinch
\oneinch=72
```

Because the overview of the layout is produced in a figure environment we need to allocate a number of counters that are used to store the values of various dimensions.

`\cnt@paperwidth` `\cnt@paperheight` The dimensions of the paper

```
\newcount\cnt@paperwidth
\newcount\cnt@paperheight
\ConvertToCount\cnt@paperwidth\paperwidth
\ConvertToCount\cnt@paperheight\paperheight
```

`\cnt@hoffset` `\cnt@voffset` the offsets,

```
\newcount\cnt@hoffset
\newcount\cnt@voffset
\ConvertToCount\cnt@hoffset\hoffset
\ConvertToCount\cnt@voffset\voffset
```

`\cnt@textheight` `\cnt@textwidth` dimensions of the text area,

```
\newcount\cnt@textheight
\newcount\cnt@textwidth
```

`\cnt@topmargin` `\cnt@oddsidemargin` `\cnt@evensidemargin` margins,

```
\newcount\cnt@topmargin
\newcount\cnt@oddsidemargin
\newcount\cnt@evensidemargin
```

`\cnt@headheight` `\cnt@headsep` dimensions of the running heads,

```
\newcount\cnt@headheight
\newcount\cnt@headsep
```

`\cnt@marginparsep` `\cnt@marginparwidth` `\cnt@marginparpush` marginal paragraphs,

```
\newcount\cnt@marginparsep
\newcount\cnt@marginparwidth
\newcount\cnt@marginparpush
```

`\cnt@footskip` the distance between the running footers and the text,

```
153 \newcount\cnt@footskip
```

and the height of the footers, which is needed here to display a box, but which isn't used by LaTeX.

`\fheight`

```
154 \newcount\fheight
155 \fheight=12
```

Apart from integer representations of the page layout parameters we also need registers to store reference values in.

`\ref@top` The position of the top of the 'printable area' is one inch below the top of the paper by default. The value of `\ref@top` is relative to the lower left corner of the picture environment that will be used.

```
156 \newcount\ref@top
157 \ref@top=\cnt@paperheight \advance\ref@top by -\oneinch
```

`\ref@hoffset` For the offsets,
`\ref@voffset`

```
158 \newcount\ref@hoffset
159 \newcount\ref@voffset
```

The `\hoffset` and `\voffset` values are added to the default offset of one inch.

```
160 \ref@hoffset=\cnt@hoffset  \advance\cnt@hoffset by \oneinch
161 \ref@voffset=\cnt@voffset
```

`\cnt@voffset` is converted to be relative to the origin of the picture.

```
162 \cnt@voffset=\ref@top
163 \advance\cnt@voffset by -\ref@voffset
```

`\ref@head` and the text areas, running heads,

```
164 \newcount\ref@head
```

`\ref@body` body of the text

```
165 \newcount\ref@body
```

`\ref@foot` and running footers.

```
166 \newcount\ref@foot
```

`\ref@margin` These are different for even and odd pages, so they are computed by `\layout`.
`\ref@marginwidth`
`\ref@marginpar`

```
167 \newcount\ref@margin
168 \newcount\ref@marginwidth
169 \newcount\ref@marginpar
```

The following are a number of scratch registers, used in the positioning of the various pices of the picture.

```
170 \newcount\Interval
171 \newcount\ExtraYPos
172 \newcount\PositionX
173 \newcount\PositionY
174 \newcount\ArrowLength
```

`\lay@getvalues` All values that might change during the document are computed by calling the macro `\lay@getvalues`. By default this macro is executed at `\begin{document}`.

```
\def\lay@getvalues{%
  \ConvertToCount\cnt@textheight\textheight
  \ConvertToCount\cnt@textwidth\textwidth
  \ConvertToCount\cnt@topmargin\topmargin
  \ConvertToCount\cnt@oddsidemargin\oddsidemargin
  \ConvertToCount\cnt@evensidemargin\evensidemargin
  \ConvertToCount\cnt@headheight\headheight
  \ConvertToCount\cnt@headsep\headsep
  \ConvertToCount\cnt@marginparsep\marginparsep
  \ConvertToCount\cnt@marginparwidth\marginparwidth
  \ConvertToCount\cnt@marginparpush\marginparpush
  \ConvertToCount\cnt@footskip\footskip
  \ref@head=\ref@top
    \advance\ref@head by -\ref@voffset
    \advance\ref@head by -\cnt@topmargin
    \advance\ref@head by -\cnt@headheight
  \ref@body=\ref@head
    \advance\ref@body by -\cnt@headsep
    \advance\ref@body by -\cnt@textheight
  \ref@foot=\ref@body
    \advance\ref@foot by -\cnt@footskip
  }
\AtBeginDocument{\lay@getvalues}
```

`\computevalues` `\layout` `\layout*` The command `\layout` makes the picture and table that display the current settings of the layout parameters.

```
\newcommand\layout{%
  \@ifstar{\lay@getvalues\lay@xlayout}{\lay@xlayout}}
\def\lay@xlayout{%
  \lay@layout
  \if@twoside
    \lay@layout
  \fi}
```

`\lay@layout` The internal macro `\lay@layout` does all the dirty work.

```
\newcommand\lay@layout{%
  \thispagestyle{empty}
```

The actions of `\layout` depend on the pagestyle.

```
  \if@twoside
    \ifodd\count\z@
```

Here we deal with an odd page in the twosided case.

```
      \typeout{Two-sided document style, odd page.}
```

So we compute `\ref@marginwidth`, `\ref@marginpar` and `\ref@margin`.

```
      \ref@marginwidth=\cnt@oddsidemargin
      \ref@marginpar=\oneinch
```

```
212       \advance\ref@marginpar by \ref@hoffset
213       \advance\ref@marginpar by \cnt@oddsidemargin
214       \ref@margin\ref@marginpar
215       \if@reversemargin
216         \advance\ref@marginpar by -\cnt@marginparsep
217         \advance\ref@marginpar by -\cnt@marginparwidth
218       \else
219         \advance\ref@marginpar by \cnt@textwidth
220         \advance\ref@marginpar by \cnt@marginparsep
221       \fi
222     \else
```

Here we deal with an even page in the twosided case.

```
223   \typeout{Two-sided document style, even page.}
```

So we compute `\ref@marginwidth`, `\ref@marginpar` and `\ref@margin`.

```
224       \ref@marginwidth=\cnt@evensidemargin
225       \ref@marginpar=\oneinch
226       \advance\ref@marginpar by \ref@hoffset
227       \advance\ref@marginpar by \cnt@evensidemargin
228       \ref@margin\ref@marginpar
229       \if@reversemargin
230         \advance\ref@marginpar by \cnt@textwidth
231         \advance\ref@marginpar by \cnt@marginparsep
232       \else
233         \advance\ref@marginpar by -\cnt@marginparsep
234         \advance\ref@marginpar by -\cnt@marginparwidth
235       \fi
236     \fi
237   \else
```

Finally we the case for single sided printing.

```
238     \typeout{One-sided document style.}
239     \ref@marginwidth=\cnt@oddsidemargin
240     \ref@marginpar=\oneinch
241     \advance\ref@marginpar by \ref@hoffset
242     \advance\ref@marginpar by \cnt@oddsidemargin
243     \ref@margin\ref@marginpar
244     \if@reversemargin
245       \advance\ref@marginpar by -\cnt@marginparsep
246       \advance\ref@marginpar by -\cnt@marginparwidth
247     \else
248       \advance\ref@marginpar by \cnt@textwidth
249       \advance\ref@marginpar by \cnt@marginparsep
250     \fi
251   \fi
```

Now we begin the picture environment; dividing all the lengths by two is done by setting `\unitlength` to `0.5pt`

```
\setlength{\unitlength}{.5pt}
\begin{picture}(\cnt@paperwidth,\cnt@paperheight)
  \centering
  \thicklines
```

First we have the pagebox and reference lines,

```
  \put(0,0){\framebox(\cnt@paperwidth,\cnt@paperheight){\mbox{}}}
  \put(0,\cnt@voffset){\dashbox{10}(\cnt@paperwidth,0){\mbox{}}}
  \put(\cnt@hoffset,0){\dashbox{10}(0,\cnt@paperheight){\mbox{}}}
```

then the header,

```
  \put(\ref@margin,\ref@head){%
    \framebox(\cnt@textwidth,\cnt@headheight)%
      {\footnotesize\Headertext}}
```

the body of the text area,

```
  \put(\ref@margin,\ref@body){%
    \framebox(\cnt@textwidth,\cnt@textheight){\Bodytext}}
```

the footer

```
  \put(\ref@margin,\ref@foot){%
    \framebox(\cnt@textwidth,\fheight){\footnotesize\Footertext}}
```

and the space for marginal notes.

```
  \put(\ref@marginpar,\ref@body){%
    \framebox(\cnt@marginparwidth,\cnt@textheight)%
             {\footnotesize\shortstack{\MarginNotestext}}}
```

Then we start putting in 'arrows' to mark the various parameters. From here we use `\thinlines`.

```
  \thinlines
```

`\PositionX` and `\PositionY` will be the coordinates of the center of the arrow displaying `\textwidth`.

```
  \SetToHalf\PositionX\cnt@textwidth
  \advance\PositionX by \ref@margin
```

The arrow should be a bit above the bottom of the 'body box'.

```
  \PositionY = \ref@body
  \advance\PositionY by 50
```

An identifying number is put here, in a circle.

```
  \Identify{8}
```

Then the arrow is drawn.

```
  \InsideHArrow\cnt@textwidth
```

Now the `\textheight`

```
  \SetToHalf\PositionY\cnt@textheight
  \advance\PositionY by \ref@body
```

The x-psition of the arrow is at 4/5 of the width of the 'body box'.

```
\PositionX = \cnt@textwidth
\divide\PositionX by 5
\multiply \PositionX by 4
\advance\PositionX by \ref@margin
```

An identifying number is put here, in a circle.

```
\Identify{7}
\InsideVArrow\cnt@textheight
```

The `\hoffset`,

```
\PositionY = 50
\SetToHalf\PositionX\cnt@hoffset
\Identify{1}
\InsideHArrow\cnt@hoffset
```

The width of the margin.

```
\SetToQuart\PositionY\cnt@textheight
\advance\PositionY by \ref@body
\ifnum\ref@marginwidth > 0
  \OutsideHArrow\ref@margin\ref@marginwidth{20}
  \PositionX = \cnt@hoffset
\else
  \OutsideHArrow\cnt@hoffset{-\ref@marginwidth}{20}
  \PositionX = \ref@margin
\fi
\advance\PositionX by -30
\Identify{3}
```

the `\marginparwidth`,

```
\SetToQuart\PositionY\cnt@textheight
\advance\PositionY by \ref@body
```

This arrow has to be bit below the one for the `\oddsidemargin` or `\evensidemargin`.

```
\advance\PositionY by 30
\SetToHalf\PositionX\cnt@marginparwidth
\advance\PositionX by \ref@marginpar
\Identify{10}
\InsideHArrow\cnt@marginparwidth
```

The `\marginparsep`, this depends on single or double sided printing.

```
\advance\PositionY by 30
\if@twoside
```

Twosided mode, reversemargin;

```
  \if@reversemargin
    \ifodd\count\z@
      \OutsideHArrow\ref@margin\cnt@marginparsep{20}
      \PositionX = \ref@margin
    \else
      \OutsideHArrow\ref@marginpar\cnt@marginparsep{20}
```

```
          \PositionX = \ref@marginpar
        \fi
      \else
```

Not reversemargin;

```
        \ifodd\count\z@
          \OutsideHArrow\ref@marginpar\cnt@marginparsep{20}
          \PositionX = \ref@marginpar
        \else
          \OutsideHArrow\ref@margin\cnt@marginparsep{20}
          \PositionX = \ref@margin
        \fi
      \fi
    \else
```

Single sided mode.

```
      \if@reversemargin
        \OutsideHArrow\ref@margin\cnt@marginparsep{20}
        \PositionX = \ref@margin
      \else
        \OutsideHArrow\ref@marginpar\cnt@marginparsep{20}
        \PositionX = \ref@marginpar
      \fi
    \fi
    \advance\PositionX by -\cnt@marginparsep
    \advance\PositionX by -30
    \Identify{9}
```

Identify the `\footskip`. The arrow will be located on 1/8th of the `\textwidth`.

```
    \PositionX = \cnt@textwidth
    \divide\PositionX by 8
    \advance\PositionX by \ref@margin
    \OutsideVArrow\ref@foot\cnt@footskip{20}{20}
    \PositionY = \ref@foot
    \advance\PositionY by \cnt@footskip
    \advance\PositionY by 30
    \Identify{11}
```

Identify the `\voffset`. The arrow will be located a bit to the left of the edge of the paper.

```
    \PositionX = \cnt@paperwidth
    \advance\PositionX by -50
    \PositionY = \cnt@paperheight
    \ExtraYPos = \PositionY
    \advance\ExtraYPos by -\cnt@voffset
    \advance\PositionY by \cnt@voffset
    \divide\PositionY by \tw@
    \Identify{2}
    \InsideVArrow\ExtraYPos
```

Identify `\topmargin`, `\headheight` and `\headsep`.

The arrows will be located on 1/8th of the `\textwidth`, with intervals of the same size, stored in `\Interval`.

```
    \Interval = \cnt@textwidth
    \divide\Interval by 8
    \PositionX = \ref@margin
    \advance\PositionX by \Interval
```

First the `\topmargin`. If `\topmargin` has a positive value, the arrow is upward. Otherwise, it is downward. The number label is always placed at the base of the arrow.

```
    \ifnum\cnt@topmargin > \z@
      \ExtraYPos = \ref@head
      \advance\ExtraYPos\cnt@headheight
      \OutsideVArrow\ExtraYPos\cnt@topmargin{20}{20}
      \PositionY = \ExtraYPos
      \advance\PositionY by \cnt@topmargin
    \else
      \ExtraYPos = \cnt@voffset
      \OutsideVArrow\ExtraYPos{-\cnt@topmargin}{20}{20}
      \PositionY = \ExtraYPos
      \advance\PositionY by -\cnt@topmargin
    \fi
    \advance\PositionY by 30
    \Identify{4}
    \advance\PositionX by \Interval
```

Then the `\headheight`

```
    \OutsideVArrow\ref@head\cnt@headheight{20}{20}
    \PositionY = \ref@head
    \advance\PositionY by \cnt@headheight
    \advance\PositionY by 30
    \Identify{5}
    \advance\PositionX by \Interval
```

and finally the `\headsep`

```
    \ExtraYPos=\ref@body
    \advance\ExtraYPos\cnt@textheight
    \OutsideVArrow\ExtraYPos\cnt@headsep{20}{20}
    \PositionY = \ref@body
    \advance\PositionY by \cnt@textheight
    \advance\PositionY by -30
    \Identify{6}
```

Here we can end the picture environment and insert a little space.

```
 \end{picture}

 \medskip
```

Below the picture we put a table to show the actual values of the parameters. Note that fractional points are truncated, i.e., `72.27pt` is displayed as `72pt`

The table is typeset inside a box with a depth of 0 to always keep it on the same page as the picture.

```
\vtop to 0pt{%
  \@minipagerestore\footnotesize\ttfamily
  \begin{tabular}{@{}rl@{\hspace{20pt}}rl}
    1 & \oneinchtext\ + \LayOutbs\texttt{hoffset}
      & 2 & \oneinchtext\ + \LayOutbs\texttt{voffset} \\
    3 & \if@twoside
          \ifodd\count\z@ \Show{cnt}{oddsidemargin}
          \else \Show{cnt}{evensidemargin}
          \fi
        \else
          \Show{cnt}{oddsidemargin}
        \fi                    & 4 & \Show{cnt}{topmargin} \\
    5 & \Show{cnt}{headheight} & 6 & \Show{cnt}{headsep} \\
    7 & \Show{cnt}{textheight} & 8 & \Show{cnt}{textwidth} \\
    9 & \Show{cnt}{marginparsep}&10& \Show{cnt}{marginparwidth} \\
    11& \Show{cnt}{footskip}   &   & \Show{cnt}{marginparpush}
     \rlap{(\notshown)}\\
      & \Show{ref}{hoffset}    &   & \Show{ref}{voffset} \\
      & \Show{cnt}{paperwidth} &   & \Show{cnt}{paperheight} \\

  \end{tabular}\vss}
```

When the option verbose was used the following lines will show dimensions on the terminal.

```
\Type{ref}{hoffset}
\Type{ref}{voffset}
\Type{cnt}{textheight}
\Type{cnt}{textwidth}
```

Finally we start a new page.

```
  \newpage
}
```

⟨/package⟩