Layered architecture

- · Example: sending of minutes from a meeting
 - layer Recorder
 - writes minutes
 - · rules: minutes outline
 - request to Secretary: send a letter [minutes;person list]
 - layer Secretary
 - · adds a header, footer, inserts into envelopes, write addresses
 - · rules: commercial letter form
 - request to Registry: send [letter;addresses]
 - layer Registry
 - stamps envelopes, places into a packet, send to a post office
 - rules: mail rules
- Benefits:
 - simpler decomposition and description of the entire process
 - easy technology change (mail/e-mail, post/messenger)
 - inter-layer co-operation (only Registry goes to the post)

Introduction to Networking (2020)

SISAL

20

We will use a layered approach to describe network communication. We will try to show the advantages of this approach using a real-life example.

A company holds regular meetings. The minutes of each meeting are recorded and sent to all participants.

Using a non-layered approach, we must describe the process to a new employee as an entire complex task, starting from recording, formatting, and packing into envelopes up to carrying them to a post office.

Another principle is to split the task to three layers:

The **Recorder** layer is represented by a person writing the minutes. He or she must follow the company's rules about how the minutes must look like – this can be considered to be a protocol. This person's work finishes at the moment when the minutes are ready and are handed over to another layer, the Secretary layer.

The **Secretary** layer does not care where minutes come from. They are handed over to this layer with instructions to prepare their sending to a list of meeting participants – this can be considered as an inter-layer interface [data=minutes; control data=person list]. A person at this layer takes the minutes, formats them into a business letter (a header with a properly placed address, date, and footer), inserts letters into envelopes and writes addresses on them. The envelopes are then passed to the Registry layer. In principle, the secretary does not need to know which kind of delivery will be used.

The **Registry** layer takes over the envelopes and chooses a delivery method according to the company's current strategy. If the company uses classic mail, the envelopes will be stamped, bundled into a packet and carried to a post office.

What are the benefits of this workflow?

 The whole process is decomposed into simple tasks that can be easily described to new employees.

- Simple tasks can be easily replaced by another solution if the company decides to stop using mail and to start using a parcel service, no other layer but the Registry needs to know about this change.
- Resources are saved thanks to layer co-operation it is not necessary that all secretaries go to the post office.

We get exactly the same benefits – ease of description, layer co-operation and substitution - with this approach for computer networks.

Network model, network architecture


- Network (reference) model:
 - number of layers and their structure
 - distribution of tasks among layers
 - e.g.: OSI model (ISO)
- Network (protocol) architecture (suite):
 - network model
 - communication technologies
 - services and protocols
 - e.g.: TCP/IP

Introduction to Networking (2020)

When talking about a network communication structure, we distinguish two terms:

A **network model** describes the number of layers, their structure and describes the tasks of the layers. An example of such a model is the Open Systems Interconnection (OSI) model made by the International Organization for Standardization (ISO).

If we take a model and add concrete services, technologies, inter-node protocols, inter-layer interfaces etc. we get a **network architecture**. An example of it is the TCP/IP protocol suite.



The Open Systems Interconnection model was introduced in 1978 by the International Organization for Standardization. It is a network architecture consisting of the Basic Reference Model and a set of protocols. While the model has been designed very well and is used for network suites documentation and teaching until now, the architecture as a whole has been significantly less successful. It was designed from the top, i.e. the decisions were made as in an ideal world, so they were too complex to achieve simple goals and were relatively inflexible, user-unfriendly...

Layer 1, the **physical layer**, is responsible for transmitting and receiving raw bit data between a node and a physical medium. It has no idea about the logic of the transmitted data and deals only with the physical aspects of the transmission.

Layer 2, the **data link layer**, provides data transfer between two directly connected nodes. Its task is to identify the source and destination of the transmission and the range of transmitted data and to detect and possibly correct errors that may occur in the physical layer.

Layer 3, the **network layer**, ensures the transmission of data blocks with variable but limited length (packets) between two nodes, possibly connected in different networks. If the source and destination are in the same network, the network layer only passes the request to the link layer, but if they are on different networks, the network layer is responsible for finding a path and routing the data through intermediate nodes.

Layer 4, the **transport layer**, is responsible for transmitting and receiving data blocks with unlimited length between source and target applications. The layer still does not understand the data, but it is able to recognize its affiliation to a particular communication channel between two applications. Some protocols at this layer provide *segmentation* of blocks that are too large and their reassembly at the target station. Some protocols provide *reliable*

transmission, i.e. they guarantee the successful transmission of the entire block, or else trigger an error condition.

Layer 5, the **session layer**, controls dialogs between applications. In many network models, its work is in fact covered by adjacent layers.

Layer 6, the **presentation layer**, provides means to hide differences between data semantics implementations on different platforms, e.g. integer endianness (an integer value is divided into bytes in different ways on different computers).

Layer 7, the **application layer**, is the closest layer to the end user; applications mediate interactions between the user and the application protocol(s) that implement communications needed to perform tasks requested by the user.

Understanding the OSI model layers is important because when dealing with various issues, we must carefully consider which solution can be used at which layer.

X.400, X.500

- OSI services implementation was based on a set of complex standards, e.g.
 - X.400: Message Handling System (e-mail), some time played the core role in Microsoft Exchange Server; address example: G=Libor; S=Forst; O=Charles University; OU=Faculty of Mathematics and Physics; OU=SISAL;
 - X.500: Directory Access Protocol (directory services like phone book), note: default attribute of a person is a favorite drink
- · Descendants:
 - X.509 Public Key Infrastructure public key management
 - LDAP (Lightweight DAP) database of information about users and service

Introduction to Networking (2020)

OSI standards were marked by the X.*number* schema. As examples, we can look at two of the most important:

- X.400 (Message Handling System) was the OSI implementation of electronic mail. For some time, it formed the core of Microsoft Exchange Server. Interestingly, X.400 used a fairly complex address structure. This complexity was inspired by classic postal addresses they also have numerous components (name, street, number, zip code, city, country) which does not surprise anybody. And such addresses have one major advantage they are unique! In the "computer age", however, nobody wants to write too much and so ambiguous but much shorter internet addresses have won.
- X.500 (Directory Access Protocol) was a directory service, one of the first implementations of something like a phone book, or Yellow Pages. It uses the same person identification structure as X.400. As an illustration of how complex this service can be, the authors decided to include a favorite drink as one of the default attributes of a person!

Although the OSI services have not been widely implemented, some of their ideas have been beneficial and have remained in some modern protocols and data structures:

- Asymmetric cryptography needs an infrastructure for public key management. Each public key must have a completely unique identifier. For that purpose, the structure of addresses designed for OSI e-mail and directory services is ideal.
- The DAP was too complex to be implemented in personal workstations, although its
 principle was good. The solution was to create a simpler version while preserving key
 features. This protocol is called LDAP and currently, it is a common solution for user and
 services information retrieval and management.

• (Grown according to	needs, de	veloped	d gra	adually	
OSI	Layer	Protocol examples				
7		FTP,			NFS	
6	application	HTTP, SMTP	DNS SIP		XDR	
5					RPC	
4	transport	TCP			UDP	IOMB
3	network		IP			ICMP
2	nativari interfere	Ethernet, FDDI, ATM, WiFi, SLIP, PPP,				ARP
1	network interface					

Unlike OSI, the TCP/IP stack was built step by step using smaller building blocks – protocols that solve one compact problem. As we mentioned, we will use the OSI model as a reference model to describe tasks solved by particular layers and protocols of TCP/IP.

OSI layers 1 and 2 are not subject to the TCP/IP stack, they are simply called network interface, and the protocols used here correspond to the type of media used for transmission.

The lowest TCP/IP layer that corresponds to OSI layer 3 is called the **network layer**, just like in OSI, and its function is the same as well. The protocol used at this layer is called the *Internet Protocol* (IP). In fact, there are currently two versions of this protocol (IPv4 and IPv6), but at the moment the differences between them are not important to us.

The next TCP/IP layer, the **transport layer**, also has the same name and function as in the OSI model. Multiple protocols are used at this layer, the most frequent being the *Transmission Control Protocol* (TCP) and the *User Datagram Protocol* (UDP). We will explain the differences between them in the next slide.

The functions of the last three OSI layers are combined in TCP/IP into a single layer, the **application layer**. For most protocols it was easier to define dialog rules and value semantics directly in the application protocol without using special intermediate layers. There are a few exceptions such as the Network File System which uses special protocols XDR (eXternal Data Representation) and RPC (Remote Procedure Call) at layers 5 and 6. Authors of each application protocol can choose which transport layer is the best for the application, so some protocols (e.g. FTP, HTTP, SMTP) use TCP, some (e.g. NFS) use UDP and some (e.g. DNS, SIP) can use either.

There are also several management protocols that represent a kind of link between layers, namely the Address Resolution Protocol and Internet Control Message Protocol, which we will talk about later.

Note that the separate terms TCP and IP refer to specific protocols at the 4^{th} and 3^{rd} layer, while the "TCP/IP" refers to an entire protocol stack (and is therefore somewhat unfair to the neglected UDP protocol).

Connection-oriented/connectionless services

- · Connection-oriented services
 - real-life example: phone call
 - reliable packet delivery guaranteed
 - simpler application logic, lack of communication control
 - in TCP/IP, TCP is used
- · Connectionless services
 - real-life example: mail
 - neither order nor delivery of packets guaranteed (unreliable)
 - control logic must be included in the application
 - in TCP/IP, UDP is used (IP itself is also unreliable)

SISAL —
Introduction to Networking (2020)

- The **Transmission Control Protocol** (TCP) is designed for connection-oriented services. An example of such a service from real life is a telephone call. When you make a call, the telephone operator establishes a connection and you do not need to worry about whether your sentences will be transferred completely and in order. So the application (you) can be very simple and all the responsibility lies in the lower layer. The same principle is used by TCP. It provides reliable packet delivery, so the application only calls a function "send data block to destination" and waits. TCP handles *segmentation* of data to smaller blocks, sending them in packets, acknowledging their successful delivery, retransmitting them in case of failure and finally it returns control to the application, resulting in a success or failure. The TCP software is therefore very complex, but it is easy for applications to use. The disadvantage of this approach is that the application loses control over the process, it cannot react flexibly to the current state of the network; it just calls the function and waits.
- The **User Datagram Protocol** (UDP) is designed for connectionless services. The classic mail service can serve as a real-life example. If you send three letters in three days, you never know whether they will all be delivered and in order. Therefore, the application (you) must pay special attention to confirming the delivery and resending the lost data, or it must be resistant to data loss. This is also the case of UDP. It is very simple and the responsibility for reliable delivery lies in the application. The advantage is that the application can react immediately to the current situation, e.g. when a delivery problem occurs, the application can try another data source, or it can ask the user whether to stop or continue.

Application models

- · Client-server model
 - client knows the fixed server address
 - client connects to the server, or sends requests
 - server usually handles more clients
 - data flow server ⇒ client: download
 - data flow client ⇒ server: upload
 - examples: DNS, WWW, SMTP
- Peer-to-peer (P2P) model
 - partners do not know data resource addresses
 - no clear roles
 - each partner plays the role of both the client and server (=offer data!)
 - Napster, Gnutella, BitTorrent

Introduction to Networking (2020)

SISAL -

26

As we already mentioned, internetworking has enabled a new application model, the **client-server** model. The client knows one or more addresses where a required service can be found, it tries to contact them and, if successful, to exchange data with a server to meet the user's needs. The roles of client and server are well defined (in terms of communication, not necessarily in terms of data flow – a client can upload data to a server, i.e. be a source of data).

The important fact is that the meaning of the terms client and server is related to a concrete application, not to a computer. It is quite common for a computer to be a server for one type of communication while in another one it plays the role of a client. A typical server implementation is to receive incoming requests from several clients in parallel.

However, the client-server model is not the only possible application model. There is also the so-called **peer-to-peer** model. The key feature of this model is that a user application does not need to know the address of the data source (although it often has some starting addresses to speed up the process). The application is able to find other computers on which the application is running and ready to exchange data. At the same time, the application running on our computer responds to all incoming requests from other instances of the application and sends them requested data. So there are no clear roles, such as client and server.

P2P applications have a bad reputation because they are often used to distribute data that the user does not have the right to distribute. The problem is not in the applications themselves, but in the data. If your application downloads data illegally, you have not committed any wrongdoing, but once it starts offering data to others, the law has been violated. The only option is to deny the application to distribute the data, if such a denial is possible.

Hosts addressing HW MAC address (physical) (data link layer) (e.g. Ethernet: 8:0:20:ae:6:1f) - factory given (formerly), programmed (now) does not respect topology · SW IP address (network layer) (e.g.: 194.50.16.71, ::1) assigned according to network topology - given border between net and host part People domain address (application layer) (e.g.: www.mff.cuni.cz) - assigned according to the organization structure - easy to remember or deduce SISAL . Introduction to Networking (2020)


When a client wants to contact a server, it needs an address. Depending on the layer at which the communication takes place, different addresses are used.

At the data link layer, **Media Access Control** (MAC) addresses are used. Since they are quite closely connected to hardware, they are sometimes called "physical" address, even though they have nothing to do with the OSI physical layer! Examples of MAC addresses are **Ethernet** addresses. They are six bytes long and consist of the manufacturer's prefix (3 bytes) and network interface card (NIC) number (3 bytes). The address was originally burned into the NIC and so it was possible to effectively restrict access to network resources by the sender's MAC address. However, current NICs have the MAC address stored in memory and so it can be easily faked. Due to their nature, these addresses cannot be used for internetwork communication since they do not respect any particular network topology.

Therefore, we must use an address type that depends on the network topology. In TCP/IP, **IP addresses** are used. We have already mentioned two versions of the protocol, so we have two address formats. Each computer is assigned an address according to where the computer is connected to the network and the address has two parts – a network address (used for routing across the network) and a computer (host) address (used locally). The boundary between these two parts varies according to the concrete network.

IP addresses are sufficient for the proper functioning of network communication, but they are somewhat user-unfriendly. Therefore, in common practice we use yet another address format, **domain addresses**. Instead of numbers, these addresses use a mnemonic format, domain names, assigned according to the organizational structure. Therefore, it is much easier to remember or to deduce them. The hierarchy is right-to-left: the rightmost name is a so-called *top level domain* (TLD), e.g. a country code, while the leftmost name is usually a host or service name.

The Domain Name System (DNS) is used to convert between domain and IP addresses. The Address Resolution Protocol (ARP) is used to convert between network and MAC addresses.



The Domain Name System is a hierarchy of *zones* that contain information about computers and child zones, and corresponding *name servers* that provide that information to clients using the DNS protocol.

Every computer should have a domain name that matches the address(es) it currently uses; many computers have multiple names, especially if they are running multiple services for multiple domains.

Domain administration

- · Top-level domains (administered by ICANN):
 - technical (arpa)
 - groups by categories (com, org, edu, mil, gov, net) later extended (info, biz, aero, ...)
 - ISO country codes (cz, sk, ...) and some exceptions (uk, eu); countries with interesting names (nu, tv) sell names
 - internationalized codes (.中国 = .xn--fiqs8s, .p中)
 - currently even private TLDs are allowed
- TLD .cz:
 - administered by CZ.NIC (ISP corporation)
 - no structure, circa 3/4 mil. names under .cz
 - no support for localized names (IDN)
- SLDs and lower level domains:
 - administered by owner (ms.[mff.[cuni.cz]])

Introduction to Networking (2020)

The top-level domains (TLDs) are administered by ICANN (the Internet Corporation for Assigned Names and Numbers). The Domain Name System structure was defined in RFC 920 and the conditions for TLDs were originally relatively strict. There was an arpa TLD, marked as "temporary" for old ARPA hosts, but it has been converted to a domain used for technical purposes. The second group of domains were country domains named after the two-letter ISO country codes (with some exceptions such as uk or eu). Then there were five TLDs collecting institutions by category (com for commercial companies, org for non-commercial organizations, edu for education and research institutions, mil for military, gov for government and later also net for networking organizations). This last group was not defined very precisely — only as "multi-organizational domains" — and was not used much. Over time, name conflicts occurred, especially in the com domain. Therefore, some new TLDs were added later (info, biz, aero, ...) but of course that could not solve the problem. Under great pressure, ICANN eventually completely opened up the name space, and nowadays even a private entity can request an individual TLD.

The TLD cz is administered by a corporation of ISPs called CZ.NIC, It has no underlying category structure like in some other countries (U.K., Austria) and there are almost a million names defined as second-level domains (SLD). Although it is currently technically possible to allow localized names, CZ.NIC has not yet allowed it, fortunately.

Second-level domains are administered by their owners who can decide on their structure. At our university, we have decided to maintain the hierarchy and only domains for faculties and university-wide facilities are allowed under the SLD cuni.cz. Similarly, our faculty's domain is administered at the faculty and has a structure according to departments and buildings (so the ms domain name is an abbreviation of "Malá Strana").

IP addresses

- Every end node in TCP/IP network must have an IP address
- · Current versions:
 - IPv4: 4 bytes (e.g. 195.113.19.71)
 - IPv6: 16 bytes (e.g. 2001:718:1e03:a01::1)
- Address block assignment:
 - public addresses for network is assigned by its ISP
 - LAN can use private addresses, unreachable from the internet (security vs. interoperability), address translation (NAT)
- · Host address assignment:
 - method (fixed vs. dynamic, free vs. limited) is defined by LAN administration
 - even for private addresses, exception: link-local addresses

Introduction to Networking (2020)

In order to communicate on a TCP/IP network, each end node must have an IP address. As already mentioned, we currently use two versions of the protocol/address. Version 4 which is still dominant in the Czech Republic, has addresses that are 4 bytes long and the common form of their notation is the so-called *dotted decimal* form. The newer version 6 expanded the address size to 16 bytes and the commonly used format for these addresses is hexadecimal notation in double-byte blocks separated by colons. Due to the large number of zeros in these addresses, the longest series of zero blocks in any address can be replaced by "::" notation.

Every address has a prefix defining a network to which the address belongs. The assignment of these *network addresses*, or address blocks, must meet certain conditions:

- Blocks of addresses that should be able to communicate directly with the rest of the world, so-called **public** addresses, are assigned to the network administrator by an ISP (or other authority) that connects the network to the Internet.
- For internal use, a network administrator may choose to use one or more private address blocks. They are inaccessible from the Internet (which increases security but complicates interoperability) and in order to enable hosts to access resources on the Internet, a router at the perimeter of the local network must use Network Address Translation (NAT).

A method of assigning addresses to hosts must be chosen by the network administrator and all hosts must follow these rules. The assignment can be static (each node has a predefined IP address) or dynamic (an address is assigned on demand), free (any host can join) or restricted (hosts must authenticate to connect). These rules apply even for **private addresses**. The only exception are so-called *link-local* addresses – they are freely chosen by the host software (with a risk of duplicate address collisions) and they allow communication only within a directly connected network (and only if some other hosts also use a link-local address).

Port, socket

Port

- ... 16bit integer identifying one end of the communication channel - an application, or a process responsible for incoming data processing
 - <u>destination-port</u> must be known by clients, usually it is one of so-called *well-known services* (formerly < 1024)

SISAL

 <u>source-port</u> is assigned by the originator's OS from unused port numbers

Socket

- ... one end of the communication channel between the client and the server
- ... identification ("address") of the channel end <IP address, port>

Introduction to Networking (2020)

If we know the address of the host we want to communicate with, we still can't contact a specific service because multiple servers may be running there. We need to somehow identify a service on the target machine. And for the same reason, we must also identify "our end" of the communication channel because when a response comes, it must be clear to which client it should be delivered – for example we must insert an incoming image into the correct web browser window...

A **socket** is one end of a communication channel between a client and a server. A socket is identified by an IP address and a 16-bit integer number called a **port**.

However, clients do not know the situation on the server machine, so they cannot always know which number a particular service has on a server, i.e. which number should be used for the *destination port number*. Therefore, there are so-called **well-known** services and their port numbers. For instance all web servers use port number 80 by default.

Well-known services, however, are not a solution for the *source port number* because we need to identify multiple clients of the same service. The usual solution is that when client software prepares a socket for connecting to a server, it asks the local operating system for an unused "**generic**" port number. The client uses is this number for the entire communication with the server and after the connection is closed, the port is released and is available for other applications.

From a mathematical point of view, the unique identification of a TCP/IP connection is an ordered quintuple < source IP address, source port, destination IP address, destination port, transport protocol type >. This fact has two consequences:


- Two different channels between two computers must differ at least in the source port.
- The same port numbers can be used for two different communication channels as long as they do not use the same transport layer protocol.

Well-known services examples

- 21/TCP: FTP File Transfer Protocol (file transfer)
- 22/TCP: SSH Secure Shell (remote logging and file transfer)
- 25/TCP: SMTP Simple Mail Transfer Protocol (electronic mail transfer)
- 53/*: DNS Domain Name System (conversion between IP addresses and names)
- 80,443/TCP: HTTP HyperText Transfer Protocol (transfer of web pages)
- 5060,5061/*: SIP Session Initiation Protocol (VoIP, IP telephony)

Introduction to Networking (2020)

These port numbers are among the essential knowledge that an educated networking specialist should know, perhaps except for the last pair which only shows that some well-known services nowadays fall outside the range from 1 to 1023... The same port numbers are usually reserved for both the TCP and UDP protocols even if a particular protocol does not use one of these transport protocols. HTTP uses port 80 for unencrypted and port 443 for encrypted connections. SIP uses different ports for different types of messages.



The concept of ports plays a very important role in NAT. Hosts with a private address cannot communicate directly with the world outside the local network because an external host has no idea how to route packets when sending a response.

A common principle of NAT is that when a host establishes a connection to a server, the router at the perimeter of the private network modifies the content of the packet so that the external host can respond. The router stores the socket address (the IP address and port) of the incoming request and replaces it in the packet by its own external address and a randomly selected free port. When sending a response, the external host uses this translated data for the delivery. When the response arrives at the router, it looks for the appropriate original socket address (according to the destination port used by the external host), changes the destination information back to the original data and delivers the response to the client.

Services addressing

- Uniform Resource Identifier (URI, RFC 3986)
 - unified resource reference system (HTML links)
 - one client can use various access methods (FTP in WWW)
 - former classification: URL (location), URN (name)

URI = scheme:[//] authority [path] [?query] [#fragment]
authority = [login[: password]@]address[: port]

e.g.: ftp://sunsite.mff.cuni.cz/Net/RFC
 http://1.2.3.4:8080/q?ID=123#Local
 mailto:forst@cuni.cz
 sip:221911111@voip.cz

Introduction to Networking (2020)

SISAL

_


To get to a particular data source, we need to address the required service as a whole. The situation before the invention of the WWW was quite broken, there were different applications for different services. Web clients were the first applications that use various protocols (FTP, Gopher, WWW), HTML links must be able to address different services. Therefore, we need a common general way to combine a retrieval method type, server address, user credentials, resource location etc. into one compact form. The original idea was to define an addressing method (URI, Uniform Resource Identifier), which can either refer to a specific resource location (URL, Uniform Resource Location), or just a service name without an explicit location (URN, Uniform Resource Name). However, URNs have never been successfully implemented, so the terms URL and URI are more or less interchangeable.

The first part of a URL is a **scheme** (followed by a colon), often incorrectly called a "protocol" because many schemes are synonyms of protocols that should be used to approach a resource. Every URL must include a scheme, unless it is clear from the context – e.g. "http" is the default scheme of a link on a HTML page (however not generally in all URLs).


The next part of a URL is an **authority**, in some URL types prefixed by a pair of slashes. An authority specifies a server (or domain) together with information about the user (if needed). If a resource uses a non-standard port, it must be specified here, otherwise the well-known port will be used. For HTML links, if the authority in the link is the same as in the referring page, the authority can be omitted.

Many URL schemes contain a **path** to the requested resource on the server. The path format is similar to paths in filesystems (just using slashes instead of backslashes to separate directory names) and the path often actually corresponds to the page's actual location on the server's filesystem. For HTML links, if the authority is omitted, a relative path anchored in the directory of the referring page can be used, similarly to how a relative path is used in a filesystem.

Some URL schemes may contain additional URL parameters used to more precisely specify a request; e.g. an HTTP URL may contain a **query** (e.g. data from an HTML form) or a **fragment** (the identifier of the location of an exact point inside the page).



- At the application layer, a client usually addresses a server using a URL. The application layer passes data together with the destination address and port to the transport layer.
- At the transport layer, the logical communication channel is addressed by the socket addresses (i.e. IP address + port number) of the client and server. The transport layer hands over the data along with the target IP address to the network layer.
- The logical communication channel at the network layer is addressed by the client and server IP addresses. However, the client must decide whether the destination address belongs to the same network. According to this decision, a *next-hop* node is chosen and data plus the next-hop address are passed to the data link layer.
 - If the server is in the same network as the client, the next hop is the server.
 - Otherwise, a router capable of forwarding packets to the destination network must be found and this router is the next hop.
- The communication channel at the data link layer connects the client with the next hop, so the destination address at the data link layer is the next-hop MAC address.
 - If the next hop is the server, data is delivered and passed to higher layers on the server.
 - If the next hop is a router, data is passed only to the network layer and this layer again decides which next hop has to be used for further delivery. The data with the next-hop address is then passed back to the data link layer for delivery.




An important method used for the efficient use of a network is called **multiplexing**. This method means that several communication channels at one layer use the same communication channel at the underlying layer.

Each communication channel at a particular layer must follow a set of rules for the correct behavior of both parties, a so-called **protocol**. Multiple protocols can be used simultaneously at one layer.

Let's imagine that we have a protocol at layer n which defines its **Protocol Data Unit** (PDU) format. The software at layer n has finished its work and has decided to call layer n-1 to perform the transmission. It takes the PDU $_n$ as data and control information (such as destination, size, delivery options etc.) as a command and makes a call to the next layer. Usually, such a call actually takes the form of calling a library function with the data and command as parameters. Upon return, the caller receives information about the success or failure of the work of layer n-1. This data exchange between layers is called an **interface** and the exchange format is the **Interface Data Unit** (IDU).

Layer n-1 takes the control information, processes it and then prepares a PDU according to the particular protocol of that layer. This PDU usually contains a *body* containing PDU_n plus a *header* with control information. We call this method the **encapsulation** of the layer n data into the data at layer n-1. This is the most common case of encapsulation, but in general it is possible to encapsulate a PDU of any layer into any layer, even including the same layer or higher layers. For instance if we need to send an IPv6 packet over an IPv4 network, we must encapsulate the PDU₃ into another PDU₃.

The header must also contain an identifier of the layer n because **decapsulation** and **demultiplexing** must be performed on the recipient side. Layer n-1 checks the control information and passes the data (body) to appropriate software at layer n.



Let's look at how multiplexing and encapsulation work in the TCP/IP protocol suite.

The application layer sends either **messages** (in connectionless mode), or a **stream** of data (in connection-oriented mode). It passes the data and the socket address to the appropriate protocol at the transport layer.

If TCP is used, it takes the data from the stream and breaks it into smaller blocks and prepends a header containing, among other information, the source and destination port numbers and an "offset" into the stream so that the data can be sorted and reassembled upon delivery. UDP has much simpler work to do, it just prepends a header with port numbers to each message. The PDU_4 is then passed to the network layer along with the destination IP address.

The network layer takes a segment and prepends a header with the source and destination IP addresses and the transport layer protocol number, creating a **packet**. It then takes the destination address and checks if the packet can be delivered directly to the destination host or if a next-hop router must be used for forwarding. The packet, along with the data link layer destination node address is passed to the data link layer. *Warning:* be careful when talking about "packets", be sure to clearly indicate whether you mean a well-defined PDU₃, or a loose term of "packet switching" networking mode.

The data link layer takes a packet and prepends a header with the destination and source MAC addresses and the network layer protocol number. Since this is the last "software" layer before the data is passed to the "hardware" (the physical layer), we need some way to check whether the data has been transferred correctly. Therefore, the data link layer PDU (called a **frame**) contains also a suffix, the so-called Frame Check Sequence (FCS), the value of which is calculated from the contents of the rest of the frame.

The last step is to pass the frame to the physical layer to be transferred.

Upon the delivery to the destination node, the physical layer decodes the data and passes it to the data link layer.

The data link layer recalculates the value of the FCS and checks whether it is equal to the value stored in the frame. It also checks the destination MAC address to see whether the data belongs to this node. According to the network layer protocol code stored in the header, the decapsulated packet is passed to the network layer.

The network layer checks the destination IP address and passes the decapsulated segment to the appropriate transport layer software.

The work of the transport layer depends on the protocol used. In the UDP case, the message is simply delivered to the application. In the TCP case, the segment is saved and the entire data block will be delivered to the application after all segments have been received.

Summary 2

- Describe the differences between TCP, UDP and IP.
- Which addresses are used at the application, transport, network, link and physical layer?
- What is the difference between the client-server and peer-to-peer application mode?
- How are domain names administered?
- How are IP addresses assigned?
- What is the meaning and principle of NAT?
- What is multiplexing and encapsulation?

Introduction to Networking (2020)	SISAL -	38