





操作系统

Operating Systems

刘川意 教授

<u>liuchuanyi@hit.edu.cn</u>

哈尔滨工业大学(深圳)

2021年9月

Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理(Free-Space Management)
- 6. 分页(Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换(Swapping)



Virtual Address

- Every address in a running program is virtual 用户态程序的内存地址是虚拟的
 - OS translates the virtual address to physical address 由OS内核完成虚拟地址到物理地址的转换

```
1. #include <stdio.h>
2. #include <stdlib.h>
3. int main(int argc, char *argv[]) {
4.    printf("location of code : %p\n", (void *) main);
5.    printf("location of heap : %p\n", (void *) malloc(1));
6.    int x = 3;
7.    printf("location of stack : %p\n", (void *) &x);

8.    return x;
9. }
```

A simple program that prints out addresses

• code: 存放程序执行代码

```
location of code :0x556f705fb155
location of heap :0x556f70ead670
location of stack :0x7ffcdc4cde64
```

stack:由编译器自动分配释放,存放函数的参数值,局部变量等值

heap: 存放进程运行中被动态分配的内存




Virtual Address(Cont.)

The output in 64-bit Linux machine

location of code : 0x40057d location of heap : 0xcf2010

location of stack: 0x7fff9ca45fcc



Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页(Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换(Swapping)



Memory API: malloc()

```
#include <stdlib.h>
void* malloc(size_t size)
```

- Allocate a memory region on the heap.
 - Argument
 - size_t size : size of the memory block(in bytes)
 - size_t is an unsigned integer type.
 - Return
 - Success: a void type pointer to the memory block allocated by malloc
 - Fail: a null pointer

公面演之業大學 HARBIN INSTITUTE OF TECHNOLOGY

sizeof()

- Routines and macros are utilized for size in malloc instead typing in a number directly.
- Two types of results of sizeof with variables
 - The actual size of `x' is known at run-time.

```
int *x = malloc(10 * sizeof(int));
printf("%d\n", sizeof(x));
```

```
4
```

The actual size of 'x' is known at compile-time.

```
int x[10];
printf("%d\n", sizeof(x));
```

```
40
```




Memory API: free()

```
#include <stdlib.h>
void free(void* ptr)
```

- Free a memory region allocated by a call to malloc.
 - Argument
 - void *ptr:a pointer to a memory block allocated with malloc
 - Return
 - none




Memory Allocating






Memory Freeing




free(pi);





Forgetting To Allocate Memory


Incorrect code



Forgetting To Allocate Memory(Cont.)

Correct code

```
char *src = "hello"; //character string constant
char *dst (char *)malloc(strlen(src) + 1 ); // allocated
strcpy(dst, src); //work properly
```






Not Allocating Enough Memory

Incorrect code, but work properly

```
char *src = "hello"; //character string constant
char *dst (char *)malloc(strlen(src)); // too small
strcpy(dst, src); //work properly
```







Forgetting to Initialize

Encounter an uninitialized read

```
int *x = (int *)malloc(sizeof(int)); // allocated
printf("*x = %d\n", *x); // uninitialized memory access
```



Address Space



Address Space




Memory Leak


A program runs out of memory and eventually dies.

unused


: unused, but not freed



Address Space



Address Space




Address Space

run out of memory



Dangling Pointer

- Freeing memory before it is finished using
 - A program accesses to memory with an invalid pointer





Other Memory APIs: calloc()

```
#include <stdlib.h>
void *calloc(size_t num, size_t size)
```


- Allocate memory on the heap and zeroes it before returning.
 - Argument
 - size t num : number of blocks to allocate
 - size t size : size of each block(in bytes)
 - Return
 - Success: a void type pointer to the memory block allocated by calloc
 - Fail: a null pointer



Double Free

Free memory that was freed already.

```
int *x = (int *)malloc(sizeof(int)); // allocated
free(x); // free memory
free(x); // free repeatedly
```





Other Memory APIs: realloc()

```
#include <stdlib.h>
void *realloc(void *ptr, size_t size)
```

- Change the size of memory block.
 - A pointer returned by realloc may be either the same as ptr or a new.
 - Argument
 - void *ptr: Pointer to memory block allocated with malloc, calloc or realloc
 - size_t size: New size for the memory block(in bytes)
 - Return
 - Success: Void type pointer to the memory block
 - ▶ Fail : Null pointer



System Calls

```
#include <unistd.h>
int brk(void *addr)
void *sbrk(intptr_t increment);
```

- malloc library call use brk system call.
 - brk is called to expand the program's break.
 - break: The location of the end of the heap in address space
 - sbrk is an additional call similar with brk.
 - Programmers should never directly call either brk or sbrk.



System Calls(Cont.)

```
#include <sys/mman.h>
void *mmap(void *ptr, size_t length, int port, int flags,
int fd, off_t offset)
```

mmap system call can create an anonymous memory region.

Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译 (Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页(Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换(Swapping)



Memory Virtualizing with Efficiency and Control

- Memory virtualizing takes a similar strategy known as limited direct execution(LDE) for efficiency and control.
- In memory virtualizing, efficiency and control are attained by hardware support.
 - e.g., registers, TLB(Translation Look-aside Buffer)s, page-table



Address Translation

- Hardware transforms a virtual address to a physical address.
 - The desired information is actually stored in a physical address.
- The OS must get involved at key points to set up the hardware.
 - The OS must manage memory to judiciously intervene.



Example: Address Translation

C - Language code

```
void func()
    int x;
    ...
    x = x + 3; // this is the line of code we are interested in
```

- Load a value from memory
- Increment it by three
- Store the value back into memory

Example: Address Translation(Cont.)




Assembly

```
128 : movl 0x0(%ebx), %eax ; load 0+ebx into eax
132 : addl $0x03, %eax ; add 3 to eax register
135 : movl %eax, 0x0(%ebx) ; store eax back to mem
```

- Load the value at that address into eax register.
- Add 3 to eax register.
- Store the value in eax back into memory.

Example: Address Translation(Cont.)



- Fetch instruction at address 128
- Execute this instruction (load from address 15KB)
- Fetch instruction at address 132
- Execute this instruction (no memory reference)
- Fetch the instruction at address 135
- Execute this instruction (store to address 15 KB)




Relocation Address Space

- The OS wants to place the process somewhere else in physical memory, not at address 0.
 - The address space start at address 0.




A Single Relocated Process





Base and Bounds Register







- When a program starts running, the OS decides **where** in physical memory a process should be **loaded**.
 - Set the base register a value.

 $phycal\ address = virtual\ address + base$

Every virtual address must not be greater than bound and negative.

 $0 \le virtual \ address virtual \ address < bounds$



1920 HARBII




128 : movl 0x0(%ebx), %eax

Fetch instruction at address 128

$$32896 = 128 + 32KB(base)$$


- **Execute** this instruction
 - Load from address 15KB

47KB = 15KB + 32KB(base)





Two ways of Bounds Register






OS Issues for Memory Virtualizing

- The OS must take action to implement base-and-bounds approach.
- Three critical junctures:
 - When a process starts running:
 - Finding space for address space in physical memory
 - When a process is terminated:
 - Reclaiming the memory for use
 - When context switch occurs:
 - Saving and storing the base-and-bounds pair

OS Issues: When a Process Starts Running





- The OS must **find a room** for a new address space.
 - free list: A list of the range of the physical memory which are not in use.



OS Issues: When a Process Is Terminated


■ The OS must put the memory back on the free list.







- The OS must save and restore the base-and-bounds pair.
 - In process structure or process control block(PCB)




Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页(Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换(Swapping)



Inefficiency of the Base and Bound Approach



- Big chunk of "free" space
- "free" space takes up physical memory.
- Hard to run when an address space does not fit into physical memory

How to support Large Address Space?




Segmentation

- Segment is just a contiguous portion of the address space of a particular length.
 - Logically-different segment: code, stack, heap
- Each segment can be placed in different part of physical memory.
 - Base and bounds exist per each segment.
 - "1个进程, 1对base & bounds" —— "1个进程, 3对base & bounds"



Placing Segment In Physical Memory




Segment	Base	Size
Code	32K	2K
Heap	34K	2K
Stack	28K	2K

Address Translation on Segmentation

$$physical\ address = offset + base$$

- The offset of virtual address 100 is 100.
 - The code segment starts at virtual address 0 in address space.






Address Translation on Segmentation(Cont.)

Virtual address + base is not the correct physical address


- The offset of virtual address 4200 is 104.
 - The heap segment starts at virtual address 4096 in address space.





Segmentation Fault or Violation

- If an illegal address such as 7KB which is beyond the end of heap is referenced, the OS occurs segmentation fault.
 - The hardware detects that address is out of bounds.




Address Space



Referring to Segment

Explicit approach

 Chop up the address space into segments based on the top few bits of virtual address.



Example: virtual address 4200 (01000001101000)

Segment	bits	ı	13	12	11	10	9	8	7	6	5	4	3	2	1	0	ı
Code	00		0 I	1	0 II	0	0	0	0	1	1	0	1	0	0	0	
Heap Stack -			Segr	ment	:				(T Offse	et .						



Referring to Segment(Cont.)


```
// get top 2 bits of 14-bit VA
Segment = (VirtualAddress & SEG_MASK) >> SEG_SHIFT
// now get offset
Offset = VirtualAddress & OFFSET_MASK
if (Offset >= Bounds[Segment])
RaiseException(PROTECTION_FAULT)
else
PhysAddr = Base[Segment] + Offset
Register = AccessMemory(PhysAddr)
```

- SEG_MASK = $0 \times 3000 (1100000000000)$
- SEG SHIFT = 12
- OFFSET MASK = $0 \times FFF$ (00111111111111)



Referring to Stack Segment

- Stack grows backward.
- Extra hardware support is needed.
 - The hardware checks which way the segment grows.
 - 1: positive direction, 0: negative direction



Segment Register(with Negative-Growth Support)

Segment	Base	Size	Grows Positive?
Code	32K	2K	1
Heap	34K	2K	1
Stack	28K	2K	0

访问 Virtual address 15KB, 其对应的物理地址是多少?



Support for Sharing

- 分段带来额外的好处, 即: 代码共享(Code sharing)
- Segment can be shared between address space.
 - Code sharing is still in use in systems today.
 - by extra hardware support.
- Extra hardware support is needed in form of Protection bits.
 - A few more bits per segment to indicate permissions of read, write and execute.

Segment Register Values(with Protection)

Segment	Base	Size	Grows Positive?	Protection
Code	32K	2K	1	Read-Execute
Heap	34K	2K	1	Read-Write
Stack	28K	2K	0	Read-Write



Fine-Grained and Coarse-Grained

- Coarse-Grained means segmentation in a small number.
 - e.g., code, heap, stack.
- Fine-Grained segmentation allows more flexibility for address space in some early system.
 - To support many segments, Hardware support with a segment table is required.
 - 更细粒度的segment, OS可以更好了解哪些段在使用, 哪些没有, 从而更高效利用内存



OS support:

Context Switch


- Segment registers 段寄存器需要保存和恢复
- OS确保这些段寄存器在进程运行前被正确赋值


■ Free Space Management

- External Fragmentation: little holes of free space in physical memory that make difficulty to allocate new segments.
 - There is 24KB free, but not in one contiguous segment.
 - The OS cannot satisfy the 20KB request.



Memory Compaction







OS support:

Context Switch

- Segment registers 段寄存器需要保存和恢复
- OS确保这些段寄存器在进程运行前被正确赋值
- Free Space Management
 - External Fragmentation: little holes of free space in physical memory that make difficulty to allocate new segments.
 - There is 24KB free, but not in one contiguous segment.
 - ▶ The OS cannot satisfy the 20KB request.
 - Compaction: rearranging the exiting segments in physical memory.
 While Compaction is costly.
 - Stop running process.
 - Copy data to somewhere.
 - Change segment register value.
 - Free-list Management
 - ▶ 如果解决一个问题有很多种方法,就没有一种是特别好的

例题



采用段式存储管理的系统中, 若地址用24位表示, 其中8位表示段号, 则允许每段的最大长度是()。

- A.2²⁴B
- B.2¹⁶B
- C.28B
- D.232B

答案:B

例题



在分段存储管理系统中,用共享段表描述所有被共享的段。若进程 P1和 P2共享段S,下列叙述中,错误的是

- A.在物理内存中仅保存一份段 S 的内容
- B.段 S 在 P1和 P2中应该具有相同的段号
- C.P1 和 P2 共享段 S 在共享段表中的段表项
- D.P1和 P2都不再使用段 S 时才回收段 S 所占的内存空间

答案:C

Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理(Free-Space Management)
- 6. 分页(Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换 (Swapping)




Assumptions

- 若需要管理的空闲空间被划分成固定大小的单元,则管理容易
- 若空闲空间由大小不同的单元构成,则管理变得困难!
 - 满足变长的分配请求,该如何组织空闲空间?
 - 如何使碎片最小化?
 - 不同方法的开销(包括时间开销和空间开销)如何?
- 分配接口假设以malloc()和free()为例
- External Fragmentation VS Internal Fragmentation
- 内存一旦被分配,无法被重定位,但是:
 - Segmented OS kernel
 - 强类型程序设计语言



Splitting


- Finding a free chunk of memory that can satisfy the request and splitting it into two.
 - When request for memory allocation is smaller than the size of free chunks.





Splitting(Cont.)

Two 10-bytes free segment with 1-byte request






Coalescing

head

- If a user requests memory that is bigger than free chunk size, the list will not find such a free chunk.
- Coalescing: Merge returning a free chunk with existing chunks into a large single free chunk if addresses of them are nearby.



NULL

len:30



Tracking The Size of Allocated Regions

- The interface to free (void *ptr) does not take a size parameter.
 - How does the library know the size of memory region that will be back into free list?
- Most allocators store extra information in a header block.

```
ptr = malloc(20);
The header used by malloc library


The 20 bytes returned to caller
```

An Allocated Region Plus Header



The Header of Allocated Memory Chunk

- The header minimally contains the size of the allocated memory region.
- The header may also contain
 - Additional pointers to speed up deallocation
 - A magic number for integrity checking



```
typedef struct __header_t {
   int size;
   int magic;
} header_t;
```



The Header of Allocated Memory Chunk(Cont.)

- The size for free region is the size of the header plus the size of the space allocated to the user.
 - If a user request n bytes, the library searches for a free chunk of size n plus the size of the header
- Simple pointer arithmetic to find the header pointer.

```
void free(void *ptr) {
    header_t *hptr = (void *)ptr - sizeof(header_t);
}
```



Embedding A Free List

- The memory-allocation library **initializes** the heap and **puts** the first element of **the free list** in the **free space**.
 - The library can't use malloc() to build a list within itself.



Embedding A Free List(Cont.)


Description of a node of the list

```
typedef struct __node_t {
    int size;
    struct __node_t *next;
} nodet_t;
```

- Building heap and putting a free list
 - Assume that the heap is built vi mmap () system call.



A Heap With One Free Chunk






Embedding A Free List: Allocation

- If a chunk of memory is requested, the library will first find a chunk that is large enough to accommodate the request.
- The library will
 - Split the large free chunk into two.
 - ▶ One for the request and the remaining free chunk
 - Shrink the size of free chunk in the list.




Embedding A Free List: Allocation(Cont.)

- **Example:** a request for 100 bytes by ptr = malloc(100)
 - Allocating 108 bytes out of the existing one free chunk.
 - shrinking the one free chunk to 3980(4088 minus 108).



Free Space With Chunks Allocated








Free Space With free ()


- Example: free(sptr)
- The 100 bytes chunks is back into the free list.
- The free list will start with a small chunk.
 - The list header will point the small chunk





Free Space With Freed Chunks


Let's assume that the last two in-use chunks are freed.





Growing The Heap

- Most allocators start with a small-sized heap and then request more memory from the OS when they run out.
 - e.g., sbrk(), brk() in most UNIX systems.



Managing Free Space: Basic Strategies

Best Fit:

- Finding free chunks that are big or bigger than the request
- Returning the one of smallest in the chunks in the group of candidates

■ Worst Fit:

- Finding the largest free chunks and allocation the amount of the request
- Keeping the remaining chunk on the free list.

Managing Free Space: Basic Strategies (Cont.)

First Fit:

- Finding the first chunk that is big enough for the request
- Returning the requested amount and remaining the rest of the chunk.

Next Fit:

- Instead of always beginning the first-fit search at the beginning of the list
- Keep an extra pointer to the location within the list where one was looking last. 即搜索的起始点是上次返回的节点位置
- The idea is to spread the searches for free space throughout the list more uniformly, thus avoiding splintering of the beginning of the list



Examples of Basic Strategies

Allocation Request Size 15



Result of Best-fit



■ Result of Worst-fit

head
$$\longrightarrow$$
 10 \longrightarrow 15 \longrightarrow NULL

例题



某基于动态分区存储管理的计算机, 其主存容量为55MB (初始为空 闲), 采用最佳适配(Best Fit)算法, 分配和释放的顺序为:分配15MB, 分配30Mb, 释放15Mb, 分配 8MB, 分配6MB, 此时主存中最大 空闲 分区的大小是()

- A.7Mb
- B.9Mb
- C.10Mb
- **D.15Mb**

答案:B





- Segregated List:
 - Keeping free chunks in different size in a separate list for the size of popular request. 拿出一部分内存专门满足特定大小的请求, 碎片就不是 事了
 - New Complication:
 - How much memory should dedicate to the pool of memory that serves specialized requests of a given size?
 - Slab allocator handles this issue.

Other Approaches: Segregated List(Cont.)

Slab Allocator

- Allocate a number of object caches.
 - ▶ The objects are likely to e requested frequently.
 - e.g., locks, file-system inodes, etc.
- Request some memory from a more general memory allocator when a given cache is running low on free space. (size一般是page size和 object size的公倍数)

Slab

- The slab is the primary unit of currency in the slab allocator.
- A separate memory pool for frequently created & deleted objects of same size.
 - e.g., task_struct, inode in Linux, etc

Other Approaches: Segregated List(Cont.)


Slab Allocator

- 数据结构初始化和销毁的代价很大,通过将空闲对象保持在初始化状态, slab allocator避免了频繁的初始化和销毁,显著降低开销
- Benefits:
 - Reclaiming unused memory is trivial.
 - Allocating and freeing memory are fast, constant-time operations.
 - Severe external fragmentation (unused buffers on the freelist) is unlikely.
 - Internal fragmentation (per-buffer wasted space) is minimal.

Other Approaches: Segregated List(Cont.)

• kmem_slab: Each slab is managed, which maintains the slab's linkage in the cache, its reference count, and its list of free buffers.

• kmem_bufctl: Each buffer in the slab is managed, which holds the freelist linkage, buffer address, and a back pointer to the controlling slab.



(bufctl-to-slab back-pointers not shown)

The Slab Allocator original paper



The Slab Allocator: An Object-Caching Kernel Memory Allocator

Jeff Bonwick
Sun Microsystems

Abstract

This paper presents a comprehensive design overview of the SunOS 5.4 kernel memory allocator. This allocator is based on a set of object-caching primitives that reduce the cost of allocating complex objects by retaining their state between uses. These same primitives prove equally effective for managing stateless memory (e.g. data pages and temporary buffers) because they are space-efficient and fast. The allocator's object caches respond dynamically to global memory pressure, and employ an object-coloring scheme that improves the system's overall cache utilization and bus balance. The allocator also has several statistical and debugging features that can detect a wide range of problems throughout the system.

generally superior in both space *and* time. Finally, Section 6 describes the allocator's debugging features, which can detect a wide variety of problems throughout the system.

2. Object Caching

Objects caching is a technique for dealing with objects that are frequently allocated and freed. The idea is to preserve the invariant portion of an object's initial state — its constructed state — between uses, so it does not have to be destroyed and recreated every time the object is used. For example, an object containing a mutex only needs to have mutex_init() applied once — the first time the object is allocated. The object can then be freed and reallocated many times without incurring

Jeff Bonwick:工程师的价值符合幂律分析的对话的



- invented and led development of the ZFS file system
- inventor of slab allocation
- ➤ In 2010 Bonwick co-founded a small company called DSSD, which was acquired by EMC Corporation in 2014


Someone who is **exceptional** in their role is not just a little better than someone who is pretty good. They are **100 times better**

——Mark Zuckerberg, Facebook)

- One or two people can start a company that changes the face of the world forever
- think Google, Apple, or Facebook



- - **Binary Buddy Allocation**
 - For coalescing tasks
 - The allocator divides free space by two until a block that is big enough to accommodate the request is **found**.



64KB free space for 7KB request

Other Approaches: Buddy Allocation (Cont.)

- Buddy allocation can suffer from internal fragmentation.
- Buddy system makes coalescing simple.
 - Coalescing two blocks in to the next level of block.
 - 判断任意block的buddy block是否in use很简单: 地址只有1 bit区别

Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页 (Paging)
- 7. 地址翻译缓存 TLB(Translation Lookaside Buffers)
- 8. 交换(Swapping)



Concept of Paging

- Paging **splits up** address space into **fixed-zed** unit called a **page**.
 - 回顾对比 Segmentation: variable size of logical segments(code, stack, heap, etc.)
- With paging, **physical memory** is also **split** into some number of pages called a **page frame**.
- Page table per process is needed to translate the virtual address to physical address.




Advantages Of Paging

- □ Flexibility: 通用性更好 Supporting the abstraction of address space effectively
 - 不需要关心heap and stack地址如何增长, 内存如何使用
- Simplicity: 空闲空间管理简单 ease of free-space management
 - The page in address space and the page frame are the same size.
 - Easy to allocate and keep a free list




Example: A Simple Paging

- Physical: 128-byte physical memory with 16 bytes page frames
- Virtual: 64-byte address space with 16 bytes pages



A Simple 64-byte Address Space




64-Byte Process Address Space Placed In 128-Byte
Physical Memory




Address Translation

- Two components in the virtual address
 - VPN: Virtual Page Number
 - Offset: offset within the page




Example: virtual address 21 in 64-byte address space





Example: Address Translation

The virtual address 21 in 64-byte address space





Where Are Page Tables Stored?


- 每个process都有一个Page Table, which can get awfully large
 - 32-bit address space, with 4KB pages, 20bits for VPN
 - ▶ 4MB = 2²⁰ entries * 4Bytes per page table entry
- Page Table存储在内存
 - Because page tables are so big, we don't keep any special on-chip hardware in the MMU to store the page table of the currently-running process.
 - Instead, we store the page table for each process in memory somewhere



What Is In The Page Table?

- The page table is just a **data structure** that is used to map the virtual address to physical address.
 - Simplest form: a linear page table, an array
- The OS **indexes** the array by VPN, and looks up the page-table entry.

Example: Page Table in Kernel Physical Memory



page frame 0 of physical memory 给出了

一个简单的page table示例


- 注意:
 - VPN就不需要存储了
 - Index代表PFN





- Valid Bit: Indicating whether the particular translation is valid.
- Protection Bit: Indicating whether the page could be read from, written to, or executed from
- Present Bit: Indicating whether this page is in physical memory or on disk(swapped out)
- **Dirty Bit**: Indicating whether the page has been modified since it was brought into memory
- Reference Bit(Accessed Bit): Indicating that a page has been accessed

Example: x86 Page Table Entry (PTE)



P: present

R/W: read/write bit

■ U/S: supervisor

A: accessed bit

■ D: dirty bit

PFN: the page frame number

- Read the Intel Architecture Manuals for more details on x86 paging support.
- Be forewarned, however; reading manuals such as these, while quite informative can be challenging at first. A little **patience**, and a lot of **desire**, is required.



Paging: Too Slow

- To find a location of the desired PTE, the **starting location** of the page table is **needed**.
- For every memory reference, paging requires the OS to perform one extra memory reference, 准确的说是至少一次

Accessing Memory With Paging



```
// Extract the VPN from the virtual address
      VPN = (VirtualAddress & VPN MASK) >> SHIFT
      // Form the address of the page-table entry (PTE)
      PTEAddr = PTBR + (VPN * sizeof(PTE))
      // Fetch the PTE
      PTE = AccessMemory(PTEAddr)
10
      // Check if process can access the page
11
      if (PTE.Valid == False)
12
             RaiseException (SEGMENTATION FAULT)
13
      else if (CanAccess(PTE.ProtectBits) == False)
14
             RaiseException (PROTECTION FAULT)
15
      else
16
             // Access is OK: form physical address and fetch it
17
             offset = VirtualAddress & OFFSET MASK
18
             PhysAddr = (PTE.PFN << PFN SHIFT) | offset
             Register = AccessMemory(PhysAddr)
19
```



A Memory Trace

Example: A Simple Memory Access

Compile and execute

```
prompt> gcc -o array array.c -Wall -o
prompt>./array
```

Resulting Assembly code

```
0x1024 movl $0x0,(%edi,%eax,4)
0x1028 incl %eax
0x102c cmpl $0x03e8,%eax
0x1030 jne 0x1024
```


A Virtual(And Physical) Memory Trace

Some assumptions:

- virtual address space size: 64KB
- page size:1KB
- a linear (array-based) page table at physical address 1KB (1024)
- Code: virtual address 1024; $VPN=1 \rightarrow PFN=4$
- Array: virtual addresses 40000 through 44000; VPN=39, ..., VPN=42

VPN	PFN
39	7
40	8
41	9
42	10

A Virtual(And Physical) Memory Trace



A Virtual(And Physical) Memory Trace

each instruction fetch will generate two memory references:

- access the page table to find the physical frame that the instruction resides within
- access the instruction itself to fetch it to the CPU for processing

mov instruction will generate one explicit memory reference:

• translate the array virtual address to the correct physical one

each array element will generate one memory references.

For each element of array:

Mov instruction accesses the page table (topmost graph) and the instruction itself (bottom graph), then accesses array virtual address (topmost graph). After that, the array accesses memory (middle graph). The other three instructions access memory twice for each.





■ 设有8页的逻辑空间,每页有1024字节,它们被映射到32块的物理存储区中,那么逻辑地址的有效位是__位,物理地址至少是__位。

■ 分析

- 逻辑地址有两个部分组成:页号和页内偏移地址。逻辑空间有8 (2³) 页, 说明页号需要3个二进制位描述,而每页有1024(2¹⁰)字节,说明页内偏移地 址为10二进制位描述,因此逻辑地址的有效位为3+10=13位。
- 因为物理地址与逻辑地址的页面大小相同,而物理存储块为32(25)占5位, 所以物理地址至少为5+10=15位


Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段(Segmentation)
- 5. 空闲空间管理(Free-Space Management)
- 6. 分页(Paging)
- 7. Paging performance: 地址翻译缓存 TLB (Translation Lookaside Buffers)
- 8. Small Page Table: 多级页表
- 9. 交换(Swapping)





- Part of the chip's Memory-Management Unit (MMU).
- A hardware cache of popular virtual-to-physical address translation.





TLB Basic Algorithms

```
1: VPN = (VirtualAddress & VPN_MASK ) >> SHIFT
2: (Success , TlbEntry) = TLB_Lookup(VPN)
3:    if(Success == Ture) { // TLB Hit
4:    if(CanAccess(TlbEntry.ProtectBit) == True ) {
5:        offset = VirtualAddress & OFFSET_MASK
6:        PhysAddr = (TlbEntry.PFN << SHIFT) | Offset
7:        AccessMemory( PhysAddr )
8:    }else RaiseException(PROTECTION_ERROR)</pre>
```

- (1 lines) extract the virtual page number(VPN).
- (2 lines) check if the TLB holds the transalation for this VPN.
- (5-8 lines) extract the page frame number from the relevant TLB entry, and form the desired physical address and access memory.




TLB Basic Algorithms (Cont.)

```
11:
       }else{ //TLB Miss
           PTEAddr = PTBR + (VPN * sizeof(PTE))
12:
13:
           PTE = AccessMemory(PTEAddr)
14:
           (...)
15:
      }else{
16:
           TLB Insert ( VPN , PTE.PFN , PTE.ProtectBits)
17:
           RetryInstruction()
18:
19:}
```

- (11-12 lines) The hardware accesses the page table to find the translation.
 Line12, PTBR (Page Table Base Register)由硬件记录页表在内存的起始位置,以及硬件需要清楚页表的结构,即可算出对应页表项的内存地址
- (16 lines) updates the TLB with the translation.



Example: Accessing An Array



```
0:    int sum = 0;
1:    for( i=0; i<10; i++) {
2:       sum+=a[i];
3:    }</pre>
```

- assume an array of 10 4-byte integers in memory, starting at virtual address 100.
- a small 8-bit virtual address space, with 16-byte pages
- pretend that the only memory accesses the loop generates are to the array


The TLB improves performance due to spatial locality

3 misses and 7 hits. Thus TLB hit rate is 70%.

公爾濱Z業大學 HARBIN INSTITUTE OF TECHNOLOGY


尽可能利用好TLB缓存!

- Temporal Locality
 - An instruction or data item that has been recently accessed will likely be reaccessed soon in the future.



Virtual Memory

- Spatial Locality
 - If a program accesses memory at address x, it will likely soon access memory near x.



Virtual Memory



Who Handles The TLB Miss?

- 2种方式:硬件或软件
- Hardware handle the TLB miss entirely on CISC (往往由复杂指令集需要提供特定的CPU指令).
 - The hardware has to know exactly where the page tables are located in memory.
 - The hardware would "walk" the page table, find the correct page-table entry and extract the desired translation, update and retry instruction.
 - hardware-managed TLB.
- 更现代体系结构, 采用**software-managed TLB, 即:** RISC 架构中, 若TLB miss, 硬件会抛出一个异常(raises exception), 暂停当前指令流, 将特权级提升至内核模式, 跳转到trap handler程序进行处理
 - <u>Trap handler is code</u> within the OS that is written with the express purpose of handling TLB miss
 - 从trap handler返回的指令不同于系统调用的trap return指令
 - trap handler要避免无限递归



TLB entry


- TLB is managed by **Full Associative** method.
 - A typical TLB might have 32,64, or 128 entries.
 - Hardware search the entire TLB in parallel to find the desired translation.
 - other bits: valid bits, protection bits, address-space identifier, dirty bit



Typical TLB entry look like this




TLB Issue: Context Switching






TLB Issue: Context Switching






TLB Issue: Context Switching

Process A



Virtual Memory



TLB Table

VPN	PFN	valid	prot
10	100	1	rwx
_	<u>-</u>	-	-
10	170	1	rwx
_	-	-	-


Can't Distinguish which entry is meant for which process



To Solve Problem

Provide an address space identifier(ASID) field in the TLB.

Process A



Virtual Memory



Virtual Memory

TLB Table

VPN	PFN	valid	prot	ASID
10	100	1	rwx	1
_	-	-	-	-
10	170	1	rwx	2
_	-	-	-	-



Another Case

- Two processes share a page.
 - Process 1 is sharing physical page 101 with Process2.
 - P1 maps this page into the 10th page of its address space.
 - P2 maps this page to the 50th page of its address space.


VPN	PFN	valid	prot	ASID
10	101	1	rwx	1
-	-	-	1	-
50	101	1	rwx	2
-	-	-	-	-

Sharing of pages is useful as it reduces the number of physical pages in use.



TLB Replacement Policy

- LRU(Least Recently Used)
 - Evict an entry that has not recently been used.
 - Take advantage of *locality* in the memory-reference stream.




Total 11 TLB miss



A Real TLB Entry

All 64 bits of this TLB entry(example of MIPS R4000)



Flag	Content
19-bit VPN	The rest reserved for the kernel.
24-bit PFN	Systems can support with up to 64GB of main memory($2^{24} * 4KB$ pages).
Global bit(G)	Used for pages that are globally-shared among processes.
ASID	OS can use to distinguish between address spaces.
Coherence bit(C)	determine how a page is cached by the hardware.
Dirty bit(D)	marking when the page has been written.
Valid bit(V)	tells the hardware if there is a valid translation present in the entry.


Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段 (Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页(Paging)
- 7. Paging performance: 地址翻译缓存 TLB (Translation Lookaside Buffers)
- 8. Small Page Table: 多级页表
- 9. 交换(Swapping)



Paging: Linear Tables

- 每个进程都有一个page table
 - Assume that 32-bit address space with 4KB pages and 4-byte page-table entry.




 $2^{32} / 2^{12} * 4 = 4MB$ per page table

Page table are too big and thus consume too much memory.



Smaller Tables: Big pages

- Page table are too big and thus consume too much memory.
 - Assume that 32-bit address space with 16KB pages and 4-byte page-table entry.




 $2^{32} / 2^{16} * 4 = 1MB$ per page table

Big pages lead to internal fragmentation.



Problem

Single page table for the entries address space of process.




PFN	valid	prot	present	dirty
10	1	r-x	1	0
-	0	-	-	-
-	0	-	-	-
-	0	-	-	-
15	1	rw-	1	1
-	0	-	-	-
3	1	rw-	1	1
23	1	rw-	1	1

A Page Table For 16KB Address Space



Problem

Most of the page table is unused, full of invalid entries.



PFN	valid	prot	present	dirty
10	1	r-x	1	0
-	0	-	-	-
-	0	-	-	-
-	0	-	-	-
15	1	rw-	1	1
-	0	-	-	-
3	1	rw-	1	1
23	1	rw-	1	1

A Page Table For 16KB Address Space

A 16KB Address Space with 1KB Pages


Hybrid Approach: Paging and Segments

- In order to reduce the memory overhead of page tables.
 - Using base not to point to the segment itself but rather to hold the physical address of the page table of that segment.
 - The bounds register is used to indicate the end of the page table.





- Each process has three page tables associated with it.
 - When process is running, the base register for each of these segments contains the physical address of a linear page table for that segment.



32-bit Virtual address space with 4KB pages

Seg value	Content
00	unused segment
01	code
10	heap
11	stack



TLB miss on Hybrid Approach

- The hardware get to **physical address** from **page table**.
 - The hardware uses the segment bits(SN) to determine which base and bounds pair to use.
 - The hardware then takes the physical address therein and combines it with the VPN as follows to form the address of the page table entry(PTE).

```
01: SN = (VirtualAddress & SEG_MASK) >> SN_SHIFT
02: VPN = (VirtualAddress & VPN_MASK) >> VPN_SHIFT
03: AddressOfPTE = Base[SN] + (VPN * sizeof(PTE))
```



Problem of Hybrid Approach

- Hybrid Approach is not without problems.
 - If we have a large but sparsely-used heap, we can still end up with a lot of page table waste.
 - Causing external fragmentation to arise again.

Big pages 和hybrid都不是好**设计!怎么办?**改进Page Table的数据结构,引入多<mark>级页表(Multi-level Page Tables)</mark>




Multi-level Page Tables

- 把linear page table换成另一种数据结构, like a tree.
 - Chop up the page table into page-sized units.
 - If an entire page of page-table entries is invalid, don't allocate that page of the page table at all.
 - To track whether a page of the page table is valid, use a new structure, called page directory.



Example: Page directory



Linear (Left) And Multi-Level (Right) Page Tables



Example: analysis

- Linear Page Table
 - even though most of the middle regions of the address space are not valid, we still require page-table space allocated for those regions (i.e., the middle two pages of the page table).
- Multi-level Page Table
 - The page directory marks just two pages of the page table as valid (the first and last); thus, just those two pages of the page table reside in memory.
 - one way to visualize what a multi-level table is doing: it just makes parts
 of the linear page table disappear (freeing those frames for other uses),
 and tracks which pages of the page table are allocated with the
 page directory.

Multi-level Page Tables: Page directory entries

- The page directory contains one entry per page of the page table.
 - It consists of a number of page directory entries(PDE).
- PDE has a valid bit and page frame number(PFN).





Advantage

- Only allocates page-table space in proportion to the amount of address space you are using.
- The OS can grab the next free page when it needs to allocate or grow a page table.

Disadvantage

- Multi-level table is a small example of a time-space trade-off.
- Complexity.

Multi-level Page Table: Level of indirection

- A multi-level structure can adjust level of indirection through use of the page directory.
 - Indirection place page-table pages wherever we would like in physical memory.




A Detailed Multi-Level Example

To understand the idea behind multi-level page tables better, let's do an example.

code
code
(free)
(free)
heap
heap
(free)
(free)
stack
stack

Flag	Detail
Address space	16 KB
Page size	64 byte
Virtual address	14 bit
VPN	8 bit
Offset	6 bit
Page table entry	2 ⁸ (256)


A 16-KB Address Space With 64-byte Pages





Page Directory Idx


- The page directory needs one entry per page of the page table
 - it has 16 entries.
- The page-directory entry is invalid → Raise an exception (The access is invalid)





Page Table Idx (cont.)

- The PDE is valid, we have more work to do.
 - To fetch the page table entry(PTE) from the page of the page table pointed to by this page-directory entry.
- This page-table index can then be used to index into the page table itself.




14-bits Virtual address



More than Two Level


In some cases, a deeper tree is possible.



Flag	Detail
Virtual address	30 bit
Page size	512 byte
VPN	21 bit
Offset	9 bit

More than Two Level: Page Table Index


In some cases, a deeper tree is possible.



Flag	Detail	
Virtual address	30 bit	
Page size	512 byte	
VPN	21 bit	
Offset	9 bit	
Page entry per page	128 PTEs	$\longrightarrow Log_2 128 = 7$

More than Two Level: Page Directory

- If our page directory has 2¹⁴entries, it spans not one page but 128.
- To remedy this problem, we build a further level of the tree, by splitting the page directory itself into multiple pages of the page directory.







```
01:
        VPN = (VirtualAddress & VPN MASK) >> SHIFT
02:
         (Success, TlbEntry) = TLB Lookup (VPN)
03:
        if (Success == True)
                                   //TLB Hit
04:
          if (CanAccess(TlbEntry.ProtectBits) == True)
05:
                 Offset = VirtualAddress & OFFSET MASK
                 PhysAddr = (TlbEntry.PFN << SHIFT) | Offset
06:
                 Register = AccessMemory(PhysAddr)
07:
08:
           else RaiseException(PROTECTION FAULT);
09:
        else // perform the full multi-level lookup
```

- (1 lines) extract the virtual page number(VPN)
- (2 lines) check if the TLB holds the transalation for this VPN
- (5-8 lines) extract the page frame number from the relevant TLB entry, and form the desired physical address and access memory



```
上路爾濱Z業大學
HARBIN INSTITUTE OF TECHNOLOGY
```

```
11: else

12: PDIndex = (VPN & PD_MASK) >> PD_SHIFT

13: PDEAddr = PDBR + (PDIndex * sizeof(PDE))

14: PDE = AccessMemory(PDEAddr)

15: if(PDE.Valid == False)

16: RaiseException(SEGMENTATION_FAULT)

17: else // PDE is Valid: now fetch PTE from PT
```

- (11 lines) extract the Page Directory Index(PDIndex)
- (13 lines) get Page Directory Entry(PDE)
- (15-17 lines) Check PDE valid flag. If valid flag is true, fetch Page Table entry from Page Table

The Translation Process: Remember the TLB

```
18:
        PTIndex = (VPN & PT MASK) >> PT SHIFT
19:
        PTEAddr = (PDE.PFN << SHIFT) + (PTIndex * sizeof(PTE))
20:
        PTE = AccessMemory(PTEAddr)
21:
        if(PTE.Valid == False)
22:
                 RaiseException (SEGMENTATION FAULT)
23:
        else if (CanAccess (PTE.ProtectBits) == False)
24:
                 RaiseException (PROTECTION FAULT);
25:
        else
26:
                 TLB Insert(VPN, PTE.PFN , PTE.ProtectBits)
                 RetryInstruction()
27:
```



Inverted Page Tables

- A single page table that has an entry for each <u>physical page</u> of the system.
- The entry tells:
 - which process is using this page
 - Which virtual page of that process maps to this physical page
- Finding the correct entry is now a matter of searching through this data structure
 - hash table is often built over the base structure to speed up lookups
 - PowerPC 是典型例子





某计算机系统按字节编址,采用二级页表的分页存储管理方式,虚拟地址格式如下所示:

10位	10位	12位
页目录号	页表索引	页内偏移量

请回答下列问题。


- (1)页和页框的大小各为多少字节?进程的虚拟地址空间大小为多少页?
- (2)假定页目录项和页表项均占4个字节,则进程的页目录和页表共占多少页?
- (3)若某指令周期内访问的虚拟地址为0100 0000H和0111 2048H,则进行地址转换时共访问多少个二级页表?要求说明理由。

Module 4: Virtualizing Memory 虚拟内存

- 1. 虚拟地址空间
- 2. 内存管理API(Memory API)
- 3. Mechanism: 地址翻译(Address Translation)
- 4. 分段(Segmentation)
- 5. 空闲空间管理 (Free-Space Management)
- 6. 分页(Paging)
- 7. Paging performance: 地址翻译缓存 TLB (Translation Lookaside Buffers)
- 8. Small Page Table: 多级页表
- 9. 交换(Swapping)

Beyond Physical Memory: Mechanisms

- Require an additional level in the memory hierarchy.
 - 实际中, OS需要支持同时运行的巨大地址空间, 因此OS需要把当前地址 空间没有使用的部分找个地方贮存起来
 - In modern systems, this role is usually served by a hard disk drive



Memory Hierarchy in modern system




Requirement: Single large address for a process

- Always need to first arrange for the code or data to be in memory when before calling a function or accessing data.
- To Beyond just a single process.
 - The addition of swap space allows the OS to support the illusion of a large virtual memory for multiple concurrently-running process



Swap Space

- Reserve some space on the disk for moving pages back and forth.
- OS need to remember to the swap space, in page-sized unit



Physical Memory and Swap Space



Present Bit

- Add some machinery higher up in the system in order to support swapping pages to and from the disk.
 - When the hardware looks in the PTE, it may find that the page is not present in physical memory.

Value	Meaning
1	page is present in physical memory
0	The page is not in memory but rather on disk.



What If Memory Is Full?

- OS like to page out pages to make room for the new pages the OS is about to bring in.
 - The process of picking a page to kick out, or replace is known as pagereplacement policy




The Page Fault

- Accessing page that is not in physical memory.
 - If a page is not present and has been swapped out to disk, the OS need to swap the page into memory in order to service the page fault.



Page Fault Control Flow

PTE used for data such as the PFN of the page for a disk address.







```
1:
        VPN = (VirtualAddress & VPN MASK) >> SHIFT
         (Success, TlbEntry) = TLB Lookup(VPN)
2:
        if (Success == True) // TLB Hit
3:
4:
                 if (CanAccess(TlbEntry.ProtectBits) == True)
5:
                          Offset = VirtualAddress & OFFSET MASK
                          PhysAddr = (TlbEntry.PFN << SHIFT) | Offset
6:
7:
                          Register = AccessMemory(PhysAddr)
8:
                 else RaiseException(PROTECTION FAULT)
```



```
哈爾濱之葉大學
HARBIN INSTITUTE OF TECHNOLOGY
```

```
else // TLB Miss
9:
10:
                  PTEAddr = PTBR + (VPN * sizeof(PTE))
11:
                  PTE = AccessMemory (PTEAddr)
12:
                  if (PTE.Valid == False)
13:
                           RaiseException (SEGMENTATION FAULT)
14:
                  else
15:
         if (CanAccess(PTE.ProtectBits) == False)
                  RaiseException (PROTECTION FAULT)
16:
        else if (PTE.Present == True)
17:
18:
        // assuming hardware-managed TLB
19:
                  TLB Insert (VPN, PTE.PFN, PTE.ProtectBits)
20:
                  RetryInstruction()
        else if (PTE.Present == False)
21:
22:
                  RaiseException(PAGE FAULT)
```



```
公爾濱Z業大學
HARBIN INSTITUTE OF TECHNOLOGY
```

```
1: PFN = FindFreePhysicalPage()

2: if (PFN == -1) // no free page found

3: PFN = EvictPage() // run replacement algorithm

4: DiskRead(PTE.DiskAddr, pfn) // sleep (waiting for I/O)

5: PTE.present = True // update page table with present

6: PTE.PFN = PFN // bit and translation (PFN)

7: RetryInstruction() // retry instruction
```

- The OS must find a physical frame for the soon-be-faulted-in page to reside within.
- If there is no such page, waiting for the replacement algorithm to run and kick some pages out of memory.



When Replacements Really Occur

- OS waits until memory is entirely full, and only then replaces a page to make room for some other page
 - This is a little bit unrealistic, and there are many reason for the OS to keep a small portion of memory free more proactively.
- 后台任务: Swap Daemon, Page Daemon
 - There are fewer than LW pages available, a background thread that is responsible for freeing memory runs.
 - The thread evicts pages until there are HW pages available.



公爾濱工業大學 HARBIN INSTITUTE OF TECHNOLOGY

- Memory pressure forces the OS to start paging out pages to make room for actively-used pages.
- Deciding which page to <u>evict</u> is encapsulated within the replacement policy of the OS.



Cache Management

- Goal in picking a replacement policy for this cache is to minimize the number of cache misses.
- The number of cache hits and misses let us calculate the *average memory access time(AMAT)*.

$$AMAT = (P_{hit} * T_{M}) + (P_{miss} * T_{D})$$

Arguement	Meaning			
T_{M}	The cost of accessing memory			
T_D	The cost of accessing disk			
P_{Hit} The probability of finding the data item in the cache(a hit)				
P_{Miss} The probability of not finding the data in the cache(a miss)				

假设内存访问的成本约100ns,磁盘访问的成本约10ms 若 $P_{hit} = 90\%$,则AMAT是? 若 $P_{hit} = 99.9\%$ 呢? 若 P_{hit} 接近 100%呢?



The Optimal Replacement Policy

- Leads to the fewest number of misses overall
 - 选择要替换的页: the page that will be accessed <u>furthest in the future</u>
 - Resulting in the fewest-possible cache misses
- Serve only as a comparison point, to know how close we are to perfect



Tracing the Optimal Policy

Reference Row

0 1 2 0 1 3 0 3 1 2 1

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	2	0,1,3
0	Hit		0,1,3
3	Hit		0,1,3
1	Hit		0,1,3
2	Miss	3	0,1,2
1	Hit		0,1,2

Future is not known.



A Simple Policy: FIFO

- Pages were placed in a queue when they enter the system.
- When a replacement occurs, the page on the tail of the queue(the "First-in" pages) is evicted.
 - It is simple to implement, but can't determine the importance of blocks.



Tracing the FIFIO Policy

Reference Row

0 1 2 0 1 3 0 3 1 2 1


Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	0	1,2,3
0	Miss	1	2,3,0
3	Hit		2,3,0
1	Miss		3,0,1
2	Miss	3	0,1,2
1	Hit		0,1,2

Even though page 0 had been accessed a number of times, FIFO still kicks it out.



BELADY'S ANOMALY

We would expect the cache hit rate to increase when the cache gets larger. But in this case, with FIFO, it gets worse.





Another Simple Policy: Random


- Picks a random page to replace under memory pressure.
 - It doesn't really try to be too intelligent in picking which blocks to evict.
 - Random does depends entirely upon how lucky <u>Random</u> gets in its choice.

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	0	1,2,3
0	Miss	1	2,3,0
3	Hit		2,3,0
1	Miss	3	2,0,1
2	Hit		2,0,1
1	Hit		2,0,1



Random Performance

Sometimes, Random is as good as optimal, achieving 6 hits on the example trace.



Random Performance over 10,000 Trials



Using History

- Lean on the past and use <u>history</u>.
 - Two type of historical information.

Historical Information	Meaning	Algorithms
recency	The more recently a page has been accessed, the more likely it will be accessed again	LRU
frequency	If a page has been accessed many times, It should not be replcaed as it clearly has some value	LFU



Using History: LRU

■ Replaces the least-recently-used page.


Reference Row
0 1 2 0 1 3 0 3 1 2 1

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		1,2,0
1	Hit		2,0,1
3	Miss	2	0,1,3
0	Hit		1,3,0
3	Hit		1,0,3
1	Hit		0,3,1
2	Miss	0	3,1,2
1	Hit		3,2,1




Workload Example: The No-Locality Workload

- Each reference is to a random page within the set of accessed pages.
 - Workload accesses 100 unique pages over time.
 - Choosing the next page to refer to at random




Workload Example: The 80-20 Workload

- Exhibits locality: 80% of the reference are made to 20% of the page
- The remaining 20% of the reference are made to the remaining 80% of the pages.



Workload Example: The Looping Sequential

- Refer to 50 pages in sequence.
 - Starting at 0, then 1, ... up to page 49, and then we Loop, repeating those accesses, for total of 10,000 accesses to 50 unique pages.



Implementing Historical Algorithms

公爾濱乙業大學 HARBIN INSTITUTE OF TECHNOLOGY

- To keep track of which pages have been least-and-recently used, the system has to do some accounting work on **every memory reference**.
 - Add a little bit of hardware support.




Approximating LRU

- Require some hardware support, in the form of a <u>use bit</u>
 - Whenever a page is referenced, the use bit is set by hardware to 1.
 - Hardware never clears the bit, though; that is the responsibility of the OS
- Clock Algorithm
 - All pages of the system arranges in a circular list.
 - A clock hand points to some particular page to begin with.



Clock Algorithm

■ The algorithm continues until it finds a use bit that is set to 0.




When a page fault occurs, the page the hand is pointing to is inspected.

The action taken depends on the Use bit



Workload with Clock Algorithm

Clock algorithm doesn't do as well as perfect LRU, it does better then approach that don't consider history at all.





Considering Dirty Pages

- The hardware include a modified bit (a.k.a dirty bit)
 - Page has been <u>modified</u> and is thus <u>dirty</u>, it must be written back to disk to evict it.在踢出dirty页的时候,需要首先把该页写到disk,代价很大, 故VMM倾向于evict干净页
 - Page has not been modified, the eviction is free.




Page Selection Policy

- The OS has to decide when to bring a page into memory.
- Presents the OS with some different options.




Prefetching

■ The OS guess that a page is about to be used, and thus bring it in ahead of time.



Physical Memory




Page 2 likely soon be accessed and thus should be brought into memory too



Clustering, Grouping


- Collect a number of pending writes together in memory and write them to disk in one write.
 - Perform a single large write more efficiently than many small ones.





Thrashing

- Memory is oversubscribed and the memory demands of the set of running processes exceeds the available physical memory.
 - Decide not to run a subset of processes.
 - Reduced set of processes working sets fit in memory.





公爾濱フ葉大學 HARBIN INSTITUTE OF TECHNOLOGY

User Heap

Page 0: Invalid

User Code

0


230

2³¹

Heap User (P0)

int *p = NULL; //set p = 0
*p = 10;//try to store value 10 to VA=0

- 内核是每个进程地址空间的一部分
 - 硬件保护.
- 页替换
 - 分段的FIFO
 - 页聚集



- System (S)

User (P1)

Unused

例题



- 有一个虚拟存储系统, 若进程在内存中占3页(开始时内存为空), 若采用先进 先出(FIFO)页面淘汰算法, 当执行如下访问页号序列后1, 2, 3, 4, 5, 1, 2, 5, 1, 2, 3, 4, 5, 会发生多少缺页?
 - A. 7
 - B. 8
 - **C.** 9
 - D. 10

答案:D

例题



某计算机按字节编址,其动态分区内存管理采用最佳适应算法,每次分配和回收内存后都对空闲分区链重新排序。当前空闲分区信息如下表所示。回收起始地址为60 K、大小为140KB的分区后,系统中空闲分区的数量、空闲分区链第一个分区的起始地址和大小分别是()。

分区起始地址	20 K	500 K	1000 K	200 K
分区大小	40 KB	80 KB	100 KB	200 KB

A. 3, 20K, 380KB B. 3, 500K, 80KB

C. 4, 20K, 180KB D. 4, 500K, 80KB

答案:B





■ 某系统采用改进型CLOCK置换算法,页表项中字段A为访问位,M为修改位。 A=0表示页最近没有被访问,A=1表示页最近被访问过。M=0表示页没有被修 改过,M=1表示页被修改过。按(A,M)所有可能的取值,将页分为四类:(0,0)、 (1,0)、(0,1)和(1,1),则该算法淘汰页的次序为()。

答案:A