

## TASK 1:

Configure EIGRP on the following network and show all necessary configuration steps for each router.




Solution:

Topology:



Setting Ips and default gateway:

# Data communication & Networking



## **Configuring EIGRP routing on router 1:**

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#Hostname R1

R1(config)#INT gig0/0

R1(config-if)#ip add 192.168.1.1 255.255.255.0

R1(config-if)#no shutdown

R1(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

R1(config-if)#exit

R1(config)#int se0/0/0

R1(config-if)#ip add 100.0.0.1 255.0.0.0

R1(config-if)#clock rate 64000

R1(config-if)#no shutdown

## Data communication & Networking Lab

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down R1(config-if)#exit

## **Configuring EIGRP routing on router 2:**

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname R2

R2(config)#int gig0/0

R2(config-if)#ip add 172.16.0.1 255.255.0.0

R2(config-if)#no shutdown

R2(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

R2(config-if)#exit

R2(config)#int se0/0/0

R2(config-if)#ip add 100.0.0.2 255.0.0.0

R2(config-if)#clock rate 64000

This command applies only to DCE interfaces

R2(config-if)#no shutdown

R2(config-if)#

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

R2(config-if)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

R2(config-if)#

R2(config-if)#exit

### **Enabling EIGRP (R1):**

R1>en

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#router eigrp 10

R1(config-router)#network 192.168.1.0 255.255.255.0

R1(config-router)#network 100.0.0.0 255.0.0.0

R1(config-router)#exit

R1(config)#

R1#

#### **Enabling EIGRP (R2):**

QAISER ABBAS (57245)

# Data communication & Networking

R2>en

R2#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#router eigrp 10


R2(config-router)#network 100.0.0.0 255.0.0.0

R2(config-router)#network 172.16.0.0 255.255.0.0


R2(config-router)#exit

R2(config)#


## Digital Ping test:



### R1#show ip eigrp neighbors




### Verify the route by pinging from PC 3 to PC 1:



### Verify the route by pinging from PC0 to PC2


```
PC0
          Config
                   Desktop
                                         Attributes
 Physical
                            Programming
  Command Prompt
  Packet Tracer PC Command Line 1.0
  C:\>ping 172.16.0.3
  Pinging 172.16.0.3 with 32 bytes of data:
  Reply from 172.16.0.3: bytes=32 time<1ms TTL=126
  Reply from 172.16.0.3: bytes=32 time<1ms TTL=126
  Reply from 172.16.0.3: bytes=32 time<lms TTL=126
  Reply from 172.16.0.3: bytes=32 time<1ms TTL=126
  Ping statistics for 172.16.0.3:
      Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
  Approximate round trip times in milli-seconds:
      Minimum = 0ms, Maximum = 0ms, Average = 0ms
  C:\>
```

Verify the route by pinging from PC2 to Router1:



## TASK 2


Configure EIGRP on the following network and show all necessary configuration steps for each router.




Solution:

# Data communication & Networking


# Topology:



## Availing extra ports on all routers:



## Adding default gateway and ip add. to every pc:



### Router 1:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#host R1

R1(config)#Int gig0/0

R1(config-if)#ip add 10.0.0.1 255.0.0.0

R1(config-if)#no shut

R1(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

R1(config-if)#exit R1(config)#int se0/0/0

# Data communication & Networking Lab

R1(config-if)#ip add 15.0.0.1 255.0.0.0

R1(config-if)#clock rate 64000

R1(config-if)#no shut

R1(config-if)#

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

R1(config-if)#exit

R1(config)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

R1(config)#

## Router2:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname R2

R2(config)#INT se0/0/0

R2(config-if)#ip add 15.0.0.2 255.0.0.0

R2(config-if)#no shut

R2(config-if)#exit

R2(config)#int se0/0/1

R2(config-if)#clock rate 64000

R2(config-if)#ip add 16.0.0.2 255.0.0.0

R2(config-if)#no shut

R2(config-if)#

R2(config-if)#exit

R2(config)#

## Router3:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname R3

R3(config)#int gig0/0

R3(config-if)#ip address 20.0.0.1 255.0.0.0

R3(config-if)#no shut

R3(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

R3(config-if)#ex

R3(config)#

R3>en

# Data communication & Networking Lab

R3#config t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#int se0/0/1

R3(config-if)#ip ad 16.0.0.1 255.0.0.0


R3(config-if)#no shut

R3(config-if)#

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up

## Configuration as per now:



### **Enabling the EIGRP (For R1):**

R1>en

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#router eigrp 10

R1(config-router)#network 10.0.0.0

R1(config-router)#network 15.0.0.0

R1(config-router)#exit

R1(config)#

### **Enabling the EIGRP (For R2):**

R2>en

R2#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#router eigrp 10

R2(config-router)#network 15.0.0.0

R2(config-router)#network 16.0.0.0

R2(config-router)#

#### **Enabling the EIGRP (For R3):**

R3>en

R3#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#router eigrp 10


R3(config-router)#network 16.0.0.0

R3(config-router)#network 20.0.0.0


R3(config-router)#exit

R3(config)#


## Digital Ping test:



# Pinging from PC 0 to PC 2:



Pinging Pc 1 from PC 3:



## Pinging Router 3 from Pc1:

```
₱PC1

  Physical
            Config
                     Desktop
                               Programming
                                             Attributes
  Command Prompt
   Packet Tracer PC Command Line 1.0
   C:\>ping 16.0.0.1
   Pinging 16.0.0.1 with 32 bytes of data:
   Reply from 16.0.0.1: bytes=32 time=28ms TTL=253
   Reply from 16.0.0.1: bytes=32 time=2ms TTL=253
   Reply from 16.0.0.1: bytes=32 time=2ms TTL=253
   Reply from 16.0.0.1: bytes=32 time=3ms TTL=253
   Ping statistics for 16.0.0.1:
   Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
       Minimum = 2ms, Maximum = 28ms, Average = 8ms
   C:\>
```