#### **Chapter 1:**

**Integer representations in computer systems** (Review)

**Topics:** 

Unsigned representations
Signed representations
Signed binary and hexadecimal arithmetic

**Reading:** 

5<sup>th</sup> Ed. Patterson and Hennessy 2.4, 3.2

### **Internal Representation of Integers**

Unsigned integers (non-negative) signed integers
Fixed number of digits

## **Decimal number system**

\* base (or radix) = 10

\* digits: 0, 1, 2, ..., 9

#### **Example:**

$$739 = 7 \times 10^2 + 3 \times 10^1 + 9 \times 10^0$$

#### **Rules:**

1) number digit positions 0,1,2..., right to left

2) multiply by radix to (digit position) power

## Binary number system

- \* base 2
- \* digits: 0, 1
- \* binary digit: bit

## **Example:**

Convert this binary number to decimal:

$$(1011)_2$$

$$= 1 \times 2^{3} + 0 \times 2^{2} + 1 \times 2^{1} + 1 \times 2^{0}$$

$$= 8 + 0 + 2 + 1$$

$$= 11$$

Useful information: powers of 2 are...

$$2^4 = 16, 2^5 = 32, 2^6 = 64, 2^7 = 128$$
  
 $2^8 = 256, 2^9 = 512, 2^{10} = 1024$ 

Table 1: All possible unsigned 4-bit binary numbers

binary	decimal
0000	0
0001	1
0010	2
0011	3
0100	4
0101	5
0110	6
0111	7
1000	8
1001	9
1010	10
1011	11
1100	12
1101	13
1110	14
1111	15

# **Example: 8-bit unsigned binary number**

 $(10010101)_2$ 

Convert to decimal:

$$= 27 + 24 + 22 + 20$$

$$= 128 + 16 + 4 + 1$$

$$= 149$$

Computer hardware is based on digital logic circuits; data is represented using binary system.

## **Convert decimal numbers to binary numbers**

#### Method 1 (slow but intuitive):

break up into sum of powers of 2

## **Example:**

 $(249)_{10}$ 

$$= 128 + 64 + 32 + 16 + 8 + 1$$

$$= 2^{7} + 2^{6} + 2^{5} + 2^{4} + 2^{3} + 2^{0}$$

$$= (1111 \ 1001)_{2}$$

### Convert decimal numbers to binary numbers

#### **Method 2 (shortcut):**

- 1) divide by 2
- 2) write down remainder
- 3) repeat until quotient = 0
- 4) combine remainders in reverse order (bottom to top)

#### **Example:**

 $(249)_{10}$ 

$$249/2 = 124 \text{ rem} = 1$$
  
 $124/2 = 62 \text{ rem} = 0$   
 $62/2 = 31 \text{ rem} = 0$   
 $31/2 = 15 \text{ rem} = 1$   
 $15/2 = 7 \text{ rem} = 1$   
 $7/2 = 3 \text{ rem} = 1$   
 $3/2 = 1 \text{ rem} = 1$   
 $1/2 = 0 \text{ rem} = 1$ 

$$249 = (1111 \ 1001)_2$$

## Hexadecimal (hex) number system

\* base 16

\* digits: 0, 1, 2, ..., 9, A, B, C, D, E, F

(shorthand for binary)

Example: (0x means base 16)

Convert 3-digit hex int to decimal:

0x38F

$$= 3 \times 16^{2} + 8 \times 16^{1} + 15 \times 16^{0}$$

$$= 3 \times 256 + 8 \times 16 + 15$$

$$= 911$$

## Convert unsigned decimal int to hex

Method 1: break into sums of powers of 16

$$(574)_{10}$$

$$= 2 \times 256 + 3 \times 16 + 14$$

$$= 2 \times 16^{2} + 3 \times 16^{1} + 14 \times 16^{0}$$

$$= 0 \times 23E$$

Method 2: divide repeatedly by 16

$$(574)_{10}$$

$$574/16 = 35$$
, rem = 14 (which is 0xE)  
 $35/16 = 2$ , rem = 3  
 $2/16 = 0$ , rem = 2

$$(574)_{10} = 0x23E$$

# **Convert hexadecimal numbers to binary** numbers

one hexadecimal digit = 4 bits start at least significant (rightmost) digit

#### **Example:**

#### 0x5B3

$$5 = 0101$$
,  $B = 1011$ ,  $3 = 0011$ 

$$0x5B3 = (0101\ 1011\ 0011)_2$$

Convert binary ints to hex (reverse):

group bits into groups of 4 start at right most bit

## Octal number system

\* base 8

\* digits: 0, 1, 2, ..., 7

#### Convert octal to decimal:

1)number digit positions 0,1,2... right to left
2) multiply each digit by radix to (digit position)
power

Convert octal to binary:

each octal digit = 3 bits

# **Unsigned integer addition**

# Binary:

#### Hexadecimal:

# **Unsigned integer subtraction**

# Binary:

## **Systems for representing signed integers:**

- 1. sign-magnitude (SM)
- 2. one's complement (OC) (*skip*)
- 3. two's complement (TC)

#### **Binary Sign-magnitude**

#### **Rules:**

- 1) most significant (leftmost) bit is sign bit non-negative if sign bit = 0, negative if sign bit = 1
- 2) non-negative numbers same as unsigned
- 3) rest of bits represents magnitude of integer

#### **Convert 8-bit binary SM to decimal:**

$$0010\ 0101 = +\ 010\ 0101 = 32 + 4 + 1 = 37$$
  
Convert binary SM to decimal:  
 $1110\ 0101 = -\ 0110\ 0101$   
 $= -\ (64 + 32 + 4 + 1)$   
 $= -\ 101$ 

# **Convert decimal to 8-bit binary SM:**

$$X = -13 = ??$$

$$-X = 13 = 0000 \ 1101$$
  
 $X = 1000 \ 1101$ 

Dirty zero problem in SM:

$$(0000)_2 = 0$$
  
 $(1000)_2 = -0 = 0$ 

Two different representations for zero Not suitable for fast hardware implementations

# **One's Complement (OC):**

#### **Rules**:

- 1) most significant (leftmost) bit is sign bit non-negative if sign bit = 0, negative if sign bit = 1
- 2) non-negative numbers same as unsigned
- 3) to negate a OC binary int:

flip/complement each bit

## **Convert 8-bit OC binary to decimal:**

$$(1100\ 0101)_2 = -(0011\ 1010)_2$$
  
=  $-(32+16+8+2) = -58$ 

## **Convert decimal to 8-bit OC binary:**

$$-58 = ??$$
Let X = -58
$$-X = 58 = (0011 \ 1010)_2$$
X = (1100 0101)<sub>2</sub>

Dirty zero problem in OC:

$$(0000)_2 = 0$$
  
 $(1111)_2 = -0 = 0$ 


## **Two's complement**

#### **Rules**:

- 1) most significant (leftmost) bit is sign bit non-negative if sign bit = 0, negative if sign bit = 1
- 2) non-negative numbers same as unsigned
- 3) to negate a two's complement binary number,
- i. complement (or flip) each bit
- ii. add 1 (discard carry out)

# **Example:**

Convert 8-bit TC binary int to decimal:



## **Example:**

Negate TC binary int:

$$X = (0010 \ 0110)_2$$

$$-X = (1101\ 1001)_2 + 1 = (1101\ 1010)_2$$

### **Example:**

Convert -29 to 8-bit TC binary:

Let 
$$X = -29$$
  
 $-X = 29 = 0001 \ 1101$   
 $X = 1110 \ 0010 + 1 = 1110 \ 0011$ 

## **Shortcut for negating binary TC int:**

- 1) look for rightmost bit == 1
- 2) complement each bit to the left
- 3) (all other bits stay the same)

#### Example:

$$X = (1011 \ \underline{1000})_2$$
 [rightmost 1 is underlined]  
- $X = (01001000)_2$ 

# Another way to convert TC binary int to decimal:

\* for n-bit ints, digit position n-1 is  $-2^{(n-1)}$ 

#### **Examples:**

$$X = (1110\ 0011)_2$$
  
= -128 + 64 + 32 + 2 + 1 = -29

### No dirty zeros in TC:

$$(0000)_2 = 0$$

Try to construct negative zero:

$$-(0000)_2 = (1111)_2 + 1 = 10000$$

Discard carryout:  $-0 = (0000)_2$ !

#### **Sign-extension in TC:**

(writing the same integer, but with more bits)

4-bit to 8-bit: 
$$(0101)_2 = (0000 \ 0101)_2$$
  
4-bit to 8-bit:  $(1101)_2 = (1111 \ 1101)_2$ 

Extend (or duplicate) the sign bit.

# **Comparison of four integer systems (4 bits):**

	Unsigned	SM	OC	TC
0000	0	0	0	0
0001	1	1	1	1
0010	2	2	2	2
0011	3	3	3	3
0100	4	4	4	4
0101	5	5	5	5
0110	6	6	6	6
0111	7	7	7	7
1000	8	0	-7	-8
1001	9	-1	-6	-7
1010	10	-2	-5	-6
1011	11	-3	-4	-5
1100	12	-4	-3	-4
1101	13	-5	-2	-3
1110	14	-6	-1	-2
1111	15	-7	0	-1

## Range of binary integer representations:

Unsigned:

4-bit: 0 to 
$$15 = 0$$
 to  $(2^4 - 1)$ 

N-bit: 0 to  $(2^N - 1)$ 

SM:

4-bit: -7 to 
$$7 = -(2^3 - 1)$$
 to  $(2^3 - 1)$ 

N-bit: 
$$-(2^{N-1}-1)$$
 to  $(2^{N-1}-1)$ 

TC:

4-bit: -8 to 
$$7 = (-2^3)$$
 to  $(2^3 - 1)$ 

N-bit: 
$$(-2^{N-1})$$
 to  $(2^{N-1} - 1)$ 

# Range of integer data types:

short (usually 16 bits)

$$(-2^{16-1})$$
 to  $(2^{16-1} - 1)$ , or  $-32768$  to  $32767$ 

int (usually 32 bits)

$$(-2^{32-1})$$
 to  $(2^{32-1} - 1)$ , or  $-2,147,483,648$  to  $2,147,483,647$ 

long (usually 64 bits)

$$(-2^{64-1})$$
 to  $(2^{64-1}-1)$ 

# Two's complement arithmetic

### similar to unsigned

- 1) treat sign bit as numeric bit
- 2) if carry out is produced, discard it
- 3) check for overflow

#### **Examples:**

$$\begin{array}{c}
11010110 \\
+ 11100001 \\
\hline
1 10110111
\end{array}$$

discard carryout: ans  $= 1011 \ 0111$ 

sum of two non-negative numbers cannot give negative result! *Overflow* occurred.

sum of two negative integers cannot give non-negative result! *Overflow* occurred.

#### **Definition of overflow:**

Overflow is an error condition in which the result of a computation does not fit into the available number of bits.

#### In TC arithmetic:

- 1) if we add 2 positive integers and get a negative result, or
- 2) if we add 2 negative integers and get a positive result,

we have overflow.

#### Consider C++ code:

```
int sum = 0, i;
  for (i=0; i<10; i++) {
    sum = sum + 1000000000;
    cout << sum << endl;
}</pre>
```

#### Compile and run; program output:

```
1000000000
2000000000
-1294967296
-294967296 [etc etc]
```

## Two's complement subtraction

$$X - Y = X + (-Y)$$

#### **Example:**

$$X = 1001 \ 0010$$

$$Y = 0101 11111$$

$$-Y = 1010\ 0001$$

$$X - Y = 1001\ 0010 + 1010\ 0001$$
  
= 1\ 00110011

Discard carryout; result = 0011 0011

overflow occurred

[Note: for subtraction, check X + (-Y), using the overflow check for addition!]

## Two's complement hexadecimal

#### **Rules**:

- 1) most significant (leftmost) digit is sign digit non-negative if sign digit = negative if sign digit =
- 2) non-negative integers same as unsigned
- 3) to negate a two's complement hex int,
- i. subtract each digit from f
- ii. add 1 (discard carry out)

## **Examples:**

Convert 2-digit TC hex int to decimal

$$X = 0xab$$
-  $X = 0xff - 0xab + 1 = 0x55$ 
=  $5 \times 16 + 5 = 85$ 
 $X = -85$ 

Convert decimal int to 2-digit TC hex:

$$X = -73$$

#### TC hex addition/subtraction:

$$0x5678 + 0x432b$$

0x5678 0x432b 0x99a3, overflow

0xdcba + 0xe2f3

0xdcba

<u>0xe2f3</u>

0x1bfad

discard carryout; result = 0xbfad

0x1cba - 0xbd0d

= 0x1cba + - (0xbd0d)

= 0x1cba + 0xffff - 0xbd0d + 1

= 0x1cba + 0x42f3

0x1cba 0x42f3 0x5fad

# Lab exercises for Chapter 1:

Lab 1.1: Binary and hexadecimal exercises

Lab 1.2: Setting up spim / xspim

#### CSc 256 Practice Exercise #1 on arithmetic

This file can be found at

http://userwww.sfsu.edu/~whsu/csc256/LABS/DOCS/ex1.txt

For problems 1-9, solutions can be found in

http://userwww.sfsu.edu/~whsu/csc256/LABS/DOCS/ex1soln.txt

1) Consider the 16-bit binary integer  $X = 1001\ 0000\ 0000\ 0011$ .

Convert X to decimal if X is

- a. unsigned b. in sign-magnitude notation
- c. in one's complement notation d. in two's complement notation

For problems 2-6, assume all integers are in binary and in two's complement notation. Remember to indicate overflow if necessary.

- $2)\ 0110\ 1010 + 1001\ 1110 = ?$
- 3)  $1001\ 11111 + 1001\ 0001 = ?$
- 4)  $1000\ 1111 0001\ 0000 = ?$
- 5) 0001 0010 0010 1111 = ?
- 6) 1111 1010 1110 1110 = ?

For problems 7-9, assume all integers are in hexadecimal and two's complement notation. Remember to indicate overflow if necessary.

- 7) 0x2AF6 + 0x7017 = ?
- 8) 0x345E + 0xFFAB = ?
- 9) 0x966A 0x6996 = ?