

VLSM untuk Vlan Dengan network 200.20.20.0/24

No	Vlan	Network	Range	Broadcast
1	vlanA1	200.20.20.0	200.20.20.1 - 200.20.20.6	200.20.20.7
2	vlanA2	200.20.20.8	200.20.20.9-200.20.20.14	200.20.20.15
3	vlanA3	200.20.20.16	200.20.20.17 - 200.20.20.22	200.20.20.23
4	vlanA4	200.20.20.24	200.20.20.25 - 200.20.20.30	200.20.20.31
5	vlanA5	200.20.20.32	200.20.20.33 - 200.20.20.38	200.20.20.39
6	vlanB1	200.20.20.40	200.20.20.41 - 200.20.20.46	200.20.20.47
7	vlanB2	200.20.20.48	200.20.20.49 - 200.20.20.54	200.20.20.55
8	vlanB3	200.20.20.56	200.20.20.57 - 200.20.20.62	200.20.20.63
9	vlanB4	200.20.20.64	200.20.20.65 - 200.20.20.70	200.20.20.71
10	vlanB5	200.20.20.72	200.20.20.73 - 200.20.20.78	200.20.20.79
11	vlanC1	200.20.20.80	200.20.20.81 - 200.20.20.86	200.20.20.87
12	vlanC2	200.20.20.88	200.20.20.89 - 200.20.20.94	200.20.20.95
13	vlanC3	200.20.20.96	200.20.20.97 - 200.20.20.102	200.20.20.103
14	vlanC4	200.20.20.104	200.20.20.105 - 200.20.20.110	200.20.20.111
15	vlanC5	200.20.20.112	200.20.20.113 - 200.20.20.118	200.20.20.119
16	vlanD1	200.20.20.120	200.20.20.121 - 200.20.20.126	200.20.20.127
17	vlanD2	200.20.20.128	200.20.20.129 - 200.20.20.134	200.20.20.135
18	vlanD3	200.20.20.136	200.20.20.137 - 200.20.20.142	200.20.20.143
19	vlanD4	200.20.20.144	200.20.20.145 - 200.20.20.150	200.20.20.151
20	vlanD5	200.20.20.152	200.20.20.153 - 200.20.20.158	200.20.20.159
21	vlanE1	200.20.20.160	200.20.20.161 - 200.20.20.166	200.20.20.167
22	vlanE2	200.20.20.168	200.20.20.169 - 200.20.20.174	200.20.20.175
23	vlanE3	200.20.20.176	200.20.20.177 - 200.20.20.182	200.20.20.183
24	vlanE4	200.20.20.184	200.20.20.185 - 200.20.20.190	200.20.20.191
25	vlanE5	200.20.20.192	200.20.20.193 - 200.20.20.198	200.20.20.199

1. Konfigurasi switch untuk VlanA1

```

Switch>en
Switch#conf t
Switch(config)#vtp mode server
Switch(config)#vtp domain vlanA
Switch(config)#vlan 10
Switch(config-vlan)#name vlanA1
Switch(config-vlan)#e
Switch(config)#vlan 20

```

```
Switch(config-vlan)#name vlanA2
Switch(config-vlan)#e
Switch(config)#vlan 30
Switch(config-vlan)#name vlanA3
Switch(config-vlan)#e
Switch(config)#vlan 40
Switch(config-vlan)#name vlanA4
Switch(config-vlan)#e
Switch(config)#vlan 50
Switch(config-vlan)#name vlanA5
Switch(config-vlan)#e
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 10
Switch(config-if-range)#e
Switch(config)#int fa0/20
Switch(config)#int range fa0/20-23
Switch(config-if-range)#sw mo trunk
Switch(config)#int gi0/1
Switch(config-if)#sw mo trunk
Switch#write memory
```

2. Konfigurasi switch untuk VlanA3

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanA
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 20
Switch(config-if-range)#ex
Switch#write memory
```

3. Konfigurasi switch untuk VlanA3

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
```

```
Setting device to VTP CLIENT mode.  
Switch(config)#vtp domain vlanA  
Domain name already set to vlanA.  
Switch(config)#int range fa0/1-10  
Switch(config-if-range)#sw mo ac  
Switch(config-if-range)#sw ac vlan 30  
Switch(config-if-range)#e  
Switch(config)#do write memory
```

4. Konfigurasi switch untuk vlanA4

```
Switch>en  
Switch#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
Switch(config)#vtp mode client  
Setting device to VTP CLIENT mode.  
Switch(config)#vtp domain vlanA  
Domain name already set to vlanA.  
Switch(config)#int range fa0/1-10  
Switch(config-if-range)#sw mo ac  
Switch(config-if-range)#sw ac vlan 40  
Switch(config-if-range)#e  
Switch(config)#do write memory
```

5. Konfigurasi switch untuk vlanA5

```
Switch>en  
Switch#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
Switch(config)#vtp mode client  
Setting device to VTP CLIENT mode.  
Switch(config)#vtp domain vlanA  
Domain name already set to vlanA.  
Switch(config)#int range fa0/1-10  
Switch(config-if-range)#sw mo ac  
Switch(config-if-range)#sw ac vlan 50  
Switch(config-if-range)#ex  
Switch(config)#do write memory
```

6. Konfigurasi Router untuk vlanA

```
Router>en  
Router#conf t  
Enter configuration commands, one per line. End with CNTL/Z.
```

```
Router(config)#hostname VlanA
^
% Invalid input detected at '^' marker.
Router(config)#hostname VlanA
Router(config)#hostname VlanA
VlanA(config)#int fa0/0
VlanA(config-if)#no sh

VlanA(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to
up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0, changed state to up

VlanA(config-if)#ex
VlanA(config)#int fa0/0.10
VlanA(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.10, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.10, changed state to up

VlanA(config-subif)#encapsulation dot1Q 10
VlanA(config-subif)#ip add 200.20.20.1 255.255.255.248
VlanA(config-subif)#no sh
VlanA(config-subif)#ex
VlanA(config)#int fa0/0.20
VlanA(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.20, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.20, changed state to up

VlanA(config-subif)#encapsulation dot1Q 20
VlanA(config-subif)#ip add 200.20.20.9 255.255.255.248
VlanA(config-subif)#no sh
VlanA(config-subif)#ex
VlanA(config)#int fa0/0.30
VlanA(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.30, changed state
to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.30, changed state to up

```
VlanA(config-subif)#encapsulation dot1Q 30
VlanA(config-subif)#ip add 200.20.20.17 255.255.255.248
VlanA(config-subif)#no sh
VlanA(config-subif)#ex
VlanA(config)#int fa0/0.40
VlanA(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.40, changed state
to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.40, changed state to up

```
VlanA(config-subif)#encapsulation dot1Q 40
VlanA(config-subif)#ip add 200.20.20.25 255.255.255.248
VlanA(config-subif)#no sh
VlanA(config-subif)#ex
VlanA(config)#int fa0/0.50
VlanA(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.50, changed state
to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.50, changed state to up

```
VlanA(config-subif)#encapsulation dot1Q 50
VlanA(config-subif)#ip add 200.20.20.33 255.255.255.248
VlanA(config-subif)#no sh
VlanA(config-subif)#ex
VlanA(config)#ip dhcp pool vlanA1
VlanA(dhcp-config)#net 200.20.20.0 255.255.255.248
VlanA(dhcp-config)#def
VlanA(dhcp-config)#default-router 200.20.20.1
VlanA(dhcp-config)#ex
VlanA(config)#ip dhcp pool vlanA2
VlanA(dhcp-config)#net 200.20.20.8 255.255.255.248
VlanA(dhcp-config)#default-router 200.20.20.9
VlanA(dhcp-config)#ex
VlanA(config)#ip dhcp pool vlanA3
VlanA(dhcp-config)#net 200.20.20.16 255.255.255.248
VlanA(dhcp-config)#default-router 200.20.20.17
VlanA(dhcp-config)#ex
VlanA(config)#ip dhcp pool vlanA4
VlanA(dhcp-config)#net 200.20.20.24 255.255.255.248
```

```
VlanA(dhcp-config)#default-router 200.20.20.25
VlanA(dhcp-config)#ex
VlanA(config)#ip dhcp pool vlanA5
VlanA(dhcp-config)#net 200.20.20.32 255.255.255.248
VlanA(dhcp-config)#default-router 200.20.20.33
VlanA(dhcp-config)#ex
VlanA(config)#do write memory
```

7. Konfigurasi switch untuk VlanB1

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode server
Device mode already VTP SERVER.
Switch(config)#vtp domain vlanB
Changing VTP domain name from NULL to vlanB
Switch(config)#vlan 10
Switch(config-vlan)#name vlanB1
Switch(config-vlan)#ex
Switch(config)#vlan 20
Switch(config-vlan)#name vlanB2
Switch(config-vlan)#e
Switch(config)#vlan 30
Switch(config-vlan)#name vlanB3
Switch(config-vlan)#e
Switch(config)#vlan 40
Switch(config-vlan)#name vlanB4
Switch(config-vlan)#e
Switch(config)#vlan 50
Switch(config-vlan)#name vlanB5
Switch(config-vlan)#e
Switch(config)#int ra fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 10
Switch(config-if-range)#ex
Switch(config)#int range fa0/20-23
Switch(config-if-range)#sw mo trunk
Switch(config-if-range)#ex
Switch(config)#int gi0/1
Switch(config-if)#sw mo trunk
Switch(config-if)#ex
Switch(config)#do write memory
```

8. Konfigurasi switch untuk VlanB2

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanB
Changing VTP domain name from NULL to vlanB
Switch(config)#int ra fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 20
Switch(config-if-range)#ex
Switch(config)#do write memory
```

9. Konfigurasi switch untuk VlanB3

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanB
Domain name already set to vlanB.
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 30
Switch(config-if-range)#ex
Switch(config)#do write memory
```

10. Konfigurasi switch untuk VlanB4

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanB
Domain name already set to vlanB.
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 40
Switch(config-if-range)#ex
Switch(config)#do write memory
```

11. Konfigurasi switch untuk VlanB2

```
Switch>en
```

```
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanB
Domain name already set to vlanB.
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 50
Switch(config-if-range)#ex
Switch(config)#do write memory
```

12. Konfigurasi Router untuk VlanB

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host vlanB
vlanB(config)#int fa0/0
vlanB(config-if)#no sh

vlanB(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to
up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0, changed state to up

vlanB(config-if)#ex
vlanB(config)#int fa0/0.10
vlanB(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.10, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.10, changed state to up

vlanB(config-subif)#encapsulation dot1Q 10
vlanB(config-subif)#ip add 200.20.20.41 255.255.255.248
vlanB(config-subif)#no sh
vlanB(config-subif)#ex
vlanB(config)#int fa0/0.20
vlanB(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.20, changed state
to up
```


%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.20, changed state to up

```
vlanB(config-subif)#encapsulation dot1Q 20
vlanB(config-subif)#ip add 200.20.20.49 255.255.255.248
vlanB(config-subif)#no sh
vlanB(config-subif)#ex
vlanB(config)#int fa0/0.30
vlanB(config-subif)#
```

%LINK-5-CHANGED: Interface FastEthernet0/0.30, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.30, changed state to up

```
vlanB(config-subif)#ex
vlanB(config)#int fa0/0.30
vlanB(config-subif)#encapsulation dot1Q 30
vlanB(config-subif)#ip add 200.20.20.57 255.255.255.248
vlanB(config-subif)#no sh
vlanB(config-subif)#ex
vlanB(config)#int fa0/0.40
vlanB(config-subif)#
```

%LINK-5-CHANGED: Interface FastEthernet0/0.40, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.40, changed state to up

```
vlanB(config-subif)#encapsulation dot1Q 40
vlanB(config-subif)#ip add 200.20.20.65 255.255.255.248
vlanB(config-subif)#no sh
vlanB(config-subif)#ex
vlanB(config)#int fa0/0.50
vlanB(config-subif)#
```

%LINK-5-CHANGED: Interface FastEthernet0/0.50, changed state
to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/0.50, changed state to up

```
vlanB(config-subif)#ip add 200.20.20.73 255.255.255.248
```

% Configuring IP routing on a LAN subinterface is only allowed if
that

subinterface is already configured as part of an IEEE 802.1Q, IEEE 802.1Q,
or ISL vLAN.

```
vlanB(config-subif)#encapsulation dot1Q 50
vlanB(config-subif)#ip add 200.20.20.73 255.255.255.248
vlanB(config-subif)#no sh
vlanB(config-subif)#ex
vlanB(config)#ip dhcp pool vlanB1
vlanB(dhcp-config)#net 200.20.20.40 255.255.255.248
vlanB(dhcp-config)#default-router 200.20.20.41
vlanB(dhcp-config)#ex
vlanB(config)#ip dhcp pool vlanB2
vlanB(dhcp-config)#net 200.20.20.48 255.255.255.248
vlanB(dhcp-config)#default-router 200.20.20.49
vlanB(dhcp-config)#no sh
vlanB(dhcp-config)#ex
vlanB(config)#ip dhcp pool vlanB3
vlanB(dhcp-config)#net 200.20.20.56 255.255.255.248
vlanB(dhcp-config)#default-router 200.20.20.57
vlanB(dhcp-config)#ex
vlanB(config)#ip dhcp pool vlanB4
vlanB(dhcp-config)#net 200.20.20.64 255.255.255.248
vlanB(dhcp-config)#default-router 200.20.20.65
vlanB(dhcp-config)#ex
vlanB(config)#ip dhcp pool vlanB5
vlanB(dhcp-config)#net 200.20.20.72 255.255.255.248
vlanB(dhcp-config)#default-router 200.20.20.73
vlanB(dhcp-config)#ex
vlanB(config)#do show write memory
vlanB(config)#do write memory
```

13. Konfigurasi switch untuk VlanC1

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode server
Device mode already VTP SERVER.
Switch(config)#vtp domain vlanC
Changing VTP domain name from NULL to vlanC
Switch(config)#vlan 10
Switch(config-vlan)#name vlanC1
Switch(config-vlan)#ex
Switch(config)#vlan 20
Switch(config-vlan)#name vlanC2
```

```
Switch(config-vlan)#e
Switch(config)#vlan 30
Switch(config-vlan)#name vlanC3
Switch(config-vlan)#e
Switch(config)#vlan 40
Switch(config-vlan)#name vlanC4
Switch(config-vlan)#e
Switch(config)#vlan 50
Switch(config-vlan)#name vlanC5
Switch(config-vlan)#e
Switch(config)#int range gi0/1-2
Switch(config-if-range)#sw mo trunk
Switch(config-if-range)#
Switch(config-if-range)#ex
Switch(config)#do write memory
Building configuration...
[OK]
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 10
```

14. Konfigurasi switch untuk VlanC2

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanC
Changing VTP domain name from NULL to vlanC
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 20
Switch(config-if-range)#ex
Switch(config)#int gi0/1
Switch(config-if)#sw mo trunk
Switch(config-if)#do write memory
```

15. Konfigurasi switch untuk VlanC3

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanC
```

```
Changing VTP domain name from NULL to vlanC
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 30
Switch(config-if-range)#ex
Switch(config)#int gi0/2
Switch(config-if)#sw mo trunk
Switch(config-if)#do write memory
```

16. Konfigurasi switch untuk VlanC4

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanC
Changing VTP domain name from NULL to vlanC
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 40
Switch(config-if-range)#ex
Switch(config)#int gi 0/1
Switch(config-if)#sw mo trunk
Switch(config-if)#do write memory
```

17. Konfigurasi switch untuk VlanC5

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#vtp domain vlanC
Changing VTP domain name from NULL to vlanC
Switch(config)#int range fa0/1-10
Switch(config-if-range)#sw mo ac
Switch(config-if-range)#sw ac vlan 50
Switch(config-if-range)#ex
Switch(config)#do write memory
```

18. Router untuk VlanC

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
```

```
Router(config)#host vlanC
vlanC(config)#int fa0/0
vlanC(config-if)#no sh
vlanC(config-if)#ex
vlanC(config)#int fa0/0.10
vlanC(config-subif)#encapsulation dot1Q 10
vlanC(config-subif)#ip add 200.20.20.81 255.255.255.248
vlanC(config-subif)#no sh
vlanC(config-subif)#ex
vlanC(config)#int fa0/0.20
vlanC(config-subif)#encapsulation dot1Q 20
vlanC(config-subif)#ip add 200.20.20.89 255.255.255.248
vlanC(config-subif)#no sh
vlanC(config-subif)#ex
vlanC(config)#int fa0/0.30
vlanC(config-subif)#
vlanC(config-subif)#encapsulation dot1Q 30
vlanC(config-subif)#ip add 200.20.20.97 255.255.255.248
vlanC(config-subif)#no sh
vlanC(config-subif)#int fa0/0.40
vlanC(config-subif)#
vlanC(config-subif)#encapsulation dot1Q 40
vlanC(config-subif)#ip add 200.20.20.105 255.255.255.248
vlanC(config-subif)#no sh
vlanC(config-subif)#ex
vlanC(config)#int fa0/0.50
vlanC(config-subif)#
vlanC(config-subif)#encapsulation dot1Q 50
vlanC(config-subif)#ip add 200.20.20.113 255.255.255.248
vlanC(config-subif)#no sh
vlanC(config-subif)#ex
vlanC(config)#ip dhcp pool vlanC1
vlanC(dhcp-config)#net 200.20.20.80 255.255.255.248
vlanC(dhcp-config)#default-router 200.20.20.81
vlanC(dhcp-config)#ex
vlanC(config)#ip dhcp pool vlanC2
vlanC(dhcp-config)#net 200.20.20.88 255.255.255.248
vlanC(dhcp-config)#default-router 200.20.20.89
vlanC(dhcp-config)#ex
vlanC(config)#ip dhcp pool vlanC3
vlanC(dhcp-config)#net 200.20.20.96 255.255.255.248
vlanC(dhcp-config)#default-router 200.20.20.97
vlanC(dhcp-config)#ex
vlanC(config)#ip dhcp pool vlanC4
vlanC(dhcp-config)#net 200.20.20.104 255.255.255.248
vlanC(dhcp-config)#default-router 200.20.20.105
```

```
vlanC(dhcp-config)#ex
vlanC(config)#ip dhcp pool vlanC5
vlanC(dhcp-config)#net 200.20.20.112 255.255.255.248
vlanC(dhcp-config)#default-router 200.20.20.113
vlanC(dhcp-config)#ex
vlanC(config)#do write memory
```

19. Konfigurasi switch untuk VlanD1, VlanD2, VlanD3, VlanD4, VlanD5

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vlan 10
Switch(config-vlan)#name vlanD1
Switch(config-vlan)#ex
Switch(config)#vlan 20
Switch(config-vlan)#name vlanD2
Switch(config-vlan)#ex
Switch(config)#vlan 30
Switch(config-vlan)#name vlanD3
Switch(config-vlan)#ex
Switch(config)#vlan 40
Switch(config-vlan)#name vlanD4
Switch(config-vlan)#ex
Switch(config)#vlan 50
Switch(config-vlan)#name vlanD5
Switch(config-vlan)#ex
Switch(config)#int fa0/1
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 10
Switch(config-if)#ex
Switch(config)#int fa0/2
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 20
Switch(config-if)#ex
Switch(config)#int fa0/3
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 30
Switch(config-if)#ex
Switch(config)#int fa0/4
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 40
Switch(config-if)#ex
```

```
Switch(config)#int fa0/5
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 50
Switch(config-if)#ex
Switch(config)#do write memory
Switch(config)#int gi0/1
Switch(config-if)#sw mo trunk
```

20. Router untuk VlanD

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host vlanD
vlanD(config)#int fa0/0
vlanD(config-if)#no sh
vlanD(config-if)#ex
vlanD(config)#int fa0/0.10
vlanD(config-subif)#
vlanD(config-subif)#encapsulation dot1Q 40
vlanD(config-subif)#encapsulation dot1Q 10
vlanD(config-subif)#ip add 200.20.20.121 255.255.255.248
vlanD(config-subif)#ex
vlanD(config)#int fa0/0.20
vlanD(config-subif)#
vlanD(config-subif)#encapsulation dot1Q 20
vlanD(config-subif)#ip add 200.20.20.129 255.255.255.248
vlanD(config-subif)#ex
vlanD(config)#int fa0/0.30
vlanD(config-subif)#
vlanD(config-subif)#encapsulation dot1Q 30
vlanD(config-subif)#ip add 200.20.20.137 255.255.255.248
vlanD(config-subif)#ex
vlanD(config)#int fa0/0.40
vlanD(config-subif)#
vlanD(config-subif)#encapsulation dot1Q 40
vlanD(config-subif)#ip add 200.20.20.145 255.255.255.248
vlanD(config-subif)#ex
vlanD(config)#int fa0/0.50
vlanD(config-subif)#
vlanD(config-subif)#encapsulation dot1Q 50
vlanD(config-subif)#ip add 200.20.20.153 255.255.255.248
vlanD(config-subif)#ex
vlanD(config)#ip dhcp pool vlanD1
vlanD(dhcp-config)#net 200.20.20.120 255.255.255.248
```



```
vlanD(dhcp-config)#default-router 200.20.20.121
vlanD(dhcp-config)#ex
vlanD(config)#ip dhcp pool vlanD2
vlanD(dhcp-config)#net 200.20.20.128 255.255.255.248
vlanD(dhcp-config)#default-router 200.20.20.129
vlanD(dhcp-config)#ex
vlanD(config)#ip dhcp pool vlanD3
vlanD(dhcp-config)#net 200.20.20.136 255.255.255.248
vlanD(dhcp-config)#default-router 200.20.20.137
vlanD(dhcp-config)#ex
vlanD(config)#ip dhcp pool vlanD4
vlanD(dhcp-config)#net 200.20.20.144 255.255.255.248
vlanD(dhcp-config)#default-router 200.20.20.145
vlanD(dhcp-config)#ex
vlanD(config)#ip dhcp pool vlanD5
vlanD(dhcp-config)#net 200.20.20.152 255.255.255.248
vlanD(dhcp-config)#default-router 200.20.20.153
vlanD(dhcp-config)#ex
```

21. Konfigurasi switch untuk VlanE1, VlanE2, VlanE3, VlanE4, VlanE5

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vlan 10
Switch(config-vlan)#name vlanE1
Switch(config-vlan)#ex
Switch(config)#vlan 20
Switch(config-vlan)#name vlanE2
Switch(config-vlan)#ex
Switch(config)#vlan 30
Switch(config-vlan)#name vlanE3
Switch(config-vlan)#e
Switch(config)#vlan 40
Switch(config-vlan)#name vlanE4
Switch(config-vlan)#e
Switch(config)#vlan 50
Switch(config-vlan)#name vlanE5
Switch(config-vlan)#e
Switch(config)#int gi0/1
Switch(config-if)#sw mo trunk
Switch(config-if)#ex
Switch(config)#int fa0/1
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 10
Switch(config-if)#ex
```



```
Switch(config)#int fa0/2
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 20
Switch(config-if)#ex
Switch(config)#int fa0/3
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 30
Switch(config-if)#ex
Switch(config)#int fa0/4
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 40
Switch(config-if)#ex
Switch(config)#int fa0/5
Switch(config-if)#sw mo ac
Switch(config-if)#sw ac vlan 50
Switch(config-if)#ex
Switch(config)#do write memory
```

22. Router untuk VlanE

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host vlanE
vlanE(config)#int fa0/0
vlanE(config-if)#no sh
vlanE(config-if)#ex
vlanE(config)#int fa0/0.10
vlanE(config-subif)#
vlanE(config-subif)#encapsulation dot1Q 10
vlanE(config-subif)#ip add 200.20.20.161 255.255.255.248
vlanE(config-subif)#no sh
vlanE(config-subif)#ex
vlanE(config)#int fa0/0.20
vlanE(config-subif)#
vlanE(config-subif)#encapsulation dot1Q 20
vlanE(config-subif)#ip add 200.20.20.169 255.255.255.248
vlanE(config-subif)#no sh
vlanE(config-subif)#ex
vlanE(config)#int fa0/0.30
vlanE(config-subif)#
vlanE(config-subif)#encapsulation dot1Q 30
vlanE(config-subif)#ip add 200.20.20.176 255.255.255.248
Bad mask /29 for address 200.20.20.176
vlanE(config-subif)#ip add 200.20.20.177 255.255.255.248
vlanE(config-subif)#no sh
```

```

vlanE(config-subif)#ex
vlanE(config)#int fa0/0.40
vlanE(config-subif)#
vlanE(config-subif)#encapsulation dot1Q 40
vlanE(config-subif)#ip add 200.20.20.185 255.255.255.248
vlanE(config-subif)#no sh
vlanE(config-subif)#ex
vlanE(config)#int fa0/0.50
vlanE(config-subif)#
vlanE(config-subif)#encapsulation dot1Q 50
vlanE(config-subif)#ip add 200.20.20.193 255.255.255.248
vlanE(config-subif)#no sh
vlanE(config-subif)#ex
vlanE(config)#ip dhcp pool vlanE1
vlanE(dhcp-config)#net 200.20.20.160 255.255.255.248
vlanE(dhcp-config)#default-router 200.20.20.161
vlanE(dhcp-config)#ex
vlanE(config)#ip dhcp pool vlanE2
vlanE(dhcp-config)#net 200.20.20.168 255.255.255.248
vlanE(dhcp-config)#default-router 200.20.20.169
vlanE(dhcp-config)#ex
vlanE(config)#ip dhcp pool vlanE3
vlanE(dhcp-config)#net 200.20.20.176 255.255.255.248
vlanE(dhcp-config)#default-router 200.20.20.177
vlanE(dhcp-config)#ex
vlanE(config)#ip dhcp pool vlanE4
vlanE(dhcp-config)#net 200.20.20.184 255.255.255.248
vlanE(dhcp-config)#default-router 200.20.20.185
vlanE(dhcp-config)#ex
vlanE(config)#ip dhcp pool vlanE5
vlanE(dhcp-config)#net 200.20.20.192 255.255.255.248
vlanE(dhcp-config)#default-router 200.20.20.193
vlanE(dhcp-config)#ex
vlanE(config)#do write memory

```

VLSM untuk Network pada router Dengan start network 200.20.20.200/24

No	Net	Network	Range	Broadcast
1	Net 1	200.20.20.200	200.20.20.201 - 200.20.20.202	200.20.20.203
2	Net 2	200.20.20.204	200.20.20.205 - 200.20.20.206	200.20.20.207
3	Net 3	200.20.20.208	200.20.20.209 - 200.20.20.210	200.20.20.211
4	Net 4	200.20.20.212	200.20.20.213 - 200.20.20.214	200.20.20.215
5	Net 5	200.20.20.216	200.20.20.217 - 200.20.20.218	200.20.20.219
6	Net 6	200.20.20.220	200.20.20.221 - 200.20.20.222	200.20.20.223

7	Net 7	200.20.20.224	200.20.20.225 - 200.20.20.226	200.20.20.227
8	Net 8	200.20.20.228	200.20.20.229 - 200.20.20.230	200.20.20.231
9	Net 9	200.20.20.232	200.20.20.233 - 200.20.20.234	200.20.20.235
10	Net 10	200.20.20.236	200.20.20.237 - 200.20.20.238	200.20.20.239
11	Net 11	200.20.20.240	200.20.20.241 - 200.20.20.242	200.20.20.243
12	Net 12	200.20.20.244	200.20.20.245 - 200.20.20.246	200.20.20.247
13	Net 13	200.20.20.248	200.20.20.249 - 200.20.20.250	200.20.20.251
14	Net 14	200.20.20.252	200.20.20.253 - 200.20.20.254	200.20.20.255
15	Net 15	200.20.21.0	200.20.21.1 - 200.20.21.2	200.20.21.3
16	Net 16	200.20.21.4	200.20.21.5 - 200.20.21.6	200.20.21.7
17	Net 17	200.20.21.8	200.20.21.9 - 200.20.21.10	200.20.21.11
18	Net 18	200.20.21.12	200.20.21.13 - 200.20.21.14	200.20.21.15
19	Net 19	200.20.21.16	200.20.21.17-200.20.21.18	200.20.21.19
20	Net 20	200.20.21.20	200.20.21.21 - 200.20.21.22	200.20.21.23
21	Net 21	200.20.21.24	200.20.21.25 - 200.20.21.26	200.20.21.27
22	Net 22	200.20.21.28	200.20.21.29 - 200.20.21.30	200.20.21.31
23	Net 23	200.20.21.32	200.20.21.33 - 200.20.21.34	200.20.21.35
24	Net 24	200.20.21.36	200.20.21.37 - 200.20.21.38	200.20.21.39
25	Net 25	200.20.21.40	200.20.21.41 - 200.20.21.42	200.20.21.43
26	Net 26	200.20.21.44	200.20.21.45 - 200.20.21.46	200.20.21.47
27	Net 27	200.20.21.48	200.20.21.49 - 200.20.21.50	200.20.21.51
28	Net 28	200.20.21.52	200.20.21.53 - 200.20.21.54	200.20.21.55
29	Net 29	200.20.21.56	200.20.21.57 - 200.20.21.58	200.20.21.59
30	Net 30	200.20.21.60	200.20.21.61 - 200.20.21.62	200.20.21.63

1. Konfigurasi ip dan routing static untuk router1

```
vlanB>en
vlanB#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vlanB(config)#int se2/0
vlanB(config-if)#ip add 200.20.20.218 255.255.255.252
vlanB(config-if)#no sh
vlanB(config-if)#ex
vlanB(config)#ip route 0.0.0.0 0.0.0.0 200.20.20.217
vlanB(config)#do write memory
```

2. Konfigurasi ip, routing OSPF, Static, Redistribut untuk router2

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
```

```
Router(config)#host router2
router2(config)#int se2/0
router2(config-if)#ip add 200.20.20.217 255.255.255.252
router2(config-if)#no sh
router2(config-if)#int se6/0
router2(config-if)#ip add 200.20.20.209 255.255.255.252
router2(config-if)#no sh
router2(config-if)#ex
router2(config)#int se5/0
router2(config-if)#ip add 200.20.20.213 255.255.255.252
router2(config-if)#no sh
router2(config-if)#ex
router2(config)#int se1/0
router2(config-if)#ip add 200.20.20.221 255.255.255.252
router2(config-if)#no sh

router2(config-if)#ex
router2(config)#int se 3/0
router2(config-if)#ip add 200.20.20.29 255.255.255.252
router2(config-if)#no sh
router2(config-if)#ex
router2(config)#int se4/0
router2(config-if)#ip add 200.20.20.225 255.255.255.252
router2(config-if)#no sh
router2(config-if)#ex
router2(config)#route ospf 1
router2(config-router)#net 200.20.20.216 0.0.0.3 area 0
router2(config-router)#net 200.20.20.208 0.0.0.3 area 0
router2(config-router)#net 200.20.20.200 0.0.0.3 area 0
router2(config-router)#net 200.20.20.204 0.0.0.3 area 0
router2(config-router)#net 200.20.20.212 0.0.0.3 area 0
router2(config-router)#net 200.20.20.220 0.0.0.3 area 0
router2(config-router)#net 200.20.20.228 0.0.0.3 area 0
router2(config-router)#net 200.20.20.224 0.0.0.3 area 0
router2(config-router)#no net 200.20.20.200 0.0.0.3 area 0
router2(config-router)#no net 200.20.20.204 0.0.0.3 area 0
router2(config-router)#ip route 200.20.20.40 255.255.255.248
200.20.20.218
router2(config)#ip route 200.20.20.40 255.255.255.248
200.20.20.218
router2(config)#ip route 200.20.20.48 255.255.255.248
200.20.20.218
router2(config)#ip route 200.20.20.56 255.255.255.248
200.20.20.218
router2(config)#ip route 200.20.20.64 255.255.255.248
200.20.20.218
```

```
router2(config)#ip route 200.20.20.73 255.255.255.248
200.20.20.218
%Inconsistent address and mask
router2(config)#ip route 200.20.20.72 255.255.255.248
200.20.20.218
router2(config-router)#redistribute static subnet
router2(config-router)#ex
router2(config)#do write memory
```

3. Konfigurasi ip dan routing OSPF untuk router3

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host router3
router3(config)#int se6/0
router3(config-if)#ip add 200.20.20.210 255.255.255.252
router3(config-if)#no sh
router3(config-if)#ex
router3(config)#int se3/0
router3(config-if)#ip add 200.20.20.202 255.255.255.252
router3(config-if)#no sh
router3(config-if)#route os
router3(config-if)#route ospf 1
router3(config-router)#net 200.20.20.200 0.0.0.3 area 0
router3(config-router)#net 200.20.20.208 0.0.0.3 area 0
router3(config-router)#ex
```

4. Konfigurasi ip dan routing OSPF untuk router4

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#int se1/0
Router(config-if)#ip add 200.20.20.206 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int se5/0
Router(config-if)#ip add 200.20.20.214 255.255.255.252
Router(config-if)#no sh
Router(config-if)#route ospf 1
Router(config-router)#net 200.20.20.204 0.0.0.3 area 0
Router(config-router)#net 200.20.20.212 0.0.0.3 area 0
Router(config-router)#ex
Router(config)#do write memory
```

5. Konfigurasi ip dan routing OSPF untuk router vlanA

```

VlanA>en
VlanA#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VlanA(config)#int se 3/0
VlanA(config-if)#ip add 200.20.20.201 255.255.255.252
VlanA(config-if)#no sh
VlanA(config-if)#ex
VlanA(config)#int se 1/0
VlanA(config-if)#ip add
VlanA(config-if)#ip add 200.20.20.205 255.255.255.252
VlanA(config-if)#no sh
VlanA(config-if)#ex
VlanA(config)#route ospf 1
VlanA(config-router)#ne
VlanA(config-router)#net 200.20.20.0 0.0.0.7 area 0
VlanA(config-router)#net 200.20.20.8 0.0.0.7 area 0
VlanA(config-router)#net 200.20.20.16 0.0.0.7 area 0
VlanA(config-router)#net 200.20.20.24 0.0.0.7 area 0
VlanA(config-router)#net 200.20.20.32 0.0.0.7 area 0
VlanA(config-router)#net 200.20.20.200 0.0.0.3 area 0
VlanA(config-router)#net 200.20.20.204 0.0.0.3 area 0
VlanA(config-router)#ex
VlanA(config)#do write memory

```

6. Konfigurasi ip dan routing OSPF untuk router5

```

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host router5
router5(config)#int se4/0
router5(config-if)#ip add 200.20.20.226 255.255.255.252
router5(config-if)#no sh
router5(config-if)#ex
router5(config)#int se1/0
router5(config-if)#ip add 244
router5(config-if)#ip add 200.20.20.234 255.255.255.252
router5(config-if)#no sh
router5(config-if)#ex
router5(config)#route ospf 1
router5(config-router)#net 200.20.20.224 0.0.0.3 area 0
router5(config-router)#net 200.20.20.232 0.0.0.3 area 0
router5(config-router)#ex
router5(config)#do write memory

```

7. Konfigurasi ip dan routing OSPF untuk router6

```

Router>en

```

```

Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se 3/0
Router(config-if)#ip add 200.20.20.230 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int se3/0
Router(config)#int se2/0
Router(config-if)#ip add 200.20.20.238 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#route ospf 1
Router(config-router)#net 200.20.20.228 0.0.0.3 area 0
Router(config-router)#net 200.20.20.236 0.0.0.3 area 0
Router(config-router)#ex
Router(config)#do write memory
Building configuration...
[OK]
Router(config)#host router6

```

8. Konfigurasi ip dan routing OSPF untuk router VlanC

```

vlanC>en
vlanC#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vlanC(config)#int se2/0
vlanC(config-if)#ip add 200.20.20.237 255.255.255.252
vlanC(config-if)#no sh
vlanC(config-if)#ex
vlanC(config)#int se2/0
vlanC(config-if)#ex
vlanC(config)#int se1/0
vlanC(config-if)#ip add 200.20.20.233 255.255.255.252
vlanC(config-if)#no sh
vlanC(config-if)#route ospf 1
vlanC(config-router)#net 200.20.20.
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0,
changed state to up
236 0.0.0.3 area 0
vlanC(config-router)#net 200.20.20.236 0.0.0.3 area 0
vlanC(config-router)#net 200.20.20.23 0.0.0.3 area 0
03:14:38: %OSPF-5-ADJCHG: Process 1, Nbr 200.20.20.238 on
Serial2/0 from LOADING to FULL, Loading Done
2
vlanC(config-router)#net 200.20.20.232 0.0.0.3 area
% Incomplete command.
vlanC(config-router)#net 200.20.20.232 0.0.0.3 area 0

```

```
vlanC(config-router)#
03:14:51: %OSPF-5-ADJCHG: Process 1, Nbr 200.20.20.234 on
Serial1/0 from LOADING to FULL, Loading Done
vlanC(config-router)#
vlanC(config-router)#net 200.20.20.80 0.0.0.7 area 0
vlanC(config-router)#net 200.20.20.88 0.0.0.7 area 0
vlanC(config-router)#net 200.20.20.96 0.0.0.7 area 0
vlanC(config-router)#net 200.20.20.104 0.0.0.7 area 0
vlanC(config-router)#net 200.20.20.112 0.0.0.7 area 0
```

9. Konfigurasi ip dan routing RIP untuk router VlanE

```
vlanE>en
vlanE#conf t
vlanE(config)#int se2/0
vlanE(config-if)#ip add 200.20.21.10 255.255.255.252
vlanE(config-if)#no sh
vlanE(config-if)#ex
vlanE(config)#route rip
vlanE(config-router)#versi 2
vlanE(config-router)#net 200.20.21.8
vlanE(config-router)#net 200.20.20.160
vlanE(config-router)#net 200.20.20.168
vlanE(config-router)#net 200.20.20.176
vlanE(config-router)#net 200.20.20.184
vlanE(config-router)#net 200.20.20.192
vlanE(config-router)#
```

10. Konfigurasi ip dan routing RIP untuk router VlanD

```
vlanD>en
vlanD#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vlanD(config)#int se 2/0
vlanD(config-if)#ip add 200.20.21.14 255.255.255.252
vlanD(config-if)#no sh

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
vlanD(config-if)#route rip
vlanD(config-router)#versi 2
vlanD(config-router)#net 200.20.21.12
vlanD(config-router)#net 200.20.20.120
vlanD(config-router)#net 200.20.20.128
vlanD(config-router)#net 200.20.20.136
vlanD(config-router)#net 200.20.20.144
vlanD(config-router)#net 200.20.20.152
```

11. Konfigurasi ip dan routing RIP untuk router7


```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host router7
router7(config)#int se2/0
router7(config-if)#ip add 200.20.21.9 255.255.255.252
router7(config-if)#ex
router7(config)#int se2/0
router7(config-if)#no sh
router7(config-if)#ex
router7(config)#int se
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0,
changed state to up
1/0
router7(config-if)#ip add 200.20.21.1 255.255.255.252
router7(config-if)#no sh
router7(config-if)#ex
router7(config)#int se3/0
router7(config-if)#ip add 200.20.20.253 255.255.255.252
router7(config-if)#no sh
router7(config-if)#ex
router7(config)#route rip
router7(config-router)#versi 2
router7(config-router)#net 200.20.20.21
router7(config-router)#net 200.20.21.8
router7(config-router)#net 200.20.21.0
router7(config-router)#net 200.20.20.252
router7(config-router)#ex
router7(config)#do write memory
```

12. Konfigurasi ip dan routing RIP untuk router8

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host router8
router8(config)#int se1/0
router8(config-if)#ip add 200.20.21.13 255.255.255.252
router8(config-if)#no sh
router8(config-if)#ip add 200.20.21.13 255.255.255.252
router8(config-if)#ip add 200.20.21.2 255.255.255.252
router8(config-if)#no sh
router8(config-if)#int se2/0
router8(config-if)#ip add 200.20.21.12 255.255.255.252
Bad mask /30 for address 200.20.21.12
router8(config-if)#ip add 200.20.21.13 255.255.255.252
router8(config-if)#no sh
```

```
router8(config-if)#ex
router8(config)#int se
router8(config)#int se4/0
router8(config-if)#ip add 200.20.21.5 255.255.255.252
router8(config-if)#no sh
router8(config-if)#ex
router8(config)#route rip
router8(config-router)#versi 2
router8(config-router)#net 200.20.21.0
router8(config-router)#net 200.20.21.12
router8(config-router)#net 200.20.21.4
router8(config-router)#ex
router8(config)#do write memory
```

13. Konfigurasi ip dan routing RIP untuk router9

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se 3/0
Router(config-if)#ip add 200.20.20.252 255.255.255.252
Bad mask /30 for address 200.20.20.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int se
Router(config)#int se2/0
Router(config-if)#ex
Router(config)#int se 3/0
Router(config-if)#ip add 200.20.20.254 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int se2/0
Router(config-if)#ip add
Router(config-if)#ip add 200.20.20.246 255.255.255.252
Router(config-if)#no sh
Router(config-if)#route rip
Router(config-router)#versi 2
Router(config-router)#net 200.20.20.252
Router(config-router)#net 200.20.20.244
Router(config-router)#ex
Router(config)#do write memory
Building configuration...
[OK]
Router(config)#host router9
```

14. Konfigurasi ip dan routing RIP untuk router10

```
Router>en
```

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#host router10
router10(config)#int se2/0
router10(config-if)#ip add 200.20.20.245 255.255.255.252
router10(config-if)#no sh
router10(config-if)#ex
router10(config)#int se 3/0
router10(config-if)#ip add 200
router10(config-if)#ip add 200.20.20.241 255.255.255.252
router10(config-if)#no sh
router10(config-if)#ex
router10(config)#int se 9/0
router10(config-if)#ex
router10(config)#int se 3/0
router10(config-if)#ip add 200.20.20.249 255.255.255.252
router10(config-if)#ex
router10(config)#int se 3/0
router10(config-if)#no sh
router10(config-if)#ex
router10(config)#int se9/0
router10(config-if)#ip add 200.20.20.241 255.255.255.252
router10(config-if)#no sh
router10(config-if)#ex
router10(config)#route rip
router10(config-router)#versi 2
router10(config-router)#net 200.20.20.244
router10(config-router)#net 200.20.20.248
router10(config-router)#net 200.20.20.240
router10(config-router)#ex
router10(config)#do write memory
```

15. Konfigurasi ip dan routing RIP untuk router11

```
Router>en
Router#conf t
Router(config)#int se4/0
Router(config-if)#ip add 200.20.21.6 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int se
Router(config)#int se3/0
Router(config-if)#ip add 200.20.20.250 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#route rip
Router(config-router)#ex
```

```
Router(config)#route rip
Router(config-router)#versi 2
Router(config-router)#net 200.20.20.248
Router(config-router)#net 200.20.21.4
Router(config-router)#ex
Router(config)#host router11
router11(config)#do write memory
```

16. Konfigurasi ip dan routing RIP untuk router12

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se9/0
Router(config-if)#ip add 200.20.20.242 255.255.255.252
Router(config-if)#no sh

Router(config-if)#int se1/0
Router(config-if)#ip add 200
Router(config-if)#ip add 200.20.20.222 255.255.255.252
Router(config-if)#no sh
Router(config-if)#
Router(config-if)#ex
Router(config)#route ospf
% Incomplete command.
Router(config)#route ospf 1
Router(config-router)#net 200.20.20.220 0.0.0.3 area 0
Router(config-router)#ex
Router(config)#route ospf 1
Router(config-router)#net 200.20.20.240 0.0.0.3 area 0
Router(config-router)#ex
Router(config)#route ospf 1
Router(config-router)#redi
Router(config-router)#redistribute
Router(config-router)#redistribute rip s
Router(config-router)#redistribute rip subnets
Router(config-router)#ex
Router(config)#route rip
Router(config-router)#red
Router(config-router)#redistribute o
Router(config-router)#redistribute ospf 1 met
Router(config-router)#redistribute ospf 1 metric 1
Router(config-router)#ex
Router(config)#host router12
router12(config)#do write memory
Building configuration...
[OK]
```

```
router12(config)#route ospf 1
router12(config-router)#no net 200.20.20.240 0.0.0.3 area 0
router12(config-router)#ex
router12(config)#route rip
router12(config-router)#net 200.20.20.240
router12(config-router)#redistribute ospf 1 metric 1
router12(config-router)#ex
router12(config)#route ospf 1
router12(config-router)#red
router12(config-router)#redistribute r
router12(config-router)#redistribute rip s
router12(config-router)#redistribute rip subnets m
router12(config-router)#redistribute rip subnets mat
router12(config-router)#redistribute rip subnets
router12(config-router)#route rip
router12(config-router)#versi 2
router12(config-router)#net 200.20.20.240
router12(config-router)#redistribute ospf 1 metric 1
router12(config-router)#ex
router12(config)#do write memory
```