

# Middle East Technical University Northern Cyprus Campus Computer Engineering Program

CNG491 Computer Engineering Design I

# **Markopy Documentation**

Ata Hakçıl - 2243467 Osman Ömer Yıldıztugay - 1921956 Celal Sahir Çetiner - 1755420 Yunus Emre Yılmaz - 2243723

Supervised by Assoc. Prof. Dr. Okan Topçu

1 Markov Passwords			3
1.1 About The Project		 	 3
1.1.1 Built With		 	 3
1.2 Getting Started		 	 3
1.2.1 Prerequisites		 	 4
1.2.2 Installing Dependencies		 	 4
1.2.3 Installation		 	 4
1.2.4 Building		 	 4
1.3 Linux		 	 4
1.4 Windows		 	 5
1.5 Known Common issues		 	 5
1.5.1 Linux		 	 5
1.5.1.1 Markopy - Python.h - N	Not found	 	 5
1.5.1.2 Markopy/MarkovPassv		•	
building			5
1.5.2 Windows			5
1.5.2.1 Boost - Bootstrap.bat "			5
1.5.2.2 Cannot open file "*.lib"			5
1.5.2.3 Python.h not found .			5
1.5.2.4 Simplified Theory			5
1.5.3 Contributing			6
1.5.4 Contact		 	 6
2 Deprecated List			7
3 Namespace Index			9
3.1 Namespace List		 	 9
4 Hierarchical Index			11
4.1 Class Hierarchy		 	 11
5 Class Index			13
5.1 Class List			13
3.1 Olass List		 	 10
6 File Index			15
6.1 File List		 	 15
7 Namespace Documentation			17
7.1 markopy_cli Namespace Reference		 	 17
7.1.1 Detailed Description		 	 17
7.1.2 Function Documentation		 	 17
7.1.2.1 cli_generate()		 	 17
7.1.2.2 cli_init()		 	 18
7.1.2.3 cli_train()			18
7.1.3 Variable Documentation		 	 19

7.1.3.1 action	. 19
7.1.3.2 args	. 19
7.1.3.3 bulk	. 19
7.1.3.4 corpus_list	. 19
7.1.3.5 default	. 19
7.1.3.6 help	. 19
7.1.3.7 model	. 19
7.1.3.8 model_base	. 19
7.1.3.9 model_extension	. 20
7.1.3.10 model_list	. 20
7.1.3.11 output	. 20
7.1.3.12 output_file_name	. 20
7.1.3.13 output_forced	. 20
7.1.3.14 parser	. 20
7.1.3.15 True	. 20
7.2 Markov Namespace Reference	. 20
7.2.1 Detailed Description	. 21
7.3 Markov::API Namespace Reference	. 21
7.3.1 Detailed Description	. 21
7.4 Markov::API::CLI Namespace Reference	. 21
7.4.1 Detailed Description	. 22
7.4.2 Typedef Documentation	. 22
7.4.2.1 ProgramOptions	. 22
7.4.3 Function Documentation	. 22
7.4.3.1 operator<<()	. 22
7.5 Markov::API::Concurrency Namespace Reference	. 22
7.5.1 Detailed Description	. 22
7.6 Markov::API::CUDA Namespace Reference	. 22
7.6.1 Detailed Description	. 23
7.6.2 Function Documentation	. 23
7.6.2.1 FastRandomWalkCUDAKernel()	. 23
7.6.2.2 strchr()	. 24
7.7 Markov::API::CUDA::Random Namespace Reference	. 24
7.7.1 Detailed Description	. 24
7.7.2 Function Documentation	. 24
7.7.2.1 devrandom()	. 24
7.8 Markov::GUI Namespace Reference	. 25
7.8.1 Detailed Description	. 25
7.9 Markov::Markopy Namespace Reference	. 25
7.9.1 Function Documentation	. 25
7.9.1.1 BOOST_PYTHON_MODULE()	. 25
7.10 Markov::Random Namespace Reference	. 26

7.10.1 Detailed Description	 26
7.11 model_2gram Namespace Reference	 26
7.11.1 Detailed Description	 27
7.11.2 Variable Documentation	 27
7.11.2.1 alphabet	 27
7.11.2.2 f	 27
7.12 random Namespace Reference	 27
7.12.1 Detailed Description	 27
7.13 random-model Namespace Reference	 27
7.13.1 Variable Documentation	 27
7.13.1.1 alphabet	 27
7.13.1.2 f	 27
7.14 Testing Namespace Reference	 28
7.14.1 Detailed Description	 28
7.15 Testing::MarkovModel Namespace Reference	 28
7.15.1 Detailed Description	 28
7.15.2 Function Documentation	 28
7.15.2.1 TEST_CLASS() [1/3]	 28
7.15.2.2 TEST_CLASS() [2/3]	 29
7.15.2.3 TEST_CLASS() [3/3]	 30
7.16 Testing::MarkovPasswords Namespace Reference	 31
7.16.1 Detailed Description	 31
7.17 Testing::MVP Namespace Reference	 31
7.17.1 Detailed Description	 31
7.18 Testing::MVP::MarkovModel Namespace Reference	 31
7.18.1 Detailed Description	 32
7.18.2 Function Documentation	 32
7.18.2.1 TEST_CLASS() [1/3]	 32
7.18.2.2 TEST_CLASS() [2/3]	 33
7.18.2.3 TEST_CLASS() [3/3]	 34
7.19 Testing::MVP::MarkovPasswords Namespace Reference	 37
7.19.1 Detailed Description	 37
7.19.2 Function Documentation	 37
7.19.2.1 TEST_CLASS()	 37
8 Class Documentation	41
8.1 Markov::API::CLI::_programOptions Struct Reference	41 43
8.1.1 Detailed Description	43
8.1.2 Member Data Documentation	43
8.1.2.2 bFailure	43
8.1.2.3 blmport	 43

8.1.2.4 datasetname	 44
8.1.2.5 exportname	 44
8.1.2.6 generateN	 44
8.1.2.7 importname	 44
8.1.2.8 outputfilename	 44
8.1.2.9 seperator	 44
8.1.2.10 wordlistname	 44
8.2 Markov::GUI::about Class Reference	 45
8.2.1 Detailed Description	 46
8.2.2 Constructor & Destructor Documentation	 46
8.2.2.1 about()	 46
8.2.3 Member Data Documentation	 46
8.2.3.1 ui	 46
8.3 Markov::API::CLI::Argparse Class Reference	 46
8.3.1 Detailed Description	 48
8.3.2 Constructor & Destructor Documentation	 48
<b>8.3.2.1 Argparse()</b> [1/2]	 48
<b>8.3.2.2 Argparse()</b> [2/2]	 48
8.3.3 Member Function Documentation	 50
8.3.3.1 getProgramOptions()	 50
8.3.3.2 help()	 50
8.3.3.3 parse()	 51
8.3.3.4 setProgramOptions()	 51
8.3.4 Member Data Documentation	 52
8.3.4.1 po	 52
8.4 Markov::GUI::CLI Class Reference	 52
8.4.1 Detailed Description	 53
8.4.2 Constructor & Destructor Documentation	 53
8.4.2.1 CLI()	 53
8.4.3 Member Function Documentation	 53
8.4.3.1 about	 54
8.4.3.2 start	 54
8.4.3.3 statistics	 54
8.4.4 Member Data Documentation	 54
8.4.4.1 ui	 54
8.5 Markov::API::CUDA::CUDADeviceController Class Reference	 54
8.5.1 Detailed Description	 56
8.5.2 Member Function Documentation	 56
8.5.2.1 CudaCheckNotifyErr()	 56
8.5.2.2 CudaMalloc2DToFlat()	 56
8.5.2.3 CudaMemcpy2DToFlat()	 57
8.5.2.4 CudaMigrate2DFlat()	 58

8.5.2.5 ListCudaDevices()	59
8.6 Markov::API::CUDA::CUDAModelMatrix Class Reference	60
8.6.1 Detailed Description	64
8.6.2 Member Function Documentation	64
8.6.2.1 AdjustEdge()	64
8.6.2.2 AllocVRAMOutputBuffer()	65
8.6.2.3 ConstructMatrix()	65
8.6.2.4 CudaCheckNotifyErr()	66
8.6.2.5 CudaMalloc2DToFlat()	67
8.6.2.6 CudaMemcpy2DToFlat()	68
8.6.2.7 CudaMigrate2DFlat()	69
8.6.2.8 DumpJSON()	70
8.6.2.9 Edges()	71
8.6.2.10 Export() [1/2]	71
8.6.2.11 Export() [2/2]	71
8.6.2.12 FastRandomWalk() [1/2]	72
8.6.2.13 FastRandomWalk() [2/2]	72
8.6.2.14 FastRandomWalkPartition()	73
8.6.2.15 FastRandomWalkThread()	75
8.6.2.16 FlattenMatrix()	76
8.6.2.17 Generate()	76
8.6.2.18 GenerateThread()	77
8.6.2.19 Import() [1/2]	78
8.6.2.20 Import() [2/2]	79
8.6.2.21 ListCudaDevices()	80
8.6.2.22 MigrateMatrix()	80
8.6.2.23 Nodes()	80
8.6.2.24 OpenDatasetFile()	80
8.6.2.25 RandomWalk()	81
8.6.2.26 Save()	82
8.6.2.27 StarterNode()	82
8.6.2.28 Train()	83
8.6.2.29 TrainThread()	84
8.6.3 Member Data Documentation	85
8.6.3.1 datasetFile	85
8.6.3.2 device_edgeMatrix	85
8.6.3.3 device_matrixIndex	85
8.6.3.4 device_outputBuffer	85
8.6.3.5 device_totalEdgeWeights	85
8.6.3.6 device_valueMatrix	85
8.6.3.7 edgeMatrix	85
8.6.3.8 edges	86

8.6.3.9 flatEdgeMatrix	 86
8.6.3.10 flatValueMatrix	 86
8.6.3.11 matrixIndex	 86
8.6.3.12 matrixSize	 86
8.6.3.13 modelSavefile	 86
8.6.3.14 nodes	 86
8.6.3.15 outputBuffer	 87
8.6.3.16 outputFile	 87
8.6.3.17 starterNode	 87
8.6.3.18 totalEdgeWeights	 87
8.6.3.19 valueMatrix	 87
8.7 Markov::Random::DefaultRandomEngine Class Reference	 87
8.7.1 Detailed Description	 89
8.7.2 Member Function Documentation	 90
8.7.2.1 distribution()	 90
8.7.2.2 generator()	 90
8.7.2.3 random()	 91
8.7.2.4 rd()	 91
8.8 Markov::Edge < NodeStorageType > Class Template Reference	 92
8.8.1 Detailed Description	 94
8.8.2 Constructor & Destructor Documentation	 94
8.8.2.1 Edge() [1/2]	 94
8.8.2.2 Edge() [2/2]	 94
8.8.3 Member Function Documentation	 95
8.8.3.1 AdjustEdge()	 95
8.8.3.2 EdgeWeight()	 95
8.8.3.3 LeftNode()	 95
8.8.3.4 RightNode()	 96
8.8.3.5 SetLeftEdge()	 96
8.8.3.6 SetRightEdge()	 96
8.8.3.7 TraverseNode()	 97
8.8.4 Member Data Documentation	 97
8.8.4.1 _left	 97
8.8.4.2 _right	 97
8.8.4.3 _weight	 97
8.9 Markov::API::MarkovPasswords Class Reference	 97
8.9.1 Detailed Description	 101
8.9.2 Constructor & Destructor Documentation	 101
8.9.2.1 MarkovPasswords() [1/2]	 101
8.9.2.2 MarkovPasswords() [2/2]	 101
8.9.3 Member Function Documentation	 101
8 9 3 1 AdjustEdge()	102

8.9.3.2 Edges()	. 102
<b>8.9.3.3 Export()</b> [1/2]	. 102
<b>8.9.3.4 Export()</b> [2/2]	. 103
8.9.3.5 Generate()	. 103
8.9.3.6 GenerateThread()	. 104
8.9.3.7 Import() [1/2]	. 105
<b>8.9.3.8 Import()</b> [2/2]	. 105
8.9.3.9 Nodes()	. 106
8.9.3.10 OpenDatasetFile()	. 107
8.9.3.11 RandomWalk()	. 107
8.9.3.12 Save()	. 108
8.9.3.13 StarterNode()	. 109
8.9.3.14 Train()	. 109
8.9.3.15 TrainThread()	. 110
8.9.4 Member Data Documentation	. 111
8.9.4.1 datasetFile	. 111
8.9.4.2 edges	. 111
8.9.4.3 modelSavefile	. 111
8.9.4.4 nodes	. 111
8.9.4.5 outputFile	. 111
8.9.4.6 starterNode	. 112
8.10 Markov::GUI::MarkovPasswordsGUI Class Reference	. 112
8.10.1 Detailed Description	. 113
8.10.2 Member Function Documentation	. 114
8.10.2.1 MarkovPasswordsGUI ::pass	. 114
8.10.2.2 MarkovPasswordsGUI::benchmarkSelected	. 114
8.10.2.3 MarkovPasswordsGUI::comparisonSelected	. 114
8.10.2.4 MarkovPasswordsGUI::home	. 114
8.10.2.5 MarkovPasswordsGUI::model	. 114
8.10.2.6 MarkovPasswordsGUI::modelvisSelected	. 114
8.10.2.7 MarkovPasswordsGUI::visualDebugSelected	. 114
8.10.3 Member Data Documentation	. 114
8.10.3.1 ui	. 114
8.11 Markov::API::CUDA::Random::Marsaglia Class Reference	. 114
8.11.1 Detailed Description	. 117
8.11.2 Member Function Documentation	. 117
8.11.2.1 CudaCheckNotifyErr()	. 117
8.11.2.2 CudaMalloc2DToFlat()	. 117
8.11.2.3 CudaMemcpy2DToFlat()	. 118
8.11.2.4 CudaMigrate2DFlat()	. 119
8.11.2.5 distribution()	. 120
8.11.2.6 generator()	. 121

8.11.2.7 ListCudaDevices()	121
8.11.2.8 MigrateToVRAM()	122
8.11.2.9 random()	122
8.11.2.10 rd()	123
8.11.3 Member Data Documentation	123
<b>8.11.3.1</b> x	123
8.11.3.2 y	123
8.11.3.3 z	123
8.12 Markov::Random::Marsaglia Class Reference	124
8.12.1 Detailed Description	126
8.12.2 Constructor & Destructor Documentation	126
8.12.2.1 Marsaglia()	126
8.12.3 Member Function Documentation	126
8.12.3.1 distribution()	126
8.12.3.2 generator()	127
8.12.3.3 random()	127
8.12.3.4 rd()	128
8.12.4 Member Data Documentation	128
<b>8.12.4.1</b> x	128
<b>8.12.4.2 y</b>	128
<b>8.12.4.3 z</b>	129
8.13 Markov::GUI::menu Class Reference	129
8.13.1 Detailed Description	130
8.13.2 Constructor & Destructor Documentation	130
8.13.2.1 menu()	130
8.13.3 Member Function Documentation	131
8.13.3.1 about	131
8.13.3.2 visualization	131
8.13.4 Member Data Documentation	131
8.13.4.1 ui	131
8.14 Markov::Random::Mersenne Class Reference	131
8.14.1 Detailed Description	133
8.14.2 Member Function Documentation	134
8.14.2.1 distribution()	134
8.14.2.2 generator()	134
8.14.2.3 random()	135
8.14.2.4 rd()	135
8.15 Markov::Model < NodeStorageType > Class Template Reference	136
8.15.1 Detailed Description	138
8.15.2 Constructor & Destructor Documentation	138
8.15.2.1 Model()	138
8.15.3 Member Function Documentation	138

8.15.3.1 AdjustEdge()	139
8.15.3.2 Edges()	139
8.15.3.3 Export() [1/2]	140
8.15.3.4 Export() [2/2]	140
8.15.3.5 Import() [1/2]	141
<b>8.15.3.6 Import()</b> [2/2]	141
8.15.3.7 Nodes()	143
8.15.3.8 RandomWalk()	143
8.15.3.9 StarterNode()	144
8.15.4 Member Data Documentation	145
8.15.4.1 edges	145
8.15.4.2 nodes	145
8.15.4.3 starterNode	145
8.16 Markov::API::ModelMatrix Class Reference	145
8.16.1 Detailed Description	149
8.16.2 Constructor & Destructor Documentation	149
8.16.2.1 ModelMatrix()	149
8.16.3 Member Function Documentation	149
8.16.3.1 AdjustEdge()	149
8.16.3.2 ConstructMatrix()	150
8.16.3.3 DumpJSON()	151
8.16.3.4 Edges()	152
8.16.3.5 Export() [1/2]	152
8.16.3.6 Export() [2/2]	153
8.16.3.7 FastRandomWalk()	153
8.16.3.8 FastRandomWalkPartition()	154
8.16.3.9 FastRandomWalkThread()	155
8.16.3.10 Generate()	157
8.16.3.11 GenerateThread()	158
<b>8.16.3.12 Import()</b> [1/2]	159
<b>8.16.3.13 Import()</b> [2/2]	159
8.16.3.14 Nodes()	160
8.16.3.15 OpenDatasetFile()	160
8.16.3.16 RandomWalk()	161
8.16.3.17 Save()	162
8.16.3.18 StarterNode()	163
8.16.3.19 Train()	163
8.16.3.20 TrainThread()	164
8.16.4 Member Data Documentation	165
8.16.4.1 datasetFile	165
8.16.4.2 edgeMatrix	165
8.16.4.3 edges	165

8.16.4.4 matrixIndex		165
8.16.4.5 matrixSize		165
8.16.4.6 modelSavefile		166
8.16.4.7 nodes		166
8.16.4.8 outputFile		166
8.16.4.9 starterNode		166
8.16.4.10 totalEdgeWeights		166
8.16.4.11 valueMatrix		166
8.17 Markov::Node < storageType > Class Template Reference	. <b></b>	166
8.17.1 Detailed Description		169
8.17.2 Constructor & Destructor Documentation		169
<b>8.17.2.1 Node()</b> [1/2]		169
<b>8.17.2.2 Node()</b> [2/2]		170
8.17.3 Member Function Documentation		171
8.17.3.1 Edges()		171
<b>8.17.3.2 FindEdge()</b> [1/2]		171
<b>8.17.3.3 FindEdge()</b> [2/2]		171
8.17.3.4 Link() [1/2]		172
<b>8.17.3.5 Link()</b> [2/2]		172
8.17.3.6 NodeValue()		173
8.17.3.7 RandomNext()		173
8.17.3.8 TotalEdgeWeights()		174
8.17.3.9 UpdateEdges()		174
8.17.3.10 UpdateTotalVerticeWeight()		175
8.17.4 Member Data Documentation		175
8.17.4.1 _value		175
8.17.4.2 edges		175
8.17.4.3 edgesV		175
8.17.4.4 total_edge_weights		175
8.18 Markov::Random::RandomEngine Class Reference		176
8.18.1 Detailed Description		177
8.18.2 Member Function Documentation		177
8.18.2.1 random()		177
8.19 Markov::API::CLI::Terminal Class Reference		177
8.19.1 Detailed Description		179
8.19.2 Member Enumeration Documentation		179
8.19.2.1 color		179
8.19.3 Constructor & Destructor Documentation		179
8.19.3.1 Terminal()		179
8.19.4 Member Data Documentation		179
8.19.4.1 colormap		180
8.19.4.2 endl		180

8.20 Markov::API::Concurrency::ThreadSharedListHandler Class Reference	 18
8.20.1 Detailed Description	 18
8.20.2 Constructor & Destructor Documentation	 18
8.20.2.1 ThreadSharedListHandler()	 18
8.20.3 Member Function Documentation	 18
8.20.3.1 next()	 18
8.20.4 Member Data Documentation	 18
8.20.4.1 listfile	 18
8.20.4.2 mlock	 18
8.21 Markov::GUI::Train Class Reference	 18
8.21.1 Detailed Description	 18
8.21.2 Constructor & Destructor Documentation	 18
8.21.2.1 Train()	 18
8.21.3 Member Function Documentation	 18
8.21.3.1 home	 18
8.21.3.2 train	 18
8.21.4 Member Data Documentation	 18
8.21.4.1 ui	 18
9 File Documentation	18
9.1 about.h File Reference	
9.2 about.h	
9.3 argparse.cpp File Reference	
9.4 argparse.cpp	
9.5 argparse.h File Reference	
9.5.1 Macro Definition Documentation	 19
9.5.1.1 BOOST_ALL_DYN_LINK	 19
9.6 argparse.h	
9.7 CLI.h File Reference	 19
9.8 CLI.h	 19
9.9 cudaDeviceController.h File Reference	 19
9.10 cudaDeviceController.h	 19
9.11 cudaModelMatrix.h File Reference	 19
9.12 cudaModelMatrix.h	 19
9.13 cudarandom.h File Reference	 19
9.14 cudarandom.h	 20
9.15 dllmain.cpp File Reference	 20
9.16 dllmain.cpp	 20
9.17 edge.h File Reference	 20
9.18 edge.h	 20
9.19 framework.h File Reference	 20
9.19.1 Macro Definition Documentation	 20

9.19.1.1 WIN32_LEAN_AND_MEAN
9.20 framework.h
9.21 main.cpp File Reference
9.21.1 Function Documentation
9.21.1.1 main()
9.22 src/main.cpp
9.23 main.cpp File Reference
9.23.1 Function Documentation
9.23.1.1 main()
9.24 UI/src/main.cpp
9.25 markopy.cpp File Reference
9.25.1 Macro Definition Documentation
9.25.1.1 BOOST_PYTHON_STATIC_LIB
9.26 markopy.cpp
9.27 markopy_cli.py File Reference
9.28 markopy_cli.py
9.29 markovPasswords.cpp File Reference
9.29.1 Function Documentation
9.29.1.1 intHandler()
9.29.2 Variable Documentation
9.29.2.1 keepRunning
9.30 markovPasswords.cpp
9.31 markovPasswords.h File Reference
9.32 markovPasswords.h
9.33 MarkovPasswordsGUI.cpp File Reference
9.34 MarkovPasswordsGUI.cpp
9.35 MarkovPasswordsGUI.h File Reference
9.36 MarkovPasswordsGUI.h
9.37 menu.cpp File Reference
9.38 menu.cpp
9.39 menu.h File Reference
9.40 menu.h
9.41 model.h File Reference
9.42 model.h
9.43 model_2gram.py File Reference
9.44 model_2gram.py
9.45 modelMatrix.cpp File Reference
9.46 modelMatrix.cpp
9.47 modelMatrix.h File Reference
9.48 modelMatrix.h
9.49 node.h File Reference
9.50 node.h

9.51 pch.cpp File Reference	239
9.52 MarkovModel/src/pch.cpp	239
9.53 pch.cpp File Reference	239
9.54 UnitTests/pch.cpp	240
9.55 pch.h File Reference	240
9.56 MarkovModel/src/pch.h	241
9.57 pch.h File Reference	241
9.58 UnitTests/pch.h	241
9.59 random-model.py File Reference	242
9.60 random-model.py	242
9.61 random.h File Reference	242
9.62 random.h	244
9.63 README.md File Reference	246
9.64 term.cpp File Reference	246
9.64.1 Function Documentation	246
9.64.1.1 operator<<<()	246
9.65 term.cpp	247
9.66 term.h File Reference	248
9.66.1 Macro Definition Documentation	249
9.66.1.1 TERM_FAIL	249
9.66.1.2 TERM_INFO	249
9.66.1.3 TERM_SUCC	249
9.66.1.4 TERM_WARN	249
9.67 term.h	249
9.68 threadSharedListHandler.cpp File Reference	250
9.69 threadSharedListHandler.cpp	250
9.70 threadSharedListHandler.h File Reference	251
9.71 threadSharedListHandler.h	252
9.72 Train.h File Reference	253
9.73 Train.h	253
9.74 UnitTests.cpp File Reference	254
9.75 UnitTests.cpp	255
Index	263

# **Markov Passwords**

Table of Contents

#### **Markov Passwords**

Generate wordlists with markov models.

```
Wiki· Complete documentation· Report Bug· Add a Bug
```

<details open="open">

- 1. About The Project
  - Built With
- 2. Getting Started
  - Prerequisites
  - Installation
- 3. Contributing
- 4. Contact

</details>

# 1.1 About The Project

This project aims to generate wordlists using markov models.

### 1.1.1 Built With

• CPP, with dependecies: boost, python3-dev, QT-5.

# 1.2 Getting Started

If you'd just like to use the project without contributing, check out the releases page. If you want to build, check out wiki for building the project.

4 Markov Passwords

## 1.2.1 Prerequisites

#### 1.2.1.0.1 MarkovModel

• Make for linux, Visual Studio/MSBuild for Windows.

#### 1.2.1.0.2 MarkovPasswords

• Boost.ProgramOptions (tested on 1.76.0)

#### 1.2.1.0.3 Markopy

- Boost.Python (tested on 1.76.0)
- Python development package (tested on python 3.8)

#### 1.2.1.0.4 MarkovPasswordsGUI

· QT development environment.

## 1.2.2 Installing Dependencies

#### 1.2.2.0.1 Windows

- QT: Install QT For Windows
- · Boost:
  - Download Boost from its website
  - Unzip the contents.
  - Launch "Visual Studio Developer Command Prompt"
  - Move to the boost installation directory. Run bootstrap.bat
  - Run b2.
- Python: You can use the windows app store to download python runtime and libraries.

#### 1.2.2.0.2 Linux

- QT: Follow this guide to install QT on Linux.
- Boost: run sudo apt-get install libboost-all-dev
- Python: run sudo apt-get install python3

#### 1.2.3 Installation

See the Wiki Page

## 1.2.4 Building

Building process can be fairly complicated depending on the environment.

## 1.3 Linux

If you've set up the dependencies, you can just build the project with make. List of directives is below.

```
.PHONY: all
all: model mp
model: $(INCLUDE)/$(MM_LIB)
mp: $(BIN)/$(MP_EXEC)
markopy: $(BIN)/$(MPY_SO)
.PHONY: clean
clean:
    $(RM) -r $(BIN)/*
```

1.4 Windows 5

#### 1.4 Windows

Set up correct environment variables for BOOST\_ROOT% (folder containing boost, libs, stage, tools) and PYTH ← ON PATH% (folder containing include, lib, libs, Tools, python.exe/python3.exe).

If you've set up the dependencies and environment variables correctly, you can open the solution with Visual Studio and build with that.

#### 1.5 Known Common issues

#### 1.5.1 Linux

#### 1.5.1.1 Markopy - Python.h - Not found

Make sure you have the development version of python package, which includes the required header files. Check if header files exist: /usr/include/python\*

If it doesn't, run sudo apt-get install python3-dev

#### 1.5.1.2 Markopy/MarkovPasswords - \*.so not found, or other library related issues when building

Run ls  $/usr/lib/x86_64-linux-gnu/$  | grep boost and check the shared object filenames. A common issue is that lboost is required but filenames are formatted as llibboost, or vice versa.

Do the same for python related library issues, run:  $ls /usr/lib/x86_64-linux-gnu/| grep python to verify filename format is as required.$ 

If not, you can modify the makefile, or create symlinks such as:  $ln -s /usr/lib/x86_64-linux-gnu/libboost \leftarrow _python38.so /usr/lib/x86_64-linux-gnu/boost_python38.so$ 

#### 1.5.2 Windows

#### 1.5.2.1 Boost - Bootstrap.bat "ctype.h" not found

- · Make sure you are working in the "Visual Studio Developer Command Prompt" terminal.
- · Make sure you have Windows 10 SDK installed.
- From VS developer terminal, run echo INCLUDE%. If result does not have the windows sdk folders, run the following before running bootstrap (change your sdk version instead of 10.0.19041.0):

```
set INCLUDE=%INCLUDE%;C:\Program Files (x86)\Windows Kits\NETFXSDK\4.8\include\um;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\ucrt;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\shared;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\um;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\umirt;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\upwinrt set LIB=%LIB%;C:\Program Files (x86)\Windows Kits\10\include\10.0.19041.0\upwinrt set LIB-%LIB%;C:\Program Files (x86)\Windows Kits\10\lib\10.0.19041.0\upwinrt set LIB-%LIB%;C:\Program Files (x86)\Windows Kits\10\lib\10.0.19041.0\um\x64
```

#### 1.5.2.2 Cannot open file "\*.lib"

Make sure you have set the BOOST\_ROOT environment variable correctly. Make sure you ran b2 to build library files from boost sources.

#### 1.5.2.3 Python.h not found

Make sure you have python installed, and make sure you set PYTHON\_PATH environment variable.

#### 1.5.2.4 Simplified Theory

**What is a markov model** Below, is the example Markov Model which can generate strings with the alphabet "a,b,c"

**Iteration 1** Below is a demonstration of how training will be done. For this example, we are going to adjust the model with string "ab", and our occurrence will be "3" From MarkovPasswords, inside the train function, Model  $\leftarrow$  ::adjust is called with "ab" and "3" parameters.

6 Markov Passwords

Now, Model::adjust will iteratively adjust the edge weights accordingly. It starts by adjusting weight between start and "a" node. This is done by calling Edge::adjust of the edge between the nodes.

After adjustment, ajust function iterates to the next character, "b", and does the same thing.

As this string is finished, it will adjust the final weight, b->"end"

Iteration 2 This time, same procedure will be applied for "bacb" string, with occurrence value of 12.

**Iteration 38271** As the model is trained, hidden linguistical patterns start to appear, and our model looks like this With our dataset, without doing any kind of linugistic analysis ourselves, our Markov Model has highlighted that strings are more likely to start with a, b tends to follow a, and a is likely to be repeated in the string.

## 1.5.3 Contributing

Feel free to contribute.

#### 1.5.4 Contact

Twitter - @ahakcil

# **Deprecated List**

Member Markov::API::MarkovPasswords::Generate (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20)

 $See\ Markov:: API:: Matrix Model:: Fast Random Walk\ for\ more\ information.$ 

8 Deprecated List

# Namespace Index

# 3.1 Namespace List

Here is a list of all namespaces with brief descriptions:	
markopy cli	17
Markov	
Namespace for the markov-model related classes. Contains Model, Node and Edge classes .	20
Markov::API	
Namespace for the MarkovPasswords API	21
Markov::API::CLI	
Structure to hold parsed cli arguements	21
Markov::API::Concurrency	
Namespace for Concurrency related classes	22
Markov::API::CUDA	
Namespace for objects requiring CUDA libraries	22
Markov::API::CUDA::Random	
Namespace for Random engines operable under <b>device</b> space	24
Markov::GUI	
Namespace for MarkovPasswords API GUI wrapper	25
Markov::Markopy	25
Markov::Random	
Objects related to RNG	26
model_2gram	26
random	27
random-model	27
Testing  Namespace for Microsoft Native Unit Testing Classes	28
Testing::MarkovModel	20
Testing namespace for MarkovModel	28
Testing::MarkovPasswords	20
Testing namespace for MarkovPasswords	31
Testing::MVP	
Testing Namespace for Minimal Viable Product	31
Testing::MVP::MarkovModel	
Testing Namespace for MVP MarkovModel	31
Testing::MVP::MarkovPasswords	
Testing namespace for MVP MarkovPasswords	37

10 Namespace Index

# **Hierarchical Index**

# 4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:
Markov::API::CLI::_programOptions
Markov::API::CLI::Argparse
Markov::API::CUDA::CUDADeviceController
Markov::API::CUDA::CUDAModelMatrix
Markov::API::CUDA::Random::Marsaglia
Markov::Edge < NodeStorageType >
Markov::Edge < char >
Markov::Edge < storageType >
Markov::Model < NodeStorageType >
Markov::Model < char >
Markov::API::MarkovPasswords
Markov::API::ModelMatrix
Markov::API::CUDA::CUDAModelMatrix
Markov::Node < storageType >
Markov::Node < char >
Markov::Node < NodeStorageType >
QMainWindow
Markov::GUI::about
Markov::GUI::CLI
Markov::GUI::MarkovPasswordsGUI
Markov::GUI::menu
Markov::GUI::Train
Markov::Random::RandomEngine
Markov::Random::DefaultRandomEngine
Markov::Random::Marsaglia
Markov::API::CUDA::Random::Marsaglia
Markov::Random::Mersenne
Markov::API::CLI::Terminal
Markov::API::Concurrency::ThreadSharedListHandler

12 Hierarchical Index

# **Class Index**

# 5.1 Class List

ere are the classes, structs, unions and interfaces with brief descriptions:	
Markov::API::CLI::_programOptions	
and a state of the	41
Markov::GUI::about	
	45
Markov::API::CLI::Argparse	
	46
Markov::GUI::CLI	
	52
Markov::API::CUDA::CUDADeviceController	
	54
Markov::API::CUDA::CUDAModelMatrix	
	60
Markov::Random::DefaultRandomEngine	
	87
Markov::Edge < NodeStorageType >	
3	92
Markov::API::MarkovPasswords	^ <del>-</del>
'	97
Markov::GUI::MarkovPasswordsGUI  Reporting UI	40
Reporting UI	12
	14
Markov::Random::Marsaglia	14
·	24
Markov::GUI::menu	24
	29
Markov::Random::Mersenne	23
	31
Markov::Model < NodeStorageType >	01
	36
Markov::API::ModelMatrix	•
	45
Markov::Node < storage Type >	
	66
Markov::Random::RandomEngine	
·	76
Markov::API::CLI::Terminal	
Pretty colors for Terminal. Windows Only	77
Markov::API::Concurrency::ThreadSharedListHandler	
·	മറ

4	Class Inde
4	Ciass illu

Markov::GUI::Train																
QT Training page class																184

# File Index

# 6.1 File List

не	re is a list of all files with brief descriptions:	
	about.h	
	argparse.cpp	188
	argparse.h	188
	CLI.h	193
	cudaDeviceController.h	194
	cudaModelMatrix.h	197
	cudarandom.h	199
	dllmain.cpp	201
	edge.h	202
	framework.h	205
	src/main.cpp	205
	UI/src/main.cpp	207
	markopy.cpp	209
	markopy_cli.py	210
	markovPasswords.cpp	213
	markovPasswords.h	216
	MarkovPasswordsGUI.cpp	219
	MarkovPasswordsGUI.h	220
	menu.cpp	221
	menu.h	222
	model.h	223
	model_2gram.py	228
	modelMatrix.cpp	229
	modelMatrix.h	232
	node.h	235
	MarkovModel/src/pch.cpp	239
	UnitTests/pch.cpp	239
	MarkovModel/src/pch.h	240
	UnitTests/pch.h	241
	random-model.py	242
	random.h	242
	term.cpp	246
	term.h	248
	threadSharedListHandler.cpp	250
	threadSharedListHandler.h	251
	Train.h	253
	UnitToota ann	25/

16 File Index

# **Namespace Documentation**

# 7.1 markopy\_cli Namespace Reference

#### **Functions**

- def cli\_init (input\_model)
- def cli\_train (model, dataset, seperator, output, output\_forced=False, bulk=False)
- def cli\_generate (model, wordlist, bulk=False)

#### **Variables**

- parser
- help
- · default
- action
- args = parser.parse\_args()
- corpus\_list = os.listdir(args.dataset)
- def model = cli\_init(args.input)
- output file name = corpus
- string model\_extension = ""
- output\_forced
- True
- bulk
- model\_list = os.listdir(args.input)
- model\_base = input
- output

## 7.1.1 Detailed Description

@namespace Markov::Markopy::Python

#### 7.1.2 Function Documentation

## 7.1.2.1 cli\_generate()

```
Definition at line 114 of file markopy_cli.py.
00114 def cli_generate(model, wordlist, bulk=False):
00115 if not (wordlist or args.count):
               {\tt logging.pprint("Generation mode requires -w/--wordlist and -n/--count parameters. Exiting.")}
00116
00117
               exit(2)
00118
00119
           if (bulk and os.path.isfile(wordlist)):
00120
               logging.pprint(f"{wordlist} exists and will be overwritten.", 1)
00121
           model.Generate(int(args.count), wordlist, int(args.min), int(args.max), int(args.threads))
00122
00123
7.1.2.2 cli_init()
def markopy_cli.cli_init (
                 input model )
Definition at line 61 of file markopy_cli.py.
00061 def cli init(input model):
           logging.VERBOSITY = 0
           if args.verbosity:
00063
00064
               logging.VERBOSITY = args.verbosity
00065
               logging.pprint(f"Verbosity set to {args.verbosity}.", 2)
00066
00067
           logging.pprint("Initializing model.", 1)
           model = markopy.MarkovPasswords()
logging.pprint("Model initialized.", 2)
00068
00069
00070
00071
           logging.pprint("Importing model file.", 1)
00072
           if (not os.path.isfile(input_model)):
00073
               logging.pprint(f"Model file at {input_model} not found. Check the file path, or working
00074
       directory")
00075
               exit(1)
00076
           model.Import(input_model)
00077
00078
           logging.pprint("Model imported successfully.", 2)
00079
           return model
00080
00081
7.1.2.3 cli_train()
def markopy_cli.cli_train (
                 model.
                 dataset,
                 seperator,
                 output.
                 output_forced = False,
                 bulk = False)
Definition at line 82 of file markopy_cli.py.
00082 def cli_train(model, dataset, seperator, output, output_forced=False, bulk=False):
00083
           if not (dataset and seperator and (output or not output_forced)):
00084
               logging.pprint(
                   f"Training mode requires -d/--dataset {\it ', -o/--output'} if output\_forced else "\it '} and
00085
        -s/--seperator parameters. Exiting.")
00086
               exit(2)
00087
00088
           if (not bulk and not os.path.isfile(dataset)):
00089
               logging.pprint(f"{dataset} doesn't exists. Check the file path, or working directory")
00090
               exit(3)
00091
00092
           if (output and os.path.isfile(output)):
               logging.pprint(f"{output} exists and will be overwritten.", 1)
00093
00094
           if (seperator == '\\t'):
    logging.pprint("Escaping seperator.", 3)
    seperator = '\t'
00095
00096
00097
00098
00099
           if (len(seperator) != 1):
00100
               logging.pprint(f'Delimiter must be a single character, and "{seperator}" is not accepted.')
00101
00102
           logging.pprint(f'Starting training.', 3)
00103
           model.Train(dataset, seperator, int(args.threads))
logging.pprint(f'Training completed.', 2)
00104
00105
00106
```

```
00107     if (output):
        logging.pprint(f'Exporting model to {output}', 2)
        model.Export(output)
00110     else:
        logging.pprint(f'Model will not be exported.', 1)
00112
00113
```

#### 7.1.3 Variable Documentation

#### 7.1.3.1 action

```
markopy_cli.action
Definition at line 49 of file markopy_cli.py.
```

#### 7.1.3.2 args

```
markopy_cli.args = parser.parse_args()
Definition at line 58 of file markopy_cli.py.
```

## 7.1.3.3 bulk

```
markopy_cli.bulk

Definition at line 139 of file markopy_cli.py.
```

### 7.1.3.4 corpus\_list

```
markopy_cli.corpus_list = os.listdir(args.dataset)
Definition at line 130 of file markopy_cli.py.
```

#### 7.1.3.5 default

```
markopy_cli.default
Definition at line 41 of file markopy_cli.py.
```

## 7.1.3.6 help

```
markopy_cli.help
Definition at line 27 of file markopy cli.py.
```

## 7.1.3.7 model

```
def markopy_cli.model = cli_init(args.input)
Definition at line 132 of file markopy_cli.py.
```

## 7.1.3.8 model\_base

```
markopy_cli.model_base = input
Definition at line 153 of file markopy_cli.py.
```

#### 7.1.3.9 model\_extension

```
markopy_cli.model_extension = ""
Definition at line 135 of file markopy cli.py.
```

#### 7.1.3.10 model list

```
markopy_cli.model_list = os.listdir(args.input)
Definition at line 147 of file markopy_cli.py.
```

#### 7.1.3.11 output

```
markopy_cli.output
Definition at line 167 of file markopy_cli.py.
```

#### 7.1.3.12 output\_file\_name

```
markopy_cli.output_file_name = corpus
Definition at line 134 of file markopy cli.py.
```

#### 7.1.3.13 output\_forced

```
markopy_cli.output_forced
Definition at line 139 of file markopy_cli.py.
```

### 7.1.3.14 parser

## 7.1.3.15 True

```
markopy_cli.True
Definition at line 139 of file markopy_cli.py.
```

# 7.2 Markov Namespace Reference

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

### **Namespaces**

API

Namespace for the MarkovPasswords API.

GUI

namespace for MarkovPasswords API GUI wrapper

- Markopy
- Random

Objects related to RNG.

#### **Classes**

• class Edge

Edge class used to link nodes in the model together.

class Model

class for the final Markov Model, constructed from nodes and edges.

class Node

A node class that for the vertices of model. Connected with eachother using Edge.

#### 7.2.1 Detailed Description

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

# 7.3 Markov::API Namespace Reference

Namespace for the MarkovPasswords API.

## **Namespaces**

• CLI

Structure to hold parsed cli arguements.

Concurrency

Namespace for Concurrency related classes.

CUDA

Namespace for objects requiring CUDA libraries.

#### **Classes**

• class MarkovPasswords

Markov::Model with char represented nodes.

· class ModelMatrix

Class to flatten and reduce Markov::Model to a Matrix.

#### 7.3.1 Detailed Description

Namespace for the MarkovPasswords API.

# 7.4 Markov::API::CLI Namespace Reference

Structure to hold parsed cli arguements.

#### **Classes**

• struct \_programOptions

Structure to hold parsed cli arguements.

class Argparse

Parse command line arguements.

class Terminal

pretty colors for Terminal. Windows Only.

## **Typedefs**

• typedef struct Markov::API::CLI::\_programOptions ProgramOptions

Structure to hold parsed cli arguements.

#### **Functions**

std::ostream & operator<< (std::ostream &os, const Markov::API::CLI::Terminal::color &c)</li>

## 7.4.1 Detailed Description

Structure to hold parsed cli arguements. Namespace for the CLI objects

#### 7.4.2 Typedef Documentation

## 7.4.2.1 ProgramOptions

typedef struct Markov::API::CLI::\_programOptions Markov::API::CLI::ProgramOptions Structure to hold parsed cli arguements.

#### 7.4.3 Function Documentation

#### 7.4.3.1 operator <<()

References Markov::API::CLI::Terminal::colormap.

## 7.5 Markov::API::Concurrency Namespace Reference

Namespace for Concurrency related classes.

## **Classes**

· class ThreadSharedListHandler

Simple class for managing shared access to file.

## 7.5.1 Detailed Description

Namespace for Concurrency related classes.

# 7.6 Markov::API::CUDA Namespace Reference

Namespace for objects requiring CUDA libraries.

## **Namespaces**

Random

Namespace for Random engines operable under device space.

#### **Classes**

- · class CUDADeviceController
  - Controller class for CUDA device.
- class CUDAModelMatrix

Extension of Markov::API::ModelMatrix which is modified to run on GPU devices.

#### **Functions**

• \_\_global\_\_ void FastRandomWalkCUDAKernel (unsigned long int n, int minLen, int maxLen, char \*output ← Buffer, char \*matrixIndex, long int \*totalEdgeWeights, long int \*valueMatrix, char \*edgeMatrix, int matrixSize, int memoryPerKernelGrid, unsigned long \*seed)

```
CUDA kernel for the FastRandomWalk operation.__device__ char * strchr (char *p, char c, int s_len)
```

srtchr implementation on device space

#### 7.6.1 Detailed Description

Namespace for objects requiring CUDA libraries.

#### 7.6.2 Function Documentation

#### 7.6.2.1 FastRandomWalkCUDAKernel()

CUDA kernel for the FastRandomWalk operation.

Will be initiated by CPU and continued by GPU (global tag)

#### **Parameters**

n	- Number of passwords to generate.
minlen	- minimum string length for a single generation
maxLen	- maximum string length for a single generation
outputBuffer	- VRAM ptr to the output buffer
matrixIndex	- VRAM ptr to the matrix indices
totalEdgeWeights	- VRAM ptr to the totalEdgeWeights array
valueMatrix	- VRAM ptr to the edge weights array
edgeMatrix	- VRAM ptr to the edge representations array
matrixSize	- Size of the matrix dimensions
memoryPerKernelGrid	- Maximum memory usage per kernel grid
seed	- seed chunk to generate the random from (generated & used by Marsaglia)

# 7.6.2.2 strchr()

srtchr implementation on **device** space Fint the first matching index of a string

#### **Parameters**

р	- string to check
С	- character to match
s_len	- maximum string length

#### Returns

pointer to the match

# 7.7 Markov::API::CUDA::Random Namespace Reference

Namespace for Random engines operable under device space.

# **Classes**

· class Marsaglia

Extension of Markov::Random::Marsaglia which is capable o working on device space.

# **Functions**

• \_\_device\_\_ unsigned long devrandom (unsigned long &x, unsigned long &y, unsigned long &z)

Marsaglia Random Generation function operable in device space.

# 7.7.1 Detailed Description

Namespace for Random engines operable under device space.

# 7.7.2 Function Documentation

# 7.7.2.1 devrandom()

```
__device__ unsigned long Markov::API::CUDA::Random::devrandom ( unsigned long & x, unsigned long & y, unsigned long & z)
```

Marsaglia Random Generation function operable in device space.

#### **Parameters**

X	marsaglia internal x. Not constant, (ref)
У	marsaglia internal y. Not constant, (ref)
Z	marsaglia internal z. Not constant, (ref)

Returns

returns z

Definition at line 43 of file cudarandom.h.

```
00044
                unsigned long t;
               x ^= x « 16;
x ^= x » 5;
00045
00046
                x ^= x « 1;
00047
00048
00049
00050
               y = z;
z = t ^ x ^ y;
00051
00052
00053
                return z;
00055
```

# 7.8 Markov::GUI Namespace Reference

namespace for MarkovPasswords API GUI wrapper

#### Classes

· class about

QT Class for about page.

class CLI

QT CLI Class.

· class MarkovPasswordsGUI

Reporting UI.

class menu

QT Menu class.

· class Train

QT Training page class.

# 7.8.1 Detailed Description

namespace for MarkovPasswords API GUI wrapper

# 7.9 Markov::Markopy Namespace Reference

# **Functions**

• BOOST PYTHON MODULE (markopy)

#### 7.9.1 Function Documentation


# 7.9.1.1 BOOST\_PYTHON\_MODULE()

```
Markov::Markopy::BOOST_PYTHON_MODULE (
                 markopy )
Definition at line 11 of file markopy.cpp.
00012
                bool (Markov::API::MarkovPasswords::*Import) (const char*) = &Markov::Model<char>::Import;
bool (Markov::API::MarkovPasswords::*Export) (const char*) = &Markov::Model<char>::Export;
00014
00015
                class_<Markov::API::MarkovPasswords>("MarkovPasswords", init<>())
00016
                    .def(init<>())
00017
                      .def("Train", &Markov::API::MarkovPasswords::Train,
                     "Train the model\n"
00018
00019
00020
                     ":param datasetFileName: Ifstream* to the dataset. If null, use class member \n"
```

```
":param delimiter: a character, same as the delimiter in dataset content\n"
00022
                      ":param threads: number of OS threads to spawn\n")
00023
                      .def("Generate", &Markov::API::MarkovPasswords::Generate,
00024
                      "Generate passwords from a trained model.\n"
                      ":param n: Ifstream* to the dataset. If null, use class member \ensuremath{\text{n}} "
00025
                      ":param wordlistFileName: a character, same as the delimiter in dataset content\n"
":param minLen: number of OS threads to spawn\n"
00026
00028
                      ":param maxLen: Ifstream* to the dataset. If null, use class member \n"
00029
                      ":param threads: a character, same as the delimiter in dataset content\n"
                      ":param threads: number of OS threads to spawn\n")
.def("Import", Import, "Import a model file.")
.def("Export", Export, "Export a model to file.")
00030
00031
00032
00033
00034
```

References Markov::Model < NodeStorageType >::Export(), Markov::API::MarkovPasswords::Generate(), Markov::Model < NodeStorageType and Markov::API::MarkovPasswords::Train().

Here is the call graph for this function:



# 7.10 Markov::Random Namespace Reference

Objects related to RNG.

#### **Classes**

· class DefaultRandomEngine

Implementation using Random.h default random engine.

· class Marsaglia

Implementation of Marsaglia Random Engine.

· class Mersenne

Implementation of Mersenne Twister Engine.

· class RandomEngine

An abstract class for Random Engine.

# 7.10.1 Detailed Description

Objects related to RNG.

# 7.11 model 2gram Namespace Reference

# Variables

• alphabet = string.printable

password alphabet

• f = open('../../models/2gram.mdl', "wb")

output file handle

# 7.11.1 Detailed Description

python script for generating a 2gram model

#### 7.11.2 Variable Documentation

#### 7.11.2.1 alphabet

```
model_2gram.alphabet = string.printable
password alphabet
Definition at line 10 of file model_2gram.py.

7.11.2.2 f
model_2gram.f = open('../../models/2gram.mdl', "wb")
output file handle
```

# 7.12 random Namespace Reference

# 7.12.1 Detailed Description

Definition at line 16 of file model\_2gram.py.

```
-model
```

python script for generating a 2gram model

# 7.13 random-model Namespace Reference

# **Variables**

```
    alphabet = string.printable
        password alphabet
    f = open('../../models/random.mdl', "wb")
        output file handle
```

# 7.13.1 Variable Documentation

# 7.13.1.1 alphabet

```
random-model.alphabet = string.printable
password alphabet
Definition at line 10 of file random-model.py.

7.13.1.2 f

random-model.f = open('../../models/random.mdl', "wb")
output file handle
Definition at line 16 of file random-model.py.
```

# 7.14 Testing Namespace Reference

Namespace for Microsoft Native Unit Testing Classes.

# **Namespaces**

MarkovModel

Testing namespace for MarkovModel.

MarkovPasswords

Testing namespace for MarkovPasswords.

MVP

Testing Namespace for Minimal Viable Product.

# 7.14.1 Detailed Description

Namespace for Microsoft Native Unit Testing Classes.

# 7.15 Testing::MarkovModel Namespace Reference

Testing namespace for MarkovModel.

# **Functions**

```
• TEST_CLASS (Edge)
```

Test class for rest of Edge cases.

• TEST\_CLASS (Node)

Test class for rest of Node cases.

TEST\_CLASS (Model)

Test class for rest of model cases.

# 7.15.1 Detailed Description

Testing namespace for MarkovModel.

# 7.15.2 Function Documentation

#### 7.15.2.1 TEST\_CLASS() [1/3]

Test class for rest of Edge cases.

send exception on integer underflow

test integer overflows


Definition at line 494 of file UnitTests.cpp.

```
00495
00496
                public:
00499
                     TEST_METHOD(except_integer_underflow) {
00500
                         auto _underflow_adjust = [] {
00501
                              Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
                              Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(('r'));
00502
00503
        RightNode);
00504
                              e->AdjustEdge(15);
00505
                               e->AdjustEdge(-30);
00506
                              delete LeftNode;
00507
                              delete RightNode;
00508
                              delete e:
00509
00510
                          Assert::ExpectException<std::underflow_error>(_underflow_adjust);
```

```
00511
                  }
00512
00515
                  TEST_METHOD(except_integer_overflow) {
00516
                       auto _overflow_adjust = [] {
                          Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00517
                          Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00518
                          Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(LeftNode,
00519
       RightNode);
00520
                           e->AdjustEdge(~0ull);
00521
                           e->AdjustEdge(1);
00522
                          delete LeftNode;
00523
                          delete RightNode;
00524
                          delete e;
00525
00526
                      Assert::ExpectException<std::underflow_error>(_overflow_adjust);
00527
00528
              };
```

#### References TEST\_CLASS().

Here is the call graph for this function:



# 7.15.2.2 TEST\_CLASS() [2/3]

#### Test class for rest of model cases.


Definition at line 592 of file UnitTests.cpp.

```
00593
                public:
00594
                    TEST_METHOD(functional_random_walk) {
   unsigned char* res2 = new unsigned char[12 + 5];
00595
00596
                         Markov::Random::Marsaglia MarsagliaRandomEngine;
00597
00598
                         Markov::Model<unsigned char> m;
00599
                         Markov::Node<unsigned char>* starter = m.StarterNode();
                         Markov::Node<unsigned char>* a = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* b = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* c = new Markov::Node<unsigned char>('c');
00600
00601
00602
00603
                         Markov::Node<unsigned char>* end = new Markov::Node<unsigned char>(0xff);
00604
                         starter->Link(a)->AdjustEdge(1);
00605
                         a->Link(b)->AdjustEdge(1);
00606
                         b->Link(c)->AdjustEdge(1);
00607
                         c->Link (end) ->AdjustEdge(1);
00608
00609
                         char* res = (char*)m.RandomWalk(&MarsagliaRandomEngine,1,12,res2);
00610
                         Assert::IsFalse(strcmp(res, "abc"));
00611
00612
                    TEST_METHOD(functionoal_random_walk_without_any) {
00613
                         Markov::Model<unsigned char> m;
                         Markov::Node<unsigned char>* starter = m.StarterNode();
00614
                         Markov::Node<unsigned char>* a = new Markov::Node<unsigned char>('a');
00615
                         Markov::Node<unsigned char>* b = new Markov::Node<unsigned char>('b');
00616
                         Markov::Node<unsigned char>* c = new Markov::Node<unsigned char>('c');
00617
00618
                         Markov::Node<unsigned char>* end = new Markov::Node<unsigned char>(0xff);
                         Markov::Edge<unsigned char>* res = NULL;
00619
                         starter->Link(a)->AdjustEdge(1);
00620
                         a->Link(b)->AdjustEdge(1);
00621
                         b->Link(c)->AdjustEdge(1);
00622
00623
                         c->Link (end) ->AdjustEdge(1);
00624
00625
                         res = starter->FindEdge('D');
00626
                         Assert::IsNull(res);
00627
00628
```

References TEST\_CLASS().
Referenced by TEST\_CLASS().
Here is the call graph for this function:



Here is the caller graph for this function:



# 7.15.2.3 TEST\_CLASS() [3/3]


Test class for rest of Node cases. test RandomNext with 64 bit high values test RandomNext with 64 bit high values randomNext when no edges are present Definition at line 532 of file UnitTests.cpp.

```
00533
00534
                public:
00535
00538
                     TEST_METHOD(rand_next_u64) {
00539
                          Markov::Random::Marsaglia MarsagliaRandomEngine;
                         Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00540
00541
                          Markov::Edge<unsigned char>* e = src->Link(target1);
00543
                          e->AdjustEdge((unsigned long)(1ull « 63));
00544
                          Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00545
                          Assert::IsTrue(res == target1);
00546
                          delete src;
00547
                          delete target1;
00548
                          delete e;
00549
00550
00551
00554
                     TEST METHOD (rand_next_u64_max) {
00555
                          Markov::Random::Marsaglia MarsagliaRandomEngine;
                          Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00556
00557
00558
                          Markov::Edge<unsigned char>* e = src->Link(target1);
00559
                          e->AdjustEdge((0xffffFFFF));
00560
                          Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
                          Assert::IsTrue(res == target1);
00561
00562
                          delete src;
00563
                          delete target1;
```

```
00564
                             delete e;
00565
00566
00567
                        TEST_METHOD(uninitialized_rand_next) {
00570
00571
00572
                             auto _invalid_next = [] {
00573
                                   Markov::Random::Marsaglia MarsagliaRandomEngine;
                                  Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00574
00575
00576
                                  Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(src, target1);
Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00577
00578
00579
00580
                                   delete target1;
00581
                                   delete e;
00582
                             };
00583
00584
                             Assert::ExpectException<std::logic_error>(_invalid_next);
                        }
00586
00587
00588
                  };
```

References TEST\_CLASS().

Here is the call graph for this function:



# 7.16 Testing::MarkovPasswords Namespace Reference

Testing namespace for MarkovPasswords.

# 7.16.1 Detailed Description

Testing namespace for MarkovPasswords.

# 7.17 Testing::MVP Namespace Reference

Testing Namespace for Minimal Viable Product.

# **Namespaces**

MarkovModel

Testing Namespace for MVP MarkovModel.

MarkovPasswords

Testing namespace for MVP MarkovPasswords.

# 7.17.1 Detailed Description

Testing Namespace for Minimal Viable Product.

# 7.18 Testing::MVP::MarkovModel Namespace Reference

Testing Namespace for MVP MarkovModel.

#### **Functions**

• TEST CLASS (Edge)

Test class for minimal viable Edge.

• TEST\_CLASS (Node)

Test class for minimal viable Node.

• TEST CLASS (Model)

Test class for minimal viable Model.

### 7.18.1 Detailed Description

Testing Namespace for MVP MarkovModel.

#### 7.18.2 Function Documentation

# 7.18.2.1 TEST\_CLASS() [1/3]

Test class for minimal viable Edge.

test default constructor

test linked constructor with two nodes

test AdjustEdge function

test TraverseNode returning RightNode

test LeftNode/RightNode setter

test negative adjustments


Definition at line 21 of file UnitTests.cpp.

```
00022
                   public:
00023
00024
00027
                       TEST METHOD (default constructor) {
00028
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>;
                           Assert::IsNull(e->LeftNode());
00029
00030
                            Assert::IsNull(e->RightNode());
00031
                           delete e;
00032
00033
00036
                       TEST METHOD (linked constructor) {
00037
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
                            Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00038
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
00039
       RightNode);
00040
                           Assert::IsTrue(LeftNode == e->LeftNode());
Assert::IsTrue(RightNode == e->RightNode());
00041
00042
                           delete LeftNode;
00043
                           delete RightNode;
00044
                           delete e;
00045
00046
00049
                       TEST METHOD (AdjustEdge) {
00050
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
                            Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00051
00052
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(LeftNode,
       RightNode);
                           e->AdjustEdge(15);
Assert::AreEqual(15ull, e->EdgeWeight());
00053
00054
00055
                           e->AdjustEdge(15);
00056
                           Assert::AreEqual(30ull, e->EdgeWeight());
00057
                            delete LeftNode;
00058
                           delete RightNode;
00059
                           delete e;
00060
00061
00064
                       TEST_METHOD (TraverseNode) {
00065
                            Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00066
                            Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00067
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(LeftNode,
       RightNode);
00068
                           Assert::IsTrue(RightNode == e->TraverseNode());
00069
                           delete LeftNode;
00070
                           delete RightNode;
```

```
00071
                              delete e;
00072
00073
00076
                          TEST_METHOD(set_left_and_right) {
                              Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00077
00078
00079
                              Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(LeftNode,
        RightNode);
00080
00081
                              Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>;
                              e2->SetLeftEdge(LeftNode);
00082
00083
                              e2->SetRightEdge(RightNode);
00084
00085
                              Assert::IsTrue(e1->LeftNode() == e2->LeftNode());
00086
                              Assert::IsTrue(e1->RightNode() == e2->RightNode());
00087
                               delete LeftNode;
00088
                              delete RightNode;
00089
                              delete e1;
00090
                              delete e2;
00091
00092
00095
                          TEST_METHOD (negative_adjust) {
00096
                              Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00097
00098
                              Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
        RightNode);
00099
                               e->AdjustEdge(15);
00100
                              Assert::AreEqual(15ull, e->EdgeWeight());
00101
                               e->AdjustEdge(-15);
                              Assert::AreEqual(Oull, e->EdgeWeight());
00102
00103
                              delete LeftNode;
00104
                              delete RightNode;
00105
                               delete e;
00106
00107
                     } ;
```

References TEST\_CLASS().

Here is the call graph for this function:



# 7.18.2.2 TEST\_CLASS() [2/3]

Test class for minimal viable Model.

test model constructor for starter node

test import

test export

test random walk

Definition at line 347 of file UnitTests.cpp.

```
00348
00349
                  public:
00352
                      TEST_METHOD (model_constructor) {
00353
                          Markov::Model<unsigned char> m;
                          Assert::AreEqual((unsigned char)'\0', m.StarterNode()->NodeValue());
00354
00355
00356
00359
                      TEST_METHOD(import_filename) {
00360
                          Markov::Model<unsigned char> m;
00361
                          Assert::IsTrue(m.Import("../MarkovPasswords/Models/2gram.mdl"));
00362
00363
00366
                      TEST METHOD (export filename) {
00367
                          Markov::Model<unsigned char> m;
00368
                          Assert::IsTrue(m.Export("../MarkovPasswords/Models/testcase.mdl"));
```

```
00369
00370
00373
TEST_METHOD(random_walk) {
00374
    unsigned char* res = new unsigned char[12 + 5];
00375
    Markov::Random::Marsaglia MarsagliaRandomEngine;
00376
    Markov::Model<unsigned char> m;
00377
    Assert::IsTrue(m.Import("../Models/finished2.mdl"));
00378
    Assert::IsNotNull(m.RandomWalk(&MarsagliaRandomEngine,1,12,res));
00379
}
00380
};
```

References TEST CLASS().

Referenced by TEST CLASS().

Here is the call graph for this function:



Here is the caller graph for this function:

```
Testing::MVP::MarkovModel ::TEST_CLASS Testing::MVP::MarkovModel ::TEST_CLASS
```

# 7.18.2.3 TEST\_CLASS() [3/3]

```
Testing::MVP::MarkovModel::TEST_CLASS (
               Node )
Test class for minimal viable Node.
test default constructor
test custom constructor with unsigned char
test link function
test link function
test RandomNext with low values
test RandomNext with 32 bit high values
random next on a node with no follow-ups
random next on a node with no follow-ups
test updateEdges
test updateEdges
test FindVertice
test FindVertice
test FindVertice
Definition at line 111 of file UnitTests.cpp.
00112
00113
                   public:
00114
00117
                       TEST_METHOD(default_constructor) {
```


```
00118
                             Markov::Node<unsigned char>* n = new Markov::Node<unsigned char>();
                             Assert::AreEqual((unsigned char)0, n->NodeValue());
00119
00120
                             delete n;
00121
                        }
00122
                        TEST_METHOD (uchar_constructor) {
00125
00126
                             Markov::Node<unsigned char>* n = NULL;
00127
                             unsigned char test_cases[] = { 'c', 0x00, 0xff, -32 };
00128
                             for (unsigned char tcase : test_cases) {
00129
                                 n = new Markov::Node<unsigned char>(tcase);
00130
                                 Assert::AreEqual(tcase, n->NodeValue());
00131
                                 delete n:
00132
                             }
00133
00134
00137
                        TEST_METHOD(link_left) {
                             Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00138
00139
                             Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00140
00141
                             Markov::Edge<unsigned char>* e = LeftNode->Link(RightNode);
00142
                             delete LeftNode;
00143
                             delete RightNode;
00144
                             delete e;
00145
00146
00149
                        TEST_METHOD(link_right) {
00150
                             Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00151
                             Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00152
00153
                             Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (NULL, RightNode);
00154
                             LeftNode->Link(e):
00155
                             Assert::IsTrue(LeftNode == e->LeftNode());
00156
                             Assert::IsTrue(RightNode == e->RightNode());
00157
                             delete LeftNode;
00158
                             delete RightNode;
00159
                             delete e;
00160
00161
00164
                        TEST_METHOD(rand_next_low) {
00165
                             Markov::Random::Marsaglia MarsagliaRandomEngine;
                            Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Edge<unsigned char>* e = src->Link(target1);
00166
00167
00168
00169
                             e->AdjustEdge(15);
00170
                             Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00171
                             Assert::IsTrue(res == target1);
00172
                             delete src;
00173
                             delete target1;
00174
                             delete e:
00175
00176
00177
00180
                        TEST_METHOD(rand_next_u32) {
00181
                             Markov::Random::Marsaglia MarsagliaRandomEngine;
                             Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00182
00183
                             Markov::Edge<unsigned char>* e = src->Link(target1);
00184
00185
                             e->AdjustEdge(1 « 31);
00186
                             Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00187
                             Assert::IsTrue(res == target1);
00188
                             delete src;
00189
                             delete target1;
00190
                             delete e;
00191
00192
00193
00196
                        TEST_METHOD(rand_next_choice_1) {
                             Markov::Random::Marsaglia MarsagliaRandomEngine;
00197
00198
                             Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                             Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00199
00200
00201
                             Markov::Edge<unsigned char>* e1 = src->Link(target1);
                             Markov::Edge<unsigned char>* e2 = src->Link(target2);
00202
00203
                             e1->AdjustEdge(1);
00204
                             e2->AdjustEdge((unsigned long)(1ull « 31));
00205
                             Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00206
                             Assert::IsNotNull(res);
                             Assert::IsTrue(res == target2);
00207
00208
                             delete src;
00209
                             delete target1;
00210
                             delete e1;
00211
                             delete e2;
00212
00213
00216
                        TEST_METHOD(rand_next_choice_2) {
                             Markov::Random::Marsaglia MarsagliaRandomEngine;
00217
00218
                             Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
```

```
00219
                                Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
                                Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
Markov::Edge<unsigned char>* e1 = src->Link(target1);
Markov::Edge<unsigned char>* e2 = src->Link(target2);
00220
00221
00222
00223
                                e2->AdjustEdge(1);
                                e1->AdjustEdge((unsigned long)(1ull « 31));
00224
                                Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00225
00226
                                Assert::IsNotNull(res);
00227
                                Assert::IsTrue(res == target1);
00228
                                delete src;
00229
                                delete target1;
00230
                                delete el:
00231
                                delete e2;
00232
00233
00234
                           TEST_METHOD (update_edges_count) {
00237
00238
00239
                                Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                                Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00240
00241
                                Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target2);
00242
00243
00244
                                e1->AdjustEdge(25):
00245
                                src->UpdateEdges(e1);
00246
                                e2->AdjustEdge(30);
00247
                                src->UpdateEdges(e2);
00248
00249
                                Assert::AreEqual((size_t)2, src->Edges()->size());
00250
00251
                                delete src:
00252
                                delete target1;
00253
                                delete e1;
00254
                                delete e2;
00255
00256
00257
00260
                           TEST_METHOD (update_edges_total) {
00261
00262
                                Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                                Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target1);
00263
00264
00265
00266
                                e1->AdjustEdge(25);
00267
                                src->UpdateEdges(e1);
00268
                                e2->AdjustEdge(30);
00269
                                src->UpdateEdges(e2);
00270
00271
                                //Assert::AreEqual(55ull, src->TotalEdgeWeights());
00272
00273
                                delete src;
00274
                                delete target1;
00275
                                delete e1;
00276
                                delete e2;
00277
00278
00279
00282
                           TEST_METHOD(find_vertice) {
00283
                                Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00284
                                Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00285
00286
00287
                                Markov::Edge<unsigned char>* res = NULL;
00288
                                src->Link(target1);
00289
                                src->Link(target2);
00290
00291
00292
                                res = src->FindEdge('b');
00293
                                Assert::IsNotNull(res);
00294
                                Assert::AreEqual((unsigned char)'b', res->TraverseNode()->NodeValue());
00295
                                res = src->FindEdge('c');
00296
                                Assert::IsNotNull(res);
00297
                                Assert::AreEqual((unsigned char)'c', res->TraverseNode()->NodeValue());
00298
00299
                                delete src;
00300
                                delete target1;
00301
                                delete target2;
00302
00303
00304
00305
00306
00309
                           TEST METHOD (find vertice without any) {
00310
00311
                                auto _invalid_next = [] {
                                     Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00312
00313
                                     Markov::Edge<unsigned char>* res = NULL;
```

```
00314
00315
                                  res = src->FindEdge('b');
00316
                                  Assert::IsNull(res);
00317
00318
                                  delete src;
00319
                              };
00320
00321
                              //Assert::ExpectException<std::logic_error>(_invalid_next);
00322
00323
                         TEST_METHOD(find_vertice_nonexistent) {
00326
00327
00328
                              Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                             Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00329
00330
00331
                             Markov::Edge<unsigned char>* res = NULL;
00332
                             src->Link(target1);
00333
                             src->Link(target2);
00334
00335
                             res = src->FindEdge('D');
00336
                             Assert::IsNull(res);
00337
00338
                             delete src;
00339
                             delete target1;
00340
                             delete target2;
00341
00342
00343
```

References TEST\_CLASS().

Here is the call graph for this function:



# 7.19 Testing::MVP::MarkovPasswords Namespace Reference

Testing namespace for MVP MarkovPasswords.

#### **Functions**

• TEST\_CLASS (ArgParser)

Test Class for Argparse class.

# 7.19.1 Detailed Description

Testing namespace for MVP MarkovPasswords.

# 7.19.2 Function Documentation

# 7.19.2.1 TEST\_CLASS()

#### test basic generate

test basic train

test basic generate

Definition at line 389 of file UnitTests.cpp.

```
00390
                 public:
00391
00394
                     TEST_METHOD(generate_basic) {
00395
                         int argc = 8;
                         char *argv[] = {"markov.exe", "generate", "-if", "model.mdl", "-of",
00396
       "passwords.txt", "-n", "100"};
00397
00398
                          /*ProgramOptions *p = Argparse::parse(argc, argv);
00399
                         Assert::IsNotNull(p);
00400
00401
                         Assert::AreEqual(p->bImport, true);
00402
                          Assert::AreEqual(p->bExport, false);
00403
                          Assert::AreEqual(p->importname, "model.mdl");
00404
                         Assert::AreEqual(p->outputfilename, "passwords.txt");
00405
                         Assert::AreEqual(p->generateN, 100); */
00406
00407
00408
00411
                     TEST_METHOD(generate_basic_reorder) {
00412
                          int argc = 8;
                         char *argv[] = { "markov.exe", "generate", "-n", "100", "-if", "model.mdl", "-of",
00413
       "passwords.txt" };
00414
00415
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00416
                          Assert::IsNotNull(p);
00417
00418
                         Assert::AreEqual(p->bImport, true);
                         Assert::AreEqual(p->bExport, false);
Assert::AreEqual(p->importname, "model.mdl");
00419
00420
                          Assert::AreEqual(p->outputfilename, "passwords.txt");
00422
                          Assert::AreEqual(p->generateN, 100); */
00423
00424
00427
                     TEST_METHOD(generate_basic_longname) {
       00428
00429
00430
00431
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00432
                         Assert::IsNotNull(p);
00433
00434
                         Assert::AreEqual(p->bImport, true);
00435
                         Assert::AreEqual(p->bExport, false);
00436
                          Assert::AreEqual(p->importname, "model.mdl");
00437
                         Assert::AreEqual(p->outputfilename, "passwords.txt");
                         Assert::AreEqual(p->generateN, 100); */
00438
00439
                     }
00440
00443
                     TEST_METHOD(generate_fail_badmethod) {
       00444
00445
00446
00447
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00448
                         Assert::IsNull(p); */
00449
00450
00453
                     TEST_METHOD(train_basic) {
00454
                         int argc = 4;
00455
                         char *argv[] = { "markov.exe", "train", "-ef", "model.mdl" };
00456
00457
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00458
                          Assert::IsNotNull(p);
00459
00460
                         Assert::AreEqual(p->bImport, false);
00461
                         Assert::AreEqual(p->bExport, true);
                         Assert::AreEqual(p->exportname, "model.mdl"); */
00462
00463
00464
00465
00468
                     TEST_METHOD(train_basic_longname) {
00469
                          int argc = 4:
                         char *argv[] = { "markov.exe", "train", "--exportfilename", "model.mdl" };
00470
00471
00472
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00473
                         Assert::IsNotNull(p);
00474
00475
                         Assert::AreEqual(p->bImport, false);
Assert::AreEqual(p->bExport, true);
00476
00477
                          Assert::AreEqual(p->exportname, "model.mdl"); */
00478
00479
```

```
00480
00481
00482 };
References TEST_CLASS().
Referenced by TEST_CLASS().
Here is the call graph for this function:
```



Here is the caller graph for this function:




# **Chapter 8**

# **Class Documentation**

8.1 Markov::API::CLI::\_programOptions Struct Reference

Collaboration diagram for Markov::API::CLI::\_programOptions:



# **Public Attributes**

bool blmport

Import flag to validate import

bool bExport

Export flag to validate export

• bool bFailure

Failure flag to validate succesfull running

• char seperator

Seperator character to use with training data. (character between occurence and value)"

• std::string importname

Import name of our model.

std::string exportname

Import name of our given wordlist

· std::string wordlistname

Import name of our given wordlist

std::string outputfilename

Output name of our generated password list

• std::string datasetname

The name of the given dataset

int generateN

Number of passwords to be generated

# 8.1.1 Detailed Description

Structure to hold parsed cli arguements. Definition at line 17 of file argparse.h.

# 8.1.2 Member Data Documentation

# 8.1.2.1 **bExport**

bool Markov::API:::CLI::\_programOptions::bExport
Export flag to validate export

Definition at line 26 of file argparse.h.

 $Referenced \ by \ Markov::API::CLI::Argparse::SetProgramOptions().$ 

#### 8.1.2.2 bFailure

bool Markov::API:::CLI::\_programOptions::bFailure
Failure flag to validate succesfull running

Definition at line 31 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.3 blmport

bool Markov::API::CLI::\_programOptions::bImport
Import flag to validate import

Definition at line 21 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.4 datasetname

std::string Markov::API::CLI::\_programOptions::datasetname

The name of the given dataset

Definition at line 61 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.5 exportname

std::string Markov::API::CLI::\_programOptions::exportname
Import name of our given wordlist

Definition at line 46 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.6 generateN

int Markov::API::CLI::\_programOptions::generateN

Number of passwords to be generated

Definition at line 66 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

#### 8.1.2.7 importname

std::string Markov::API::CLI::\_programOptions::importname

Import name of our model.

Definition at line 41 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.8 outputfilename

std::string Markov::API::CLI::\_programOptions::outputfilename

Output name of our generated password list

Definition at line 56 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse(), and Markov::API::CLI::Argparse::setProgramOptions().

# 8.1.2.9 seperator

char Markov::API::CLI::\_programOptions::seperator

Seperator character to use with training data. (character between occurence and value)"

Definition at line 36 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::setProgramOptions().

#### 8.1.2.10 wordlistname

std::string Markov::API::CLI::\_programOptions::wordlistname
Import name of our given wordlist

Definition at line 51 of file argparse.h.

Referenced by Markov::API::CLI::Argparse::Argparse().

The documentation for this struct was generated from the following file:


· argparse.h

# 8.2 Markov::GUI::about Class Reference


QT Class for about page.

#include <about.h>

Inheritance diagram for Markov::GUI::about:



Collaboration diagram for Markov::GUI::about:



# **Public Member Functions**

about (QWidget \*parent=Q\_NULLPTR)

# **Private Attributes**

• Ui::main ui

# 8.2.1 Detailed Description

QT Class for about page. Definition at line 12 of file about.h.

# 8.2.2 Constructor & Destructor Documentation

# 8.2.2.1 about()

# 8.2.3 Member Data Documentation

#### 8.2.3.1 ui

```
Ui:: main Markov::GUI::about::ui [private]

Definition at line 18 of file about.h.
```

The documentation for this class was generated from the following file:


about.h

# 8.3 Markov::API::CLI::Argparse Class Reference

Parse command line arguements.

```
#include <argparse.h>
```

Collaboration diagram for Markov::API::CLI::Argparse:



# **Public Member Functions**

- Argparse ()
- Argparse (int argc, char \*\*argv)

Parse command line arguements.

• Markov::API::CLI::ProgramOptions getProgramOptions (void)

Getter for command line options.

void setProgramOptions (bool i, bool e, bool bf, char s, std::string iName, std::string exName, std::string oName, std::string dName, int n)

Initialize program options structure.

# **Static Public Member Functions**

static Markov::API::CLI::ProgramOptions \* parse (int argc, char \*\*argv)
 parse cli commands and return

• static void help ()

Print help string.

# **Private Attributes**

· Markov::API::CLI::ProgramOptions po

ProgramOptions structure object.

# 8.3.1 Detailed Description

Parse command line arguements.

Definition at line 73 of file argparse.h.

#### 8.3.2 Constructor & Destructor Documentation

#### 8.3.2.1 Argparse() [1/2]

```
Markov::API::CLI::Argparse::Argparse ( )
```

# 8.3.2.2 Argparse() [2/2]

Parse command line arguements.

Parses command line arguements to populate ProgramOptions structure.

#### **Parameters**

argc	Number of command line arguements
argv	Array of command line parameters

### Definition at line 85 of file argparse.h.

```
00085
00086
00087
                  /*bool bImp;
00088
                  bool bExp;
00089
                  bool bFail;
00090
                  char sprt;
00091
                  std::string imports;
00092
                  std::string exports;
00093
                  std::string outputs;
00094
                  std::string datasets;
00095
                  int generateN;
00096
00097
                  opt::options_description desc("Options");
00098
00099
00100
                  desc.add_options()
00101
                      ("generate", "Generate strings with given parameters")
00102
                       ("train", "Train model with given parameters")
```

```
00103
                        ("combine", "Combine")
                        ("import", opt::value<std::string>(), "Import model file")
("output", opt::value<std::string>(), "Output model file. This model will be exported
00104
00105
       when done. Will be ignored for generation mode")
00106
                        ("dataset", opt::value<std::string>(), "Dataset file to read input from training. Will
       be ignored for generation mode")
00107
                        ("seperator", opt::value<char>(), "Seperator character to use with training data.
        (character between occurence and value)")
00108
                        ("wordlist", opt::value<std::string>(), "Wordlist file path to export generation
       results to. Will be ignored for training mode")
                        ("count", opt::value<int>(), "Number of lines to generate. Ignored in training mode") ("verbosity", "Output verbosity")
00109
00110
                        ("help", "Option definitions");
00111
00112
00113
                        opt::variables_map vm;
00114
00115
                        opt::store(opt::parse_command_line(argc, argv, desc), vm);
00116
00117
                        opt::notify(vm);
00118
00119
                        //std::cout « desc « std::endl;
00120
                        if (vm.count("help")) {
00121
                        std::cout « desc « std::endl;
00122
00123
                        if (vm.count("output") == 0) this->po.outputfilename = "NULL";
00124
00125
                        else if (vm.count("output") == 1) {
00126
                            this->po.outputfilename = vm["output"].as<std::string>();
00127
                            this->po.bExport = true;
00128
00129
                        else {
00130
                            this->po.bFailure = true;
00131
                            std::cout « "UNIDENTIFIED INPUT" « std::endl;
00132
                            std::cout « desc « std::endl;
00133
00134
00135
00136
                        if (vm.count("dataset") == 0) this->po.datasetname = "NULL";
00137
                        else if (vm.count("dataset") == 1) {
00138
                            this->po.datasetname = vm["dataset"].as<std::string>();
00139
00140
                        else (
                            this->po.bFailure = true:
00141
                            std::cout « "UNIDENTIFIED INPUT" « std::endl;
00142
                            std::cout « desc « std::endl;
00143
00144
00145
00146
                        if (vm.count("wordlist") == 0) this->po.wordlistname = "NULL";
00147
00148
                        else if (vm.count("wordlist") == 1) {
                            this->po.wordlistname = vm["wordlist"].as<std::string>();
00149
00150
00151
                        else {
00152
                            this->po.bFailure = true;
std::cout « "UNIDENTIFIED INPUT" « std::endl;
00153
                            std::cout « desc « std::endl;
00154
00156
00157
                        if (vm.count("import") == 0) this->po.importname = "NULL";
                        else if (vm.count("import") == 1) {
    this->po.importname = vm["import"].as<std::string>();
00158
00159
00160
                            this->po.bImport = true;
00161
00162
00163
                            this->po.bFailure = true;
                            std::cout « "UNIDENTIFIED INPUT" « std::endl;
00164
00165
                            std::cout « desc « std::endl;
00166
00167
00168
00169
                        if (vm.count("count") == 0) this->po.generateN = 0;
00170
                        else if (vm.count("count") == 1)
                            this->po.generateN = vm["count"].as<int>();
00171
00172
00173
                        else {
00174
                            this->po.bFailure = true;
                            std::cout « "UNIDENTIFIED INPUT" « std::endl;
00175
00176
                            std::cout « desc « std::endl;
00177
00178
00179
                        /*std::cout « vm["output"].as<std::string>() « std::endl;
                        std::cout « vm["dataset"].as<std::string>() « std::endl;
std::cout « vm["wordlist"].as<std::string>() « std::endl;
00180
00181
00182
                        std::cout « vm["output"].as<std::string>() « std::endl;
                        std::cout « vm["count"].as<int>() « std::endl;*/
00183
00184
00185
```

```
00186 //else if (vm.count("train")) std::cout « "train oldu" « std::endl;
```

References Markov::API::CLI::\_programOptions::bExport, Markov::API::CLI::\_programOptions::bFailure, Markov::API::CLI::\_programOptions::bFailure, Markov::API::CLI::\_programOptions::datasetname, Markov::API::CLI::\_programOptions::generateN, Markov::API::CLI::\_programOptions::wordlistname.

Here is the caller graph for this function:

Referenced by main().



#### 8.3.3 Member Function Documentation

#### 8.3.3.1 getProgramOptions()

Getter for command line options.

Getter for ProgramOptions populated by the arguement parser

Returns

ProgramOptions structure.

```
Definition at line 194 of file argparse.h.
```

References po.

#### 8.3.3.2 help()

```
void Markov::API::CLI::Argparse::help ( ) [static]
```

# Print help string.

```
Definition at line 8 of file argparse.cpp.
```

```
00008
00009
          std::cout «
          "Markov Passwords - Help\n"
00011
          "Options:\n"
00012
              \n"
00013
              -of --outputfilename\n"
                  Filename to output the generation results\n"
00014
00015
              -ef --exportfilename\n"
00016
                  filename to export built model to\n"
00017
              -if --importfilename\n"
              filename to import model from\n"
-n (generate count)\n"
00018
00019
00020
                  Number of lines to generate\n"
             \n"
00021
00022
          "Usage: \n"
00023
            markov.exe -if empty_model.mdl -ef model.mdl\n"
00024
                  import empty_model.mdl and train it with data from stdin. When done, output the model to
       model.mdl\n"
00025
          "\n"
00026
             markov.exe -if empty_model.mdl -n 15000 -of wordlist.txt\n"
00027
                  import empty_model.mdl and generate 15000 words to wordlist.txt\n"
00028
```

```
00029
          « std::endl;
00030 }
```

# 8.3.3.3 parse()

```
Markov::API::CLI::ProgramOptions * Markov::API::CLI::Argparse::parse (
             int argc,
            char ** argv ) [static]
```

parse cli commands and return

#### **Parameters**

argc	- Program arguement count
argv	- Program arguement values array

#### Returns

ProgramOptions structure.

```
Definition at line 4 of file argparse.cpp.
00004 { return 0; }
```

# 8.3.3.4 setProgramOptions()

```
void Markov::API::CLI::Argparse::setProgramOptions (
             bool i,
             bool e,
             bool bf,
             char s,
             std::string iName,
             std::string exName,
             std::string oName,
             std::string dName,
             int n ) [inline]
```

Initialize program options structure.

#### **Parameters**

i	boolean, true if import operation is flagged
е	boolean, true if export operation is flagged
bf	boolean, true if there is something wrong with the command line parameters
s	seperator character for the import function
iName	import filename
exName	export filename
oName	output filename
dName	corpus filename
n	number of passwords to be generated

# Definition at line 211 of file argparse.h.

```
00211
00212
                          this->po.bImport = i;
                          this->po.bExport = e;
00213
                          this->po.seperator = s;
this->po.bFailure = bf;
00214
00215
                          this->po.sratiute = b;
this->po.generateN = n;
this->po.importname = iName;
00216
00217
```

References Markov::API::CLI::\_programOptions::bExport, Markov::API::CLI::\_programOptions::bFailure, Markov::API::CLI::\_programOptions::bFailure, Markov::API::CLI::\_programOptions::exportname, Markov::API::CLI::\_programOptions::exportname, Markov::API::CLI::\_programOptions::outputfilename, po, and Markov::API::CLI::\_programOptions::seperator.

#### 8.3.4 Member Data Documentation

#### 8.3.4.1 po

Markov::API::CLI::ProgramOptions Markov::API::CLI::Argparse::po [private]

ProgramOptions structure object.

Definition at line 246 of file argparse.h.

Referenced by Argparse(), getProgramOptions(), and setProgramOptions().

The documentation for this class was generated from the following files:


- · argparse.h
- · argparse.cpp

# 8.4 Markov::GUI::CLI Class Reference


QT CLI Class.

#include <CLI.h>

Inheritance diagram for Markov::GUI::CLI:



Collaboration diagram for Markov::GUI::CLI:



# **Public Slots**

- void start ()
- void statistics ()
- void about ()

# **Public Member Functions**

• CLI (QWidget \*parent=Q\_NULLPTR)

# **Private Attributes**

• Ui::CLI ui

# 8.4.1 Detailed Description

QT CLI Class.

Definition at line 8 of file CLI.h.

# 8.4.2 Constructor & Destructor Documentation

# 8.4.2.1 CLI()

# 8.4.3 Member Function Documentation

# 8.4.3.1 about

```
void Markov::GUI::CLI::about ( ) [slot]
```

#### 8.4.3.2 start

```
void Markov::GUI::CLI::start ( ) [slot]
Referenced by main().
```

ricicioneca by main().

Here is the caller graph for this function:



# 8.4.3.3 statistics

```
void Markov::GUI::CLI::statistics ( ) [slot]
```

#### 8.4.4 Member Data Documentation

# 8.4.4.1 ui

```
Ui::CLI Markov::GUI::CLI::ui [private]
```

Definition at line 14 of file CLI.h.

The documentation for this class was generated from the following file:


• CLI.h

# 8.5 Markov::API::CUDA::CUDADeviceController Class Reference

Controller class for CUDA device.

#include <cudaDeviceController.h>

Inheritance diagram for Markov::API::CUDA::CUDADeviceController:



 $Collaboration\ diagram\ for\ Markov:: API:: CUDA:: CUDA Device Controller:$ 

# Markov::API::CUDA:: CUDADeviceController + ListCudaDevices() # CudaCheckNotifyErr() # CudaMalloc2DToFlat() # CudaMemcpy2DToFlat() # CudaMigrate2DFlat()

#### **Static Public Member Functions**

static \_\_host\_\_ void ListCudaDevices ()
 List CUDA devices in the system.

## **Static Protected Member Functions**

```
    static __host__ int CudaCheckNotifyErr (cudaError_t _status, const char *msg, bool bExit=true)
    Check results of the last operation on GPU.
```

```
• template<typename T >
```

```
static __host__ cudaError_t CudaMalloc2DToFlat (T **dst, int row, int col)
```

Malloc a 2D array in device space.

template<typename T >

```
static __host__ cudaError_t CudaMemcpy2DToFlat (T *dst, T **src, int row, int col)
```

Memcpy a 2D array in device space after flattening.

• template<typename T >

```
static __host__ cudaError_t CudaMigrate2DFlat (T **dst, T **src, int row, int col)
```

Both malloc and memcpy a 2D array into device VRAM.

# 8.5.1 Detailed Description

Controller class for CUDA device.

This implementation only supports Nvidia devices.

Definition at line 16 of file cudaDeviceController.h.

#### 8.5.2 Member Function Documentation

# 8.5.2.1 CudaCheckNotifyErr()

Check results of the last operation on GPU.

Check the status returned from cudaMalloc/cudaMemcpy to find failures.

If a failure occurs, its assumed beyond redemption, and exited.

#### **Parameters**

_status	Cuda error status to check
msg	Message to print in case of a failure

# Returns

```
0 if successful, 1 if failure. Example output:
```

```
char *da, a = "test";
cudastatus = cudaMalloc((char **)&da, 5*sizeof(char*));
CudaCheckNotifyErr(cudastatus, "Failed to allocate VRAM for *da.\n");
```

# 8.5.2.2 CudaMalloc2DToFlat()

```
int row,
int col ) [inline], [static], [protected]
```

Malloc a 2D array in device space.

This function will allocate enough space on VRAM for flattened 2D array.

#### **Parameters**

dst	destination pointer
row	row size of the 2d array
col	column size of the 2d array


#### Returns

cudaError\_t status of the cudaMalloc operation

#### **Example output:**

References CudaMigrate2DFlat().

Here is the call graph for this function:



#### 8.5.2.3 CudaMemcpy2DToFlat()

Memcpy a 2D array in device space after flattening.

Resulting buffer will not be true 2D array.

#### **Parameters**

dst	destination pointer
rc	source pointer
row	row size of the 2d array
col	column size of the 2d array

#### Returns


cudaError\_t status of the cudaMalloc operation

#### **Example output:**

```
cudaError_t cudastatus;
char* dst;
cudastatus = CudaMalloc2DToFlat<char>(&dst, 5, 15);
CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
cudastatus = CudaMemcpy2DToFlat<char>(*dst,src,15,15);
CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
Definition at line 101 of file cudaDeviceController.h.
00102
                    T* tempbuf = new T[row*col];
00103
                     for (int i=0;i<row;i++) {</pre>
00104
                         memcpy(\&(tempbuf[row*i]), src[i], col);
00105
00106
                    return cudaMemcpy(dst, tempbuf, row*col*sizeof(T), cudaMemcpyHostToDevice);
00107
00108
```

#### References CudaMigrate2DFlat().

Here is the call graph for this function:



#### 8.5.2.4 CudaMigrate2DFlat()

Both malloc and memcpy a 2D array into device VRAM.

Resulting buffer will not be true 2D array.

### **Parameters**

	dst	destination pointer
	rc	source pointer
	row	row size of the 2d array
	col	column size of the 2d array

#### Returns

cudaError\_t status of the cudaMalloc operation

### **Example output:**

```
cudaError_t cudastatus;
char* dst;
cudastatus = CudaMigrate2DFlat<long int>(
   &dst, this->valueMatrix, this->matrixSize, this->matrixSize);
CudaCheckNotifyErr(cudastatus, " Cuda failed to initialize value matrix row.");
```


Definition at line 130 of file cudaDeviceController.h.

```
00131
                 cudaError_t cudastatus;
                  cudastatus = CudaMalloc2DToFlat<T>(dst, row, col);
00132
00133
                  if(cudastatus!=cudaSuccess){
                      CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00134
00135
                     return cudastatus;
00136
00137
                  cudastatus = CudaMemcpy2DToFlat<T>(*dst,src,row,col);
00138
                  CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
                  return cudastatus;
00139
00140
```


References CudaMigrate2DFlat().

Referenced by CudaMalloc2DToFlat(), CudaMemcpy2DToFlat(), and CudaMigrate2DFlat().

Here is the call graph for this function:



Here is the caller graph for this function:



# 8.5.2.5 ListCudaDevices()

```
static __host__ void Markov::API::CUDA::CUDADeviceController::ListCudaDevices ( ) [static]
List CUDA devices in the system.
```

This function will print details of every CUDA capable device in the system.

#### **Example output:**

```
Device Number: 0
Device name: GeForce RTX 2070
Memory Clock Rate (KHz): 7001000
Memory Bus Width (bits): 256
Peak Memory Bandwidth (GB/s): 448.064
Max Linear Threads: 1024
```

The documentation for this class was generated from the following file:


• cudaDeviceController.h

# 8.6 Markov::API::CUDA::CUDAModelMatrix Class Reference


Extension of Markov::API::ModelMatrix which is modified to run on GPU devices.

#include <cudaModelMatrix.h>

Inheritance diagram for Markov::API::CUDA::CUDAModelMatrix:



Collaboration diagram for Markov::API::CUDA::CUDAModelMatrix:



# **Public Member Functions**

- \_\_host\_\_ void MigrateMatrix ()
   Migrate the class members to the VRAM.
- \_\_host\_\_ void FlattenMatrix ()

  Flatten migrated matrix from 2d to 1d.
- \_\_host\_\_ void FastRandomWalk (unsigned long int n, const char \*wordlistFileName, int minLen, int maxLen, bool bFileIO)

Random walk on the Matrix-reduced Markov::Model.

void ConstructMatrix ()

Construct the related Matrix data for the model.

• void DumpJSON ()

Debug function to dump the model to a JSON file.

• void FastRandomWalk (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20, bool bFileIO=true)

Random walk on the Matrix-reduced Markov::Model.

std::ifstream \* OpenDatasetFile (const char \*filename)

Open dataset file and return the ifstream pointer.

• void Train (const char \*datasetFileName, char delimiter, int threads)

Train the model with the dataset file.

• std::ofstream \* Save (const char \*filename)

Export model to file.

• void Generate (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20)

Call Markov::Model::RandomWalk n times, and collect output.

 char \* RandomWalk (Markov::Random::RandomEngine \*randomEngine, int minSetting, int maxSetting, char \*buffer)

Do a random walk on this model.

void AdjustEdge (const char \*payload, long int occurrence)

Adjust the model with a single string.

bool Import (std::ifstream \*)

Import a file to construct the model.

bool Import (const char \*filename)

Open a file to import with filename, and call bool Model::Import with std::ifstream.

bool Export (std::ofstream \*)

Export a file of the model.

• bool Export (const char \*filename)

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Node< char > \* StarterNode ()

Return starter Node.

std::vector< Edge< char > \* > \* Edges ()

Return a vector of all the edges in the model.

std::map< char, Node< char > \* > \* Nodes ()

Return starter Node.

# **Static Public Member Functions**

static \_\_host\_\_ void ListCudaDevices ()
 List CUDA devices in the system.

#### **Protected Member Functions**

Allocate the output buffer for kernel operation.

• void FastRandomWalkPartition (std::mutex \*mlock, std::ofstream \*wordlist, unsigned long int n, int minLen, int maxLen, bool bFileIO, int threads)

A single partition of FastRandomWalk event.

• void FastRandomWalkThread (std::mutex \*mlock, std::ofstream \*wordlist, unsigned long int n, int minLen, int maxLen, int id, bool bFileIO)

A single thread of a single partition of FastRandomWalk.

### **Static Protected Member Functions**

```
    static __host__ int CudaCheckNotifyErr (cudaError_t _status, const char *msg, bool bExit=true)
    Check results of the last operation on GPU.
```

• template<typename T >

```
static __host__ cudaError_t CudaMalloc2DToFlat (T **dst, int row, int col)
```

Malloc a 2D array in device space.

• template<typename T >

```
static host cudaError t CudaMemcpy2DToFlat (T *dst, T **src, int row, int col)
```

Memcpy a 2D array in device space after flattening.

• template<typename T >

```
static host cudaError t CudaMigrate2DFlat (T **dst, T **src, int row, int col)
```

Both malloc and memcpy a 2D array into device VRAM.

### **Protected Attributes**

char \*\* edgeMatrix

2-D Character array for the edge Matrix (The characters of Nodes)

long int \*\* valueMatrix

2-d Integer array for the value Matrix (For the weights of Edges)

· int matrixSize

to hold Matrix size

char \* matrixIndex

to hold the Matrix index (To hold the orders of 2-D arrays')

long int \* totalEdgeWeights

Array of the Total Edge Weights.

# **Private Member Functions**

• void TrainThread (Markov::API::Concurrency::ThreadSharedListHandler \*listhandler, char delimiter)

A single thread invoked by the Train function.

void GenerateThread (std::mutex \*outputLock, unsigned long int n, std::ofstream \*wordlist, int minLen, int maxLen)

A single thread invoked by the Generate function.

#### **Private Attributes**

• char \* device edgeMatrix

VRAM Address pointer of edge matrix (from modelMatrix.h)

long int \* device\_valueMatrix

VRAM Address pointer of value matrix (from modelMatrix.h)

char \* device\_matrixIndex

VRAM Address pointer of matrixIndex (from modelMatrix.h)

• long int \* device\_totalEdgeWeights

VRAM Address pointer of total edge weights (from modelMatrix.h)

char \* device outputBuffer

RandomWalk results in device.

char \* outputBuffer

RandomWalk results in host.

char \* flatEdgeMatrix

Adding Edge matrix end-to-end and resize to 1-D array for better perfomance on traversing.

long int \* flatValueMatrix

Adding Value matrix end-to-end and resize to 1-D array for better perfomance on traversing.

- std::ifstream \* datasetFile
- std::ofstream \* modelSavefile

Dataset file input of our system

• std::ofstream \* outputFile

File to save model of our system

std::map< char, Node< char > \* > nodes

Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.

Node< char > \* starterNode

Starter Node of this model.

std::vector< Edge< char > \* > edges

A list of all edges in this model.

# 8.6.1 Detailed Description

Extension of Markov::API::ModelMatrix which is modified to run on GPU devices.

This implementation only supports Nvidia devices.

Definition at line 11 of file cudaModelMatrix.h.

### 8.6.2 Member Function Documentation

### 8.6.2.1 AdjustEdge()

Adjust the model with a single string.

Start from the starter node, and for each character, AdjustEdge the edge EdgeWeight from current node to the next, until NULL character is reached.

Then, update the edge EdgeWeight from current node, to the terminator node.

This function is used for training purposes, as it can be used for adjusting the model with each line of the corpus file.

**Example Use:** Create an empty model and train it with string: "testdata"

```
Markov::Model<char> model;
char test[] = "testdata";
model.AdjustEdge(test, 15);
```

#### **Parameters**

string	- String that is passed from the training, and will be used to AdjustEdge the model with	
occurrence	urrence - Occurrence of this string.	

# Definition at line 323 of file model.h.

```
00323
00324
          NodeStorageType p = payload[0];
          Markov::Node<NodeStorageType>* curnode = this->starterNode;
00325
          Markov::Edge<NodeStorageType>* e;
00326
00327
          int i = 0;
00328
          if (p == 0) return;
while (p != 0) {
00329
00330
              e = curnode->FindEdge(p);
00331
              if (e == NULL) return;
00332
00333
              e->AdjustEdge (occurrence);
              curnode = e->RightNode();
00334
00335
              p = payload[++i];
00336
          }
00337
00338
          e = curnode->FindEdge('\xff');
00339
          e->AdjustEdge (occurrence);
00340
          return;
```

00341 }

#### 8.6.2.2 AllocVRAMOutputBuffer()

Allocate the output buffer for kernel operation.

**TODO** 

#### **Parameters**

п	- Number of passwords to generate.
singleGenMaxLen	- maximum string length for a single generation
CUDAKernelGridSize	- Total number of grid members in CUDA kernel
sizePerGrid	- Size to allocate per grid member

#### Returns

pointer to the allocation on VRAM

### 8.6.2.3 ConstructMatrix()

```
void Markov::API::ModelMatrix::ConstructMatrix ( ) [inherited]
```

Construct the related Matrix data for the model.

This operation can be used after importing/training to allocate and populate the matrix content.

this will initialize: char\*\* edgeMatrix -> a 2D array of mapping left and right connections of each edge. long int \*\*valueMatrix -> a 2D array representing the edge weights. int matrixSize -> Size of the matrix, aka total number of nodes. char\* matrixIndex -> order of nodes in the model long int \*totalEdgeWeights -> total edge weights of each Node.


Definition at line 11 of file modelMatrix.cpp.

```
00011
00012
          this->matrixSize = this->StarterNode()->edgesV.size() + 2;
00013
00014
          this->matrixIndex = new char[this->matrixSize];
00015
          this->totalEdgeWeights = new long int[this->matrixSize];
00016
00017
          this->edgeMatrix = new char*[this->matrixSize];
00018
          for(int i=0;i<this->matrixSize;i++) {
00019
              this->edgeMatrix[i] = new char[this->matrixSize];
00020
00021
          this->valueMatrix = new long int*[this->matrixSize];
          for (int i=0; i<this->matrixSize; i++) {
00022
00023
              this->valueMatrix[i] = new long int[this->matrixSize];
00024
00025
          std::map< char, Node< char > * > *nodes;
00026
          nodes = this->Nodes();
          int i=0;
00027
00028
          for (auto const& [repr, node] : *nodes) {
00029
              if(repr!=0) this->matrixIndex[i] = repr;
              else this->matrixIndex[i] = 199;
00030
00031
              this->totalEdgeWeights[i] = node->TotalEdgeWeights();
00032
              for(int j=0; j<this->matrixSize; j++) {
00033
                  char val = node->NodeValue();
                  if(val < 0){</pre>
00034
00035
                      for(int k=0;k<this->matrixSize;k++){
00036
                          this->valueMatrix[i][k] = 0;
00037
                          this->edgeMatrix[i][k] = 255;
00038
00039
                      break:
00040
                  else if(node->NodeValue() == 0 && j>(this->matrixSize-3)){
00041
00042
                      this->valueMatrix[i][j] = 0;
00043
                      this->edgeMatrix[i][j] = 255;
```


```
}else if(j==(this->matrixSize-1)) {
                             this->valueMatrix[i][j] = 0;
this->edgeMatrix[i][j] = 255;
00045
00046
00047
                        }else{
                             this->valueMatrix[i][j] = node->edgesV[j]->EdgeWeight();
this->edgeMatrix[i][j] = node->edgesV[j]->RightNode()->NodeValue();
00048
00049
00050
00051
00052
00053
                   i++;
00054
00055
             //this->DumpJSON();
00056
00057 }
```

References Markov::API::ModelMatrix::edgeMatrix, Markov::Edge < NodeStorageType >::EdgeWeight(), Markov::API::ModelMatrix::Markov::API::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix::ModelMatrix:

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.6.2.4 CudaCheckNotifyErr()

Check results of the last operation on GPU.

Check the status returned from cudaMalloc/cudaMemcpy to find failures. If a failure occurs, its assumed beyond redemption, and exited.

#### **Parameters**

_status	Cuda error status to check
msg	Message to print in case of a failure

#### Returns

```
0 if successful, 1 if failure. Example output:
```

```
char *da, a = "test";
cudastatus = cudaMalloc((char **)&da, 5*sizeof(char*));
CudaCheckNotifyErr(cudastatus, "Failed to allocate VRAM for *da.\n");
```

# 8.6.2.5 CudaMalloc2DToFlat()

Malloc a 2D array in device space.

This function will allocate enough space on VRAM for flattened 2D array.

#### **Parameters**

dst	destination pointer
row	row size of the 2d array
col	column size of the 2d array


# Returns

cudaError\_t status of the cudaMalloc operation

# **Example output:**

 $References\ Markov:: API:: CUDA:: CUDADevice Controller:: CudaMigrate 2DFlat().$ 

Here is the call graph for this function:



# 8.6.2.6 CudaMemcpy2DToFlat()

Memcpy a 2D array in device space after flattening.

Resulting buffer will not be true 2D array.

#### **Parameters**

dst	destination pointer
rc	source pointer
row row size of the 2d array	
col	column size of the 2d array

#### Returns


cudaError\_t status of the cudaMalloc operation

# Example output:

```
cudaError_t cudastatus;
char* dst:
cudastatus = CudaMalloc2DToFlat<char>(&dst, 5, 15);
CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
cudastatus = CudaMemcpy2DToFlat<char>(*dst,src,15,15);
CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
Definition at line 101 of file cudaDeviceController.h.
00101
00102
                  T* tempbuf = new T[row*col];
00103
                  for (int i=0;i<row;i++) {</pre>
                       \verb|memcpy(&(tempbuf[row*i]), src[i], col);|\\
00104
00105
00106
                  return cudaMemcpy(dst, tempbuf, row*col*sizeof(T), cudaMemcpyHostToDevice);
```

References Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Here is the call graph for this function:



# 8.6.2.7 CudaMigrate2DFlat()

Both malloc and memcpy a 2D array into device VRAM.

Resulting buffer will not be true 2D array.

#### **Parameters**

dst	destination pointer
rc	source pointer
row row size of the 2d array	
col	column size of the 2d array

#### Returns

cudaError\_t status of the cudaMalloc operation


#### **Example output:**

```
cudaError_t cudastatus;
char* dst;
cudastatus = CudaMigrate2DFlat<long int>(
&dst, this->valueMatrix, this->matrixSize, this->matrixSize);
CudaCheckNotifyErr(cudastatus, " Cuda failed to initialize value matrix row.");
Definition at line 130 of file cudaDeviceController.h.
00130
00131
                    cudaError_t cudastatus;
00132
                    cudastatus = CudaMalloc2DToFlat<T>(dst, row, col);
00133
                    if (cudastatus!=cudaSuccess) {
00134
                        CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00135
                         return cudastatus;
00136
00137
                    cudastatus = CudaMemcpy2DToFlat<T>(*dst,src,row,col);
                    CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
00138
                    return cudastatus;
00139
00140
```


References Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Referenced by Markov::API::CUDA::CUDADeviceController::CudaMalloc2DToFlat(), Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Here is the call graph for this function:



Here is the caller graph for this function:



## 8.6.2.8 **DumpJSON()**

```
void Markov::API::ModelMatrix::DumpJSON ( ) [inherited]
```

Debug function to dump the model to a JSON file.

Might not work 100%. Not meant for production use.

Definition at line 60 of file modelMatrix.cpp.

```
00061
                                   \"index\": \"";
00062
            std::cout « "{\n
            for(int i=0;i<this>matrixSize;i++) {
   if(this->matrixIndex[i]=='"') std::cout « "\\"";
   else if(this->matrixIndex[i]=='\\') std::cout « "\\\";
   else if(this->matrixIndex[i]==0) std::cout « "\\\x00";
00063
00064
00065
00066
                 else if(i==0) std::cout « "\\\xff";
else if(this->matrixIndex[i]=='\n') std::cout « "\\n";
00067
00068
                 else std::cout « this->matrixIndex[i];
00069
00070
00071
            std::cout «
            "\",\n"
" \"edgemap\": {\n";
00072
00073
00074
            00075
00076
00077
00078
00079
00080
00081
00082
00083
00084
00085
                      else if(this->edgeMatrix[i][j]<0) std::cout « "\"\\\xff\"";</pre>
```

```
else if (this->matrixIndex[i]=='\n') std::cout « "\"\\n\""; else std::cout « "\"" « this->edgeMatrix[i][j] « "\""; if (j!=this->matrixSize-1) std::cout « ", ";
00086
00087
00088
00089
00090
              std::cout « "], \n";
00091
00092
         std::cout « "}, \n";
00093
         std::cout « "\" weightmap\": {\n";
00094
         00095
                                      00096
00097
00098
00099
00100
              else std::cout « "
00101
              for(int j=0; j<this->matrixSize; j++) {
00102
                  std::cout « this->valueMatrix[i][j];
00103
                  if(j!=this->matrixSize-1) std::cout « ", ";
00104
00105
00106
              std::cout « "], \n";
00107
          std::cout « " }\n}\n";
00108
00109 }
```

References Markov::API::ModelMatrix::edgeMatrix, Markov::API::ModelMatrix::matrixIndex, Markov::API::ModelMatrix::matrixSize, and Markov::API::ModelMatrix::valueMatrix.

### 8.6.2.9 Edges()

std::vector<Edge<char >\*>\* Markov::Model< char >::Edges ( ) [inline], [inherited]
Return a vector of all the edges in the model.

Returns

vector of edges

Definition at line 172 of file model.h.

```
00172 { return &edges;}
```

# 8.6.2.10 Export() [1/2]

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Returns

True if successful, False for incomplete models or corrupt file formats

#### **Example Use:** Export file to filename

```
Markov::Model<char> model;
model.Export("test.mdl");
```

# Definition at line 286 of file model.h.

```
00286

00287 std::ofstream exportfile;

00288 exportfile.open(filename);

00289 return this->Export(&exportfile);

00290 }
```

## 8.6.2.11 Export() [2/2]

Export a file of the model.

File contains a list of edges. Format is: Left\_repr;EdgeWeight;right\_repr. For more information on the format, check out the project wiki or github readme.

Iterate over this vertices, and their edges, and write them to file.

#### Returns

True if successful, False for incomplete models.

### **Example Use:** Export file to ofstream

```
Markov::Model<char> model;
std::ofstream file("test.mdl");
model.Export(&file);
Definition at line 274 of file model.h.
00274
          Markov::Edge<NodeStorageType>* e;
00275
          for (std::vector<int>::size_type i = 0; i != this->edges.size(); i++) {
00276
00277
               e = this->edges[i];
00278
               //std::cout « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," «
       e->RightNode()->NodeValue() « "\n";
               *f « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," « e->RightNode()->NodeValue() «
00279
       "\n";
00280
00281
00282
          return true;
00283 }
```

### 8.6.2.12 FastRandomWalk() [1/2]

Random walk on the Matrix-reduced Markov::Model.

TODO

#### **Parameters**

n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn
bFileIO	- If false, filename will be ignored and will output to stdout.

```
Markov::API::ModelMatrix mp;
mp.Import("models/finished.mdl");
mp.FastRandomWalk(50000000,"./wordlist.txt",6,12,25, true);
```

## 8.6.2.13 FastRandomWalk() [2/2]

```
void Markov::API::ModelMatrix::FastRandomWalk (
    unsigned long int n,
    const char * wordlistFileName,
    int minLen = 6,
    int maxLen = 12,
    int threads = 20,
    bool bFileIO = true ) [inherited]
```

Random walk on the Matrix-reduced Markov::Model.

This has an O(N) Memory complexity. To limit the maximum usage, requests with n>50M are partitioned using Markov::API::ModelMatrix::FastRandomWalkPartition.

If n>50M, threads are going to be synced, files are going to be flushed, and buffers will be reallocated every 50M generations. This comes at a minor performance penalty.

While it has the same functionality, this operation reduces Markov::API::MarkovPasswords::Generate runtime by %96.5

This function has deprecated Markov::API::MarkovPasswords::Generate, and will eventually replace it.

#### **Parameters**


n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn
bFileIO	- If false, filename will be ignored and will output to stdout.

```
Markov::API::ModelMatrix mp;
mp.Import("models/finished.mdl");
mp.FastRandomWalk(50000000, "./wordlist.txt", 6, 12, 25, true);
Definition at line 163 of file modelMatrix.cpp.
00164
00165
          std::ofstream wordlist;
00166
00167
          if(bFileIO)
00168
              wordlist.open(wordlistFileName);
00169
00170
          std::mutex mlock;
00171
          if(n<=50000000ull) return this->FastRandomWalkPartition(&mlock, &wordlist, n, minLen, maxLen,
      bFileIO, threads);
00172
         else{
00173
             int numberOfPartitions = n/50000000ull;
00174
              for (int i=0;i<numberOfPartitions;i++)</pre>
00175
                  this->FastRandomWalkPartition(&mlock, &wordlist, 50000000ull, minLen, maxLen, bFileIO,
       threads);
00176
00177
00178
00179 }
```


References Markov::API::ModelMatrix::FastRandomWalkPartition().

Referenced by main().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.6.2.14 FastRandomWalkPartition()

```
void Markov::API::ModelMatrix::FastRandomWalkPartition (
    std::mutex * mlock,
    std::ofstream * wordlist,
    unsigned long int n,
    int minLen,
```

```
int maxLen,
bool bFileIO,
int threads ) [protected], [inherited]
```

A single partition of FastRandomWalk event.

Since FastRandomWalk has to allocate its output buffer before operation starts and writes data in chunks, large n parameters would lead to huge memory allocations. **Without Partitioning:** 

- 50M results 12 characters max -> 550 Mb Memory allocation
- 5B results 12 characters max -> 55 Gb Memory allocation
- 50B results 12 characters max -> 550GB Memory allocation

Instead, FastRandomWalk is partitioned per 50M generations to limit the top memory need.

#### **Parameters**

mlock	- mutex lock to distribute to child threads
wordlist	- Reference to the wordlist file to write to
п	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn
bFileIO	- If false, filename will be ignored and will output to stdout.

Definition at line 182 of file modelMatrix.cpp.

```
00182
00183
          int iterationsPerThread = n/threads;
00184
00185
          int iterationsPerThreadCarryOver = n%threads;
00186
          std::vector<std::thread*> threadsV;
00188
00189
           int id = 0;
          for(int i=0;i<threads;i++){</pre>
00190
               threadsV.push_back(new std::thread(&Markov::API::ModelMatrix::FastRandomWalkThread, this,
00191
       mlock, wordlist, iterationsPerThread, minLen, maxLen, id, bFileIO));
00192
               id++;
00193
00194
          threadsV.push_back(new std::thread(&Markov::API::ModelMatrix::FastRandomWalkThread, this, mlock,
00195
       \verb|wordlist|, iterationsPerThreadCarryOver|, \verb|minLen|, \verb|maxLen|, id|, \verb|bFileIO||); \\
00196
00197
           for(int i=0;i<threads;i++){</pre>
00198
               threadsV[i]->join();
00199
00200 }
```

 $References\ Markov::API::Model Matrix::FastRandom Walk Thread().$ 

Referenced by Markov::API::ModelMatrix::FastRandomWalk().

Here is the call graph for this function:

```
Markov::API::ModelMatrix ::FastRandomWalkPartition ::FastRandomWalkThread ::random
```

Here is the caller graph for this function:



# 8.6.2.15 FastRandomWalkThread()

```
void Markov::API::ModelMatrix::FastRandomWalkThread (
    std::mutex * mlock,
    std::ofstream * wordlist,
    unsigned long int n,
    int minLen,
    int maxLen,
    int id,
    bool bFileIO ) [protected], [inherited]
```

A single thread of a single partition of FastRandomWalk.

A FastRandomWalkPartition will initiate as many of this function as requested.

This function contains the bulk of the generation algorithm.

#### **Parameters**

mlock	- mutex lock to distribute to child threads
wordlist	- Reference to the wordlist file to write to
n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
id	- DEPRECATED Thread id - No longer used
bFileIO	- If false, filename will be ignored and will output to stdout.


# Definition at line 112 of file modelMatrix.cpp.

```
00112
00113
          if(n==0) return;
00114
00115
          Markov::Random::Marsaglia MarsagliaRandomEngine;
00116
          char* e;
00117
          char *res = new char[maxLen*n];
          int index = 0;
00118
00119
          char next;
00120
          int len=0;
00121
          long int selection;
00122
          char cur;
00123
          long int bufferctr = 0;
          for (int i = 0; i < n; i++) {
00124
00125
              cur=199;
00126
              len=0;
00127
               while (true) {
00128
                 e = strchr(this->matrixIndex, cur);
                  index = e - this->matrixIndex;
selection = MarsagliaRandomEngine.random() % this->totalEdgeWeights[index];
00129
00130
00131
                   for(int j=0;j<this->matrixSize;j++) {
                       selection -= this->valueMatrix[index][j];
00132
00133
                       if (selection < 0) {</pre>
00134
                           next = this->edgeMatrix[index][j];
                           break;
00135
00136
00137
                   }
00138
00139
                   if (len >= maxLen) break;
```

```
else if ((next < 0) && (len < minLen)) continue;</pre>
00141
                   else if (next < 0) break;</pre>
                   cur = next;
00142
00143
                   res[bufferctr + len++] = cur;
00144
00145
              res[bufferctr + len++] = '\n';
00146
              bufferctr+=len;
00147
00148
          if (bFileIO) {
00149
00150
              mlock->lock();
00151
              *wordlist « res;
00152
              mlock->unlock();
00153
          }else{
00154
              mlock->lock();
00155
              std::cout « res;
00156
              mlock->unlock();
00157
00158
          delete res;
00159
00160 }
```

References Markov::API::ModelMatrix::edgeMatrix, Markov::API::ModelMatrix::matrixIndex, Markov::API::ModelMatrix::matrixSize, Markov::Random::Marsaglia::random(), Markov::API::ModelMatrix::totalEdgeWeights, and Markov::API::ModelMatrix::valueMatrix. Referenced by Markov::API::ModelMatrix::FastRandomWalkPartition().

Here is the call graph for this function:



Here is the caller graph for this function:



# 8.6.2.16 FlattenMatrix()

```
__host__ void Markov::API::CUDA::CUDAModelMatrix::FlattenMatrix ( ) Flatten migrated matrix from 2d to 1d.
```

## 8.6.2.17 Generate()

```
void Markov::API::MarkovPasswords::Generate (
    unsigned long int n,
    const char * wordlistFileName,
    int minLen = 6,
    int maxLen = 12,
    int threads = 20 ) [inherited]
```

Call Markov::Model::RandomWalk n times, and collect output.

Generate from model and write results to a file. a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

**Deprecated** See Markov::API::MatrixModel::FastRandomWalk for more information.

#### **Parameters**

n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn

Definition at line 110 of file markovPasswords.cpp.

```
00111
          char* res;
00112
          char print[100];
          std::ofstream wordlist;
00114
          wordlist.open(wordlistFileName);
00115
          std::mutex mlock;
          int iterationsPerThread = n/threads;
int iterationsCarryOver = n%threads;
00116
00117
00118
          std::vector<std::thread*> threadsV;
00119
          for(int i=0;i<threads;i++){</pre>
00120
               threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::GenerateThread, this,
       &mlock, iterationsPerThread, &wordlist, minLen, maxLen));
00121
00122
00123
          for(int i=0;i<threads;i++){</pre>
               threadsV[i]->join();
00125
               delete threadsV[i];
00126
00127
00128
          this->GenerateThread(&mlock, iterationsCarryOver, &wordlist, minLen, maxLen);
00129
00130 }
```

References Markov::API::MarkovPasswords::GenerateThread(). Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



## 8.6.2.18 GenerateThread()

```
void Markov::API::MarkovPasswords::GenerateThread (
    std::mutex * outputLock,
    unsigned long int n,
    std::ofstream * wordlist,
    int minLen,
    int maxLen ) [private], [inherited]
```

A single thread invoked by the Generate function.

**DEPRECATED:** See Markov::API::MatrixModel::FastRandomWalkThread for more information. This has been replaced with a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

#### **Parameters**

outputLock	- shared mutex lock to lock during output operation. Prevents race condition on write.
n	number of lines to be generated by this thread
wordlist	wordlistfile
minLen - Minimum password length to generate	
maxLen	- Maximum password length to generate


Definition at line 132 of file markovPasswords.cpp.

```
00133
          char* res = new char[maxLen+5];
00134
          if(n==0) return;
00135
00136
          Markov::Random::Marsaglia MarsagliaRandomEngine;
00137
           for (int i = 0; i < n; i++) {</pre>
00138
               this->RandomWalk(&MarsagliaRandomEngine, minLen, maxLen, res);
               outputLock->lock();
*wordlist « res « "\n";
00139
00140
00141
               outputLock->unlock();
00142
00143 }
```

References Markov::Model < NodeStorageType >::RandomWalk().

Referenced by Markov::API::MarkovPasswords::Generate().

Here is the call graph for this function:



Here is the caller graph for this function:



### 8.6.2.19 Import() [1/2]

Open a file to import with filename, and call bool Model::Import with std::ifstream.

# Returns

True if successful, False for incomplete models or corrupt file formats

```
Example Use: Import a file with filename
```

```
Markov::Model<char> model;
model.Import("test.mdl");
```

Definition at line 266 of file model.h.

00266

```
00267     std::ifstream importfile;
00268     importfile.open(filename);
00269     return this->Import(&importfile);
00270
00271 }
```

### 8.6.2.20 Import() [2/2]

Import a file to construct the model.

File contains a list of edges. For more info on the file format, check out the wiki and github readme pages. Format is: Left repr;EdgeWeight;right repr

Iterate over this list, and construct nodes and edges accordingly.

#### Returns

True if successful, False for incomplete models or corrupt file formats

#### **Example Use:** Import a file from ifstream

```
Markov::Model<char> model;
std::ifstream file("test.mdl");
model.Import(&file);
Definition at line 207 of file model.h.
00207
00208
                     std::string cell;
00209
00210
                    char src;
00211
                    char target;
00212
                    long int oc;
00213
00214
                    while (std::getline(*f, cell)) {
                            //std::cout « "cell: " « cell « std::endl;
00215
                             src = cell[0];
00216
00217
                             target = cell[cell.length() - 1];
00218
                             char* j;
00219
                             oc = std::strtol(cell.substr(2, cell.length() - 2).c_str(),&j,10);
00220
                              //std::cout « oc « "\n";
00221
                             Markov::Node<NodeStorageType>* srcN;
                             Markov::Node<NodeStorageType>* targetN;
00222
00223
                             Markov::Edge<NodeStorageType>* e;
                             if (this->nodes.find(src) == this->nodes.end()) {
00224
                                     srcN = new Markov::Node<NodeStorageType>(src);
00225
00226
                                     this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(src, srcN));
00227
                                      //std::cout « "Creating new node at start.\n";
00228
00229
                            else {
00230
                                     srcN = this->nodes.find(src)->second;
00231
                             }
00232
00233
                             if (this->nodes.find(target) == this->nodes.end()) {
                                     targetN = new Markov::Node<NodeStorageType>(target);
this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(target, targetN));
00234
00235
00236
                                     //std::cout « "Creating new node at end.\n";
00237
00238
                             else {
00239
                                     targetN = this->nodes.find(target)->second;
00240
00241
                             e = srcN->Link(targetN);
00242
                             e->AdjustEdge(oc);
00243
                             this->edges.push_back(e);
00244
00245
                             //std::cout « int(srcN->NodeValue()) « " --" « e->EdgeWeight() « "--> " «
              int(targetN->NodeValue()) « "\n";
00246
00247
00248
00249
                     for (std::pair<unsigned char, Markov::Node<NodeStorageType>*> const& x : this->nodes) {
    //std::cout « "Total edges in EdgesV: " « x.second->edgesV.size() « "\n";
00250
00251
                             \verb|std::sort| (x.second->edgesV.begin(), x.second->edgesV.end(), [] (Edge<NodeStorageType> *lhs, for the context of the conte
00252
              Edge<NodeStorageType> *rhs)->bool{
00253
                                     return lhs->EdgeWeight() > rhs->EdgeWeight();
00254
00255
                             //for(int i=0;i<x.second->edgesV.size();i++)
                             // std::cout « x.second->edgesV[i]->EdgeWeight() « ", ";
//std::cout « "\n";
00256
00257
00258
00259
                     //std::cout « "Total number of nodes: " « this->nodes.size() « std::endl;
                     //std::cout « "Total number of edges: " « this->edges.size() « std::endl;
```

```
00261
00262 return true;
00263 }
```

#### 8.6.2.21 ListCudaDevices()

```
static __host__ void Markov::API::CUDA::CUDADeviceController::ListCudaDevices ( ) [static],
[inherited]
```

List CUDA devices in the system.

This function will print details of every CUDA capable device in the system.

#### **Example output:**

```
Device Number: 0
Device name: GeForce RTX 2070
Memory Clock Rate (KHz): 7001000
Memory Bus Width (bits): 256
Peak Memory Bandwidth (GB/s): 448.064
Max Linear Threads: 1024
```

### 8.6.2.22 MigrateMatrix()

```
__host__ void Markov::API::CUDA::CUDAModelMatrix::MigrateMatrix ( )
```

Migrate the class members to the VRAM.

Cannot be used without calling Markov::API::ModelMatrix::ConstructMatrix at least once. This function will manage the memory allocation and data transfer from CPU RAM to GPU VRAM.

Newly allocated VRAM pointers are set in the class member variables.

#### 8.6.2.23 Nodes()

```
std::map<char , Node<char >*>* Markov::Model< char >::Nodes ( ) [inline], [inherited]
Return starter Node.
```

Returns

starter node with 00 NodeValue

```
Definition at line 177 of file model.h.
00177 { return &nodes; }
```

#### 8.6.2.24 OpenDatasetFile()

Open dataset file and return the ifstream pointer.

#### **Parameters**

```
filename - Filename to open
```

# Returns

ifstream\* to the the dataset file

Definition at line 43 of file markovPasswords.cpp.

```
00043
00044
00045
          std::ifstream* datasetFile;
00046
00047
          std::ifstream newFile(filename);
00048
00049
          datasetFile = &newFile;
00050
00051
          this->Import (datasetFile);
00052
          return datasetFile;
00053 }
```

References Markov::Model < NodeStorageType >::Import(). Here is the call graph for this function:



## 8.6.2.25 RandomWalk()

Do a random walk on this model.

Start from the starter node, on each node, invoke RandomNext using the random engine on current node, until terminator node is reached. If terminator node is reached before minimum length criateria is reached, ignore the last selection and re-invoke randomNext

If maximum length criteria is reached but final node is not, cut off the generation and proceed to the final node. This function takes Markov::Random::RandomEngine as a parameter to generate pseudo random numbers from

This library is shipped with two random engines, Marsaglia and Mersenne. While mersenne output is higher in entropy, most use cases don't really need super high entropy output, so Markov::Random::Marsaglia is preferable for better performance.

This function WILL NOT reallocate buffer. Make sure no out of bound writes are happening via maximum length criteria.

Example Use: Generate 10 lines, with 5 to 10 characters, and print the output. Use Marsaglia

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::Marsaglia MarsagliaRandomEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
    std::cout « res « "\n";
```

#### **Parameters**

randomEngine	Random Engine to use for the random walks. For examples, see Markov::Random::Mersenne and Markov::Random::Marsaglia
minSetting	Minimum number of characters to generate
maxSetting	Maximum number of character to generate
buffer	buffer to write the result to

## Returns

Null terminated string that was generated.

Definition at line 293 of file model.h.

```
00302
                else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00303
                    continue;
00304
00305
00306
               else if (temp_node == NULL) {
00307
                   break;
00308
00309
00310
               n = temp_node;
00311
00312
               buffer[len++] = n->NodeValue();
00313
           }
00314
00315
           //\mathrm{null} terminate the string
00316
           buffer[len] = 0x00;
00317
00318
           //do something with the generated string
return buffer; //for now
00319
00320 }
```

### 8.6.2.26 Save()

### **Parameters**

```
filename - Export filename.
```

### Returns


std::ofstream\* of the exported file.

Definition at line 98 of file markovPasswords.cpp.

```
00098
00099    std::ofstream* exportFile;
00100
00101    std::ofstream newFile(filename);
00102
00103    exportFile = &newFile;
00104
00105    this->Export(exportFile);
00106    return exportFile;
00107 }
```

References Markov::Model < NodeStorageType >::Export().

Here is the call graph for this function:



# 8.6.2.27 StarterNode()

Node<char >\* Markov::Model< char >::StarterNode ( ) [inline], [inherited]
Return starter Node.

#### Returns

starter node with 00 NodeValue

```
Definition at line 167 of file model.h. 00167 { return starterNode; }
```

### 8.6.2.28 Train()

Train the model with the dataset file.

#### **Parameters**


datasetFileName	- Ifstream* to the dataset. If null, use class member
delimiter	- a character, same as the delimiter in dataset content
threads	- number of OS threads to spawn

```
Markov::API::MarkovPasswords mp;
mp.Import("models/2gram.mdl");
mp.Train("password.corpus");
Definition at line 57 of file markovPasswords.cpp.
00057
00058
                                signal(SIGINT, intHandler);
                                        Markov::API::Concurrency::ThreadSharedListHandler listhandler(datasetFileName);
00059
00060
                                        auto start = std::chrono::high_resolution_clock::now();
00061
00062
                                        std::vector<std::thread*> threadsV;
00063
                                        for(int i=0;i<threads;i++) {</pre>
00064
                                                       threads V.push\_back (new std::thread(\&Markov::API::MarkovPasswords::TrainThread, this, and the statement of the statement o
                           &listhandler, delimiter));
00065
                                      }
00066
00067
                                        for(int i=0;i<threads;i++){</pre>
00068
                                                       threadsV[i]->join();
00069
                                                       delete threadsV[i];
00070
                                      auto finish = std::chrono::high_resolution_clock::now(); std::chrono::duration<double> elapsed = finish - start; std::cout « "Elapsed time: " « elapsed.count() « " s\n";
00071
00072
00073
00074
00075 }
```

References intHandler(), Markov::API::Concurrency::ThreadSharedListHandler::ThreadSharedListHandler(), and Markov::API::MarkovPasswords::TrainThread().

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



# 8.6.2.29 TrainThread()

A single thread invoked by the Train function.

#### **Parameters**


listhandler	- Listhandler class to read corpus from
delimiter	- a character, same as the delimiter in dataset content

Definition at line 77 of file markovPasswords.cpp.

```
00078
          char format_str[] ="%ld,%s";
00079
          format_str[2] = delimiter;
00080
          std::string line;
00081
          while (listhandler->next(&line) && keepRunning) {
00082
              long int oc;
00083
              if (line.size() > 100)
00084
                  line = line.substr(0, 100);
00085
00086
              char* linebuf = new char[line.length()+5];
00087 #ifdef _WIN32
00088
              sscanf_s(line.c_str(), "%ld,%s", &oc, linebuf, line.length()+5); //<== changed format_str to->
       "%ld,%s"
00089 #else
00090
              sscanf(line.c_str(), format_str, &oc, linebuf);
00091 #endif
              this->AdjustEdge((const char*)linebuf, oc);
delete linebuf;
00092
00093
00094
00095 }
```

References Markov::Model < NodeStorageType >::AdjustEdge(), keepRunning, and Markov::API::Concurrency::ThreadSharedListHaReferenced by Markov::API::MarkovPasswords::Train().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.6.3 Member Data Documentation

#### 8.6.3.1 datasetFile

std::ifstream\* Markov::API::MarkovPasswords::datasetFile [private], [inherited] Definition at line 106 of file markovPasswords.h.

### 8.6.3.2 device\_edgeMatrix

char\* Markov::API::CUDA::CUDAModelMatrix::device\_edgeMatrix [private]
VRAM Address pointer of edge matrix (from modelMatrix.h)
Definition at line 73 of file cudaModelMatrix.h.

### 8.6.3.3 device\_matrixIndex

char\* Markov::API::CUDA::CUDAModelMatrix::device\_matrixIndex [private]
VRAM Address pointer of matrixIndex (from modelMatrix.h)
Definition at line 83 of file cudaModelMatrix.h.

# 8.6.3.4 device\_outputBuffer

char\* Markov::API::CUDA::CUDAModelMatrix::device\_outputBuffer [private]
RandomWalk results in device.
Definition at line 94 of file cudaModelMatrix.h.

# 8.6.3.5 device\_totalEdgeWeights

long int\* Markov::API::CUDA::CUDAModelMatrix::device\_totalEdgeWeights [private]
VRAM Address pointer of total edge weights (from modelMatrix.h)
Definition at line 88 of file cudaModelMatrix.h.

### 8.6.3.6 device\_valueMatrix

long int\* Markov::API::CUDA::CUDAModelMatrix::device\_valueMatrix [private]
VRAM Address pointer of value matrix (from modelMatrix.h)
Definition at line 78 of file cudaModelMatrix.h.

# 8.6.3.7 edgeMatrix

char\*\* Markov::API::ModelMatrix::edgeMatrix [protected], [inherited]
2-D Character array for the edge Matrix (The characters of Nodes)
Definition at line 116 of file modelMatrix.h.

Referenced by Markov::API::ModelMatrix::ConstructMatrix(), Markov::API::ModelMatrix::DumpJSON(), and Markov::API::ModelMatrix::FastRandomWalkThread().

### 8.6.3.8 edges

std::vector<Edge<char >\*> Markov::Model< char >::edges [private], [inherited]
A list of all edges in this model.
Definition at line 195 of file model.h.

#### 8.6.3.9 flatEdgeMatrix

char\* Markov::API::CUDA::CUDAModelMatrix::flatEdgeMatrix [private]

Adding Edge matrix end-to-end and resize to 1-D array for better perfomance on traversing.

Definition at line 104 of file cudaModelMatrix.h.

#### 8.6.3.10 flatValueMatrix

long int\* Markov::API::CUDA::CUDAModelMatrix::flatValueMatrix [private] Adding Value matrix end-to-end and resize to 1-D array for better perfomance on traversing. Definition at line 109 of file cudaModelMatrix.h.

#### 8.6.3.11 matrixIndex

char\* Markov::API::ModelMatrix::matrixIndex [protected], [inherited] to hold the Matrix index (To hold the orders of 2-D arrays')

Definition at line 131 of file modelMatrix.h.

Referenced by Markov::API::ModelMatrix::ConstructMatrix(), Markov::API::ModelMatrix::DumpJSON(), and Markov::API::ModelMatrix::FastRandomWalkThread().

### 8.6.3.12 matrixSize

int Markov::API::ModelMatrix::matrixSize [protected], [inherited]
to hold Matrix size

Definition at line 126 of file modelMatrix.h.

 $\label{lem:lem:modelMatrix::DumpJSON()} Referenced by $\mathsf{Markov}::\mathsf{API}::\mathsf{ModelMatrix}::\mathsf{DumpJSON}(), $$ and $\mathsf{Markov}::\mathsf{API}::\mathsf{ModelMatrix}::\mathsf{FastRandomWalkThread}().$ 

# 8.6.3.13 modelSavefile

std::ofstream\* Markov::API::MarkovPasswords::modelSavefile [private], [inherited]
Dataset file input of our system

Definition at line 107 of file markovPasswords.h.

# 8.6.3.14 nodes

std::map<char , Node<char >\*> Markov::Model< char >::nodes [private], [inherited] Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.

Definition at line 184 of file model.h.

## 8.6.3.15 outputBuffer

 $\label{local_chark_arkov::API::CUDA::CUDAModelMatrix::outputBuffer [private] } \textbf{RandomWalk results in host}.$ 

Definition at line 99 of file cudaModelMatrix.h.

### 8.6.3.16 outputFile

std::ofstream\* Markov::API::MarkovPasswords::outputFile [private], [inherited]
File to save model of our system

Definition at line 108 of file markovPasswords.h.

#### 8.6.3.17 starterNode

Node<char >\* Markov::Model< char >::starterNode [private], [inherited]
Starter Node of this model.

Definition at line 189 of file model.h.

## 8.6.3.18 totalEdgeWeights

long int\* Markov::API::ModelMatrix::totalEdgeWeights [protected], [inherited]

Array of the Total Edge Weights.

Definition at line 136 of file modelMatrix.h.

Referenced by Markov::API::ModelMatrix::ConstructMatrix(), and Markov::API::ModelMatrix::FastRandomWalkThread().

### 8.6.3.19 valueMatrix

long int\*\* Markov::API::ModelMatrix::valueMatrix [protected], [inherited]

2-d Integer array for the value Matrix (For the weights of Edges)

Definition at line 121 of file modelMatrix.h.

Referenced by Markov::API::ModelMatrix::ConstructMatrix(), Markov::API::ModelMatrix::DumpJSON(), and Markov::API::ModelMatrix::FastRandomWalkThread().

The documentation for this class was generated from the following file:


· cudaModelMatrix.h

# 8.7 Markov::Random::DefaultRandomEngine Class Reference


Implementation using Random.h default random engine.

#include <random.h>

Inheritance diagram for Markov::Random::DefaultRandomEngine:



Collaboration diagram for Markov::Random::DefaultRandomEngine:



## **Public Member Functions**

unsigned long random ()
 Generate Random Number.

# **Protected Member Functions**

• std::random\_device & rd ()

Default random device for seeding.

• std::default\_random\_engine & generator ()

Default random engine for seeding.

std::uniform\_int\_distribution < long long unsigned > & distribution ()

Distribution schema for seeding.

# 8.7.1 Detailed Description

Implementation using Random.h default random engine.

This engine is also used by other engines for seeding.

**Example Use:** Using Default Engine with RandomWalk

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::DefaultRandomEngine randomEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(@randomEngine, 5, 10, res);
    std::cout « res « "\n";
```

Example Use: Generating a random number with Marsaglia Engine

```
std::cout « de.random();
```

Definition at line 52 of file random.h.

# 8.7.2 Member Function Documentation

### 8.7.2.1 distribution()


std::uniform\_int\_distribution<long long unsigned>& Markov::Random::DefaultRandomEngine::distribution
( ) [inline], [protected]

Distribution schema for seeding.

```
Definition at line 81 of file random.h.
```

Referenced by Markov::Random::Marsaglia::Marsaglia(), and random().

Here is the caller graph for this function:



# 8.7.2.2 generator()

std::default\_random\_engine& Markov::Random::DefaultRandomEngine::generator ( ) [inline],
[protected]


Default random engine for seeding.

```
Definition at line 73 of file random.h.
```


References rd().

Referenced by Markov::Random::Marsaglia::Marsaglia(), and random().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.7.2.3 random()

```
unsigned long Markov::Random::DefaultRandomEngine::random ( ) [inline], [virtual]
Generate Random Number.
```

Returns

random number in long range.


```
Implements Markov::Random::RandomEngine.
```

Reimplemented in Markov::Random::Marsaglia.

```
Definition at line 57 of file random.h.
```

References distribution(), and generator().

Here is the call graph for this function:



# 8.7.2.4 rd()

```
std::random_device& Markov::Random::DefaultRandomEngine::rd () [inline], [protected]
```


Default random device for seeding.

Definition at line 65 of file random.h.

```
00065 {
00066 static std::random_device _rd;
00067 return _rd;
00068 }
```

Referenced by generator().

Here is the caller graph for this function:



The documentation for this class was generated from the following file:


· random.h

# 8.8 Markov::Edge < NodeStorageType > Class Template Reference


Edge class used to link nodes in the model together.

#include <model.h>

Inheritance diagram for Markov::Edge < NodeStorageType >:



Collaboration diagram for Markov::Edge < NodeStorageType >:



# **Public Member Functions**

• Edge ()

Default constructor.

• Edge (Node< NodeStorageType > \*\_left, Node< NodeStorageType > \*\_right)

Constructor. Initialize edge with given RightNode and LeftNode.

void AdjustEdge (long int offset)

Adjust the edge EdgeWeight with offset. Adds the offset parameter to the edge EdgeWeight.

Node< NodeStorageType > \* TraverseNode ()

Traverse this edge to RightNode.

void SetLeftEdge (Node< NodeStorageType > \*)

Set LeftNode of this edge.

void SetRightEdge (Node< NodeStorageType > \*)

Set RightNode of this edge.

• uint64\_t EdgeWeight ()

return edge's EdgeWeight.

Node < NodeStorageType > \* LeftNode ()

return edge's LeftNode

Node < NodeStorageType > \* RightNode ()

return edge's RightNode

### **Private Attributes**

```
    Node< NodeStorageType > * _left
        source node
    Node< NodeStorageType > * _right
        target node
    long int _weight
        Edge Edge Weight.
```

# 8.8.1 Detailed Description

```
\label{lem:lemplate} \textbf{template} \negthinspace < \negthinspace \textbf{typename NodeStorageType} \negthinspace > \negthinspace \textbf{class Markov::Edge} \negthinspace < \negthinspace \textbf{NodeStorageType} \negthinspace > \negthinspace \\ \\ \mbox{}
```

Edge class used to link nodes in the model together.

Has LeftNode, RightNode, and EdgeWeight of the edge. Edges are *UNIDIRECTIONAL* in this model. They can only be traversed LeftNode to RightNode.

Definition at line 26 of file model.h.

# 8.8.2 Constructor & Destructor Documentation

# 8.8.2.1 Edge() [1/2]

# 8.8.2.2 Edge() [2/2]

Constructor. Initialize edge with given RightNode and LeftNode.

# Parameters

_left	- Left node of this edge.
_right	- Right node of this edge.

#### **Example Use:** Construct edge

### 8.8.3 Member Function Documentation

# 8.8.3.1 AdjustEdge()

Adjust the edge EdgeWeight with offset. Adds the offset parameter to the edge EdgeWeight.

### **Parameters**

```
offset - NodeValue to be added to the EdgeWeight
```

### Example Use: Construct edge

# 8.8.3.2 EdgeWeight()

```
template<typename NodeStorageType >
uint64_t Markov::Edge< NodeStorageType >::EdgeWeight [inline]
return edge's EdgeWeight.
```

#### Returns

edge's EdgeWeight.

```
Definition at line 153 of file edge.h.


00153

00154 return this->_weight;

00155 }
```

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



#### 8.8.3.3 LeftNode()

```
template<typename NodeStorageType >
Markov::Node< NodeStorageType > * Markov::Edge< NodeStorageType >::LeftNode
return edge's LeftNode
```

#### Returns

edge's LeftNode.

```
Definition at line 158 of file edge.h.

00158

00159     return this->_left;

00160 }
```

# 8.8.3.4 RightNode()

```
template<typename NodeStorageType >
Markov::Node< NodeStorageType > * Markov::Edge< NodeStorageType >::RightNode [inline]
return edge's RightNode
```

#### Returns

edge's RightNode.

```
Definition at line 163 of file edge.h.

00163

00164 return this->_right;

00165 }
```

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



#### 8.8.3.5 SetLeftEdge()

Set LeftNode of this edge.

# **Parameters**

```
node - Node to be linked with.
```

Definition at line 143 of file edge.h.

```
00143
00144 this->_left = n;
00145 }
```

#### 8.8.3.6 SetRightEdge()

Set RightNode of this edge.

# **Parameters**

node - Node to be linked with.	
--------------------------------	--

```
Definition at line 148 of file edge.h.

00148

00149    this->_right = n;

00150 }
```

#### 8.8.3.7 TraverseNode()

```
template<typename NodeStorageType >
Markov::Node< NodeStorageType > * Markov::Edge< NodeStorageType >::TraverseNode [inline]
Traverse this edge to RightNode.
```

Returns

Right node. If this is a terminator node, return NULL

#### **Example Use:** Traverse a node

# 8.8.4 Member Data Documentation

# 8.8.4.1 \_left

```
template<typename NodeStorageType >
Node<NodeStorageType>* Markov::Edge< NodeStorageType >::_left [private]
source node
Definition at line 98 of file edge.h.
```

# 8.8.4.2 right

```
template<typename NodeStorageType >
Node<NodeStorageType>* Markov::Edge< NodeStorageType >::_right [private]
target node
Definition at line 103 of file edge.h.
```

# 8.8.4.3 \_weight

```
template<typename NodeStorageType >
long int Markov::Edge< NodeStorageType >::_weight [private]
Edge Edge Weight.
```

Referenced by Markov::Edge< char >::TraverseNode().

Definition at line 108 of file edge.h.

The documentation for this class was generated from the following files:

- · model.h
- · edge.h

# 8.9 Markov::API::MarkovPasswords Class Reference


Markov::Model with char represented nodes.

#include <markovPasswords.h>

Inheritance diagram for Markov::API::MarkovPasswords:



Collaboration diagram for Markov::API::MarkovPasswords:



# **Public Member Functions**

- MarkovPasswords ()
  - Initialize the markov model from MarkovModel::Markov::Model.
- MarkovPasswords (const char \*filename)
  - Initialize the markov model from MarkovModel::Markov::Model, with an import file.
- std::ifstream \* OpenDatasetFile (const char \*filename)
  - Open dataset file and return the ifstream pointer.

• void Train (const char \*datasetFileName, char delimiter, int threads)

Train the model with the dataset file.

std::ofstream \* Save (const char \*filename)

Export model to file.

• void Generate (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20)

Call Markov::Model::RandomWalk n times, and collect output.

 char \* RandomWalk (Markov::Random::RandomEngine \*randomEngine, int minSetting, int maxSetting, char \*buffer)

Do a random walk on this model.

void AdjustEdge (const char \*payload, long int occurrence)

Adjust the model with a single string.

bool Import (std::ifstream \*)

Import a file to construct the model.

bool Import (const char \*filename)

Open a file to import with filename, and call bool Model::Import with std::ifstream.

bool Export (std::ofstream \*)

Export a file of the model.

bool Export (const char \*filename)

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Node< char > \* StarterNode ()

Return starter Node.

std::vector< Edge< char > \* > \* Edges ()

Return a vector of all the edges in the model.

• std::map< char, Node< char > \* > \* Nodes ()

Return starter Node.

#### **Private Member Functions**

void TrainThread (Markov::API::Concurrency::ThreadSharedListHandler \*listhandler, char delimiter)

A single thread invoked by the Train function.

void GenerateThread (std::mutex \*outputLock, unsigned long int n, std::ofstream \*wordlist, int minLen, int maxLen)

A single thread invoked by the Generate function.

# **Private Attributes**

- std::ifstream \* datasetFile
- std::ofstream \* modelSavefile

Dataset file input of our system

• std::ofstream \* outputFile

File to save model of our system

std::map< char, Node< char > \* > nodes

Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.

Node< char > \* starterNode

Starter Node of this model.

• std::vector< Edge< char > \* > edges

A list of all edges in this model.

# 8.9.1 Detailed Description

Markov::Model with char represented nodes.

Includes wrappers for Markov::Model and additional helper functions to handle file I/O

This class is an extension of Markov::Model<char>, with higher level abstractions such as train and generate. Definition at line 17 of file markovPasswords.h.

#### 8.9.2 Constructor & Destructor Documentation

#### 8.9.2.1 MarkovPasswords() [1/2]

```
Markov::API::MarkovPasswords::MarkovPasswords ( )
Initialize the markov model from MarkovModel::Markov::Model.

Parent constructor. Has no extra functionality.

Definition at line 26 of file markovPasswords.cpp.

00026
00027
00028
00029 }
```

## 8.9.2.2 MarkovPasswords() [2/2]

Initialize the markov model from MarkovModel::Markov::Model, with an import file.

This function calls the Markov::Model::Import on the filename to construct the model. Same thing as creating and empty model, and calling MarkovPasswords::Import on the filename.

# Parameters

```
filename - Filename to import
```

#### Example Use: Construction via filename

```
MarkovPasswords mp("test.mdl");
```

```
Definition at line 31 of file markovPasswords.cpp.

00031
00032
00033    std::ifstream* importFile;
00034
00035    this->Import(filename);
00036
00037    //std::ifstream* newFile(filename);
00038
00039    //importFile = newFile;
00040
00041 }
```

References Markov::Model < NodeStorageType >::Import().

Here is the call graph for this function:



# 8.9.3 Member Function Documentation

# 8.9.3.1 AdjustEdge()

Adjust the model with a single string.

Start from the starter node, and for each character, AdjustEdge the edge EdgeWeight from current node to the next, until NULL character is reached.

Then, update the edge EdgeWeight from current node, to the terminator node.

This function is used for training purposes, as it can be used for adjusting the model with each line of the corpus file

**Example Use:** Create an empty model and train it with string: "testdata"

```
Markov::Model<char> model;
char test[] = "testdata";
model.AdjustEdge(test, 15);
```

#### **Parameters**

string	- String that is passed from the training, and will be used to AdjustEdge the model with
occurrence	- Occurrence of this string.

#### Definition at line 323 of file model.h.

```
00324
          NodeStorageType p = payload[0];
00325
          Markov::Node<NodeStorageType>* curnode = this->starterNode;
00326
          Markov::Edge<NodeStorageType>* e;
00327
         int i = 0;
00328
00329
          if (p == 0) return;
         while (p != 0) {
00330
             e = curnode->FindEdge(p);
00331
              if (e == NULL) return:
00332
              e->AdjustEdge(occurrence);
00333
             curnode = e->RightNode();
00335
             p = payload[++i];
00336
00337
         e = curnode->FindEdge('\xff'):
00338
00339
         e->AdjustEdge (occurrence);
00340
         return;
00341 }
```

#### 8.9.3.2 Edges()

 $\verb|std::vector<| Edge < char >*>* Markov::Model < char >:: Edges [inline], [inherited] \\ | Return a vector of all the edges in the model. \\ |$ 

# Returns

vector of edges

Definition at line 172 of file model.h.

```
00172 { return &edges;}
```

# 8.9.3.3 Export() [1/2]

Open a file to export with filename, and call bool Model::Export with std::ofstream.

#### Returns

True if successful, False for incomplete models or corrupt file formats

# Example Use: Export file to filename

```
Markov::Model<char> model;
model.Export("test.mdl");
```

```
Definition at line 286 of file model.h.
```

```
00286

00287 std::ofstream exportfile;

00288 exportfile.open(filename);

00289 return this->Export(&exportfile);

00290 }
```

# 8.9.3.4 Export() [2/2]

Export a file of the model.

File contains a list of edges. Format is: Left\_repr;EdgeWeight;right\_repr. For more information on the format, check out the project wiki or github readme.

Iterate over this vertices, and their edges, and write them to file.

#### Returns

True if successful, False for incomplete models.

#### Example Use: Export file to ofstream

# 8.9.3.5 Generate()

```
void Markov::API::MarkovPasswords::Generate (
    unsigned long int n,
    const char * wordlistFileName,
    int minLen = 6,
    int maxLen = 12,
    int threads = 20 )
```

Call Markov::Model::RandomWalk n times, and collect output.

Generate from model and write results to a file. a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

**Deprecated** See Markov::API::MatrixModel::FastRandomWalk for more information.

#### **Parameters**

n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn

Definition at line 110 of file markovPasswords.cpp.

```
00110 char* res;
```

```
00112
          char print[100];
00113
          std::ofstream wordlist;
00114
          wordlist.open(wordlistFileName);
00115
          std::mutex mlock;
          int iterationsPerThread = n/threads;
00116
          int iterationsCarryOver = n%threads;
00117
00118
          std::vector<std::thread*> threadsV;
00119
          for(int i=0;i<threads;i++){</pre>
00120
              threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::GenerateThread, this,
       &mlock, iterationsPerThread, &wordlist, minLen, maxLen));
00121
00122
00123
          for(int i=0;i<threads;i++){</pre>
00124
              threadsV[i]->join();
00125
              delete threadsV[i];
00126
00127
00128
          this->GenerateThread(&mlock, iterationsCarryOver, &wordlist, minLen, maxLen);
00129
00130 }
```

References GenerateThread().

Referenced by Markov::Markopy::BOOST PYTHON MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.9.3.6 GenerateThread()

```
void Markov::API::MarkovPasswords::GenerateThread (
    std::mutex * outputLock,
    unsigned long int n,
    std::ofstream * wordlist,
    int minLen,
    int maxLen ) [private]
```

A single thread invoked by the Generate function.

**DEPRECATED:** See Markov::API::MatrixModel::FastRandomWalkThread for more information. This has been replaced with a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

#### **Parameters**

outputLock	- shared mutex lock to lock during output operation. Prevents race condition on write.
n	number of lines to be generated by this thread
wordlist	wordlistfile
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate

Definition at line 132 of file markovPasswords.cpp.

```
00133
          char* res = new char[maxLen+5];
          if(n==0) return;
00134
00135
00136
          Markov::Random::Marsaglia MarsagliaRandomEngine;
00137
           for (int i = 0; i < n; i++) {</pre>
00138
               this->RandomWalk(&MarsagliaRandomEngine, minLen, maxLen, res);
               outputLock->lock();
*wordlist « res « "\n";
00139
00140
00141
               outputLock->unlock();
00142
00143 }
```

References Markov::Model < NodeStorageType >::RandomWalk().

Referenced by Generate().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.9.3.7 Import() [1/2]

Open a file to import with filename, and call bool Model::Import with std::ifstream.

Returns

True if successful, False for incomplete models or corrupt file formats

#### Example Use: Import a file with filename

#### 8.9.3.8 Import() [2/2]

Import a file to construct the model.

File contains a list of edges. For more info on the file format, check out the wiki and github readme pages. Format is: Left\_repr;EdgeWeight;right\_repr

Iterate over this list, and construct nodes and edges accordingly.

#### Returns

True if successful, False for incomplete models or corrupt file formats

```
Example Use: Import a file from ifstream
```

```
Markov::Model<char> model;
std::ifstream file("test.mdl");
model.Import(&file);
Definition at line 207 of file model.h.
00207
                                                                             {
00208
            std::string cell;
00209
00210
            char src:
00211
            char target;
00212
            long int oc;
00213
            while (std::getline(*f, cell)) {
    //std::cout « "cell: " « cell « std::endl;
00214
00215
                 src = cell[0];
00216
00217
                 target = cell[cell.length() - 1];
00218
                 oc = std::strtol(cell.substr(2, cell.length() - 2).c_str(),&j,10);
//std::cout « oc « "\n";
00219
00220
                 Markov::Node<NodeStorageType>* srcN;
00221
00222
                 Markov::Node<NodeStorageType>* targetN;
00223
                 Markov::Edge<NodeStorageType>* e;
00224
                 if (this->nodes.find(src) == this->nodes.end())
00225
                      srcN = new Markov::Node<NodeStorageType>(src);
00226
                      this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(src, srcN));
00227
                      //std::cout « "Creating new node at start.\n";
00228
00229
                 else {
00230
                      srcN = this->nodes.find(src)->second;
00231
00232
00233
                 if (this->nodes.find(target) == this->nodes.end()) {
                      targetN = new Markov::Node<NodeStorageType>(target);
this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(target, targetN));
00234
00235
00236
                      //std::cout « "Creating new node at end.\n";
00237
00238
                      targetN = this->nodes.find(target)->second;
00239
00240
00241
                 e = srcN->Link(targetN);
00242
                 e->AdjustEdge(oc);
00243
                 this->edges.push_back(e);
00244
                 //std::cout \ll int(srcN->NodeValue()) \ll " --" \ll e->EdgeWeight() \ll "--> " \ll
00245
        int(targetN->NodeValue()) « "\n";
00246
00247
00248
            }
00249
            for (std::pair<unsigned char, Markov::Node<NodeStorageType>*> const& x : this->nodes) {
   //std::cout « "Total edges in EdgesV: " « x.second->edgesV.size() « "\n";
   std::sort (x.second->edgesV.begin(), x.second->edgesV.end(), [](Edge<NodeStorageType> *lhs,
00250
00251
00252
        Edge<NodeStorageType> *rhs)->bool{
00253
                     return lhs->EdgeWeight() > rhs->EdgeWeight();
00254
00255
                 //for(int i=0;i<x.second->edgesV.size();i++)
00256
                 // std::cout < x.second->edgesV[i]->EdgeWeight() < ", ";
00257
                 //std::cout « "\n";
00258
            //std::cout « "Total number of nodes: " « this->nodes.size() « std::endl; //std::cout « "Total number of edges: " « this->edges.size() « std::endl;
00259
00260
00261
00262
            return true;
00263 }
```

# 8.9.3.9 Nodes()

std::map<char , Node<char >\*>\* Markov::Model< char >::Nodes [inline], [inherited]
Return starter Node.

Returns

starter node with 00 NodeValue

```
Definition at line 177 of file model.h. 00177 { return &nodes;}
```

# 8.9.3.10 OpenDatasetFile()

Open dataset file and return the ifstream pointer.

#### **Parameters**

```
filename - Filename to open
```

#### Returns

ifstream\* to the the dataset file

Definition at line 43 of file markovPasswords.cpp.

References Markov::Model < NodeStorageType >::Import().

Here is the call graph for this function:

```
Markov::API::MarkovPasswords
::OpenDatasetFile

Markov::Model::Import
```

# 8.9.3.11 RandomWalk()

Do a random walk on this model.

Start from the starter node, on each node, invoke RandomNext using the random engine on current node, until terminator node is reached. If terminator node is reached before minimum length criateria is reached, ignore the last selection and re-invoke randomNext

If maximum length criteria is reached but final node is not, cut off the generation and proceed to the final node. This function takes Markov::Random::RandomEngine as a parameter to generate pseudo random numbers from

This library is shipped with two random engines, Marsaglia and Mersenne. While mersenne output is higher in entropy, most use cases don't really need super high entropy output, so Markov::Random::Marsaglia is preferable for better performance.

This function WILL NOT reallocate buffer. Make sure no out of bound writes are happening via maximum length criteria.

Example Use: Generate 10 lines, with 5 to 10 characters, and print the output. Use Marsaglia

```
Markov::ModelModel.import("model.mdl");
char* res = new char[11];
Markov::Random::Marsaglia MarsagliaRandomEngine;
for (int i = 0; i < 10; i++) {</pre>
```

```
this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
std::cout « res « "\n";
}
```

#### **Parameters**

randomEngine	Random Engine to use for the random walks. For examples, see Markov::Random::Mersenne and Markov::Random::Marsaglia
minSetting	Minimum number of characters to generate
maxSetting	Maximum number of character to generate
buffer	buffer to write the result to

#### Returns

Null terminated string that was generated.

Definition at line 293 of file model.h.

```
00294
          Markov::Node<NodeStorageType>* n = this->starterNode;
00295
          int len = 0;
          Markov::Node<NodeStorageType>* temp_node;
00296
          while (true) {
   temp_node = n->RandomNext(randomEngine);
00297
00298
00299
               if (len >= maxSetting) {
00300
                   break;
00301
00302
               else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00303
                   continue;
00304
00305
00306
               else if (temp_node == NULL) {
00307
                   break;
               }
00308
00309
00310
              n = temp_node;
00311
00312
               buffer[len++] = n->NodeValue();
00313
          }
00314
00315
           //null terminate the string
00316
          buffer[len] = 0 \times 00;
00317
00318
          //{\rm do} something with the generated string
00319
          return buffer; //for now
00320 }
```

# 8.9.3.12 Save()

Export model to file.

## **Parameters**

filename	- Export filename.

# Returns

std::ofstream\* of the exported file.

# Definition at line 98 of file markovPasswords.cpp.

```
00098
00099 std::ofstream* exportFile;
00100
00101 std::ofstream newFile(filename);
00102
00103 exportFile = &newFile;
00104
00105 this->Export(exportFile);
```

```
00106 return exportFile;
```

References Markov::Model < NodeStorageType >::Export().

Here is the call graph for this function:

```
Markov::API::MarkovPasswords
::Save

Markov::Model::Export
```

#### 8.9.3.13 StarterNode()

```
Node<char >* Markov::Model< char >::StarterNode [inline], [inherited]
Return starter Node.
```

Returns

starter node with 00 NodeValue

```
Definition at line 167 of file model.h. 00167 { return starterNode; }
```

# 8.9.3.14 Train()

Train the model with the dataset file.

#### **Parameters**

datasetFileName	- Ifstream* to the dataset. If null, use class member
delimiter	- a character, same as the delimiter in dataset content
threads	- number of OS threads to spawn


```
Markov::API::MarkovPasswords mp;
mp.Import("models/2gram.mdl");
mp.Train("password.corpus");
Definition at line 57 of file markovPasswords.cpp.
00057
00058
                           signal(SIGINT, intHandler);
                                 Markov::API::Concurrency::ThreadSharedListHandler listhandler(datasetFileName);
00059
00060
                                auto start = std::chrono::high_resolution_clock::now();
00061
00062
                                 std::vector<std::thread*> threadsV;
00063
                              for(int i=0;i<threads;i++){</pre>
00064
                                               threads V.push\_back (new std::thread(\&Markov::API::MarkovPasswords::TrainThread, this, and the statement of the statement o
                       &listhandler, delimiter));
00065
                                 }
00066
00067
                                  for (int i=0;i<threads;i++) {</pre>
00068
                                               threadsV[i]->join();
00069
                                               delete threadsV[i];
00070
00071
                                 auto finish = std::chrono::high_resolution_clock::now();
00072
                                 std::chrono::duration<double> elapsed = finish - start;
00073
                                 std::cout « "Elapsed time: " « elapsed.count() « " s\n";
00074
00075 }
```

References intHandler(), Markov::API::Concurrency::ThreadSharedListHandler::ThreadSharedListHandler(), and

# TrainThread().

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



# 8.9.3.15 TrainThread()

A single thread invoked by the Train function.

# **Parameters**


listhandler	- Listhandler class to read corpus from
delimiter	- a character, same as the delimiter in dataset content

Definition at line 77 of file markovPasswords.cpp.

```
00078
          char format_str[] ="%ld,%s";
00079
         format_str[2]=delimiter;
08000
          std::string line;
00081
          while (listhandler->next(&line) && keepRunning) {
00082
              long int oc;
00083
              if (line.size() > 100) {
00084
                  line = line.substr(0, 100);
00085
00086
              char* linebuf = new char[line.length()+5];
00087 #ifdef _WIN32
      sscanf_s(line.c_str(), "%ld,%s", &oc, linebuf, line.length()+5); //<== changed format_str to->
"%ld,%s"
00088
00089 #else
00090
              sscanf(line.c_str(), format_str, &oc, linebuf);
00091 #endif
00092
              this->AdjustEdge((const char*)linebuf, oc);
00093
00094
00095 }
```

References Markov::Model < NodeStorageType >::AdjustEdge(), keepRunning, and Markov::API::Concurrency::ThreadSharedListHarReferenced by Train().

Here is the call graph for this function:



Here is the caller graph for this function:



# 8.9.4 Member Data Documentation

#### 8.9.4.1 datasetFile

std::ifstream\* Markov::API::MarkovPasswords::datasetFile [private] Definition at line 106 of file markovPasswords.h.

# 8.9.4.2 edges

std::vector<Edge<char >\*> Markov::Model< char >::edges [private], [inherited]
A list of all edges in this model.
Definition at line 195 of file model.h.

#### 8.9.4.3 modelSavefile

std::ofstream\* Markov::API::MarkovPasswords::modelSavefile [private]
Dataset file input of our system

Definition at line 107 of file markovPasswords.h.

## 8.9.4.4 nodes

std::map<char , Node<char >\*> Markov::Model< char >::nodes [private], [inherited]
Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.
Definition at line 184 of file model.h.

#### 8.9.4.5 outputFile

std::ofstream\* Markov::API::MarkovPasswords::outputFile [private]
File to save model of our system

Definition at line 108 of file markovPasswords.h.

#### 8.9.4.6 starterNode

Node<char >\* Markov::Model< char >::starterNode [private], [inherited]

Starter Node of this model.

Definition at line 189 of file model.h.

The documentation for this class was generated from the following files:


- markovPasswords.h
- · markovPasswords.cpp

# 8.10 Markov::GUI::MarkovPasswordsGUI Class Reference


# Reporting UI.

#include <MarkovPasswordsGUI.h>

Inheritance diagram for Markov::GUI::MarkovPasswordsGUI:



Collaboration diagram for Markov::GUI::MarkovPasswordsGUI:



# **Public Slots**

- void MarkovPasswordsGUI::benchmarkSelected ()
- void MarkovPasswordsGUI::modelvisSelected ()
- void MarkovPasswordsGUI::visualDebugSelected ()
- void MarkovPasswordsGUI::comparisonSelected ()
- void MarkovPasswordsGUI::home ()
- void MarkovPasswordsGUI ::pass ()
- · void MarkovPasswordsGUI::model ()

## **Private Attributes**

• Ui::MarkovPasswordsGUIClass ui

# 8.10.1 Detailed Description

Reporting UI.

UI for reporting and debugging tools for MarkovPassword Definition at line 13 of file MarkovPasswordsGUI.h.

#### 8.10.2 Member Function Documentation

# 8.10.2.2 MarkovPasswordsGUI::MarkovPasswordsGUI::MarkovPasswordsGUI::pass () [slot] 8.10.2.2 MarkovPasswordsGUI::MarkovPasswordsGUI::benchmarkSelected void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::benchmarkSelected () [slot] 8.10.2.3 MarkovPasswordsGUI::comparisonSelected void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::comparisonSelected () [slot] 8.10.2.4 MarkovPasswordsGUI::home void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::home () [slot] 8.10.2.5 MarkovPasswordsGUI::model void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::model () [slot] 8.10.2.6 MarkovPasswordsGUI::modelvisSelected void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::modelvisSelected () [slot]

void Markov::GUI::MarkovPasswordsGUI::MarkovPasswordsGUI::visualDebugSelected ( ) [slot]

# 8.10.3 Member Data Documentation

#### 8.10.3.1 ui

Ui::MarkovPasswordsGUIClass Markov::GUI::MarkovPasswordsGUI::ui [private] Definition at line 17 of file MarkovPasswordsGUI.h.


The documentation for this class was generated from the following file:

· MarkovPasswordsGUI.h


# 8.11 Markov::API::CUDA::Random::Marsaglia Class Reference

Extension of Markov::Random::Marsaglia which is capable o working on **device** space. #include <cudarandom.h>

Inheritance diagram for Markov::API::CUDA::Random::Marsaglia:



Collaboration diagram for Markov::API::CUDA::Random::Marsaglia:



# **Public Member Functions**

unsigned long random ()
 Generate Random Number.

# **Static Public Member Functions**

- static unsigned long \* MigrateToVRAM (Markov::API::CUDA::Random::Marsaglia \*MEarr, long int gridSize)
   Migrate a Marsaglia[] to VRAM as seedChunk.
- static \_\_host\_\_ void ListCudaDevices ()

List CUDA devices in the system.

# **Public Attributes**

- · unsigned long x
- · unsigned long y
- unsigned long z

#### **Protected Member Functions**

• std::random\_device & rd ()

Default random device for seeding.

• std::default\_random\_engine & generator ()

Default random engine for seeding.

• std::uniform\_int\_distribution < long long unsigned > & distribution ()

Distribution schema for seeding.

# **Static Protected Member Functions**

```
    static __host__ int CudaCheckNotifyErr (cudaError_t _status, const char *msg, bool bExit=true)
    Check results of the last operation on GPU.
```

```
• template<typename T >
```

```
static __host__ cudaError_t CudaMalloc2DToFlat (T **dst, int row, int col)
```

Malloc a 2D array in device space.

• template<typename T >

```
static __host__ cudaError_t CudaMemcpy2DToFlat (T *dst, T **src, int row, int col)
```

Memcpy a 2D array in device space after flattening.

• template<typename T >

```
static __host__ cudaError_t CudaMigrate2DFlat (T **dst, T **src, int row, int col)
```

Both malloc and memcpy a 2D array into device VRAM.

# 8.11.1 Detailed Description

Extension of Markov::Random::Marsaglia which is capable o working on **device** space. Definition at line 11 of file cudarandom.h.

#### 8.11.2 Member Function Documentation

# 8.11.2.1 CudaCheckNotifyErr()

Check results of the last operation on GPU.

Check the status returned from cudaMalloc/cudaMemcpy to find failures.

If a failure occurs, its assumed beyond redemption, and exited.

#### **Parameters**

_status	Cuda error status to check
msg	Message to print in case of a failure

## Returns

#### 0 if successful, 1 if failure. Example output:

```
cnar *da, a = "test";
cudastatus = cudaMalloc((char **)&da, 5*sizeof(char*));
CudaCheckNotifyErr(cudastatus, "Failed to allocate VRAM for *da.\n");
```

# 8.11.2.2 CudaMalloc2DToFlat()

```
template<typename T >
```

Malloc a 2D array in device space.

This function will allocate enough space on VRAM for flattened 2D array.

#### **Parameters**

dst	destination pointer
row	row size of the 2d array
col	column size of the 2d array


#### Returns

cudaError\_t status of the cudaMalloc operation

# **Example output:**

References Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Here is the call graph for this function:



# 8.11.2.3 CudaMemcpy2DToFlat()

Memcpy a 2D array in device space after flattening.

Resulting buffer will not be true 2D array.

# **Parameters**

dst	destination pointer
rc	source pointer

#### **Parameters**

row	row size of the 2d array
col	column size of the 2d array

#### Returns


cudaError\_t status of the cudaMalloc operation

#### **Example output:**

```
cudaError_t cudastatus;
char* dst;
cudastatus = CudaMalloc2DToFlat<char>(&dst, 5, 15);
CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
cudastatus = CudaMemcpy2DToFlat<char>(*dst, src, 15, 15);
CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
Definition at line 101 of file cudaDeviceController.h.
00101
                    T* tempbuf = new T[row*col];
00103
                     for (int i=0;i<row;i++) {</pre>
00104
                         memcpy(\&(tempbuf[row*i]), src[i], col);
00105
00106
                     return cudaMemcpy(dst, tempbuf, row*col*sizeof(T), cudaMemcpyHostToDevice);
00107
00108
```

References Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Here is the call graph for this function:



# 8.11.2.4 CudaMigrate2DFlat()

Both malloc and memcpy a 2D array into device VRAM.

Resulting buffer will not be true 2D array.

# **Parameters**

	dst	destination pointer
	rc	source pointer
ſ	row	row size of the 2d array
Ī	col	column size of the 2d array

#### Returns

cudaError\_t status of the cudaMalloc operation


#### **Example output:**

```
cudaError_t cudastatus;
char* dst;
cudastatus = CudaMigrate2DFlat<long int>(
&dst, this->valueMatrix, this->matrixSize, this->matrixSize); CudaCheckNotifyErr(cudastatus, " Cuda failed to initialize va
                                          Cuda failed to initialize value matrix row.");
Definition at line 130 of file cudaDeviceController.h.
00130
00131
                     cudaError_t cudastatus;
                     cudastatus = CudaMalloc2DToFlat<T>(dst, row, col);
00132
00133
                      if(cudastatus!=cudaSuccess){
00134
                          CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00135
                          return cudastatus;
00136
                     cudastatus = CudaMemopy2DToFlat<T>(*dst,src,row,col);
CudaCheckNotifyErr(cudastatus, " CudaMemopy2DToFlat Failed.", false);
00137
00138
00139
                      return cudastatus;
00140
```


References Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Referenced by Markov::API::CUDA::CUDADeviceController::CudaMalloc2DToFlat(), Markov::API::CUDA::CUDADeviceController::CudaMigrate2DFlat().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.11.2.5 distribution()


std::uniform\_int\_distribution<long long unsigned>& Markov::Random::DefaultRandomEngine::distribution
( ) [inline], [protected], [inherited]

Distribution schema for seeding.

```
Definition at line 81 of file random.h.
```

```
00081 {
00082 static std::uniform_int_distribution<long long unsigned> _distribution(0, 0xffffffff);
00083 return _distribution;
00084 }
```

Referenced by Markov::Random::Marsaglia::Marsaglia(), and Markov::Random::DefaultRandomEngine::random(). Here is the caller graph for this function:



#### 8.11.2.6 generator()

```
std::default_random_engine& Markov::Random::DefaultRandomEngine::generator ( ) [inline],
[protected], [inherited]
```

Default random engine for seeding.


Definition at line 73 of file random.h.

```
00073
00074
00075
return _generator;
00076
}


{
    constant std::default_random_engine _generator(rd()());
    return _generator;
}
```

References Markov::Random::DefaultRandomEngine::rd().

Referenced by Markov::Random::Marsaglia::Marsaglia(), and Markov::Random::DefaultRandomEngine::random(). Here is the call graph for this function:



Here is the caller graph for this function:



# 8.11.2.7 ListCudaDevices()

```
static __host__ void Markov::API::CUDA::CUDADeviceController::ListCudaDevices ( ) [static],
```

[inherited]

List CUDA devices in the system.

This function will print details of every CUDA capable device in the system.

# **Example output:**

```
Device Number: 0
Device name: GeForce RTX 2070
Memory Clock Rate (KHz): 7001000
Memory Bus Width (bits): 256
Peak Memory Bandwidth (GB/s): 448.064
Max Linear Threads: 1024
```

# 8.11.2.8 MigrateToVRAM()

Migrate a Marsaglia[] to VRAM as seedChunk.

#### **Parameters**

MEarr	Array of Marsaglia Engines
gridSize	GridSize of the CUDA Kernel, aka size of array

#### Returns

pointer to the resulting seed chunk in device VRAM.

Definition at line 19 of file cudarandom.h.

```
00020
                     cudaError_t cudastatus;
00021
                     unsigned long* seedChunk;
                     \verb|cudastatus| = \verb|cudaMalloc((unsigned long**)&seedChunk, gridSize*3*sizeof(unsigned long));|
00022
                     CudaCheckNotifyErr(cudastatus, "Failed to allocate seed buffer");
unsigned long *temp = new unsigned long[gridSize*3];
00023
00024
00025
                     for(int i=0;i<gridSize;i++){</pre>
                        temp[i*3] = MEarr[i].x;
temp[i*3+1] = MEarr[i].y;
00026
00027
                         temp[i*3+2] = MEarr[i].z;
00028
00029
00030
                     //for(int i=0;i<gridSize*3;i++) std::cout « temp[i] « "\n";
00031
                     cudaMemcpy(seedChunk, temp, gridSize*3*sizeof(unsigned long), cudaMemcpyHostToDevice);
00032
                     CudaCheckNotifyErr(cudastatus, "Failed to memcpy seed buffer.");
00033
                     return seedChunk;
00034
```

References Markov::Random::Marsaglia::x, Markov::Random::Marsaglia::y, and Markov::Random::Marsaglia::z.

## 8.11.2.9 random()

```
unsigned long Markov::Random::Marsaglia::random ( ) [inline], [virtual], [inherited]
Generate Random Number.
```

Returns

random number in long range.

Reimplemented from Markov::Random::DefaultRandomEngine.

```
Definition at line 131 of file random.h.
```

```
00131
00132
               unsigned long t;
00133
               x ^= x < 16;
               x ^= x » 5;
00134
               x ^= x « 1;
00135
00136
00137
               t = x;
00138
               x = y;
              y = z;
z = t ^ x ^ y;
00139
00140
00141
00142
               return z;
```

```
00143 }
```

References Markov::Random::Marsaglia::x, Markov::Random::Marsaglia::y, and Markov::Random::Marsaglia::z. Referenced by Markov::API::ModelMatrix::FastRandomWalkThread().

Here is the caller graph for this function:

```
main Markov::API::ModelMatrix ::FastRandomWalk ::FastRandomWalk ::FastRandomWalkPartition ::FastRandomWalkTrix ::FastRandomWalkTrix ::FastRandomWalkPartition ::FastRandomWalkTrix ::FastRandomWalkTri
```

#### 8.11.2.10 rd()

std::random\_device& Markov::Random::DefaultRandomEngine::rd ( ) [inline], [protected], [inherited]
Default random device for seeding.

Definition at line 65 of file random.h.

Referenced by Markov::Random::DefaultRandomEngine::generator().

Here is the caller graph for this function:



#### 8.11.3 Member Data Documentation

# 8.11.3.1 x

unsigned long Markov::Random::Marsaglia::x [inherited]

Definition at line 146 of file random.h.

Referenced by Markov::Random::Marsaglia::Marsaglia(), MigrateToVRAM(), and Markov::Random::Marsaglia::random().

#### 8.11.3.2 y

unsigned long Markov::Random::Marsaglia::y [inherited]

Definition at line 147 of file random.h.

Referenced by Markov::Random::Marsaglia::Marsaglia(), MigrateToVRAM(), and Markov::Random::Marsaglia::random().

#### 8.11.3.3 z

 $\verb"unsigned long Markov::Random::Marsaglia::z [inherited]"$ 

Definition at line 148 of file random.h.

Referenced by Markov::Random::Marsaglia::Marsaglia(), MigrateToVRAM(), and Markov::Random::Marsaglia::random(). The documentation for this class was generated from the following file:


· cudarandom.h

# 8.12 Markov::Random::Marsaglia Class Reference


Implementation of Marsaglia Random Engine.

#include <random.h>

Inheritance diagram for Markov::Random::Marsaglia:



Collaboration diagram for Markov::Random::Marsaglia:



# **Public Member Functions**

• Marsaglia ()

Construct Marsaglia Engine.

• unsigned long random ()

Generate Random Number.

# **Public Attributes**

- unsigned long x
- · unsigned long y
- unsigned long z

# **Protected Member Functions**

• std::random\_device & rd ()

Default random device for seeding.

std::default\_random\_engine & generator ()

Default random engine for seeding.

std::uniform\_int\_distribution < long long unsigned > & distribution ()

Distribution schema for seeding.

# 8.12.1 Detailed Description

Implementation of Marsaglia Random Engine.

This is an implementation of Marsaglia Random engine, which for most use cases is a better fit than other solutions. Very simple mathematical formula to generate pseudorandom integer, so its crazy fast.

This implementation of the Marsaglia Engine is seeded by random.h default random engine. RandomEngine is only seeded once so its not a performance issue.

Example Use: Using Marsaglia Engine with RandomWalk

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::Marsaglia MarsagliaRandomEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
    std::cout « res « "\n";
}
```

Example Use: Generating a random number with Marsaglia Engine

```
Markov::Random::Marsaglia me;
std::cout « me.random();
```

Definition at line 116 of file random.h.

#### 8.12.2 Constructor & Destructor Documentation

#### 8.12.2.1 Marsaglia()

```
Markov::Random::Marsaglia::Marsaglia ( ) [inline]
```


Construct Marsaglia Engine.

Initialize x,y and z using the default random engine.

```
Definition at line 123 of file random.h.
```

References Markov::Random::DefaultRandomEngine::distribution(), Markov::Random::DefaultRandomEngine::generator(), x, y, and z.

Here is the call graph for this function:



# 8.12.3 Member Function Documentation

# 8.12.3.1 distribution()


std::uniform\_int\_distribution<long long unsigned>& Markov::Random::DefaultRandomEngine::distribution
( ) [inline], [protected], [inherited]

Distribution schema for seeding.

```
Definition at line 81 of file random.h.
```

Referenced by Marsaglia(), and Markov::Random::DefaultRandomEngine::random().

Here is the caller graph for this function:



## 8.12.3.2 generator()

```
std::default_random_engine& Markov::Random::DefaultRandomEngine::generator ( ) [inline],
[protected], [inherited]
```


Default random engine for seeding.

Definition at line 73 of file random.h.


References Markov::Random::DefaultRandomEngine::rd().

Referenced by Marsaglia(), and Markov::Random::DefaultRandomEngine::random().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.12.3.3 random()

```
unsigned long Markov::Random::Marsaglia::random ( ) [inline], [virtual]
Generate Random Number.
```

#### Returns

random number in long range.

Reimplemented from Markov::Random::DefaultRandomEngine.

```
Definition at line 131 of file random.h.
00132
                 unsigned long t;
                x ^= x « 16;
x ^= x » 5;
00133
00134
                x ^= x « 1;
00135
00136
00137
                t = x:
00138
                 x = y;
                x - 1,
y = z;
z = t ^ x ^ y;
00139
00140
00141
00142
                 return z;
00143
            }
```

References x, y, and z.

Referenced by Markov::API::ModelMatrix::FastRandomWalkThread().

Here is the caller graph for this function:



#### 8.12.3.4 rd()

std::random\_device& Markov::Random::DefaultRandomEngine::rd ( ) [inline], [protected], [inherited]


Default random device for seeding.

```
Definition at line 65 of file random.h.

00065
00066
static std::random_device _rd;
00067
return _rd;
00068
}
```

Referenced by Markov::Random::DefaultRandomEngine::generator().

Here is the caller graph for this function:



# 8.12.4 Member Data Documentation

#### 8.12.4.1 x

unsigned long Markov::Random::Marsaglia::x

Definition at line 146 of file random.h.

Referenced by Marsaglia(), Markov::API::CUDA::Random::Marsaglia::MigrateToVRAM(), and random().

#### 8.12.4.2 y

unsigned long Markov::Random::Marsaglia::y Definition at line 147 of file random.h.

Referenced by Marsaglia(), Markov::API::CUDA::Random::Marsaglia::MigrateToVRAM(), and random().

# 8.12.4.3 z

unsigned long Markov::Random::Marsaglia::z

Definition at line 148 of file random.h.

Referenced by Marsaglia(), Markov::API::CUDA::Random::Marsaglia::MigrateToVRAM(), and random().

The documentation for this class was generated from the following file:


· random.h

# 8.13 Markov::GUI::menu Class Reference


# QT Menu class.

#include <menu.h>

Inheritance diagram for Markov::GUI::menu:



Collaboration diagram for Markov::GUI::menu:



# **Public Slots**

- void about ()
- void visualization ()

# **Public Member Functions**

• menu (QWidget \*parent=Q\_NULLPTR)

# **Private Attributes**

· Ui::main ui

# 8.13.1 Detailed Description

QT Menu class.

Definition at line 9 of file menu.h.

# 8.13.2 Constructor & Destructor Documentation

# 8.13.2.1 menu()

# 8.13.3 Member Function Documentation

# 8.13.3.1 about

```
void menu::about ( ) [slot]
Definition at line 17 of file menu.cpp.
00017
00018
00019
00020 }
```

#### 8.13.3.2 visualization

# 8.13.4 Member Data Documentation

# 8.13.4.1 ui

```
Ui::main Markov::GUI::menu::ui [private]
Definition at line 15 of file menu.h.
```


The documentation for this class was generated from the following files:

- menu.h
- menu.cpp


# 8.14 Markov::Random::Mersenne Class Reference

```
Implementation of Mersenne Twister Engine.
#include <random.h>
```

Inheritance diagram for Markov::Random::Mersenne:



Collaboration diagram for Markov::Random::Mersenne:



## **Public Member Functions**

unsigned long random ()
 Generate Random Number.

## **Protected Member Functions**

• std::random\_device & rd ()

Default random device for seeding.

• std::default\_random\_engine & generator ()

Default random engine for seeding.

std::uniform\_int\_distribution < long long unsigned > & distribution ()

Distribution schema for seeding.

## 8.14.1 Detailed Description

Implementation of Mersenne Twister Engine.

This is an implementation of Mersenne Twister Engine, which is slow but is a good implementation for high entropy pseudorandom.

Example Use: Using Mersenne Engine with RandomWalk

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::Mersenne MersenneTwisterEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(&MersenneTwisterEngine, 5, 10, res);
    std::cout « res « "\n";
}
```

Example Use: Generating a random number with Marsaglia Engine

```
Markov::Random::Mersenne me;
std::cout « me.random();
```

Definition at line 176 of file random.h.

### 8.14.2 Member Function Documentation

#### 8.14.2.1 distribution()

```
std::uniform_int_distribution<long long unsigned>& Markov::Random::DefaultRandomEngine::distribution
( ) [inline], [protected], [inherited]
```

Distribution schema for seeding.

Definition at line 81 of file random.h.

Referenced by Markov::Random::Marsaglia::Marsaglia(), and Markov::Random::DefaultRandomEngine::random(). Here is the caller graph for this function:

```
Markov::Random::Marsaglia
::Marsaglia
::Marsaglia

Markov::Random::DefaultRandom
Engine::distribution
```

## 8.14.2.2 generator()

```
std::default_random_engine& Markov::Random::DefaultRandomEngine::generator ( ) [inline],
[protected], [inherited]
```

Default random engine for seeding.


Definition at line 73 of file random.h.

References Markov::Random::DefaultRandomEngine::rd().

Referenced by Markov::Random::Marsaglia::Marsaglia(), and Markov::Random::DefaultRandomEngine::random(). Here is the call graph for this function:

```
Markov::Random::DefaultRandom Engine::generator Markov::Random::DefaultRandom Engine::rd
```

Here is the caller graph for this function:



#### 8.14.2.3 random()

unsigned long Markov::Random::DefaultRandomEngine::random ( ) [inline], [virtual], [inherited]
Generate Random Number.

Returns

random number in long range.

Implements Markov::Random::RandomEngine.

Reimplemented in Markov::Random::Marsaglia.

```
Definition at line 57 of file random.h.
```

References Markov::Random::DefaultRandomEngine::distribution(), and Markov::Random::DefaultRandomEngine::generator(). Here is the call graph for this function:

```
Markov::Random::DefaultRandom Engine::random

Markov::Random::DefaultRandom Engine::distribution

Markov::Random::DefaultRandom Engine::generator Engine::rd
```

## 8.14.2.4 rd()

std::random\_device& Markov::Random::DefaultRandomEngine::rd ( ) [inline], [protected], [inherited]

Default random device for seeding.

Definition at line 65 of file random.h.

```
00065 {
00066 static std::random_device _rd;
00067 return _rd;
00068 }
```

Referenced by Markov::Random::DefaultRandomEngine::generator().

Here is the caller graph for this function:




The documentation for this class was generated from the following file:

· random.h


# 8.15 Markov::Model < NodeStorageType > Class Template Reference

class for the final Markov Model, constructed from nodes and edges.
#include <model.h>

Inheritance diagram for Markov::Model < NodeStorageType >:



Collaboration diagram for Markov::Model < NodeStorageType >:



## **Public Member Functions**

- Model ()
  - Initialize a model with only start and end nodes.
- NodeStorageType \* RandomWalk (Markov::Random::RandomEngine \*randomEngine, int minSetting, int maxSetting, NodeStorageType \*buffer)
  - Do a random walk on this model.
- void AdjustEdge (const NodeStorageType \*payload, long int occurrence)
  - Adjust the model with a single string.
- bool Import (std::ifstream \*)

Import a file to construct the model.

bool Import (const char \*filename)

Open a file to import with filename, and call bool Model::Import with std::ifstream.

bool Export (std::ofstream \*)

Export a file of the model.

bool Export (const char \*filename)

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Node< NodeStorageType > \* StarterNode ()

Return starter Node.

std::vector< Edge< NodeStorageType > \* > \* Edges ()

Return a vector of all the edges in the model.

std::map< NodeStorageType, Node< NodeStorageType > \* > \* Nodes ()

Return starter Node.

#### **Private Attributes**

std::map< NodeStorageType, Node< NodeStorageType > \* > nodes

Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.

Node< NodeStorageType > \* starterNode

Starter Node of this model.

std::vector< Edge< NodeStorageType > \* > edges

A list of all edges in this model.

## 8.15.1 Detailed Description

```
template < typename NodeStorageType > class Markov::Model < NodeStorageType >
```

class for the final Markov Model, constructed from nodes and edges.

Each atomic piece of the generation result is stored in a node, while edges contain the relation weights. *Extending:* To extend the class, implement the template and inherit from it, as "class MyModel: public Markov::Model<char>". For a complete demonstration of how to extend the class, see MarkovPasswords.

Whole model can be defined as a list of the edges, as dangling nodes are pointless. This approach is used for the import/export operations. For more information on importing/exporting model, check out the github readme and wiki page.

Definition at line 41 of file model.h.

#### 8.15.2 Constructor & Destructor Documentation

#### 8.15.2.1 Model()

```
template<typename NodeStorageType >
Markov::Model< NodeStorageType >::Model
```

Initialize a model with only start and end nodes.

Initialize an empty model with only a starterNode Starter node is a special kind of node that has constant 0x00 value, and will be used to initiate the generation execution from.

Definition at line 201 of file model.h.

```
00201
00202     this->starterNode = new Markov::Node<NodeStorageType>(0);
00203     this->nodes.insert({ 0, this->starterNode });
00204 }
```

#### 8.15.3 Member Function Documentation

#### 8.15.3.1 AdjustEdge()

Adjust the model with a single string.

Start from the starter node, and for each character, AdjustEdge the edge EdgeWeight from current node to the next, until NULL character is reached.

Then, update the edge EdgeWeight from current node, to the terminator node.

This function is used for training purposes, as it can be used for adjusting the model with each line of the corpus file

Example Use: Create an empty model and train it with string: "testdata"

```
Markov::Model<char> model;
char test[] = "testdata";
model.AdjustEdge(test, 15);
```

#### **Parameters**


string	- String that is passed from the training, and will be used to AdjustEdge the model with	l
occurrence	- Occurrence of this string.	Ì

#### Definition at line 323 of file model.h.

```
00323
00324
          NodeStorageType p = payload[0];
00325
          Markov::Node<NodeStorageType>* curnode = this->starterNode;
00326
          Markov::Edge<NodeStorageType>* e;
00327
          int i = 0;
00328
          if (p == 0) return;
00329
00330
         while (p != 0) {
             e = curnode->FindEdge(p);
00331
00332
              if (e == NULL) return;
00333
              e->AdjustEdge (occurrence);
00334
              curnode = e->RightNode();
00335
             p = payload[++i];
00336
         }
00337
00338
          e = curnode->FindEdge('\xff');
00339
          e->AdjustEdge (occurrence);
00340
          return;
00341 }
```

Referenced by Markov::API::MarkovPasswords::TrainThread().

Here is the caller graph for this function:



### 8.15.3.2 Edges()

```
template<typename NodeStorageType >
std::vector<Edge<NodeStorageType>*>* Markov::Model< NodeStorageType >::Edges ( ) [inline]
Return a vector of all the edges in the model.
```

#### Returns

vector of edges

```
Definition at line 172 of file model.h.
```

```
00172 { return &edges;}
```

### 8.15.3.3 Export() [1/2]

Open a file to export with filename, and call bool Model::Export with std::ofstream.

#### Returns


True if successful, False for incomplete models or corrupt file formats

#### **Example Use:** Export file to filename

```
model.Export("test.md1");
Definition at line 286 of file model.h.
00286
00287     std::ofstream exportfile;
00288     exportfile.open(filename);
00289     return this->Export(&exportfile);
00290 }
```

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the caller graph for this function:



#### 8.15.3.4 Export() [2/2]

Export a file of the model.

File contains a list of edges. Format is: Left\_repr;EdgeWeight;right\_repr. For more information on the format, check out the project wiki or github readme.

Iterate over this vertices, and their edges, and write them to file.

### Returns

True if successful, False for incomplete models.

#### **Example Use:** Export file to ofstream

```
Markov::Model<char> model;
std::ofstream file("test.mdl");
model.Export(&file);
Definition at line 274 of file model.h.
00274
00275
          Markov::Edge<NodeStorageType>* e;
00276
          for (std::vector<int>::size_type i = 0; i != this->edges.size(); i++) {
            e = this->edges[i];
00278
               //std::cout « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," «
       e->RightNode()->NodeValue() « "\n";
               *f « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," « e->RightNode()->NodeValue() «
00279
       "\n";
00280
00281
          return true;
```

Referenced by Markov::API::MarkovPasswords::Save().

Here is the caller graph for this function:



#### 8.15.3.5 Import() [1/2]

Open a file to import with filename, and call bool Model::Import with std::ifstream.

Returns

True if successful, False for incomplete models or corrupt file formats


### Example Use: Import a file with filename

```
Markov::Model<char> model;
model.Import("test.mdl");

Definition at line 266 of file model.h.

00266
00267     std::ifstream importfile;
00268     importfile.open(filename);
00269     return this->Import(&importfile);
00270
00271 }
```

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE(), main(), and Markov::API::MarkovPasswords::MarkovPasswords(). Here is the caller graph for this function:



### 8.15.3.6 Import() [2/2]

Import a file to construct the model.

File contains a list of edges. For more info on the file format, check out the wiki and github readme pages. Format is: Left\_repr;EdgeWeight;right\_repr

Iterate over this list, and construct nodes and edges accordingly.

#### Returns

True if successful, False for incomplete models or corrupt file formats

```
Example Use: Import a file from ifstream
```

```
Markov::Model<char> model;
std::ifstream file("test.mdl");
model.Import(&file);
Definition at line 207 of file model.h.
00207
00208
          std::string cell;
00209
00210
          char src;
00211
          char target;
00212
          long int oc;
00213
00214
          while (std::getline(*f, cell)) {
00215
              //std::cout « "cell: " « cell « std::endl;
00216
               src = cell[0];
00217
               target = cell[cell.length() - 1];
00218
               char* j;
00219
               oc = std::strtol(cell.substr(2, cell.length() - 2).c_str(),&j,10);
               //std::cout « oc « "\n";
00220
               Markov::Node<NodeStorageType>* srcN;
00221
00222
               Markov::Node<NodeStorageType>* targetN;
00223
               Markov::Edge<NodeStorageType>* e;
00224
               if (this->nodes.find(src) == this->nodes.end()) {
                   srcN = new Markov::Node<NodeStorageType>(src);
00225
                   this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(src, srcN));
00226
00227
                   //std::cout « "Creating new node at start.\n";
00228
00229
               else {
00230
                   srcN = this->nodes.find(src)->second;
00231
              }
00232
00233
               if (this->nodes.find(target) == this->nodes.end()) {
00234
                   targetN = new Markov::Node<NodeStorageType>(target);
00235
                   this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(target, targetN));
00236
                   //std::cout « "Creating new node at end.\n";
00237
00238
               else {
00239
                   targetN = this->nodes.find(target)->second;
00240
00241
               e = srcN->Link(targetN);
00242
               e->AdjustEdge(oc);
00243
               this->edges.push_back(e);
00244
               //std::cout « int(srcN->NodeValue()) « " --" « e->EdgeWeight() « "--> " «
00245
       int(targetN->NodeValue()) « "\n";
00246
00247
00248
          }
00249
00250
          for (std::pair<unsigned char, Markov::Node<NodeStorageType>*> const& x : this->nodes) {
               //std::cout « "Total edges in EdgesV: " « x.second->edgesV.size() « "\n";
00251
               std::sort (x.second->edgesV.begin(), x.second->edgesV.end(), [](Edge<NodeStorageType> *lhs,
00252
       Edge<NodeStorageType> *rhs)->bool{
00253
                  return lhs->EdgeWeight() > rhs->EdgeWeight();
00254
00255
               //for(int i=0;i<x.second->edgesV.size();i++)
              ///std::cout « x.second->edgesV[i]->EdgeWeight() « ", ";
//std::cout « "\n";
00256
00258
          //std::cout « "Total number of nodes: " « this->nodes.size() « std::endl; //std::cout « "Total number of edges: " « this->edges.size() « std::endl;
00259
00260
00261
00262
00263 }
```

Referenced by Markov::API::MarkovPasswords::OpenDatasetFile().

Here is the caller graph for this function:



#### 8.15.3.7 Nodes()

```
template<typename NodeStorageType >
std::map<NodeStorageType, Node<NodeStorageType>*>* Markov::Model< NodeStorageType >::Nodes (
) [inline]
Return starter Node.
```

## Returns

starter node with 00 NodeValue

```
Definition at line 177 of file model.h. 00177 { return &nodes;}
```

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



#### 8.15.3.8 RandomWalk()

Do a random walk on this model.

Start from the starter node, on each node, invoke RandomNext using the random engine on current node, until terminator node is reached. If terminator node is reached before minimum length criateria is reached, ignore the last selection and re-invoke randomNext

If maximum length criteria is reached but final node is not, cut off the generation and proceed to the final node. This function takes Markov::Random::RandomEngine as a parameter to generate pseudo random numbers from

This library is shipped with two random engines, Marsaglia and Mersenne. While mersenne output is higher in entropy, most use cases don't really need super high entropy output, so Markov::Random::Marsaglia is preferable for better performance.

This function WILL NOT reallocate buffer. Make sure no out of bound writes are happening via maximum length criteria.

Example Use: Generate 10 lines, with 5 to 10 characters, and print the output. Use Marsaglia

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::Marsaglia MarsagliaRandomEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
    std::cout « res « "\n";
}
```

#### **Parameters**

randomEngine	Random Engine to use for the random walks. For examples, see Markov::Random::Mersenne and Markov::Random::Marsaglia
minSetting	Minimum number of characters to generate

#### **Parameters**

maxSetting	Maximum number of character to generate
buffer	buffer to write the result to

#### Returns

Null terminated string that was generated.

Definition at line 293 of file model.h.

```
00294
           Markov::Node<NodeStorageType>* n = this->starterNode;
00295
           int len = 0;
00296
           Markov::Node<NodeStorageType>* temp_node;
00297
           while (true) {
                temp_node = n->RandomNext(randomEngine);
if (len >= maxSetting) {
00298
00299
00300
                    break;
00301
00302
                else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00303
                    continue;
00304
00305
00306
                else if (temp_node == NULL) {
00307
                    break;
00308
00309
00310
               n = temp_node;
00311
               buffer[len++] = n->NodeValue();
00312
00313
           }
00314
00315
            //null terminate the string
00316
           buffer[len] = 0x00;
00317
00318
           //do something with the generated string
return buffer; //for now
00319
00320 }
```

Referenced by Markov::API::MarkovPasswords::GenerateThread().

Here is the caller graph for this function:



## 8.15.3.9 StarterNode()

```
template<typename NodeStorageType >
Node<NodeStorageType>* Markov::Model< NodeStorageType >::StarterNode ( ) [inline]
Return starter Node.
```

#### Returns

starter node with 00 NodeValue

Definition at line 167 of file model.h. 00167 { return starterNode;}

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



### 8.15.4 Member Data Documentation

### 8.15.4.1 edges

```
template<typename NodeStorageType >
std::vector<Edge<NodeStorageType>*> Markov::Model< NodeStorageType >::edges [private]
A list of all edges in this model.
Definition at line 195 of file model.h.
Referenced by Markov::Model< char >::Edges().
```

#### 8.15.4.2 nodes

```
template<typename NodeStorageType >
std::map<NodeStorageType, Node<NodeStorageType>*> Markov::Model< NodeStorageType >::nodes
[private]
Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.
```

Definition at line 184 of file model.h.

Referenced by Markov::Model < char >::Nodes().

## 8.15.4.3 starterNode

```
template<typename NodeStorageType >
Node<NodeStorageType>* Markov::Model< NodeStorageType >::starterNode [private]
Starter Node of this model.
Definition at line 189 of file model.h.
Referenced by Markov::Model< char >::StarterNode().
```


The documentation for this class was generated from the following file:

model.h


## 8.16 Markov::API::ModelMatrix Class Reference

Class to flatten and reduce Markov::Model to a Matrix. #include <modelMatrix.h>

Inheritance diagram for Markov::API::ModelMatrix:



Collaboration diagram for Markov::API::ModelMatrix:



## **Public Member Functions**

- ModelMatrix ()
- void ConstructMatrix ()

Construct the related Matrix data for the model.

• void DumpJSON ()

Debug function to dump the model to a JSON file.

 void FastRandomWalk (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20, bool bFileIO=true)

Random walk on the Matrix-reduced Markov::Model.

std::ifstream \* OpenDatasetFile (const char \*filename)

Open dataset file and return the ifstream pointer.

void Train (const char \*datasetFileName, char delimiter, int threads)

Train the model with the dataset file.

std::ofstream \* Save (const char \*filename)

Export model to file.

void Generate (unsigned long int n, const char \*wordlistFileName, int minLen=6, int maxLen=12, int threads=20)

Call Markov::Model::RandomWalk n times, and collect output.

 char \* RandomWalk (Markov::Random::RandomEngine \*randomEngine, int minSetting, int maxSetting, char \*buffer)

Do a random walk on this model.

• void AdjustEdge (const char \*payload, long int occurrence)

Adjust the model with a single string.

bool Import (std::ifstream \*)

Import a file to construct the model.

• bool Import (const char \*filename)

Open a file to import with filename, and call bool Model::Import with std::ifstream.

bool Export (std::ofstream \*)

Export a file of the model.

bool Export (const char \*filename)

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Node < char > \* StarterNode ()

Return starter Node.

std::vector< Edge< char > \* > \* Edges ()

Return a vector of all the edges in the model.

• std::map< char, Node< char > \* > \* Nodes ()

Return starter Node.

#### **Protected Member Functions**

• void FastRandomWalkPartition (std::mutex \*mlock, std::ofstream \*wordlist, unsigned long int n, int minLen, int maxLen, bool bFileIO, int threads)

A single partition of FastRandomWalk event.

void FastRandomWalkThread (std::mutex \*mlock, std::ofstream \*wordlist, unsigned long int n, int minLen, int maxLen, int id, bool bFileIO)

A single thread of a single partition of FastRandomWalk.

## **Protected Attributes**

char \*\* edgeMatrix

2-D Character array for the edge Matrix (The characters of Nodes)

long int \*\* valueMatrix

2-d Integer array for the value Matrix (For the weights of Edges)

· int matrixSize

to hold Matrix size

• char \* matrixIndex

to hold the Matrix index (To hold the orders of 2-D arrays')

long int \* totalEdgeWeights

Array of the Total Edge Weights.

#### **Private Member Functions**

- void TrainThread (Markov::API::Concurrency::ThreadSharedListHandler \*listhandler, char delimiter)
  - A single thread invoked by the Train function.
- void GenerateThread (std::mutex \*outputLock, unsigned long int n, std::ofstream \*wordlist, int minLen, int maxLen)

A single thread invoked by the Generate function.

#### **Private Attributes**

- std::ifstream \* datasetFile
- std::ofstream \* modelSavefile

Dataset file input of our system

std::ofstream \* outputFile

File to save model of our system

std::map< char, Node< char > \* > nodes

Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.

Node< char > \* starterNode

Starter Node of this model.

std::vector< Edge< char > \* > edges

A list of all edges in this model.

## 8.16.1 Detailed Description

Class to flatten and reduce Markov::Model to a Matrix.

Matrix level operations can be used for Generation events, with a significant performance optimization at the cost of O(N) memory complexity (O(1) memory space for slow mode)

To limit the maximum memory usage, each generation operation is partitioned into 50M chunks for allocation. Threads are sychronized and files are flushed every 50M operations.

Definition at line 13 of file modelMatrix.h.

## 8.16.2 Constructor & Destructor Documentation

#### 8.16.2.1 ModelMatrix()

```
Markov::API::ModelMatrix::ModelMatrix ( )
Definition at line 6 of file modelMatrix.cpp.
00006
00007
00008 }
```

#### 8.16.3 Member Function Documentation

### 8.16.3.1 AdjustEdge()

Adjust the model with a single string.

Start from the starter node, and for each character, AdjustEdge the edge EdgeWeight from current node to the next, until NULL character is reached.

Then, update the edge EdgeWeight from current node, to the terminator node.

This function is used for training purposes, as it can be used for adjusting the model with each line of the corpus file

Example Use: Create an empty model and train it with string: "testdata"

```
Markov::Model<char> model;
char test[] = "testdata";
model.AdjustEdge(test, 15);
```

#### **Parameters**

string	- String that is passed from the training, and will be used to AdjustEdge the model with	Ì
occurrence	- Occurrence of this string.	Ì

Definition at line 323 of file model.h.

```
00323
00324
          NodeStorageType p = payload[0];
          Markov::Node<NodeStorageType>* curnode = this->starterNode;
00325
00326
          Markov::Edge<NodeStorageType>* e;
00327
00328
00329
          if (p == 0) return;
00330
          while (p != 0) {
             e = curnode->FindEdge(p);
00331
              if (e == NULL) return;
00332
              e->AdjustEdge (occurrence);
00334
              curnode = e->RightNode();
00335
             p = payload[++i];
00336
          }
00337
00338
          e = curnode->FindEdge('\xff');
00339
          e->AdjustEdge (occurrence);
00340
          return;
00341 }
```

### 8.16.3.2 ConstructMatrix()

```
void Markov::API::ModelMatrix::ConstructMatrix ( )
```

Construct the related Matrix data for the model.

This operation can be used after importing/training to allocate and populate the matrix content.

this will initialize: char\*\* edgeMatrix -> a 2D array of mapping left and right connections of each edge. long int \*\*valueMatrix -> a 2D array representing the edge weights. int matrixSize -> Size of the matrix, aka total number of nodes. char\* matrixIndex -> order of nodes in the model long int \*totalEdgeWeights -> total edge weights of each Node.


Definition at line 11 of file modelMatrix.cpp.

```
00012
          this->matrixSize = this->StarterNode()->edgesV.size() + 2;
00013
00014
          this->matrixIndex = new char[this->matrixSize];
00015
          this->totalEdgeWeights = new long int[this->matrixSize];
00016
00017
          this->edgeMatrix = new char*[this->matrixSize];
00018
          for(int i=0;i<this->matrixSize;i++) {
00019
              this->edgeMatrix[i] = new char[this->matrixSize];
00020
00021
          this->valueMatrix = new long int*[this->matrixSize];
00022
          for (int i=0; i<this->matrixSize; i++) {
00023
              this->valueMatrix[i] = new long int[this->matrixSize];
00024
00025
          std::map< char, Node< char > * > *nodes;
00026
          nodes = this->Nodes();
00027
          int i=0:
00028
          for (auto const& [repr, node] : *nodes) {
00029
              if(repr!=0) this->matrixIndex[i] = repr;
00030
                 se this->matrixIndex[i] = 199;
00031
              this->totalEdgeWeights[i] = node->TotalEdgeWeights();
              for(int j=0;j<this->matrixSize;j++) {
00032
00033
                  char val = node->NodeValue();
                  if(val < 0){</pre>
00034
00035
                       for(int k=0;k<this->matrixSize;k++){
00036
                          this->valueMatrix[i][k] = 0;
00037
                           this->edgeMatrix[i][k] = 255;
00038
00039
                      break:
00040
00041
                  else if (node->NodeValue() == 0 && j>(this->matrixSize-3)){
00042
                      this->valueMatrix[i][j] = 0;
```


```
00043
                          this->edgeMatrix[i][j] = 255;
00044
                      }else if(j==(this->matrixSize-1)) {
00045
                           this->valueMatrix[i][j] = 0;
00046
                          this->edgeMatrix[i][j] = 255;
00047
                      }else{
                          this->valueMatrix[i][j] = node->edgesV[j]->EdgeWeight();
this->edgeMatrix[i][j] = node->edgesV[j]->RightNode()->NodeValue();
00048
00050
00051
00052
00053
                 i++;
00054
00055
00056
            //this->DumpJSON();
00057 }
```

References edgeMatrix, Markov::Edge 
NodeStorageType >::EdgeWeight(), matrixIndex, matrixSize, Markov::Model 
NodeStorageType 
NodeStorageType >::RightNode(), Markov::Model 
NodeStorageType 
NodeStorageTyp

Here is the call graph for this function:



Here is the caller graph for this function:



## 8.16.3.3 DumpJSON()

```
void Markov::API::ModelMatrix::DumpJSON ( )
Debug function to dump the model to a JSON file.
Might not work 100%. Not meant for production use.
Definition at line 60 of file modelMatrix.cpp.
```

```
00062
                   std::cout « "{\n \"index\": \"";
                  for(int i=0;i<this->matrixSize;i++) {
   if(this->matrixIndex[i]=='"') std::cout « "\\\"";
   else if(this->matrixIndex[i]=='\\') std::cout « "\\\";
   else if(this->matrixIndex[i]==0) std::cout « "\\\x00";
00063
00064
00065
00066
                          else if(ti=0) std::cout « "\\\xff";
else if(this->matrixIndex[i]=='\n') std::cout « "\\n";
00067
00068
00069
                           else std::cout « this->matrixIndex[i];
00070
00071
                   std::cout «
                    "\",\n"
" \"edgemap\": {\n";
00072
00073
00074
00075
                   for(int i=0;i<this->matrixSize;i++){
                       if(this->matrixIndex[i]=='"') std::cout « " \"\\\": [";
else if(this->matrixIndex[i]=='\') std::cout « " \"\\\\": [";
else if(this->matrixIndex[i]==0) std::cout « " \"\\\x00\\": [";
else if(this->matrixIndex[i]<0) std::cout « " \"\\\xff\\": [";
else std::cout « " \"" « this->matrixIndex[i] « "\": [";
00076
00077
00078
00080
                          else std::cout « " \"" « this->matrixIndex[i] « "\": [";
for(int j=0;j<this->matrixSize;j++){
    if(this->edgeMatrix[i][j]=='"') std::cout « "\"\\\"";
    else if(this->edgeMatrix[i][j]=='\\') std::cout « "\"\\\\"";
    else if(this->edgeMatrix[i][j]==0) std::cout « "\"\\\x00\\"";
    else if(this->edgeMatrix[i][j]<0) std::cout « "\"\\\xff\"";
    else if(this->matrixIndex[i]=='\n') std::cout « "\"\\\\rf\"";
    else std::cout « "\"" « this->edgeMatrix[i][j] « "\"";
    if(i]=this->matrixGize-1) std::cout « ". ":
00081
00082
00083
00084
00085
00087
00088
                                   if(j!=this->matrixSize-1) std::cout « ", ";
00089
                          std::cout « "], \n";
00090
00091
00092
                  std::cout « "},\n";
00093
                   std::cout « "\" weightmap\": \{\n";
00094
                  for(int i=0;i<br/>this>>matrixSize;i++){
   if(this->matrixIndex[i]=='"') std::cout « "
00095
                                                                                                                           \"\\\"\": [";
00096
                          else if(this->matrixIndex[i]=='\\') std::cout « "
else if(this->matrixIndex[i]==0) std::cout « "
else if(this->matrixIndex[i]<0) std::cout « "</pre>
                                                                                                                              \"\\\\": [";
\"\\\x00\": [";
00097
                                                                        dex[i]<0) std::cout « " \"\\\xff\": ["; \"" « this->matrixIndex[i] « "\": [";
00099
00100
                          else std::cout « "
00101
00102
                           for(int j=0; j<this->matrixSize; j++) {
                                  std::cout « this->valueMatrix[i][j];
00103
00104
                                   if(j!=this->matrixSize-1) std::cout « ", ";
00105
00106
                           std::cout « "], \n";
00107
                   std::cout « " }\n}\n";
00108
00109 }
```

References edgeMatrix, matrixIndex, matrixSize, and valueMatrix.

### 8.16.3.4 Edges()

std::vector<Edge<char >\*>\* Markov::Model< char >::Edges ( ) [inline], [inherited]
Return a vector of all the edges in the model.

Returns

vector of edges

```
Definition at line 172 of file model.h. 00172 { return &edges;}
```

## 8.16.3.5 Export() [1/2]

Open a file to export with filename, and call bool Model::Export with std::ofstream.

Returns

True if successful, False for incomplete models or corrupt file formats

### Example Use: Export file to filename

```
Markov::Model<char> model;
model.Export("test.mdl");
```

```
Definition at line 286 of file model.h.
```

```
00286
00287    std::ofstream exportfile;
00288    exportfile.open(filename);
00289    return this->Export(&exportfile);
00290 }
```

### 8.16.3.6 Export() [2/2]

```
bool Markov::Model < char >::Export (
    std::ofstream * f ) [inherited]
```

Export a file of the model.

File contains a list of edges. Format is: Left\_repr;EdgeWeight;right\_repr. For more information on the format, check out the project wiki or github readme.

Iterate over this vertices, and their edges, and write them to file.

#### Returns

00283 }

True if successful, False for incomplete models.

#### Example Use: Export file to ofstream

```
Markov::Model<char> model;
std::ofstream file("test.mdl");
model.Export(&file);
Definition at line 274 of file model.h.
           Markov::Edge<NodeStorageType>* e;
00276
           for (std::vector<int>::size_type i = 0; i != this->edges.size(); i++) {
00277
               e = this->edges[i];
               //std::cout \ll e->LeftNode()->NodeValue() \ll "," \ll e->EdgeWeight() \ll "," \ll
00278
       e->RightNode()->NodeValue() « "\n";
00279
               *f « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," « e->RightNode()->NodeValue() «
00280
00281
00282
           return true;
```

## 8.16.3.7 FastRandomWalk()

```
void Markov::API::ModelMatrix::FastRandomWalk (
    unsigned long int n,
    const char * wordlistFileName,
    int minLen = 6,
    int maxLen = 12,
    int threads = 20,
    bool bFileIO = true )
```

Random walk on the Matrix-reduced Markov::Model.

This has an O(N) Memory complexity. To limit the maximum usage, requests with n>50M are partitioned using Markov::API::ModelMatrix::FastRandomWalkPartition.

If n>50M, threads are going to be synced, files are going to be flushed, and buffers will be reallocated every 50M generations. This comes at a minor performance penalty.

While it has the same functionality, this operation reduces Markov::API::MarkovPasswords::Generate runtime by %96.5

This function has deprecated Markov::API::MarkovPasswords::Generate, and will eventually replace it.

#### **Parameters**


n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn
bFileIO	- If false, filename will be ignored and will output to stdout.

```
Markov::API::ModelMatrix mp;
mp.Import("models/finished.mdl");
mp.FastRandomWalk(50000000,"./wordlist.txt",6,12,25, true);
Definition at line 163 of file modelMatrix.cpp.
00164
00165
00166
           std::ofstream wordlist;
           if(bFileIO)
00167
00168
               wordlist.open(wordlistFileName);
00169
00170
          std::mutex mlock;
           if(n<=50000000ull) return this->FastRandomWalkPartition(&mlock, &wordlist, n, minLen, maxLen,
00171
       bFileIO, threads);
00172
          else{
00173
              int numberOfPartitions = n/50000000ull;
00174
               for(int i=0;i<numberOfPartitions;i++)</pre>
00175
                   this->FastRandomWalkPartition(&mlock, &wordlist, 50000000ull, minLen, maxLen, bFileIO,
       threads);
00176
00177
00178
00179 }
```

References FastRandomWalkPartition().

Referenced by main().

Here is the call graph for this function:



Here is the caller graph for this function:



## 8.16.3.8 FastRandomWalkPartition()

```
void Markov::API::ModelMatrix::FastRandomWalkPartition (
    std::mutex * mlock,
    std::ofstream * wordlist,
    unsigned long int n,
    int minLen,
    int maxLen,
    bool bFileIO,
    int threads ) [protected]
```

A single partition of FastRandomWalk event.

Since FastRandomWalk has to allocate its output buffer before operation starts and writes data in chunks, large n parameters would lead to huge memory allocations. **Without Partitioning:** 

- 50M results 12 characters max -> 550 Mb Memory allocation
- 5B results 12 characters max -> 55 Gb Memory allocation

50B results 12 characters max -> 550GB Memory allocation

Instead, FastRandomWalk is partitioned per 50M generations to limit the top memory need.

#### **Parameters**

mlock	- mutex lock to distribute to child threads
wordlist	- Reference to the wordlist file to write to
n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn
bFileIO	- If false, filename will be ignored and will output to stdout.


Definition at line 182 of file modelMatrix.cpp.

```
00183
00184
          int iterationsPerThread = n/threads;
00185
          int iterationsPerThreadCarryOver = n%threads;
00186
00187
          std::vector<std::thread*> threadsV;
00188
          int id = 0;
for(int i=0;i<threads;i++){</pre>
00189
00190
00191
              threadsV.push_back(new std::thread(&Markov::API::ModelMatrix::FastRandomWalkThread, this,
       mlock, wordlist, iterationsPerThread, minLen, maxLen, id, bFileIO));
00192
              id++;
00193
00194
          threadsV.push_back(new std::thread(&Markov::API::ModelMatrix::FastRandomWalkThread, this, mlock,
00195
       wordlist, iterationsPerThreadCarryOver, minLen, maxLen, id, bFileIO));
00196
00197
          for(int i=0;i<threads;i++){</pre>
00198
              threadsV[i]->join();
00199
00200 }
```

References FastRandomWalkThread().

Referenced by FastRandomWalk().

Here is the call graph for this function:



Here is the caller graph for this function:



### 8.16.3.9 FastRandomWalkThread()

```
std::ofstream * wordlist,
unsigned long int n,
int minLen,
int maxLen,
int id,
bool bFileIO ) [protected]
```

A single thread of a single partition of FastRandomWalk.

A FastRandomWalkPartition will initiate as many of this function as requested.

This function contains the bulk of the generation algorithm.

#### **Parameters**


mlock	- mutex lock to distribute to child threads
wordlist	- Reference to the wordlist file to write to
n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
id	- DEPRECATED Thread id - No longer used
bFileIO	- If false, filename will be ignored and will output to stdout.

Definition at line 112 of file modelMatrix.cpp.

```
00112
00113
          if(n==0) return;
00114
00115
          Markov::Random::Marsaglia MarsagliaRandomEngine;
00116
          char* e;
          char *res = new char[maxLen*n];
00117
00118
          int index = 0;
00119
          char next;
00120
          int len=0;
00121
          long int selection;
00122
          char cur;
          long int bufferctr = 0;
00123
          for (int i = 0; i < n; i++) {
00124
00125
              cur=199;
00126
              len=0;
00127
              while (true) {
00128
                   e = strchr(this->matrixIndex, cur);
                  index = e - this->matrixIndex;
selection = MarsagliaRandomEngine.random() % this->totalEdgeWeights[index];
00129
00130
                   for(int j=0;j<this->matrixSize;j++){
00131
00132
                       selection -= this->valueMatrix[index][j];
00133
                       if (selection < 0){</pre>
00134
                           next = this->edgeMatrix[index][j];
00135
                           break:
00136
                       }
00137
                   }
00138
00139
                   if (len >= maxLen) break;
                  else if ((next < 0) && (len < minLen)) continue;
else if (next < 0) break;</pre>
00140
00141
00142
                   cur = next;
00143
                  res[bufferctr + len++] = cur;
00144
00145
               res[bufferctr + len++] = ' \ n';
00146
              bufferctr+=len;
00147
00148
00149
          if(bFileIO) {
              mlock->lock();
00150
00151
               *wordlist « res;
00152
               mlock->unlock();
00153
          }else{
              mlock->lock();
00154
00155
              std::cout « res;
00156
              mlock->unlock();
00157
00158
          delete res;
00159
00160 }
```

References edgeMatrix, matrixIndex, matrixSize, Markov::Random::Marsaglia::random(), totalEdgeWeights, and valueMatrix.

Referenced by FastRandomWalkPartition(). Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.16.3.10 Generate()

```
void Markov::API::MarkovPasswords::Generate (
    unsigned long int n,
    const char * wordlistFileName,
    int minLen = 6,
    int maxLen = 12,
    int threads = 20 ) [inherited]
```

Call Markov::Model::RandomWalk n times, and collect output.

Generate from model and write results to a file. a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

**Deprecated** See Markov::API::MatrixModel::FastRandomWalk for more information.

### **Parameters**

n	- Number of passwords to generate.
wordlistFileName	- Filename to write to
minLen	- Minimum password length to generate
maxLen	- Maximum password length to generate
threads	- number of OS threads to spawn

Definition at line 110 of file markovPasswords.cpp.

```
00110
00111
           char* res;
00112
           char print[100];
00113
           std::ofstream wordlist;
00114
           wordlist.open(wordlistFileName);
00115
           std::mutex mlock;
          int iterationsPerThread = n/threads;
int iterationsCarryOver = n%threads;
00116
00117
00118
           std::vector<std::thread*> threadsV;
00119
           for(int i=0;i<threads;i++){</pre>
00120
               threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::GenerateThread, this,
       &mlock, iterationsPerThread, &wordlist, minLen, maxLen));
00121
           }
00122
00123
           for(int i=0;i<threads;i++){</pre>
00124
               threadsV[i]->join();
```

```
00125          delete threadsV[i];
00126    }
00127
00128    this->GenerateThread(&mlock, iterationsCarryOver, &wordlist, minLen, maxLen);
00129
00130 }
```

References Markov::API::MarkovPasswords::GenerateThread().

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.16.3.11 GenerateThread()

```
void Markov::API::MarkovPasswords::GenerateThread (
    std::mutex * outputLock,
    unsigned long int n,
    std::ofstream * wordlist,
    int minLen,
    int maxLen ) [private], [inherited]
```

A single thread invoked by the Generate function.

**DEPRECATED:** See Markov::API::MatrixModel::FastRandomWalkThread for more information. This has been replaced with a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5 on average.

### **Parameters**

outputLock	- shared mutex lock to lock during output operation. Prevents race condition on write.	
n	number of lines to be generated by this thread	
wordlist	wordlistfile	
minLen	- Minimum password length to generate	
maxLen	- Maximum password length to generate	

Definition at line 132 of file markovPasswords.cpp.

```
00133
           char* res = new char[maxLen+5];
00134
           if(n==0) return;
00135
00136
           Markov::Random::Marsaglia MarsagliaRandomEngine;
00137
           for (int i = 0; i < n; i++) {</pre>
               this->RandomWalk(&MarsagliaRandomEngine, minLen, maxLen, res);
00138
00139
               outputLock->lock();
*wordlist « res « "\n";
00140
00141
               outputLock->unlock();
00142
```

```
00143 }
```

References Markov::Model < NodeStorageType >::RandomWalk().

Referenced by Markov::API::MarkovPasswords::Generate().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.16.3.12 Import() [1/2]

Open a file to import with filename, and call bool Model::Import with std::ifstream.

## Returns

True if successful, False for incomplete models or corrupt file formats

## Example Use: Import a file with filename

```
Markov::Model<char> model;
model.Import("test.mdl");

Definition at line 266 of file model.h.

00266
00267 std::ifstream importfile;
00268 importfile.open(filename);
00269 return this->Import(&importfile);
00270
00271 }
```

## 8.16.3.13 Import() [2/2]

Import a file to construct the model.

File contains a list of edges. For more info on the file format, check out the wiki and github readme pages. Format is: Left\_repr;EdgeWeight;right\_repr

{

Iterate over this list, and construct nodes and edges accordingly.

#### Returns

True if successful, False for incomplete models or corrupt file formats

#### Example Use: Import a file from ifstream

```
Markov::Model<char> model;
std::ifstream file("test.mdl");
model.Import(&file);
Definition at line 207 of file model.h.
00207
```

```
00208
                    std::string cell;
00209
00210
                    char src;
00211
                    char target;
00212
                    long int oc;
00213
00214
                    while (std::getline(*f, cell)) {
00215
                             //std::cout « "cell: " « cell « std::endl;
00216
                             src = cell[0];
00217
                             target = cell[cell.length() - 1];
00218
                             char* j;
00219
                             oc = std::strtol(cell.substr(2, cell.length() - 2).c_str(),&j,10);
                             //std::cout « oc « "\n";
Markov::Node<NodeStorageType>* srcN;
00220
00221
00222
                             Markov::Node<NodeStorageType>* targetN;
00223
                             Markov::Edge<NodeStorageType>* e;
00224
                             if (this->nodes.find(src) == this->nodes.end()) {
                                     tchis >nodes.irind();
srcN = new Markov::Node<NodeStorageType>(src);
this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(src, srcN));
00225
00226
00227
                                     //std::cout « "Creating new node at start.\n";
00228
00229
                             else {
                                     srcN = this->nodes.find(src)->second;
00230
00231
                             }
00232
00233
                             if (this->nodes.find(target) == this->nodes.end()) {
                                      targetN = new Markov::Node<NodeStorageType>(target);
00234
00235
                                     this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(target, targetN));
00236
                                     //std::cout « "Creating new node at end.\n";
00237
00238
                             else (
00239
                                     targetN = this->nodes.find(target)->second;
00240
00241
                             e = srcN->Link(targetN);
00242
                             e->AdjustEdge(oc);
00243
                             this->edges.push_back(e);
00244
00245
                             //std::cout « int(srcN->NodeValue()) « " --" « e->EdgeWeight() « "--> " «
             int(targetN->NodeValue()) « "\n";
00246
00247
00248
                    }
00249
00250
                     //std::cout « "Total edges in EdgesV: " « x.second->edgesV.size() « "\n";
00251
00252
                             \verb|std::sort| (x.second->edgesV.begin(), x.second->edgesV.end(), [] (Edge<NodeStorageType> *lhs, and the state of the sta
              Edge<NodeStorageType> *rhs)->bool{
00253
                                     return lhs->EdgeWeight() > rhs->EdgeWeight();
00254
                             });
00255
                             //for(int i=0;i<x.second->edgesV.size();i++)
                             /// std::cout « x.second->edgesV[i]->EdgeWeight() « ", ";
//std::cout « "\n";
00256
00257
00258
                    //std::cout « "Total number of nodes: " « this->nodes.size() « std::endl; //std::cout « "Total number of edges: " « this->edges.size() « std::endl;
00259
00260
00261
00262
                     return true:
00263 }
```

## 8.16.3.14 Nodes()

std::map<char , Node<char >\*>\* Markov::Model< char >::Nodes ( ) [inline], [inherited]
Return starter Node.

Returns

starter node with 00 NodeValue

Definition at line 177 of file model.h. 00177 { return &nodes; }

### 8.16.3.15 OpenDatasetFile()

Open dataset file and return the ifstream pointer.

#### **Parameters**

```
filename - Filename to open
```

#### Returns

ifstream\* to the the dataset file

Definition at line 43 of file markovPasswords.cpp.

```
00043
00044
00045
          std::ifstream* datasetFile;
00046
00047
          std::ifstream newFile(filename);
00048
00049
          datasetFile = &newFile;
00050
          this->Import (datasetFile);
00051
00052
          return datasetFile;
00053 }
```

References Markov::Model < NodeStorageType >::Import().

Here is the call graph for this function:



### 8.16.3.16 RandomWalk()

Do a random walk on this model.

Start from the starter node, on each node, invoke RandomNext using the random engine on current node, until terminator node is reached. If terminator node is reached before minimum length criateria is reached, ignore the last selection and re-invoke randomNext

If maximum length criteria is reached but final node is not, cut off the generation and proceed to the final node. This function takes Markov::Random::RandomEngine as a parameter to generate pseudo random numbers from

This library is shipped with two random engines, Marsaglia and Mersenne. While mersenne output is higher in entropy, most use cases don't really need super high entropy output, so Markov::Random::Marsaglia is preferable for better performance.

This function WILL NOT reallocate buffer. Make sure no out of bound writes are happening via maximum length criteria.

Example Use: Generate 10 lines, with 5 to 10 characters, and print the output. Use Marsaglia

```
Markov::Model<char> model;
Model.import("model.mdl");
char* res = new char[11];
Markov::Random::Marsaglia MarsagliaRandomEngine;
for (int i = 0; i < 10; i++) {
    this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
    std::cout « res « "\n";
}
```

#### **Parameters**

randomEngine	Random Engine to use for the random walks. For examples, see Markov::Random::Mersenne and Markov::Random::Marsaglia
minSetting	Minimum number of characters to generate
maxSetting	Maximum number of character to generate
buffer	buffer to write the result to

#### Returns

Null terminated string that was generated.

Definition at line 293 of file model.h.

```
00293
00294
           Markov::Node<NodeStorageType>* n = this->starterNode;
00295
           int len = 0;
           Markov::Node<NodeStorageType>* temp_node;
00296
00297
           while (true) {
              temp_node = n->RandomNext(randomEngine);
if (len >= maxSetting) {
00298
00299
00300
00301
               else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00302
00303
                   continue;
00304
00305
00306
               else if (temp_node == NULL) {
00307
                   break;
00308
00309
00310
               n = temp_node;
00311
00312
               buffer[len++] = n->NodeValue();
00313
00314
00315
           // \\ \\ \text{null terminate the string}
00316
          buffer[len] = 0x00;
00317
00318
           //do something with the generated string
00319
           return buffer; //for now
00320 }
```

#### 8.16.3.17 Save()

Export model to file.

#### **Parameters**

filename	- Export filename.
----------	--------------------

### Returns

std::ofstream\* of the exported file.

## Definition at line 98 of file markovPasswords.cpp.

```
00098
00099    std::ofstream* exportFile;
00100
00101    std::ofstream newFile(filename);
00102
00103    exportFile = &newFile;
00104
00105    this->Export(exportFile);
00106    return exportFile;
00107 }
```

References Markov::Model < NodeStorageType >::Export().

Here is the call graph for this function:



## 8.16.3.18 StarterNode()

```
Node<char >* Markov::Model< char >::StarterNode ( ) [inline], [inherited]
Return starter Node.
```

#### Returns

starter node with 00 NodeValue

```
Definition at line 167 of file model.h. 00167 { return starterNode; }
```

## 8.16.3.19 Train()

Train the model with the dataset file.

Markov::API::MarkovPasswords mp;

## **Parameters**


datasetFileName	- Ifstream* to the dataset. If null, use class member
delimiter	- a character, same as the delimiter in dataset content
threads	- number of OS threads to spawn

```
mp.Import("models/2gram.mdl");
mp.Train("password.corpus");
Definition at line 57 of file markovPasswords.cpp.
00057
00058
        signal(SIGINT, intHandler);
00059
          Markov::API::Concurrency::ThreadSharedListHandler listhandler(datasetFileName);
00060
           auto start = std::chrono::high_resolution_clock::now();
00061
00062
           std::vector<std::thread*> threadsV;
         for(int i=0;i<threads;i++) {</pre>
00063
               threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::TrainThread, this,
00064
       &listhandler, delimiter));
00065
          }
00066
           for(int i=0;i<threads;i++) {
    threadsV[i]->join();
00067
00068
00069
               delete threadsV[i];
00070
00071
           auto finish = std::chrono::high_resolution_clock::now();
           std::chrono::duration<double> elapsed = finish - start;
std::cout « "Elapsed time: " « elapsed.count() « " s\n";
00072
00073
00074
00075 }
```

References intHandler(), Markov::API::Concurrency::ThreadSharedListHandler::ThreadSharedListHandler(), and Markov::API::MarkovPasswords::TrainThread().

Referenced by Markov::Markopy::BOOST\_PYTHON\_MODULE().

Here is the call graph for this function:



Here is the caller graph for this function:



### 8.16.3.20 TrainThread()

A single thread invoked by the Train function.

#### **Parameters**


listhandler	- Listhandler class to read corpus from
delimiter	- a character, same as the delimiter in dataset content

Definition at line 77 of file markovPasswords.cpp.

```
00078
          char format_str[] ="%ld,%s";
00079
         format_str[2]=delimiter;
08000
          std::string line;
00081
          while (listhandler->next(&line) && keepRunning) {
00082
00083
              if (line.size() > 100) {
00084
                  line = line.substr(0, 100);
00085
00086
              char* linebuf = new char[line.length()+5];
      sscanf_s(line.c_str(), "%ld,%s", &oc, linebuf, line.length()+5); //<== changed format_str to->
"%ld,%s"
00087 #ifdef _WIN32
00088
00089 #else
00090
              sscanf(line.c_str(), format_str, &oc, linebuf);
00091 #endif
00092
              this->AdjustEdge((const char*)linebuf, oc);
00093
00094
00095 }
```

References Markov::Model < NodeStorageType >::AdjustEdge(), keepRunning, and Markov::API::Concurrency::ThreadSharedListHarReferenced by Markov::API::MarkovPasswords::Train().

Here is the call graph for this function:



Here is the caller graph for this function:



#### 8.16.4 Member Data Documentation

#### 8.16.4.1 datasetFile

std::ifstream\* Markov::API::MarkovPasswords::datasetFile [private], [inherited] Definition at line 106 of file markovPasswords.h.

### 8.16.4.2 edgeMatrix

char\*\* Markov::API::ModelMatrix::edgeMatrix [protected]

2-D Character array for the edge Matrix (The characters of Nodes)

Definition at line 116 of file modelMatrix.h.

Referenced by ConstructMatrix(), DumpJSON(), and FastRandomWalkThread().

#### 8.16.4.3 edges

std::vector<Edge<char >\*> Markov::Model< char >::edges [private], [inherited]
A list of all edges in this model.

Definition at line 195 of file model.h.

## 8.16.4.4 matrixIndex

char\* Markov::API::ModelMatrix::matrixIndex [protected]

to hold the Matrix index (To hold the orders of 2-D arrays')

Definition at line 131 of file modelMatrix.h.

Referenced by ConstructMatrix(), DumpJSON(), and FastRandomWalkThread().

#### 8.16.4.5 matrixSize

int Markov::API::ModelMatrix::matrixSize [protected]

to hold Matrix size

Definition at line 126 of file modelMatrix.h.

Referenced by ConstructMatrix(), DumpJSON(), and FastRandomWalkThread().

#### 8.16.4.6 modelSavefile

std::ofstream\* Markov::API::MarkovPasswords::modelSavefile [private], [inherited]
Dataset file input of our system

Definition at line 107 of file markovPasswords.h.

#### 8.16.4.7 nodes

std::map<char , Node<char >\*> Markov::Model< char >::nodes [private], [inherited]
Map LeftNode is the Nodes NodeValue Map RightNode is the node pointer.
Definition at line 184 of file model.h.

#### 8.16.4.8 outputFile

std::ofstream\* Markov::API::MarkovPasswords::outputFile [private], [inherited]
File to save model of our system

Definition at line 108 of file markovPasswords.h.

#### 8.16.4.9 starterNode

Node<char >\* Markov::Model< char >::starterNode [private], [inherited]
Starter Node of this model.
Definition at line 189 of file model.h.

## 8.16.4.10 totalEdgeWeights

long int\* Markov::API::ModelMatrix::totalEdgeWeights [protected]
Array of the Total Edge Weights.
Definition at line 136 of file modelMatrix.h.
Referenced by ConstructMatrix(), and FastRandomWalkThread().

#### 8.16.4.11 valueMatrix

long int\*\* Markov::API::ModelMatrix::valueMatrix [protected]
2-d Integer array for the value Matrix (For the weights of Edges)
Definition at line 121 of file modelMatrix.h.
Referenced by ConstructMatrix(), DumpJSON(), and FastRandomWalkThread().
The documentation for this class was generated from the following files:

- · modelMatrix.h
- · modelMatrix.cpp


# 8.17 Markov::Node < storageType > Class Template Reference

A node class that for the vertices of model. Connected with eachother using Edge. #include <model.h>

Inheritance diagram for Markov::Node < storageType >:

#### Markov::Node < storageType > + edgesV \_value - total\_edge\_weights - edges + Node() + Node() + Link() + Link() + RandomNext() + UpdateEdges() + FindEdge() + FindEdge() + NodeValue() + UpdateTotalVerticeWeight() + Edges() + TotalEdgeWeights() < char > < NodeStorageType > Markov::Node < NodeStorage Markov::Node < char > Type > + edgesV + edgesV value value - total\_edge\_weights - total\_edge\_weights - edges - edges + Node() + Node() + Node() + Node() + Link() + Link() + Link() + Link() + RandomNext() + RandomNext() + UpdateEdges() + UpdateEdges() + FindEdge() + FindEdge() + FindEdge() + FindEdge() + NodeValue() + NodeValue() + UpdateTotalVerticeWeight() + UpdateTotalVerticeWeight() + Edges() + Edges() + TotalEdgeWeights() + TotalEdgeWeights()

Collaboration diagram for Markov::Node < storageType >:



### **Public Member Functions**

• Node ()

Default constructor. Creates an empty Node.

Node (storageType \_value)

Constructor. Creates a Node with no edges and with given NodeValue.

• Edge< storageType > \* Link (Node< storageType > \*)

Link this node with another, with this node as its source.

Edge< storageType > \* Link (Edge< storageType > \*)

Link this node with another, with this node as its source.

Node< storageType > \* RandomNext (Markov::Random::RandomEngine \*randomEngine)

Chose a random node from the list of edges, with regards to its EdgeWeight, and TraverseNode to that.

bool UpdateEdges (Edge < storageType > \*)

Insert a new edge to the this.edges.

Edge< storageType > \* FindEdge (storageType repr)

Find an edge with its character representation.

Edge< storageType > \* FindEdge (Node< storageType > \*target)

Find an edge with its pointer. Avoid unless neccessary because comptutational cost of find by character is cheaper (because of std::map)

unsigned char NodeValue ()

Return character representation of this node.

void UpdateTotalVerticeWeight (long int offset)

Change total weights with offset.

• std::map< storageType, Edge< storageType > \* > \* Edges ()

return edges

· long int TotalEdgeWeights ()

return total edge weights

#### **Public Attributes**

std::vector< Edge< storageType > \* > edgesV

#### **Private Attributes**

• storageType \_value

Character representation of this node. 0 for starter, 0xff for terminator.

· long int total\_edge\_weights

Total weights of the vertices, required by RandomNext.

• std::map< storageType, Edge< storageType > \* > edges

A map of all edges connected to this node, where this node is at the LeftNode. Map is indexed by unsigned char, which is the character representation of the node.

## 8.17.1 Detailed Description

```
template<typename storageType> class Markov::Node< storageType >
```

A node class that for the vertices of model. Connected with eachother using Edge.

This class will later be templated to accept other data types than char\*.

Definition at line 23 of file model.h.

#### 8.17.2 Constructor & Destructor Documentation

#### 8.17.2.1 Node() [1/2]

## 8.17.2.2 Node() [2/2]

Constructor. Creates a Node with no edges and with given NodeValue.

#### **Parameters**

_value	- Nodes character representation.
--------	-----------------------------------

#### **Example Use:** Construct nodes

## 8.17.3 Member Function Documentation

#### 8.17.3.1 Edges()

#### 8.17.3.2 FindEdge() [1/2]

```
template<typename storageType >
Edge<storageType>* Markov::Node< storageType >::FindEdge (
          Node< storageType > * target )
```

Find an edge with its pointer. Avoid unless neccessary because comptutational cost of find by character is cheaper (because of std::map)

#### **Parameters**

```
target - target node.
```

#### Returns

Edge that is connected between this node, and the target node.

## 8.17.3.3 FindEdge() [2/2]

Find an edge with its character representation.

#### **Parameters**

```
repr - character NodeValue of the target node.
```

#### Returns

Edge that is connected between this node, and the target node.

#### Example Use: Construct and update edges

#### 8.17.3.4 Link() [1/2]

Link this node with another, with this node as its source.

DOES NOT create a new Edge.

#### **Parameters**

```
Edge - Edge that will accept this node as its LeftNode.
```

#### Returns

the same edge as parameter target.

#### **Example Use:** Construct and link nodes

```
Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
Markov::Edge<unsigned char>* e = LeftNode->Link(RightNode);
LeftNode->Link(e);
```

## Definition at line 219 of file node.h.

```
00220 v->SetLeftEdge(this);
00221 this->UpdateEdges(v);
00222 return v;
00223 }
```

#### 8.17.3.5 Link() [2/2]

Link this node with another, with this node as its source.

Creates a new Edge.

#### **Parameters**

```
target - Target node which will be the RightNode() of new edge.
```

#### **Returns**

A new node with LeftNode as this, and RightNode as parameter target.

#### Example Use: Construct nodes

```
Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
```

#### 8.17.3.6 NodeValue()

```
template<typename storageType >
unsigned char Markov::Node< storageType >::NodeValue [inline]
Return character representation of this node.
```

#### Returns

character representation at \_value.

```
Definition at line 207 of file node.h.

00207

00208     return _value;

00209 }
```

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



## 8.17.3.7 RandomNext()

Chose a random node from the list of edges, with regards to its EdgeWeight, and TraverseNode to that.

This operation is done by generating a random number in range of 0-this.total\_edge\_weights, and then iterating over the list of edges. At each step, EdgeWeight of the edge is subtracted from the random number, and once it is 0, next node is selected.

#### Returns

Node that was chosen at EdgeWeight biased random.

#### **Example Use:** Use randomNext to do a random walk on the model

```
char* buffer[64];
Markov::Model<char> model;
model.Import("model.mdl");
    Markov::Node<char>* n = model.starterNode;
int len = 0;
Markov::Node<char>* temp_node;
while (true) {
    temp_node = n->RandomNext(randomEngine);
    if (len >= maxSetting) {
        break;
    }
    else if ((temp_node == NULL) && (len < minSetting)) {
        continue;
    }
    else if (temp_node == NULL) {
        break;
}</pre>
```

```
n = temp_node;
   buffer[len++] = n->NodeValue();
Definition at line 226 of file node.h.
00226
00227
          //get a random NodeValue in range of total_vertice_weight
long int selection = randomEngine->random() %
00228
00229
       this->total_edge_weights;//distribution() (generator());// distribution(generator);
00230
          //make absolute, no negative modulus values wanted
00231
           //selection = (selection >= 0) ? selection : (selection + this->total_edge_weights);
           for(int i=0;i<this->edgesV.size();i++){
00232
00233
               selection -= this->edgesV[i]->EdgeWeight();
00234
               if (selection < 0) return this->edgesV[i]->TraverseNode();
00235
00236
00237
           //if this assertion is reached, it means there is an implementation error above
00238
          std::cout « "This should never be reached (node failed to walk to next) \n"; //cant assert from
       child thread
00239
          assert(true && "This should never be reached (node failed to walk to next)");
00240
          return NULL:
00241 }
```

#### 8.17.3.8 TotalEdgeWeights()

Referenced by Markov::API::ModelMatrix::ConstructMatrix().

Here is the caller graph for this function:



#### 8.17.3.9 UpdateEdges()

#### Parameters

```
edge - New edge that will be inserted.
```

#### Returns

true if insertion was successful, false if it fails.

### Example Use: Construct and update edges

```
Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target2);
e1->AdjustEdge(25);
src->UpdateEdges(e1);
```

#### 8.17.3.10 UpdateTotalVerticeWeight()

Change total weights with offset.

#### **Parameters**

offset	to adjust the vertice weight with
onsei	to adjust the vertice weight with

#### Definition at line 259 of file node.h.

```
00259
00260     this->total_edge_weights += offset;
00261 }
```

#### 8.17.4 Member Data Documentation

#### 8.17.4.1 \_value

```
template<typename storageType >
storageType Markov::Node< storageType >::_value [private]
Character representation of this node. 0 for starter, 0xff for terminator.
```

Definition at line 171 of file node.h.

Referenced by Markov::Node < NodeStorageType >::NodeValue().

#### 8.17.4.2 edges

```
template<typename storageType >
std::map<storageType, Edge<storageType>*> Markov::Node< storageType >::edges [private]
```

A map of all edges connected to this node, where this node is at the LeftNode. Map is indexed by unsigned char, which is the character representation of the node.

Definition at line 182 of file node.h.

#### 8.17.4.3 edgesV

```
template<typename storageType >
std::vector<Edge<storageType>*> Markov::Node< storageType >::edgesV
Definition at line 165 of file node.h.
```

#### 8.17.4.4 total\_edge\_weights

```
template<typename storageType >
long int Markov::Node< storageType >::total_edge_weights [private]
Total weights of the vertices, required by RandomNext.
Definition at line 176 of file node.h.
```

The documentation for this class was generated from the following files:


- · model.h
- · node.h

## 8.18 Markov::Random::RandomEngine Class Reference


An abstract class for Random Engine.

#include <random.h>

Inheritance diagram for Markov::Random::RandomEngine:



Collaboration diagram for Markov::Random::RandomEngine:



#### **Public Member Functions**

virtual unsigned long random ()=0

#### 8.18.1 Detailed Description

An abstract class for Random Engine.

This class is used for generating random numbers, which are used for random walking on the graph.

Main reason behind allowing different random engines is that some use cases may favor performance, while some favor good random.

Mersenne can be used for truer random, while Marsaglia can be used for deterministic but fast random. Definition at line 21 of file random.h.


#### 8.18.2 Member Function Documentation

## 8.18.2.1 random()

virtual unsigned long Markov::Random::RandomEngine::random ( ) [inline], [pure virtual] Implemented in Markov::Random::Marsaglia, and Markov::Random::DefaultRandomEngine.

Referenced by Markov::Node < NodeStorageType >::RandomNext().

Here is the caller graph for this function:




The documentation for this class was generated from the following file:

· random.h

## 8.19 Markov::API::CLI::Terminal Class Reference

pretty colors for Terminal. Windows Only.
#include <term.h>

Collaboration diagram for Markov::API::CLI::Terminal:



## **Public Types**

enum color {
 RESET, BLACK, RED, GREEN,
 YELLOW, BLUE, MAGENTA, CYAN,
 WHITE, LIGHTGRAY, DARKGRAY, BROWN }

## **Public Member Functions**

• Terminal ()

## **Static Public Attributes**

- static std::map< Markov::API::CLI::Terminal::color, int > colormap
- · static std::ostream endl

## 8.19.1 Detailed Description

pretty colors for Terminal. Windows Only. Definition at line 18 of file term.h.

## 8.19.2 Member Enumeration Documentation

## 8.19.2.1 color

```
enum Markov::API::CLI::Terminal::color
```

#### Enumerator

```
Definition at line 26 of file term.h.
00026 { RESET, BLACK, RED, GREEN, YELLOW, BLUE, MAGENTA, CYAN, WHITE, LIGHTGRAY, DARKGRAY, BROWN };
```

### 8.19.3 Constructor & Destructor Documentation

### 8.19.3.1 Terminal()

```
Terminal::Terminal ( )

Default constructor. Get references to stdout and stderr handles.

Definition at line 56 of file term.cpp.

00056

00057 /*this->;*/
00058 }
```

#### 8.19.4 Member Data Documentation

#### 8.19.4.1 colormap

#### 8.19.4.2 endl


```
std::ostream Markov::API::CLI::Terminal::endl [static]
Definition at line 37 of file term.h.
```

The documentation for this class was generated from the following files:

- · term.h
- · term.cpp

# 8.20 Markov::API::Concurrency::ThreadSharedListHandler Class Reference

Simple class for managing shared access to file. #include <threadSharedListHandler.h>  $Collaboration\ diagram\ for\ Markov:: API:: Concurrency:: Thread Shared List Handler:$ 



## **Public Member Functions**

• ThreadSharedListHandler (const char \*filename)

Construct the Thread Handler with a filename.

• bool next (std::string \*line)

Read the next line from the file.

#### **Private Attributes**

- std::ifstream listfile
- std::mutex mlock

#### 8.20.1 Detailed Description

Simple class for managing shared access to file.

This class maintains the handover of each line from a file to multiple threads.

When two different threads try to read from the same file while reading a line isn't completed, it can have unexpected results. Line might be split, or might be read twice. This class locks the read action on the list until a line is completed, and then proceeds with the handover.

Definition at line 18 of file threadSharedListHandler.h.

#### 8.20.2 Constructor & Destructor Documentation

#### 8.20.2.1 ThreadSharedListHandler()

Construct the Thread Handler with a filename.

Simply open the file, and initialize the locks.

```
Example Use: Simple file read
```

```
ThreadSharedListHandler listhandler("test.txt");
std::string line;
std::cout « listhandler->next(&line) « "\n";
```

```
Example Use: Example use case from MarkovPasswords showing multithreaded access void MarkovPasswords::Train(const char* datasetFileName, char delimiter, int threads)
```

```
ThreadSharedListHandler listhandler(datasetFileName);
    auto start = std::chrono::high_resolution_clock::now();
    std::vector<std::thread*> threadsV;
    for(int i=0;i<threads;i++){</pre>
       threadsV.push_back(new std::thread(&MarkovPasswords::TrainThread, this, &listhandler,
     datasetFileName, delimiter));
  for(int i=0;i<threads;i++) {</pre>
       threadsV[i]->join();
       delete threadsV[i];
   auto finish = std::chrono::high_resolution_clock::now();
   std::chrono::duration<double> elapsed = finish - start;
    std::cout « "Elapsed time: " « elapsed.count() « " s\n";
void MarkovPasswords::TrainThread(ThreadSharedListHandler *listhandler, const char* datasetFileName, char
     delimiter) {
    char format_str[] ="%ld,%s";
    format_str[2]=delimiter;
    std::string line;
    while (listhandler->next(&line)) {
       long int oc;
       if (line.size() > 100) {
            line = line.substr(0, 100);
       char* linebuf = new char[line.length()+5];
       sscanf_s(line.c_str(), format_str, &oc, linebuf, line.length()+5);
       this->AdjustEdge((const char*)linebuf, oc);
       delete linebuf;
}
```

#### **Parameters**

*filename* Filename for the file to manage.

Definition at line 4 of file threadSharedListHandler.cpp.

```
00004
00005 this->listfile;
00006 this->listfile.open(filename, std::ios_base::binary);
00007 }
```

References listfile.

Referenced by Markov::API::MarkovPasswords::Train().

Here is the caller graph for this function:



#### 8.20.3 Member Function Documentation

#### 8.20.3.1 next()

Read the next line from the file.

This action will be blocked until another thread (if any) completes the read operation on the file.

#### Example Use: Simple file read

```
ThreadSharedListHandler listhandler("test.txt");
std::string line;
std::cout « listhandler->next(&line) « "\n";

Definition at line 10 of file threadSharedListHandler.cpp.
00010
00011 bool res = false;
00012 this->mlock.lock();
00013 res = (std::getline(this->listfile,*line,'\n'))? true : false;
00014 this->mlock.unlock();
00015
00016 return res;
00017 }
```

References listfile, and mlock.

Referenced by Markov::API::MarkovPasswords::TrainThread().

Here is the caller graph for this function:



### 8.20.4 Member Data Documentation

#### 8.20.4.1 listfile

```
std::ifstream Markov::API::Concurrency::ThreadSharedListHandler::listfile [private]

Definition at line 88 of file threadSharedListHandler.h.

Referenced by next(), and ThreadSharedListHandler().
```

### 8.20.4.2 mlock

 $\verb|std::mutex Markov::API::Concurrency::ThreadSharedListHandler::mlock [private]| \\ \textbf{Definition at line 89 of file threadSharedListHandler.h.} \\$ 

Referenced by next().

The documentation for this class was generated from the following files:


- · threadSharedListHandler.h
- threadSharedListHandler.cpp

## 8.21 Markov::GUI::Train Class Reference


QT Training page class.

#include <Train.h>

Inheritance diagram for Markov::GUI::Train:



Collaboration diagram for Markov::GUI::Train:



## **Public Slots**

- void home ()
- void train ()

#### **Public Member Functions**

• Train (QWidget \*parent=Q\_NULLPTR)

#### **Private Attributes**

• Ui::Train ui

## 8.21.1 Detailed Description

QT Training page class.

Definition at line 9 of file Train.h.

#### 8.21.2 Constructor & Destructor Documentation

## 8.21.2.1 Train()

#### 8.21.3 Member Function Documentation

#### 8.21.3.1 home

```
void Markov::GUI::Train::home ( ) [slot]
```

### 8.21.3.2 train

```
void Markov::GUI::Train::train ( ) [slot]
```

## 8.21.4 Member Data Documentation

#### 8.21.4.1 ui

```
Ui::Train Markov::GUI::Train::ui [private]

Definition at line 15 of file Train.h.
```

The documentation for this class was generated from the following file:


• Train.h

## **Chapter 9**

## **File Documentation**

## 9.1 about.h File Reference

```
#include <QtWidgets/QMainWindow>
#include "ui_about.h"
#include <ui_menu.h>
Include dependency graph for about.h:
```



## Classes

class Markov::GUI::about
 QT Class for about page.

#### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::GUI

namespace for MarkovPasswords API GUI wrapper


## 9.2 about.h

```
00001 #pragma once
00002 #include <QtWidgets/QMainWindow>
00003 #include "ui_about.h"
00004 #include <ui_menu.h>
00005
00006 /** @brief namespace for MarkovPasswords API GUI wrapper
00007 */
00008 namespace Markov::GUI{
00009
00010 /** @brief QT Class for about page
00011 */
00012 class about :public QMainWindow {
```

```
00013
          Q_OBJECT
00014
         public:
              about(QWidget* parent = Q_NULLPTR);
00015
00016
00017
         private:
00018
             Ui:: main ui:
00019
00020
00021
         };
00022 };
```

## 9.3 argparse.cpp File Reference

```
#include "argparse.h"
#include "color/term.h"
Include dependency graph for argparse.cpp:
```




## 9.4 argparse.cpp

```
00001 #include "argparse.h"
00002 #include "color/term.h"
00003
00004 Markov::API::CLI::ProgramOptions* Markov::API::CLI::Argparse::parse(int argc, char** argv) { return 0;
00005
00006
00007
00008 void Markov::API::CLI::Argparse::help() {
00009
          std::cout «
00010
           "Markov Passwords - Help\n"
00011
          "Options:\n"
          " \n"
" -of --outputfilename\n"
00012
00013
                 Filename to output the generation results\n"
00014
              -ef --exportfilename\n"
00015
00016
                  filename to export built model to\n"
              -if --importfilename\n"
00017
00018
                  filename to import model from\n"
00019
             Number of lines to generate\n"
              -n (generate count)\n"
00020
00021
00022
           "Usage: \n"
          " markov.exe -if empty_model.mdl -ef model.mdl\n"
" import empty_model."
00024
                   import empty_model.mdl and train it with data from stdin. When done, output the model to
       model.mdl\n"
00025
             markov.exe -if empty_model.mdl -n 15000 -of wordlist.txt\n"
00026
00027
                   import empty model.mdl and generate 15000 words to wordlist.txt\n"
00028
           « std::endl;
00030 }
```


## 9.5 argparse.h File Reference

#include <string>

#include <iostream>
#include <boost/program\_options.hpp>
Include dependency graph for argparse.h:



This graph shows which files directly or indirectly include this file:



### **Classes**

struct Markov::API::CLI::\_programOptions

Structure to hold parsed cli arguements.

class Markov::API::CLI::Argparse

Parse command line arguements.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::CLI

Structure to hold parsed cli arguements.

#### **Macros**

• #define BOOST\_ALL\_DYN\_LINK 1

## **Typedefs**

• typedef struct Markov::API::CLI::\_programOptions Markov::API::CLI::ProgramOptions Structure to hold parsed cli arguements.

#### 9.5.1 Macro Definition Documentation

## 9.5.1.1 BOOST\_ALL\_DYN\_LINK

#define BOOST\_ALL\_DYN\_LINK 1
Definition at line 4 of file argparse.h.

## 9.6 argparse.h

```
00001 #include<string>
00002 #include<iostream>
00003
00004 #define BOOST ALL DYN LINK 1
00005
00006 #include <boost/program_options.hpp>
00007 /** @brief Structure to hold parsed cli arguements.
00008 */
00009 namespace opt = boost::program_options;
00010
00011 /**
00012
        Obrief Namespace for the CLI objects
00013 */
00014 namespace Markov::API::CLI{
00015
          /** @brief Structure to hold parsed cli arguements. */
00016
00017
          typedef struct _programOptions {
00018
00019
                 Obrief Import flag to validate import
00020
00021
              bool bImport;
00022
00023
00024
                Obrief Export flag to validate export
00025
00026
              bool bExport;
00027
00028
                 Obrief Failure flag to validate successfull running
00029
00030
00031
              bool bFailure;
00032
00033
                @brief Seperator character to use with training data. (character between occurence and
00034
      value)"
00035
00036
              char seperator;
00037
00038
              .   
@brief Import name of our model \star/
00039
00040
00041
              std::string importname;
00042
00043
              .   
    @brief Import name of our given wordlist \star/
00044
00045
00046
              std::string exportname;
00047
00048
              .   
@brief Import name of our given wordlist \star/
00049
00050
00051
              std::string wordlistname;
00052
00053
                @brief Output name of our generated password list
00054
00055
00056
              std::string outputfilename;
00057
00058
00059
                 @brief The name of the given dataset
00060
00061
              std::string datasetname;
00062
```

9.6 argparse.h 191

```
00063
00064
                    @brief Number of passwords to be generated
00065
00066
                int generateN;
00067
00068
           } ProgramOptions:
00069
00070
00071
            /** @brief Parse command line arguements
00072
00073
           class Argparse {
00074
           public:
00075
00076
                Argparse();
00077
00078
                /** @brief Parse command line arguements.
00079
00080
                 * Parses command line arguements to populate ProgramOptions structure.
00081
00082
                 * @param argc Number of command line arguements
00083
                 * @param argv Array of command line parameters
00084
00085
                Argparse(int argc, char** argv) {
00086
00087
                     /*bool bImp;
00088
                    bool bExp;
00089
                    bool bFail;
                     char sprt;
00090
00091
                     std::string imports;
00092
                     std::string exports;
00093
                     std::string outputs;
00094
                     std::string datasets;
00095
                     int generateN;
00096
00097
                     opt::options_description desc("Options");
00098
00099
00100
                     desc.add_options()
00101
                         ("generate", "Generate strings with given parameters")
                          ("train", "Train model with given parameters") ("combine", "Combine")
00102
00103
                         ("import", opt::value<std::string>(), "Import model file")
("output", opt::value<std::string>(), "Output model file. This model will be exported
00104
00105
        when done. Will be ignored for generation mode")
00106
                         ("dataset", opt::value<std::string>(), "Dataset file to read input from training. Will
        be ignored for generation mode")
00107
                          ("seperator", opt::value<char>(), "Seperator character to use with training data.
        (character between occurence and value)")
        ("wordlist", opt::value<std::string>(), "Wordlist file path to export generation results to. Will be ignored for training mode")
00108
00109
                          ("count", opt::value<int>(), "Number of lines to generate. Ignored in training mode")
                          ("verbosity", "Output verbosity")
00110
00111
                          ("help", "Option definitions");
00112
00113
                         opt::variables_map vm;
00114
00115
                         opt::store(opt::parse_command_line(argc, argv, desc), vm);
00116
00117
                         opt::notify(vm);
00118
00119
                          //std::cout « desc « std::endl:
                          if (vm.count("help")) {
00120
00121
                          std::cout « desc « std::endl;
00122
00123
                         if (vm.count("output") == 0) this->po.outputfilename = "NULL";
else if (vm.count("output") == 1) {
    this->po.outputfilename = vm["output"].as<std::string>();
00124
00125
00126
00127
                              this->po.bExport = true;
00128
00129
                          else {
                              this->po.bFailure = true;
std::cout « "UNIDENTIFIED INPUT" « std::endl;
00130
00131
00132
                              std::cout « desc « std::endl;
00133
00134
00135
                         if (vm.count("dataset") == 0) this->po.datasetname = "NULL";
else if (vm.count("dataset") == 1) {
00136
00137
                              this->po.datasetname = vm["dataset"].as<std::string>();
00138
00139
00140
                         else {
                              this->po.bFailure = true;
std::cout « "UNIDENTIFIED INPUT" « std::endl;
00141
00142
00143
                              std::cout « desc « std::endl;
00144
00145
```


```
if (vm.count("wordlist") == 0) this->po.wordlistname = "NULL";
00147
00148
                        else if (vm.count("wordlist") == 1) {
                            this->po.wordlistname = vm["wordlist"].as<std::string>();
00149
00150
00151
                        else {
00152
                            this->po.bFailure = true;
00153
                             std::cout « "UNIDENTIFIED INPUT" « std::endl;
00154
                             std::cout « desc « std::endl;
00155
00156
                        if (vm.count("import") == 0) this->po.importname = "NULL";
00157
00158
                        else if (vm.count("import") == 1) {
00159
                             this->po.importname = vm["import"].as<std::string>();
00160
                             this->po.bImport = true;
00161
00162
                        else (
00163
                            this->po.bFailure = true;
                             std::cout « "UNIDENTIFIED INPUT" « std::endl;
00164
00165
                            std::cout « desc « std::endl;
00166
00167
00168
                        if (vm.count("count") == 0) this->po.generateN = 0;
else if (vm.count("count") == 1) {
00169
00170
00171
                             this->po.generateN = vm["count"].as<int>();
00172
00173
00174
                            this->po.bFailure = true;
                             std::cout « "UNIDENTIFIED INPUT" « std::endl;
00175
00176
                             std::cout « desc « std::endl;
00177
00178
00179
                        /*std::cout « vm["output"].as<std::string>() « std::endl;
                        std::cout « vm["dataset"].as<std::string>() « std::endl;
std::cout « vm["wordlist"].as<std::string>() « std::endl;
00180
00181
                        std::cout « vm["output"].as<std::string>() « std::endl;
std::cout « vm["count"].as<int>() « std::endl;*/
00182
00183
00184
00185
00186
                        //else if (vm.count("train")) std::cout « "train oldu" « std::endl;
               }
00187
00188
00189
               /** @brief Getter for command line options
00190
00191
                * Getter for ProgramOptions populated by the arguement parser
00192
                * @returns ProgramOptions structure.
00193
               Markov::API::CLI::ProgramOptions getProgramOptions(void) {
00194
00195
                   return this->po:
00196
               }
00197
00198
               /** @brief Initialize program options structure.
00199
                * @param i boolean, true if import operation is flagged
00200
00201
                * @param e boolean, true if export operation is flagged
* @param bf boolean, true if there is something wrong with the command line parameters
00202
00203
                * @param s seperator character for the import function
                * @param iName import filename
00204
00205
                * @param exName export filename
00206
                \star @param oName output filename
00207
                * @param dName corpus filename
00208
                * @param n number of passwords to be generated
00209
00210
00211
               void setProgramOptions(bool i, bool e, bool bf, char s, std::string iName, std::string exName,
       std::string oName, std::string dName, int n) {
00212
                    this->po.bImport = i;
                   this->po.bExport = e;
00213
                    this->po.seperator =
00215
                   this->po.bFailure = bf;
00216
                   this->po.generateN = n;
                   this->po.importname = iName;
this->po.exportname = exName;
this->po.outputfilename = oName;
00217
00218
00219
00220
                   this->po.datasetname = dName;
00221
00222
                    /*strcpy_s(this->po.importname,256,iName);
00223
                   strcpy_s(this->po.exportname,256,exName);
00224
                   strcpy s(this->po.outputfilename, 256, oName);
00225
                   strcpy_s(this->po.datasetname, 256, dName); */
00226
00227
00228
00229
               * @param argc - Program arguement count
* @param argv - Program arguement values array
00230
00231
```

9.7 CLI.h File Reference 193


```
00232
              \star @return ProgramOptions structure.
00233
              static Markov::API::CLI::ProgramOptions* parse(int argc, char** argv);
00234
00235
00236
00237
              /** @brief Print help string.
00238
00239
              static void help();
00240
          private:
00241
00242
              /**
    @brief ProgramOptions structure object
*/
00243
00244
00245
00246
              Markov::API::CLI::ProgramOptions po;
00247
00248
00249 };
```

## 9.7 CLI.h File Reference

```
#include <QtWidgets/QMainWindow>
#include "ui_CLI.h"
Include dependency graph for CLI.h:
```



This graph shows which files directly or indirectly include this file:



#### **Classes**

• class Markov::GUI::CLI

QT CLI Class.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::GUI


namespace for MarkovPasswords API GUI wrapper

## 9.8 CLI.h


```
00001 #pragma once
00002 #include <QtWidgets/QMainWindow>
00003 #include "ui_CLI.h"
00004
00005 namespace Markov::GUI{
          /** @brief QT CLI Class
00007
00008
          class CLI :public QMainWindow {
          Q_OBJECT public:
00009
00010
00011
              CLI(QWidget* parent = Q_NULLPTR);
00012
00013
          private:
00014
              Ui::CLI ui;
00015
          public slots:
00016
00017
              void start();
00018
              void statistics();
00019
              void about();
00020
00021 };
```

## 9.9 cudaDeviceController.h File Reference

```
#include <iostream>
#include <curand_kernel.h>
#include <cuda.h>
#include <cuda_runtime.h>
#include <device_launch_parameters.h>
Include dependency graph for cudaDeviceController.h:
```



This graph shows which files directly or indirectly include this file:



#### **Classes**

class Markov::API::CUDA::CUDADeviceController
 Controller class for CUDA device.

#### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::CUDA

Namespace for objects requiring CUDA libraries.

## 9.10 cudaDeviceController.h


```
00001
00002 #pragma once
00003 #include <iostream>
00004 #include <curand_kernel.h>
00005 #include <cuda.h>
00006 #include <cuda_runtime.h>
00007 #include <device_launch_parameters.h>
80000
00009 /** @brief Namespace for objects requiring CUDA libraries.
00010 */
00011 namespace Markov::API::CUDA{
00012
         /** @brief Controller class for CUDA device
00013
00014
          \star This implementation only supports Nvidia devices.
00015
          class CUDADeviceController{
00017
00018
             /** @brief List CUDA devices in the system.
00019
               \star This function will print details of every CUDA capable device in the system.
00020
00021
00022
               * @b Example @b output:
00023
               * @code{.txt}
00024
               * Device Number: 0
00025
               * Device name: GeForce RTX 2070
               * Memory Clock Rate (KHz): 7001000
* Memory Bus Width (bits): 256
00026
00027
00028
               * Peak Memory Bandwidth (GB/s): 448.064
00029
               * Max Linear Threads: 1024
00030
               * @endcode
00031
00032
              __host__ static void ListCudaDevices();
00033
00034
          protected:
00035
              /** @brief Check results of the last operation on GPU.
```

```
00037
                * Check the status returned from cudaMalloc/cudaMemcpy to find failures.
00038
00039
                \star If a failure occurs, its assumed beyond redemption, and exited.
               * @param _status Cuda error status to check
* @param msg Message to print in case of a failure
00040
00041
               * @return 0 if successful, 1 if failure.
00042
00043
               * @b Example @b output:
               * @code{.cpp}
00044
               * char *da, a = "test";
00045
               * cudastatus = cudaMalloc((char **)&da, 5*sizeof(char*));
* CudaCheckNotifyErr(cudastatus, "Failed to allocate VRAM for *da.\n");
00046
00047
00048
                * @endcode
00049
00050
               __host__ static int CudaCheckNotifyErr(cudaError_t _status, const char* msg, bool bExit=true);
00051
00052
00053
               /** @brief Malloc a 2D array in device space
00054
00055
               \star This function will allocate enough space on VRAM for flattened 2D array.
00056
00057
               * @param dst destination pointer
00058
               \star @param row row size of the 2d array
00059
               * @param col column size of the 2d array
00060
               * @return cudaError_t status of the cudaMalloc operation
00061
00062
               * @b Example @b output:
00063
               * @code{.cpp}
00064
               * cudaError_t cudastatus;
00065
                    char* dst:
00066
                    cudastatus = CudaMalloc2DToFlat<char>(&dst, 5, 15);
00067
                    if (cudastatus!=cudaSuccess) {
00068
                        CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00069
00070
               * @endcode
00071
00072
              template <typename T>
               __host__ static cudaError_t CudaMalloc2DToFlat(T** dst, int row, int col){
00074
                   cudaError_t cudastatus = cudaMalloc((T **)dst, row*col*sizeof(T));
00075
                   CudaCheckNotifyErr(cudastatus, "cudaMalloc Failed.", false);
00076
                   return cudastatus;
00077
              }
00078
00079
00080
               /** @brief Memcpy a 2D array in device space after flattening
00081
00082
                * Resulting buffer will not be true 2D array.
00083
00084
               * @param dst destination pointer
00085
               * @param rc source pointer
00086
               * @param row row size of the 2d array
00087
               * @param col column size of the 2d array
00088
                * @return cudaError_t status of the cudaMalloc operation
00089
00090
               * @b Example @b output:
00091
               * @code{.cpp}
               * cudaError_t cudastatus;
00092
00093
                    cudastatus = CudaMalloc2DToFlat<char>(&dst, 5, 15);
CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00094
00095
                    cudastatus = CudaMemcpy2DToFlat<char>(*dst,src,15,15);
00096
                    CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
00097
00098
                * @endcode
00099
00100
               template <typename T>
00101
              __host__ static cudaError_t CudaMemcpy2DToFlat(T* dst, T** src, int row, int col){
00102
                   T* tempbuf = new T[row*col];
                   for (int i=0;i<row;i++) {</pre>
00103
00104
                       memcpv(&(tempbuf[row*i]), src[i], col);
00105
00106
                   return cudaMemcpy(dst, tempbuf, row*col*sizeof(T), cudaMemcpyHostToDevice);
00107
00108
              }
00109
               /** @brief Both malloc and memcpy a 2D array into device VRAM.
00110
00111
00112
                * Resulting buffer will not be true 2D array.
00113
00114
               * @param dst destination pointer
00115
               * @param rc source pointer
* @param row row size of the 2d array
00116
00117
               * @param col column size of the 2d array
               * @return cudaError_t status of the cudaMalloc operation
00118
00119
00120
               * @b Example @b output:
00121
                * @code{.cpp}
00122
                   cudaError t cudastatus;
```

```
00123
                     char* dst;
00124
                     cudastatus = CudaMigrate2DFlat<long int>(
                     &dst, this->valueMatrix, this->matrixSize, this->matrixSize);
CudaCheckNotifyErr(cudastatus, " Cuda failed to initialize va
00125
00126
                                                              Cuda failed to initialize value matrix row.");
00127
                 * @endcode
00128
00129
               template <typename T>
00130
                         _ static cudaError_t CudaMigrate2DFlat(T** dst, T** src, int row, int col){
                    cudaError_t cudastatus;
cudastatus = CudaMalloc2DToFlat<T>(dst, row, col);
00131
00132
                    if (cudastatus!=cudaSuccess) {
00133
                        CudaCheckNotifyErr(cudastatus, " CudaMalloc2DToFlat Failed.", false);
00134
00135
                         return cudastatus;
00136
00137
                    cudastatus = CudaMemcpy2DToFlat<T>(*dst,src,row,col);
00138
                    CudaCheckNotifyErr(cudastatus, " CudaMemcpy2DToFlat Failed.", false);
00139
                    return cudastatus:
00140
00141
00142
00143
           private:
00144
00145 };
```

## 9.11 cudaModelMatrix.h File Reference

#include "MarkovPasswords/src/modelMatrix.h"
#include "cudaDeviceController.h"
Include dependency graph for cudaModelMatrix.h:



### Classes

class Markov::API::CUDA::CUDAModelMatrix

Extension of Markov::API::ModelMatrix which is modified to run on GPU devices.

#### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::CUDA

Namespace for objects requiring CUDA libraries.

#### **Functions**

• \_\_global\_\_ void Markov::API::CUDA::FastRandomWalkCUDAKernel (unsigned long int n, int minLen, int maxLen, char \*outputBuffer, char \*matrixIndex, long int \*totalEdgeWeights, long int \*valueMatrix, char \*edgeMatrix, int matrixSize, int memoryPerKernelGrid, unsigned long \*seed)

CUDA kernel for the FastRandomWalk operation.

\_\_device\_\_ char \* Markov::API::CUDA::strchr (char \*p, char c, int s\_len)
 srtchr implementation on device space

## 9.12 cudaModelMatrix.h


```
00001 #include "MarkovPasswords/src/modelMatrix.h" 00002 #include "cudaDeviceController.h"
00004 /** @brief Namespace for objects requiring CUDA libraries.
00005 */
00006 namespace Markov::API::CUDA{
           /** @brief Extension of Markov::API::ModelMatrix which is modified to run on GPU devices.
00007
00008
00009
            * This implementation only supports Nvidia devices.
00011
           class CUDAModelMatrix : public ModelMatrix, public CUDADeviceController{
           public:
00012
00013
00014
               /** @brief Migrate the class members to the VRAM
00015
00016
                * Cannot be used without calling Markov::API::ModelMatrix::ConstructMatrix at least once.
00017
                * This function will manage the memory allocation and data transfer from CPU RAM to GPU VRAM.
00018
00019
                \star Newly allocated VRAM pointers are set in the class member variables.
00020
00021
00022
                __host__ void MigrateMatrix();
00023
00024
                /** @brief Flatten migrated matrix from 2d to 1d
00025
00026
00027
               __host__ void FlattenMatrix();
00028
00029
00030
               /** @brief Random walk on the Matrix-reduced Markov::Model
00031
00032
                * TODO
00033
00034
00035
                * @param n - Number of passwords to generate.
00036
                * @param wordlistFileName - Filename to write to
                * @param minLen - Minimum password length to generate
* @param maxLen - Maximum password length to generate
00037
00038
                * @param threads - number of OS threads to spawn
* @param bFileIO - If false, filename will be ignored and will output to stdout.
00039
00040
00041
00042
00043
                * @code{.cpp}
                * Markov::API::ModelMatrix mp;
* mp.Import("models/finished.mdl");
00044
00045
00046
                * mp.FastRandomWalk(50000000,"./wordlist.txt",6,12,25, true);
00047
                * @endcode
00048
00049
00050
                 _host__ void FastRandomWalk(unsigned long int n, const char* wordlistFileName, int minLen,
        int maxLen, bool bFileIO);
00051
00052
           protected:
00053
00054
               /** @brief Allocate the output buffer for kernel operation
00055
00056
                * TODO
00057
00058
                * @param n - Number of passwords to generate.
00060
                 \star @param singleGenMaxLen - maximum string length for a single generation
00061
                \star @param CUDAKernelGridSize - Total number of grid members in CUDA kernel
                * @param sizePerGrid - Size to allocate per grid member
* @return pointer to the allocation on VRAM
00062
00063
00064
00065
00066
00067
                host
                        _ char* AllocVRAMOutputBuffer(long int n, long int singleGenMaxLen, long int
        CUDAKernelGridSize,long int sizePerGrid);
00068
           private:
00069
00071
                   @brief VRAM Address pointer of edge matrix (from modelMatrix.h)
00072
00073
               char* device_edgeMatrix;
00074
00075
00076
                    @brief VRAM Address pointer of value matrix (from modelMatrix.h)
```

```
00078
               long int *device_valueMatrix;
00079
00080
00081
                  @brief VRAM Address pointer of matrixIndex (from modelMatrix.h)
00082
00083
               char *device matrixIndex;
00084
00085
                % @brief VRAM Address pointer of total edge weights (from modelMatrix.h) \star/
00086
00087
               long int *device_totalEdgeWeights;
00088
00089
00090
00091
               00092
00093
00094
               char* device_outputBuffer;
00095
00096
00097
                  @brief RandomWalk results in host
00098
00099
               char* outputBuffer;
00100
00101
                   @brief Adding Edge matrix end-to-end and resize to 1-D array for better perfomance on
00102
00103
00104
               char* flatEdgeMatrix;
00105
00106
                  Obrief Adding Value matrix end-to-end and resize to 1-D array for better perfomance on
00107
        traversing
00108
00109
               long int* flatValueMatrix;
00110
00111
           };
00112
00113
           /** @brief CUDA kernel for the FastRandomWalk operation
00114
00115
            * Will be initiated by CPU and continued by GPU (__global__ tag)
00116
00117
           * @param n - Number of passwords to generate.
00118
           * @param minlen - minimum string length for a single generation
* @param maxLen - maximum string length for a single generation
00119
00120
           * @param outputBuffer - VRAM ptr to the output buffer
* @param matrixIndex - VRAM ptr to the matrix indices
00121
00122
           * @param totalEdgeWeights - VRAM ptr to the totalEdgeWeights array
* @param valueMatrix - VRAM ptr to the edge weights array
* @param edgeMatrix - VRAM ptr to the edge representations array
00123
00124
00125
           * @param matrixSize - Size of the matrix dimensions
00126
00127
           * @param memoryPerKernelGrid - Maximum memory usage per kernel grid
00128
            \star @param seed - seed chunk to generate the random from (generated & used by Marsaglia)
00129
00130
00131
00133
           __global__ void FastRandomWalkCUDAKernel(unsigned long int n, int minLen, int maxLen, char*
        outputBuffer,
00134
              char* matrixIndex, long int* totalEdgeWeights, long int* valueMatrix, char *edgeMatrix,
00135
               int matrixSize, int memoryPerKernelGrid, unsigned long *seed);//, unsigned long mex, unsigned
        long mey, unsigned long mez);
00136
00137
00138
           /** @brief srtchr implementation on __device__ space
00139
00140
            \star Fint the first matching index of a string
00141
00142
00143
           * @param p - string to check
00144
            * @param c - character to match
00145
           * @param s_len - maximum string length
00146
            * @returns pointer to the match
00147
00148
           __device__ char* strchr(char* p, char c, int s_len);
00149
00150 };
```

## 9.13 cudarandom.h File Reference

```
#include "MarkovModel/src/random.h"
#include "CudaMarkovPasswords/src/cudaDeviceController.h"
```

Include dependency graph for cudarandom.h:



#### **Classes**

class Markov::API::CUDA::Random::Marsaglia

Extension of Markov::Random::Marsaglia which is capable o working on device space.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::CUDA

Namespace for objects requiring CUDA libraries.

Markov::API::CUDA::Random

Namespace for Random engines operable under device space.

#### **Functions**

\_\_device\_\_ unsigned long Markov::API::CUDA::Random::devrandom (unsigned long &x, unsigned long &y, unsigned long &z)

Marsaglia Random Generation function operable in device space.

### 9.14 cudarandom.h


```
00001 #pragma once
00002 #include "MarkovModel/src/random.h"
00003 #include "CudaMarkovPasswords/src/cudaDeviceController.h"
00004
00005 /** @brief Namespace for Random engines operable under __device__ space.
00006 */
00007 namespace Markov::API::CUDA::Random{
80000
00009
          /** @brief Extension of Markov::Random::Marsaglia which is capable o working on __device__ space.
00010
00011
          class Marsaglia : public Markov::Random::Marsaglia, public CUDADeviceController{
          public:
00012
00013
              /** @brief Migrate a Marsaglia[] to VRAM as seedChunk
00014
00015
               * @param MEarr Array of Marsaglia Engines
               * @param gridSize GridSize of the CUDA Kernel, aka size of array
00016
00017
                 Oreturns pointer to the resulting seed chunk in device VRAM.
00018
00019
              static unsigned long* MigrateToVRAM(Markov::API::CUDA::Random::Marsaglia *MEarr, long int
       gridSize){
00020
                  cudaError_t cudastatus;
00021
                   unsigned long* seedChunk;
00022
                   cudastatus = cudaMalloc((unsigned long**)&seedChunk, gridSize*3*sizeof(unsigned long));
00023
                   CudaCheckNotifyErr(cudastatus, "Failed to allocate seed buffer");
                   unsigned long *temp = new unsigned long[gridSize*3];
for(int i=0;i<gridSize;i++){</pre>
00024
00025
                       temp[i*3] = MEarr[i].x;
temp[i*3+1] = MEarr[i].y;
00026
00027
00028
                       temp[i*3+2] = MEarr[i].z;
```

```
00029
00030
                   //for(int i=0;i<gridSize*3;i++) std::cout « temp[i] « "\n";
00031
                   cudaMemcpy(seedChunk, temp, gridSize*3*sizeof(unsigned long), cudaMemcpyHostToDevice);
                   CudaCheckNotifyErr(cudastatus, "Failed to memcpy seed buffer.");
00032
00033
                   return seedChunk;
00034
               }
00035
           };
00036
00037
           /** @brief Marsaglia Random Generation function operable in __device__ space
00038
           \star @param x marsaglia internal x. Not constant, (ref)
00039
           \star @param y marsaglia internal y. Not constant, (ref)
00040
           * @param z marsaglia internal z. Not constant, (ref)
00041
           * @returns returns z
00042
00043
           __device__ unsigned long devrandom(unsigned long &x, unsigned long &y, unsigned long &z){
              unsigned long t;
x ^= x « 16;
x ^= x » 5;
00044
00045
00046
00047
              x ^= x « 1;
00048
00049
00050
               y = z;
z = t ^ x ^ y;
00051
00052
00053
00054
               return z;
00055
00056 };
```

## 9.15 dllmain.cpp File Reference

```
#include "pch.h"
#include "model.h"
#include <iostream>
```

Include dependency graph for dllmain.cpp:




## 9.16 dllmain.cpp

```
00001 #include "pch.h"
00002 #include "model.h"
00003 #include <iostream>
00004
00005
00006 #ifdef WIN32
00007 __declspec(dllexport) void dll_loadtest() {
         std::cout « "External function called.\n";
80000
00009
          //cudaTestEntry();
00010 }
00011
00012 BOOL APIENTRY D11Main(HMODULE hModule, DWORD ul_reason_for_call, LPV0ID lpReserved)
00013 {
00014
          switch (ul_reason_for_call)
00015
00016
          case DLL_PROCESS_ATTACH:
00017
          case DLL_THREAD_ATTACH:
00018
          case DLL THREAD DETACH:
          case DLL_PROCESS_DETACH:
00019
00020
              break;
```


```
00022 return TRUE;
00023 }
00024
00025 #endif
```

## 9.17 edge.h File Reference

```
#include <cstdint>
#include <cstddef>
Include dependency graph for edge.h:
```



This graph shows which files directly or indirectly include this file:



#### **Classes**

class Markov::Node < storageType >

A node class that for the vertices of model. Connected with eachother using Edge.

 $\bullet \ \, {\sf class\ Markov::Edge}{<{\sf NodeStorageType}}>$ 

Edge class used to link nodes in the model together.

9.18 edge.h 203

### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

## 9.18 edge.h

```
00001 #pragma once
00002 #include <cstdint>
00003 #include <cstddef>
00004
00005 namespace Markov {
00006
00007
           template <typename NodeStorageType>
00008
00009
00010
           /{**} @brief Edge class used to link nodes in the model together.
00011
00012
           Has LeftNode, RightNode, and EdgeWeight of the edge.
00013
           Edges are *UNIDIRECTIONAL* in this model. They can only be traversed LeftNode to RightNode.
00014
00015
           template <typename NodeStorageType>
00016
           class Edge {
00017
           public:
00018
00019
               /** @brief Default constructor.
00020
00021
               Edge<NodeStorageType>();
00022
               /** @brief Constructor. Initialize edge with given RightNode and LeftNode
00023
                * @param _left - Left node of this edge.
* @param _right - Right node of this edge.
00024
00025
00026
00027
                * @b Example @b Use: Construct edge
00028
               * @code{.cpp}
                * Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
* Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00029
00030
00031
                * Markov::Edge<unsigned char>* el = new Markov::Edge<unsigned char>(src, target1);
00032
00033
00034
00035
               {\tt Edge < Node Storage Type > (Node < Node Storage Type > * \_left, Node < Node Storage Type > * \_right);}
00036
               /** @brief Adjust the edge EdgeWeight with offset.
00037
00038
                * Adds the offset parameter to the edge EdgeWeight.
00039
                * @param offset - NodeValue to be added to the EdgeWeight
00040
00041
                * @b Example @b Use: Construct edge
00042
               * @code{.cpp}
00043
                * Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                * Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00044
00045
                * Markov::Edge<unsigned char>* el = new Markov::Edge<unsigned char>(src, target1);
00046
00047
                * e1->AdjustEdge(25);
00048
00049
                * @endcode
00050
00051
               void AdjustEdge(long int offset);
00052
00053
               /** @brief Traverse this edge to RightNode.
00054
                \star @return Right node. If this is a terminator node, return NULL
00055
00056
00057
                * @b Example @b Use: Traverse a node
00058
                * @code{.cpp}
00059
                * Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                * Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');


* Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
00060
00061
00062
00063
                * e1->AdjustEdge(25);
00064
                * Markov::Edge<unsigned char>* e2 = e1->traverseNode();
00065
                * @endcode
00066
00067
00068
               inline Node<NodeStorageType>* TraverseNode();
00069
00070
               /** @brief Set LeftNode of this edge.
00071
               * @param node - Node to be linked with.
00072
00073
               void SetLeftEdge (Node<NodeStorageType>*);
00074
               /** @brief Set RightNode of this edge.
00075
               * @param node - Node to be linked with.
```

```
void SetRightEdge(Node<NodeStorageType>*);
00078
00079
              /** @brief return edge's EdgeWeight.
00080
              \star @return edge's EdgeWeight.
00081
00082
              inline uint64 t EdgeWeight();
00083
00084
              /** @brief return edge's LeftNode
00085
              * @return edge's LeftNode.
00086
00087
              Node<NodeStorageType>* LeftNode();
00088
00089
              /** @brief return edge's RightNode
00090
               * @return edge's RightNode.
00091
00092
              inline Node<NodeStorageType>* RightNode();
00093
00094
          private:
00095
00096
                 @brief source node
00097
00098
              Node<NodeStorageType>* _left;
00099
              . @brief target node */
00100
00101
00102
00103
              Node<NodeStorageType>* _right;
00104
              Edge Edge Weight
00105
00106
00107
00108
              long int _weight;
00109
00110
00111
00112 };
00113
00114 //default constructor of edge
00115 template <typename NodeStorageType>
00116 Markov::Edge<NodeStorageType>::Edge() {
00117
          this->_left = NULL;
         this->_right = NULL;
this->_weight = 0;
00118
00119
00120 }
00121 //constructor of edge
00122 template <typename NodeStorageType>
00123 Markov::Edge<NodeStorageType>::Edge(Markov::Node<NodeStorageType>* _left,
      Markov::Node<NodeStorageType>* _right) {
00124
         this->_left = _left;
this->_right = _right;
this->_weight = 0;
00125
00126
00127 }
00128 //to AdjustEdge the edges by the edge with its offset
00129 template <typename NodeStorageType>
00130 void Markov::Edge<NodeStorageType>::AdjustEdge(long int offset) {
         this->_weight += offset;
00131
          this->LeftNode()->UpdateTotalVerticeWeight(offset);
00132
00133 }
00134 //to TraverseNode the node
00135 template <typename NodeStorageType>
00136 inline Markov::Node<NodeStorageType>* Markov::Edge<NodeStorageType>::TraverseNode() {
       if (this->RightNode()->NodeValue() == 0xff) //terminator node
00137
00138
              return NULL;
          return _right;
00139
00140 }
00141 //to set the LeftNode of the node
00142 template <typename NodeStorageType>
00143 void Markov::Edge<NodeStorageType>::SetLeftEdge(Markov::Node<NodeStorageType>* n) {
00144
         this-> left = n:
00145 }
00146 //to set the RightNode of the node
00147 template <typename NodeStorageType>
00148 void Markov::Edge<NodeStorageType>::SetRightEdge (Markov::Node<NodeStorageType>* n) {
00149
          this -> _right = n;
00150 }
00151 //to get the EdgeWeight of the node
00152 template <typename NodeStorageType>
00153 inline uint64_t Markov::Edge<NodeStorageType>::EdgeWeight() {
00154
          return this->_weight;
00155 }
00156 //to get the LeftNode of the node
00157 template <typename NodeStorageType>
00158 Markov::Node<NodeStorageType>* Markov::Edge<NodeStorageType>::LeftNode() {
00159
          return this->_left;
00160 }
00161 //to get the RightNode of the node
00162 template <typename NodeStorageType>
```

```
00163 inline Markov::Node<NodeStorageType>* Markov::Edge<NodeStorageType>::RightNode() {
00164     return this->_right;
00165 }
```

# 9.19 framework.h File Reference

This graph shows which files directly or indirectly include this file:



### **Macros**

• #define WIN32 LEAN AND MEAN

## 9.19.1 Macro Definition Documentation

## 9.19.1.1 WIN32\_LEAN\_AND\_MEAN

#define WIN32\_LEAN\_AND\_MEAN
Definition at line 3 of file framework.h.


### 9.20 framework.h

# 9.21 main.cpp File Reference

```
#include <iostream>
#include "color/term.h"
#include "argparse.h"
#include <string>
#include <cstring>
```

```
#include <sstream>
#include "markovPasswords.h"
#include "modelMatrix.h"
#include <chrono>
```

Include dependency graph for src/main.cpp:



### **Functions**

int main (int argc, char \*\*argv)
 Launch CLI tool.

#### 9.21.1 Function Documentation

## 9.21.1.1 main()


int main (

```
int argc,
                  char ** argv )
Launch CLI tool.
Definition at line 14 of file src/main.cpp.
00014
00015
00016
            Markov::API::CLI::Terminal t;
00017
00018
            ProgramOptions* p = Argparse::parse(argc, argv);
00019
            if (p==0 \mid \mid p->bFailure) {
00020
00021
                 std::cout « TERM_FAIL « "Arguments Failed to Parse" « std::endl;
00022
                 Argparse::help();
00023
00024
            Markov::API::CLI::Argparse a(argc,argv);
00025
            Markov::API::ModelMatrix markovPass;
std::cerr « "Importing model.\n";
00026
00027
            markovPass.Import("models/finished.mdl");
00028
            std::cerr « "Import done. \n";
00029
00030
            markovPass.ConstructMatrix();
            std::chrono::steady_clock::time_point begin = std::chrono::steady_clock::now();
//markovPass.FastRandomWalk(50000000, "/media/ignis/Stuff/wordlist.txt",6,12,25, true);
markovPass.FastRandomWalk(500000000, "/media/ignis/Stuff/wordlist2.txt",6,12,25, true);
00031
00032
00033
00034
            std::chrono::steady_clock::time_point end = std::chrono::steady_clock::now();
00035
00036
            std::cerr « "Finished in:" « std::chrono::duration_cast<std::chrono::milliseconds> (end -
        begin).count() « " milliseconds" « std::endl;
00037
00038 }
```

References Markov::API::CLI::Argparse::Argparse(), Markov::API::ModelMatrix::ConstructMatrix(), Markov::API::ModelMatrix::FastRatand Markov::Model< NodeStorageType >::Import().

9.22 src/main.cpp 207

Here is the call graph for this function:




# 9.22 src/main.cpp

```
00001 #pragma once
00002 #include <iostream>
00003 #include "color/term.h"
00004 #include "argparse.h"
00005 #include <string>
00006 #include <cstring>
00007 #include <sstream>
00008 #include "markovPasswords.h"
00009 #include "modelMatrix.h"
00010 #include <chrono>
00011
00012 /** @brief Launch CLI tool.
00013 */
00014 int main(int argc, char** argv) {
00015
00016
          Markov::API::CLI::Terminal t;
00017
00018
          ProgramOptions* p = Argparse::parse(argc, argv);
00019
00020
          if (p==0 || p->bFailure) {
              std::cout « TERM_FAIL « "Arguments Failed to Parse" « std::endl;
00021
00022
              Argparse::help();
00023
00024
          Markov::API::CLI::Argparse a(argc,argv);
00025
          Markov::API::ModelMatrix markovPass;
00026
          std::cerr « "Importing model.\n";
00027
00028
          markovPass.Import("models/finished.mdl");
00029
          std::cerr « "Import done. \n";
00030
          markovPass.ConstructMatrix();
          std::chrono::steady_clock::time_point begin = std::chrono::steady_clock::now();
00031
          //markovPass.FastRandomWalk(50000000, "/media/ignis/Stuff/wordlist.txt",6,12,25, true); markovPass.FastRandomWalk(50000000, "/media/ignis/Stuff/wordlist2.txt",6,12,25, true);
00032
00033
00034
          std::chrono::steady_clock::time_point end = std::chrono::steady_clock::now();
00035
       00036
00037
          return 0:
00038 }
```

# 9.23 main.cpp File Reference

```
#include "menu.h"
#include <QtWidgets/QApplication>
#include <QSplashScreen>
#include <QDateTime>
#include "CLI.h"
```

Include dependency graph for UI/src/main.cpp:



### **Functions**

int main (int argc, char \*argv[])
 Launch UI.

### 9.23.1 Function Documentation

### 9.23.1.1 main()

```
int main (
          int argc,
          char * argv[] )
```

### Launch UI.

Definition at line 12 of file Ul/src/main.cpp.

```
00013 {
00014
00015
00016
00017
          QApplication a(argc, argv);
00018
00019
          QPixmap loadingPix("views/startup.jpg");
00020
          QSplashScreen splash(loadingPix);
00021
          splash.show();
00022
          QDateTime time = QDateTime::currentDateTime();
00023
          QDateTime currentTime = QDateTime::currentDateTime();
                                                                    //Record current time
00024
          while (time.secsTo(currentTime) <= 5)</pre>
                                                                     //5 is the number of seconds to delay
00025
00026
              currentTime = QDateTime::currentDateTime();
00027
              a.processEvents();
00028
          };
00029
00030
00031
          CLI w;
00032
          w.show();
          splash.finish(&w);
00033
00034
          return a.exec();
00035 }
```

References Markov::GUI::CLI::start().

Here is the call graph for this function:




9.24 Ul/src/main.cpp 209

# 9.24 UI/src/main.cpp

```
00001 //#include "MarkovPasswordsGUI.h"
00002 #include "menu.h"
00003 #include <QtWidgets/QApplication>
00004 #include <QSplashScreen>
00005 #include < QDateTime >
00006 #include "CLI.h"
00007
00008 using namespace Markov::GUI;
00009
00010 /** @brief Launch UI.
00011 */
00012 int main(int argc, char *argv[])
00013 {
00014
00015
00016
00017
           QApplication a(argc, argv);
00018
00019
           QPixmap loadingPix("views/startup.jpg");
00020
           QSplashScreen splash(loadingPix);
00021
           splash.show();
00022
           ODateTime time = ODateTime::currentDateTime();
           QDateTime currentTime = QDateTime::currentDateTime();
00023
                                                                           //Record current time
00024
           while (time.secsTo(currentTime) <= 5)</pre>
                                                                           //5 is the number of seconds to delay
00025
00026
                currentTime = QDateTime::currentDateTime();
00027
                a.processEvents();
00028
00029
00030
00031
           CLI w;
00032
           w.show();
00033
           splash.finish(&w);
00034
           return a.exec();
00035 }
```

# 9.25 markopy.cpp File Reference

```
#include "../../MarkovPasswords/src/markovPasswords.h"
#include <Python.h>
#include <boost/python.hpp>
Include dependency graph for markopy.cpp:
```



### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

· Markov::Markopy

### **Macros**

• #define BOOST PYTHON STATIC LIB

#### **Functions**

Markov::Markopy::BOOST PYTHON MODULE (markopy)

#### 9.25.1 Macro Definition Documentation

### 9.25.1.1 BOOST\_PYTHON\_STATIC\_LIB

```
#define BOOST_PYTHON_STATIC_LIB

Definition at line 4 of file markopy.cpp.
```

# 9.26 markopy.cpp

```
00001 #pragma once
00002 #include "../../MarkovPasswords/src/markovPasswords.h"
00004 #define BOOST_PYTHON_STATIC_LIB
00005 #include <Python.h>
00006 #include <boost/python.hpp>
00007
00008 using namespace boost::python;
00009
00010 namespace Markov::Markopy{
00011
          BOOST_PYTHON_MODULE(markopy)
00012
00013
               bool (Markov::API::MarkovPasswords::*Import) (const char*) = &Markov::Model<char>::Import;
               bool (Markov::API::MarkovPasswords::*Export) (const char*) = &Markov::Model<char>::Export;
00014
00015
               class_<Markov::API::MarkovPasswords>("MarkovPasswords", init<>())
00016
                   .def(init<>())
00017
                     .def("Train", &Markov::API::MarkovPasswords::Train,
                    "Train the model\n"
00018
                   "\n"
00019
                   ":param datasetFileName: Ifstream* to the dataset. If null, use class member\n"
00020
00021
                   ":param delimiter: a character, same as the delimiter in dataset content\n'
                   ":param threads: number of OS threads to spawn\n")
00022
00023
                    .def("Generate", &Markov::API::MarkovPasswords::Generate,
00024
                   "Generate passwords from a trained model.\n"
                   ":param n: Ifstream* to the dataset. If null, use class member\n"
00025
                   ":param wordlistFileName: a character, same as the delimiter in dataset content\n"
":param minLen: number of OS threads to spawn\n"
00026
00027
00028
                   ":param maxLen: Ifstream* to the dataset. If null, use class member\n"
00029
                   ":param threads: a character, same as the delimiter in dataset content\n"
                   ":param threads: number of OS threads to spawn\n")
.def("Import", Import, "Import a model file.")
.def("Export", Export, "Export a model to file.")
00030
00031
00032
00033
               ;
          };
00035 };
```

# 9.27 markopy\_cli.py File Reference

### **Namespaces**

· markopy cli

### **Functions**

- def markopy\_cli.cli\_init (input\_model)
- · def markopy\_cli.cli\_train (model, dataset, seperator, output, output\_forced=False, bulk=False)
- def markopy\_cli.cli\_generate (model, wordlist, bulk=False)

9.28 markopy\_cli.py 211

#### **Variables**

- · markopy cli.parser
- · markopy\_cli.help
- · markopy cli.default
- · markopy\_cli.action
- markopy cli.args = parser.parse args()
- markopy\_cli.corpus\_list = os.listdir(args.dataset)
- def markopy\_cli.model = cli\_init(args.input)
- markopy\_cli.output\_file\_name = corpus
- string markopy cli.model extension = ""
- · markopy\_cli.output\_forced
- markopy\_cli.True
- markopy\_cli.bulk
- markopy\_cli.model\_list = os.listdir(args.input)
- markopy cli.model base = input
- · markopy cli.output

# 9.28 markopy\_cli.py

```
00001 #!/usr/bin/python3
00002 """
00003
        @namespace Markov::Markopy::Python
00004 """
00005
00006 import markopy
00007 import argparse
00008 import allogate as logging
00009 import re
00010 import os
00011
00012 parser = argparse.ArgumentParser(description="Python wrapper for MarkovPasswords.",
00013 epilog=f"""Sample runs:
00014 {__file__} train untrained.mdl -d dataset.dat -s "\\t" -o trained.mdl
00015
          Import untrained.mdl, train it with dataset.dat which has tab delimited data, output resulting
       model to trained.mdl\n
00016
00017 {__file__} generate trained.mdl -n 500 -w output.txt
00018
          Import trained.mdl, and generate 500 lines to output.txt
00019
00020 {__file__} combine untrained.mdl -d dataset.dat -s "\\t" -n 500 -w output.txt
00021
          Train and immediately generate 500 lines to output txt. Do not export trained model.
00022
00023 {__file__} combine untrained.mdl -d dataset.dat -s "\\t" -n 500 -w output.txt -o trained.mdl
00024
          Train and immediately generate 500 lines to output.txt. Export trained model.
00025 """, formatter_class=argparse.RawTextHelpFormatter)
00026
00027 parser.add_argument("mode", help="Operation mode, supported modes: \"generate\", \"train\" and
        ("combine\".")
00028 parser.add_argument("input", help="Input model file. This model will be imported before starting
       operation.\n'
00029
                                         + "For more information on the file structure for input, check out
       the wiki page.")
00030 parser.add_argument("-o", "--output",
                          help="Output model filename. This model will be exported when done. Will be
00031
       ignored for generation mode.")
00032 parser.add_argument("-d", "--dataset",
                          help="Dataset filename to read input from for training. Will be ignored for
00033
       generation mode.\n"
                          + "Dataset is occurrence of a string and the string value seperated by a
00034
       seperator. For more info
                            "on the dataset file structure, check out the github wiki page.")
00036 parser.add_argument("-s",
                                "--seperator",
00037
                          help="Seperator character to use with training data.(character between occurrence
       and value) \n"
00038
                          + "For more information on dataset/corpus file structure, check out the github
       wiki.")
00039 parser.add_argument("-w", "--wordlist",
                          help="Wordlist filename path to export generation results to. Will be ignored for
       training mode")
00041 parser.add_argument("--min", default=6, help="Minimum length that is allowed during generation. \n"
00042
                           + "Any string shorter than this paremeter will retry to continue instead of
       proceeding to "
                           + "finishing node")
00044 parser.add_argument("--max", default=12, help="Maximum length that is allowed during generation.\n"
```


```
+"Any string that does reaches this length are cut off irregardless to their
       position on the model.")
00046 parser.add_argument("-n", "--count", help="Number of lines to generate. Ignored in training mode.")
00047 parser.add_argument("-t", "--threads", default=10, help="Number of threads to use with training/generation.\n"
00048
                            +"This many OS threads will be created for training/generation functions")
00049 parser.add_argument("-v", "--verbosity", action="count", help="Output verbosity.\n
00050
                            + "Set verbosity to 1: -v n"
00051
                            + "Set verbosity to 3: -vvv\n"
00052 + "Print pretty much everything, including caller functions: -vvvvvvvvvvvv")
00053 parser.add_argument("-b", "--bulk", action="store_true",
00054 help="Bulk generate or bulk train every corpus/model in the folder.\n"
00055
                               If working on this mode, output/input/dataset parameters should be a folder.\n"
                            + "Selected operation (generate/train) will be applied to each file in the folder,
00056
       and "
00057
                           + "output to the output directory.")
00058 args = parser.parse_args()
00059
00060
00061 def cli_init(input_model):
00062
           logging.VERBOSITY = 0
           if args.verbosity:
00063
               logging.VERBOSITY = args.verbosity
00064
00065
               logging.pprint(f"Verbosity set to {args.verbosity}.", 2)
00066
00067
           logging.pprint("Initializing model.", 1)
           model = markopy.MarkovPasswords()
00068
00069
           logging.pprint("Model initialized.", 2)
00070
00071
           logging.pprint("Importing model file.", 1)
00072
00073
          if (not os.path.isfile(input_model)):
               logging.pprint(f"Model file at {input_model} not found. Check the file path, or working
00074
       directory")
00075
               exit(1)
00076
00077
          model.Import(input model)
          logging.pprint("Model imported successfully.", 2)
00079
           return model
08000
00081
00082 def cli_train(model, dataset, seperator, output, output_forced=False, bulk=False):
00083
          if not (dataset and seperator and (output or not output_forced)):
00084
               logging.pprint(
00085
                   f"Training mode requires -d/--dataset{', -o/--output' if output_forced else "} and
        -s/--seperator parameters. Exiting.")
00086
               exit(2)
00087
00088
          if (not bulk and not os.path.isfile(dataset)):
               logging.pprint(f"{dataset} doesn't exists. Check the file path, or working directory")
00089
00090
               exit(3)
00091
00092
           if (output and os.path.isfile(output)):
00093
               logging.pprint(f"{output} exists and will be overwritten.", 1)
00094
00095
          if (seperator == '\\t'):
    logging.pprint("Escaping seperator.", 3)
00096
00097
               seperator = ' \t'
00098
00099
           if (len(seperator) != 1):
               logging.pprint(f'Delimiter \ must \ be \ a \ single \ character, \ and \ "{seperator}" \ is \ not \ accepted.')
00100
00101
               exit(4)
00102
00103
           logging.pprint(f'Starting training.', 3)
00104
           model.Train(dataset, seperator, int(args.threads))
00105
           logging.pprint(f'Training completed.', 2)
00106
00107
           if (output):
00108
               logging.pprint(f'Exporting model to {output}', 2)
00109
               model.Export (output)
00110
00111
               logging.pprint(f'Model will not be exported.', 1)
00112
00113
00114 def cli_generate(model, wordlist, bulk=False):
00115 if not (wordlist or args.count):
00116
               logging.pprint("Generation mode requires -w/--wordlist and -n/--count parameters. Exiting.")
00117
               exit(2)
00118
00119
          if (bulk and os.path.isfile(wordlist)):
               logging.pprint(f"{wordlist} exists and will be overwritten.", 1)
00120
          model.Generate(int(args.count), wordlist, int(args.min), int(args.max), int(args.threads))
00122
00123
00124 if (args.bulk):
           logging.pprint(f"Bulk mode operation chosen.", 4)
00125
00126
```

```
if (args.mode.lower() == "train"):
00128
              if (os.path.isdir(args.output) and not os.path.isfile(args.output)) and (
00129
                       os.path.isdir(args.dataset) and not os.path.isfile(args.dataset)):
00130
                  corpus_list = os.listdir(args.dataset)
00131
                  for corpus in corpus_list:
   model = cli_init(args.input)
00132
00133
                       logging.pprint(f"Training {args.input} with {corpus}", 2)
00134
                       output_file_name = corpus
                       model_extension = ""
00135
00136
                       if "." in args.input:
                       model_extension = args.input.split(".")[-1]
cli_train(model, f"{args.dataset}/{corpus}", args.seperator,
00137
00138
                                 f"{args.output}/{corpus}.{model_extension}", output_forced=True, bulk=True)
00140
00141
                  logging.pprint("In bulk training, output and dataset should be a directory.")
00142
00143
00144
         elif (args.mode.lower() == "generate"):
              if (os.path.isdir(args.wordlist) and not os.path.isfile(args.wordlist)) and (
                       os.path.isdir(args.input) and not os.path.isfile(args.input)):
                  model_list = os.listdir(args.input)
00147
00148
                  print(model_list)
                   for input in model_list:
00149
                       logging.pprint(f"Generating from {args.input}/{input} to {args.wordlist}/{input}.txt",
00150
00151
                      model = cli_init(f"{args.input}/{input}")
00152
                      model_base = input
if "." in args.input:
00153
00154
00155
                           model_base = input.split(".")[1]
00156
                       cli_generate(model, f"{args.wordlist}/{model_base}.txt", bulk=True)
00157
              else:
00158
                  logging.pprint("In bulk generation, input and wordlist should be directory.")
00159
00160 else:
          model = cli_init(args.input)
00161
          if (args.mode.lower() == "generate"):
00162
              cli_generate(model, args.wordlist)
00163
00164
00165
00166
          elif (args.mode.lower() == "train"):
00167
              cli_train(model, args.dataset, args.seperator, args.output, output_forced=True)
00168
00169
00170
          elif (args.mode.lower() == "combine"):
00171
              cli_train(model, args.dataset, args.seperator, args.output)
00172
              cli_generate(model, args.wordlist)
00173
00174
00175
              logging.pprint("Invalid mode arguement given.")
00177
              logging.pprint("Accepted modes: 'Generate', 'Train', 'Combine'")
00178
              exit(5)
```

# 9.29 markovPasswords.cpp File Reference

```
#include "markovPasswords.h"
#include <string.h>
#include <chrono>
#include <thread>
#include <vector>
#include <mutex>
#include <string>
#include <signal.h>
#include <unistd.h>
```

Include dependency graph for markovPasswords.cpp:



## **Functions**

• void intHandler (int dummy)

### **Variables**

• static volatile int keepRunning = 1

### 9.29.1 Function Documentation

### 9.29.1.1 intHandler()

Referenced by Markov::API::MarkovPasswords::Train().

Here is the caller graph for this function:



### 9.29.2 Variable Documentation

### 9.29.2.1 keepRunning

```
volatile int keepRunning = 1 [static]
Definition at line 16 of file markovPasswords.cpp.
Referenced by intHandler(), and Markov::API::MarkovPasswords::TrainThread().
```

# 9.30 markovPasswords.cpp

```
00001 #pragma once
00002 #include "markovPasswords.h"
00003 #include <string.h>
00004 #include <chrono>
00005 #include <thread>
00006 #include <vector>
00007 #include <mutex>
00008 #include <string>
00009 #include <signal.h>
00010 #ifdef _WIN32
00011 #include <Windows.h>
00012 #else
00013 #include <unistd.h>
00014 #endif
00015
00016 static volatile int keepRunning = 1;
00017
00018 void intHandler(int dummy) {
00019
         std::cout « "You wanted this man by presing CTRL-C ! Ok bye.";
          //Sleep(5000);
00020
00021
          keepRunning = 0;
          exit(0);
00023 }
00024
00025
00026 Markov::API::MarkovPasswords::MarkovPasswords() : Markov::Model<char>(){
00027
00028
00029 }
00030
00031 Markov::API::MarkovPasswords::MarkovPasswords(const char* filename) {
00032
00033
          std::ifstream* importFile;
00034
00035
          this->Import(filename);
00036
00037
          //std::ifstream* newFile(filename);
00038
          //importFile = newFile:
00039
00040
00041 }
00042
00043 std::ifstream* Markov::API::MarkovPasswords::OpenDatasetFile(const char* filename){
00044
00045
          std::ifstream* datasetFile;
00046
00047
          std::ifstream newFile(filename);
00048
00049
          datasetFile = &newFile;
00050
00051
          this->Import (datasetFile);
00052
          return datasetFile;
00053 }
00054
00055
00056
00057 void Markov::API::MarkovPasswords::Train(const char* datasetFileName, char delimiter, int threads)
00058
       signal(SIGINT, intHandler);
00059
          Markov::API::Concurrency::ThreadSharedListHandler listhandler(datasetFileName);
00060
          auto start = std::chrono::high_resolution_clock::now();
00061
00062
          std::vector<std::thread*> threadsV;
00063
          for(int i=0;i<threads;i++) {</pre>
00064
              threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::TrainThread, this,
       &listhandler, delimiter));
00065
         }
00066
00067
          for(int i=0;i<threads;i++){</pre>
00068
              threadsV[i]->join();
00069
              delete threadsV[i]:
00070
00071
          auto finish = std::chrono::high_resolution_clock::now();
00072
          std::chrono::duration<double> elapsed = finish - start;
00073
          std::cout « "Elapsed time: " « elapsed.count() « " sn";
00074
00075 }
00076
00077 void Markov::API::MarkovPasswords::TrainThread(Markov::API::Concurrency::ThreadSharedListHandler
       *listhandler, char delimiter){
00078
          char format_str[] ="%ld,%s";
00079
          format_str[2] = delimiter;
00080
          std::string line;
00081
          while (listhandler->next(&line) && keepRunning) {
00082
             long int oc;
              if (line.size() > 100) {
```


```
line = line.substr(0, 100);
00085
00086
              char* linebuf = new char[line.length()+5];
00087 #ifdef _WIN32
              sscanf_s(line.c_str(), "%ld,%s", &oc, linebuf, line.length()+5); //<== changed format_str to->
00088
       "%ld,%s"
00089 #else
00090
              sscanf(line.c_str(), format_str, &oc, linebuf);
00091 #endif
00092
              this->AdjustEdge((const char*)linebuf, oc);
00093
              delete linebuf;
00094
          }
00095 }
00096
00097
00098 std::ofstream* Markov::API::MarkovPasswords::Save(const char* filename) {
00099
          std::ofstream* exportFile;
00100
00101
          std::ofstream newFile(filename);
00102
00103
          exportFile = &newFile;
00104
00105
          this->Export (exportFile);
00106
          return exportFile;
00107 }
00108
00109
00110 void Markov::API::MarkovPasswords::Generate(unsigned long int n, const char* wordlistFileName, int
      minLen, int maxLen, int threads)
00111
          char* res:
          char print[100];
00112
00113
          std::ofstream wordlist;
00114
          wordlist.open(wordlistFileName);
00115
          std::mutex mlock;
00116
          int iterationsPerThread = n/threads;
          int iterationsCarryOver = n%threads;
00117
00118
          std::vector<std::thread*> threadsV;
00119
          for (int i=0;i<threads;i++) {</pre>
00120
              threadsV.push_back(new std::thread(&Markov::API::MarkovPasswords::GenerateThread, this,
       &mlock, iterationsPerThread, &wordlist, minLen, maxLen));
00121
        }
00122
          for(int i=0;i<threads;i++){</pre>
00123
00124
              threadsV[i]->join();
00125
              delete threadsV[i];
00126
00127
00128
          this->GenerateThread(&mlock, iterationsCarryOver, &wordlist, minLen, maxLen);
00129
00130 }
00131
00132 void Markov::API::MarkovPasswords::GenerateThread(std::mutex *outputLock, unsigned long int n,
       std::ofstream *wordlist, int minLen, int maxLen)
00133
          char* res = new char[maxLen+5];
          if(n==0) return;
00134
00135
00136
          Markov::Random::Marsaglia MarsagliaRandomEngine;
00137
          for (int i = 0; i < n; i++)
00138
              this->RandomWalk(&MarsagliaRandomEngine, minLen, maxLen, res);
              outputLock->lock();
*wordlist « res « "\n";
00139
00140
00141
              outputLock->unlock();
00142
          }
00143 }
```

### 9.31 markovPasswords.h File Reference


```
#include "threadSharedListHandler.h"
#include "MarkovModel/src/model.h"
```

9.32 markovPasswords.h 217

Include dependency graph for markovPasswords.h:



This graph shows which files directly or indirectly include this file:



## **Classes**

class Markov::API::MarkovPasswords
 Markov::Model with char represented nodes.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

## 9.32 markovPasswords.h

```
00014
           * This class is an extension of Markov::Model<char>, with higher level abstractions such as train
       and generate.
00015
00016
00017
          class MarkovPasswords : public Markov::Model<char>{
00018
          public:
00020
              /** @brief Initialize the markov model from MarkovModel::Markov::Model.
00021
00022
               * Parent constructor. Has no extra functionality.
00023
00024
              MarkovPasswords():
00025
00026
              /** @brief Initialize the markov model from MarkovModel::Markov::Model, with an import file.
00027
00028
               * This function calls the Markov::Model::Import on the filename to construct the model.
00029
               \star Same thing as creating and empty model, and calling MarkovPasswords::Import on the
       filename.
00030
00031
               * @param filename - Filename to import
00032
00033
              * @b Example @b Use: Construction via filename
00034
00035
              * @code{.cpp}
00036
               * MarkovPasswords mp("test.mdl");
00037
               * @endcode
00038
00039
              MarkovPasswords(const char* filename);
00040
00041
              /** @brief Open dataset file and return the ifstream pointer
00042
               * @param filename - Filename to open
00043
               * @return ifstream* to the the dataset file
00044
00045
              std::ifstream* OpenDatasetFile(const char* filename);
00046
00047
00048
              /** @brief Train the model with the dataset file.
              * @param datasetFileName - Ifstream* to the dataset. If null, use class member
00049
00050
               \star @param delimiter - a character, same as the delimiter in dataset content
00051
               * @param threads - number of OS threads to spawn
00052
00053
               * @code{.cpp}
              * Markov::API::MarkovPasswords mp;
00054
               * mp.Import("models/2gram.mdl");
00055
00056
               * mp.Train("password.corpus");
00057
               * @endcode
00058
00059
              void Train(const char* datasetFileName, char delimiter, int threads);
00060
00061
00062
00063
              /** @brief Export model to file.
00064
              \star @param filename - Export filename.
00065
              * @return std::ofstream* of the exported file.
00066
00067
              std::ofstream* Save(const char* filename);
00068
00069
              /** @brief Call Markov::Model::RandomWalk n times, and collect output.
00070
00071
               \star Generate from model and write results to a file.
               \star a much more performance-optimized method. FastRandomWalk will reduce the runtime by %96.5
00072
      on average.
00073
00074
               * @deprecated See Markov::API::MatrixModel::FastRandomWalk for more information.
00075
               * @param n - Number of passwords to generate.
00076
               * @param wordlistFileName - Filename to write to
               * @param minLen - Minimum password length to generate


* @param maxLen - Maximum password length to generate
00077
00078
00079
               * @param threads - number of OS threads to spawn
00080
              void Generate (unsigned long int n, const char* wordlistFileName, int minLen=6, int maxLen=12,
00081
       int threads=20);
00082
00083
00084
          private:
00085
00086
              /** @brief A single thread invoked by the Train function.
00087
               * @param listhandler - Listhandler class to read corpus from
00088
               \star @param delimiter - a character, same as the delimiter in dataset content
00089
00090
              */
00091
              void TrainThread(Markov::API::Concurrency::ThreadSharedListHandler *listhandler, char
       delimiter);
00092
00093
              /** @brief A single thread invoked by the Generate function.
00094
00095
               * @b DEPRECATED: See Markov::API::MatrixModel::FastRandomWalkThread for more information.
```

```
This has been replaced with
00096
                \star a much more performance-optimized method. FastRandomWalk will reduce the runtime by \$96.5
       on average.
00097
00098
                * @param outputLock - shared mutex lock to lock during output operation. Prevents race
       condition on write.
00099
               * @param n number of lines to be generated by this thread
00100
                \star @param wordlist wordlistfile
00101
                \star @param minLen - Minimum password length to generate
00102
                * @param maxLen - Maximum password length to generate
00103
00104
00105
               void GenerateThread(std::mutex *outputLock, unsigned long int n, std::ofstream *wordlist, int
00106
              std::ifstream* datasetFile; /** @brief Dataset file input of our system
               std::ofstream* modelSavefile; /** @brief File to save model of our system
std::ofstream* outputFile; /** @brief Generated output file of our system
00107
00108
          };
00109
00110
00111
00112
00113 };
```

# 9.33 MarkovPasswordsGUI.cpp File Reference

```
#include "MarkovPasswordsGUI.h"
#include <fstream>
#include <qwebengineview.h>
#include <Windows.h>
#include "CLI.h"
```

Include dependency graph for MarkovPasswordsGUI.cpp:




# 9.34 MarkovPasswordsGUI.cpp

```
00001 #include "MarkovPasswordsGUI.h"
00002 #include <fstream>
00003 #include <qwebengineview.h>
00004 #include <Windows.h>
00005 #include "CLI.h"
00006
00007 using namespace Markov::GUI;
00008
00009 MarkovPasswordsGUI::MarkovPasswordsGUI(QWidget *parent)
00010
          : QMainWindow(parent)
00011 {
          ui.setupUi(this);
00012
00013
00014
00015
          QObject::connect(ui.pushButton, &QPushButton::clicked, this, [this] {home(); });
00016
          QObject::connect(ui.pushButton_2, &QPushButton::clicked, this, [this] {model(); });
00017
          QObject::connect(ui.pushButton_3, &QPushButton::clicked, this, [this] {pass(); });
00018 }
00019
00020
00021 void MarkovPasswordsGUI::home() {
00022
         CLI* w = new CLI;
00023
          w->show();
00024
          this->close();
00025 }
00026 void MarkovPasswordsGUI::pass() {
          QWebEngineView* webkit = ui.centralWidget->findChild<QWebEngineView*>("chartArea");
```


```
00028
00029
          //get working directory
00030
          char path[255];
00031
          GetCurrentDirectoryA(255, path);
00032
00033
          //get absolute path to the layout html
00034
          std::string layout = "file:///" + std::string(path) + "\\views\\bar.html";
00035
          std::replace(layout.begin(), layout.end(), ' \setminus ', '/');
00036
          webkit->setUrl(QUrl(layout.c_str()));
00037 }
00038
00039 void MarkovPasswordsGUI::model() {
00040
          QWebEngineView* webkit = ui.centralWidget->findChild<QWebEngineView*>("chartArea");
00041
00042
          //get working directory
00043
          char path[255];
          GetCurrentDirectoryA(255, path);
00044
00045
00046
          //get absolute path to the layout html
00047
          std::string layout = "file:///" + std::string(path) + "\\views\\index.html";
          std::replace(layout.begin(), layout.end(), '\\', '/');
00048
00049
          webkit->setUrl(QUrl(layout.c_str()));
00050 }
```

## 9.35 MarkovPasswordsGUI.h File Reference

```
#include <QtWidgets/QMainWindow>
#include "ui_MarkovPasswordsGUI.h"
Include dependency graph for MarkovPasswordsGUI.h:
```



This graph shows which files directly or indirectly include this file:



### **Classes**

• class Markov::GUI::MarkovPasswordsGUI

Reporting UI.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

· Markov::GUI


namespace for MarkovPasswords API GUI wrapper

# 9.36 MarkovPasswordsGUI.h

```
00001 #pragma once
00002
00003 #include <QtWidgets/QMainWindow>
00004 #include "ui_MarkovPasswordsGUI.h"
00005
00006
00007
00008 namespace Markov::GUI{
00009
         /** @brief Reporting UI.
00011
          * UI for reporting and debugging tools for MarkovPassword
00012
         class MarkovPasswordsGUI : public QMainWindow {
00013
00014
              Q_OBJECT
00015
00016
         private:
00017
             Ui::MarkovPasswordsGUIClass ui;
00018
00019
00020
              //Slots for buttons in GUI.
00021
         public slots:
00022
              void MarkovPasswordsGUI::benchmarkSelected();
00024
              void MarkovPasswordsGUI::modelvisSelected();
00025
              void MarkovPasswordsGUI::visualDebugSelected();
00026
              void MarkovPasswordsGUI::comparisonSelected();
00027
00028
00029
       public slots:
00030
00031
            void MarkovPasswordsGUI::home();
00032
            void MarkovPasswordsGUI :: pass();
00033
            void MarkovPasswordsGUI::model();
00034
       };
00035 };
```

# 9.37 menu.cpp File Reference

```
#include "menu.h"
#include <fstream>
#include "MarkovPasswordsGUI.h"
#include <QtWidgets/QApplication>
Include dependency graph for menu.cpp:
```




# 9.38 menu.cpp

```
00001 #include "menu.h"
```


```
00002 #include <fstream>
00003 #include "MarkovPasswordsGUI.h"
00004 #include <QtWidgets/QApplication>
00005
00006 using namespace Markov::GUI;
00007
00008 menu::menu(QWidget* parent)
00009
            : QMainWindow(parent)
00010 {
00011
           ui.setupUi(this);
00012
00013
           //QObject::connect(ui.pushButton, &QPushButton::clicked, this, [this] {about(); }); QObject::connect(ui.visu, &QPushButton::clicked, this, [this] {visualization(); });
00014
00015
00016 }
00017 void menu::about() {
00018
00019
00020 }
00021 void menu::visualization() {
00022
           MarkovPasswordsGUI* w = new MarkovPasswordsGUI;
00023
            w->show();
00024
           this->close();
00025 }
```

## 9.39 menu.h File Reference

```
#include <QtWidgets/QMainWindow>
#include "ui_menu.h"
Include dependency graph for menu.h:
```



This graph shows which files directly or indirectly include this file:



9.40 menu.h 223

### **Classes**

· class Markov::GUI::menu

QT Menu class.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::GUI

namespace for MarkovPasswords API GUI wrapper


## 9.40 menu.h

```
00001 #pragma once
00002 #include <QtWidgets/QMainWindow>
00003 #include "ui_menu.h"
00004
00005
00006 namespace Markov::GUI{
          /** @brief QT Menu class
00007
80000
00009
          class menu:public QMainWindow {
00010
          Q_OBJECT
00011
          public:
00012
              menu(QWidget* parent = Q_NULLPTR);
00013
00014
          private:
              Ui::main ui;
00015
00016
00017
          public slots:
00018
             void about();
00019
               void visualization();
00020
00021 };
```


# 9.41 model.h File Reference

```
#include <map>
#include <vector>
#include <fstream>
#include <assert.h>
#include <string>
#include <algorithm>
#include "node.h"
#include "edge.h"
```

Include dependency graph for model.h:



This graph shows which files directly or indirectly include this file:



#### Classes

class Markov::Node < storageType >

A node class that for the vertices of model. Connected with eachother using Edge.

class Markov::Edge < NodeStorageType >

Edge class used to link nodes in the model together.

class Markov::Model < NodeStorageType >

class for the final Markov Model, constructed from nodes and edges.

### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

### 9.42 model.h

```
00001 /** @dir Model.h
00002
00003
00004
00005
00006 #pragma once
00007 #include <map>
00008 #include <vector>
00009 #include <fstream>
00010 #include <assert.h>
00011 #include <string>
00012 #include <algorithm>
00013 #include "node.h"
00014 #include "edge.h"
00015
00016 /**
00017
         Obrief Namespace for the markov-model related classes.
00018
          Contains Model, Node and Edge classes
00019 */
00020 namespace Markov {
00021
00022
           template <typename NodeStorageType>
00023
          class Node;
00024
00025
           template <typename NodeStorageType>
00026
          class Edge;
00027
00028
           template <typename NodeStorageType>
00029
00030
           /\star\star @brief class for the final Markov Model, constructed from nodes and edges.
00031
00032
            * Each atomic piece of the generation result is stored in a node, while edges contain the
       relation weights.
00033
            * *Extending:*
```

9.42 model.h 225

```
00034
           \star To extend the class, implement the template and inherit from it, as "class MyModel : public
       Markov::Model<char>"
00035
           \star For a complete demonstration of how to extend the class, see MarkovPasswords.
00036
           \star Whole model can be defined as a list of the edges, as dangling nodes are pointless. This
00037
       approach is used for the import/export operations.
00038
          * For more information on importing/exporting model, check out the github readme and wiki page.
00039
00040
00041
         class Model {
00042
         public:
00043
00044
              00045
00046
               * Initialize an empty model with only a starterNode
00047
               \star Starter node is a special kind of node that has constant 0x00 value, and will be used to
       initiate the generation execution from.
00048
00049
              Model<NodeStorageType>();
00050
00051
              /** @brief Do a random walk on this model.
00052
00053
               \star Start from the starter node, on each node, invoke RandomNext using the random engine on
       current node, until terminator node is reached.
   * If terminator node is reached before minimum length criateria is reached, ignore the last
00054
       selection and re-invoke randomNext
00055
00056
               \star If maximum length criteria is reached but final node is not, cut off the generation and
       proceed to the final node.
00057
               * This function takes Markov::Random::RandomEngine as a parameter to generate pseudo random
       numbers from
00058
               \star This library is shipped with two random engines, Marsaglia and Mersenne. While mersenne
       output is higher in entropy, most use cases
00060
               * don't really need super high entropy output, so Markov::Random::Marsaglia is preferable for
       better performance.
00061
00062
               * This function WILL NOT reallocate buffer. Make sure no out of bound writes are happening
       via maximum length criteria.
00063
00064
               \star 0b Example 0b Use: Generate 10 lines, with 5 to 10 characters, and print the output. Use
      Marsaglia
              * @code{.cpp}
00065
00066
               * Markov::Model<char> model;
               * Model.import("model.mdl");
00067
00068
               * char* res = new char[11];
00069
               * Markov::Random::Marsaglia MarsagliaRandomEngine;
00070
              * for (int i = 0; i < 10; i++) {
00071
                      this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
00072
                      std::cout « res « "\n";
00073
00074
               * @endcode
00075
00076
               \star @param randomEngine Random Engine to use for the random walks. For examples, see
      Markov::Random::Mersenne and Markov::Random::Marsaglia
00077
              * @param minSetting Minimum number of characters to generate
00078
               * @param maxSetting Maximum number of character to generate
00079
               * @param buffer buffer to write the result to
00080
              * @return Null terminated string that was generated.
00081
00082
              NodeStorageType* RandomWalk (Markov::Random::RandomEngine* randomEngine, int minSetting, int
      maxSetting, NodeStorageType* buffer);
00083
00084
              /** @brief Adjust the model with a single string.
00085
00086
               \star Start from the starter node, and for each character, AdjustEdge the edge EdgeWeight from
       current node to the next, until NULL character is reached.
00087
00088
               * Then, update the edge EdgeWeight from current node, to the terminator node.
               \star This function is used for training purposes, as it can be used for adjusting the model with
00090
       each line of the corpus file.
00091
00092
               * @b Example @b Use: Create an empty model and train it with string: "testdata"
00093
               * @code{.cpp}
               * Markov::Model<char> model;
00094
00095
               * char test[] = "testdata";
00096
               * model.AdjustEdge(test, 15);
00097
               * @endcode
00098
00099
00100
               * @param string - String that is passed from the training, and will be used to AdjustEdge the
       model with
00101
              * @param occurrence - Occurrence of this string.
00102
00103
              */
00104
```

```
void AdjustEdge(const NodeStorageType* payload, long int occurrence);
00106
00107
             /** @brief Import a file to construct the model.
00108
              \star File contains a list of edges. For more info on the file format, check out the wiki and
00109
      github readme pages.
00110
              * Format is: Left_repr; EdgeWeight; right_repr
00111
00112
              \star Iterate over this list, and construct nodes and edges accordingly.
00113
              * @return True if successful, False for incomplete models or corrupt file formats
00114
00115
              * @b Example @b Use: Import a file from ifstream
00116
              * @code{.cpp}
00117
              * Markov::Model<char> model;
00118
              * std::ifstream file("test.mdl");
00119
              * model.Import(&file);
00120
              * Gendoode
00121
00122
             bool Import(std::ifstream*);
00123
00124
             00125
              \star @return True if successful, False for incomplete models or corrupt file formats
00126
00127
              * @b Example @b Use: Import a file with filename
00128
              * @code{.cpp}
              * Markov::Model<char> model;
00129
00130
              * model.Import("test.mdl");
00131
              * @endcode
00132
00133
             bool Import (const char* filename);
00134
00135
             /** @brief Export a file of the model.
00136
00137
              * File contains a list of edges.
00138
              * Format is: Left_repr; EdgeWeight; right_repr.
              * For more information on the format, check out the project wiki or github readme.
00139
00140
00141
              \star Iterate over this vertices, and their edges, and write them to file.
00142
              * @return True if successful, False for incomplete models.
00143
00144
              * @b Example @b Use: Export file to ofstream
00145
              * @code{.cpp}
00146
              * Markov::Model<char> model:
              * std::ofstream file("test.mdl");
00147
00148
                model.Export(&file);
00149
              * @endcode
00150
00151
             bool Export(std::ofstream*);
00152
00153
             /** @brief Open a file to export with filename, and call bool Model::Export with std::ofstream
00154
              * @return True if successful, False for incomplete models or corrupt file formats
00155
00156
              * @b Example @b Use: Export file to filename
00157
              * @code{.cpp}
              * Markov::Model<char> model;
00158
              * model.Export("test.mdl");
00159
00160
              * @endcode
00161
00162
             bool Export(const char* filename);
00163
             /** @brief Return starter Node
00164
00165
              * @return starter node with 00 NodeValue
00166
00167
             Node<NodeStorageType>* StarterNode() { return starterNode;}
00168
00169
              /** Obrief Return a vector of all the edges in the model
00170
              * @return vector of edges
00171
00172
             std::vector<Edge<NodeStorageType>*>* Edges() { return &edges;}
00173
00174
              /** @brief Return starter Node
00175
              \star @return starter node with 00 NodeValue
00176
00177
             std::map<NodeStorageType, Node<NodeStorageType>*>* Nodes() { return &nodes;}
00178
00179
         private:
00180
00181
                 @brief Map LeftNode is the Nodes NodeValue
00182
                 \star Map RightNode is the node pointer
00183
             std::map<NodeStorageType, Node<NodeStorageType>*> nodes;
00184
00185
00186
00187
                 @brief Starter Node of this model.
00188
00189
             Node<NodeStorageType>* starterNode;
00190
```

9.42 model.h 227

```
00192
00193
                  Obrief A list of all edges in this model.
00194
00195
               std::vector<Edge<NodeStorageType>*> edges;
00196
          };
00197
00198 };
00199
00200 template <typename NodeStorageType>
00201 Markov::Model<NodeStorageType>::Model() {
          this->starterNode = new Markov::Node<NodeStorageType>(0);
00202
00203
          this->nodes.insert({ 0, this->starterNode });
00204 }
00205
00206 template <typename NodeStorageType>
00207 bool Markov::Model<NodeStorageType>::Import(std::ifstream* f) {
00208
          std::string cell;
00210
          char src;
00211
          char target;
00212
          long int oc;
00213
          while (std::getline(*f, cell)) {
    //std::cout « "cell: " « cell « std::endl;
00214
00215
               src = cell[0];
00216
00217
               target = cell[cell.length() - 1];
00218
               char* j;
               oc = std::strtol(cell.substr(2, cell.length() - 2).c_str(),&j,10);
//std::cout « oc « "\n";
00219
00220
00221
               Markov::Node<NodeStorageType>* srcN;
00222
               Markov::Node<NodeStorageType>* targetN;
00223
               Markov::Edge<NodeStorageType>* e;
00224
               if (this->nodes.find(src) == this->nodes.end()) {
00225
                   srcN = new Markov::Node<NodeStorageType>(src);
                   this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(src, srcN));
00226
00227
                   //std::cout « "Creating new node at start.\n";
00229
               else {
00230
                  srcN = this->nodes.find(src)->second;
00231
               }
00232
               if (this->nodes.find(target) == this->nodes.end()) {
00233
00234
                   targetN = new Markov::Node<NodeStorageType>(target);
00235
                   this->nodes.insert(std::pair<char, Markov::Node<NodeStorageType>*>(target, targetN));
00236
                   //std::cout « "Creating new node at end.\n";
00237
00238
               else {
00239
                   targetN = this->nodes.find(target)->second;
00240
               e = srcN->Link(targetN);
00241
00242
               e->AdjustEdge(oc);
00243
               this->edges.push_back(e);
00244
              //std::cout « int(srcN->NodeValue()) « " --" « e->EdgeWeight() « "--> " «
00245
       int(targetN->NodeValue()) « "\n";
00246
00247
00248
00249
          00250
               //std::cout « "Total edges in EdgesV: " « x.second->edgesV.size() « "\n";
00251
00252
               std::sort (x.second->edgesV.begin(), x.second->edgesV.end(), [](Edge<NodeStorageType> *lhs,
       Edge<NodeStorageType> *rhs) ->bool{
00253
                   return lhs->EdgeWeight() > rhs->EdgeWeight();
00254
               //for(int i=0;i<x.second->edgesV.size();i++)
// std::cout « x.second->edgesV[i]->EdgeWeight() « ", ";
//std::cout « "\n";
00255
00256
00257
00258
          //std::cout « "Total number of nodes: " « this->nodes.size() « std::endl; //std::cout « "Total number of edges: " « this->edges.size() « std::endl;
00259
00260
00261
00262
          return true;
00263 }
00264
00265 template <typename NodeStorageType>
00266 bool Markov::Model<NodeStorageType>::Import(const char* filename) {
00267
          std::ifstream importfile;
00268
          importfile.open(filename);
00269
          return this->Import(&importfile);
00270
00271 }
00272
00273 template <typename NodeStorageType>
00274 bool Markov::Model<NodeStorageType>::Export(std::ofstream* f) {
00275
          Markov::Edge<NodeStorageType>* e;
```

```
for (std::vector<int>::size_type i = 0; i != this->edges.size(); i++) {
           e = this->edges[i];
             //std::cout « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," «
00278
       e->RightNode()->NodeValue() « "\n";
             *f « e->LeftNode()->NodeValue() « "," « e->EdgeWeight() « "," « e->RightNode()->NodeValue() «
00279
       "\n";
00280
00281
00282
         return true;
00283 }
00284
00285 template <typename NodeStorageType>
00286 bool Markov::Model<NodeStorageType>::Export(const char* filename) {
00287
        std::ofstream exportfile;
00288
         exportfile.open(filename);
00289
         return this->Export(&exportfile);
00290 }
00291
00292 template <typename NodeStorageType>
00293 NodeStorageType* Markov::Model<NodeStorageType>::RandomWalk(Markov::Random::RandomEngine*
      randomEngine, int minSetting, int maxSetting, NodeStorageType* buffer) {
00294
         Markov::Node<NodeStorageType>* n = this->starterNode;
00295
          int len = 0;
00296
         Markov::Node<NodeStorageType>* temp_node;
00297
         while (true) {
00298
            temp_node = n->RandomNext(randomEngine);
00299
              if (len >= maxSetting) {
00300
                 break;
00301
00302
             else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00303
                 continue:
00304
00305
00306
              else if (temp_node == NULL) {
00307
                  break;
             }
00308
00309
00310
             n = temp_node;
00311
00312
             buffer[len++] = n->NodeValue();
00313
00314
00315
          //null terminate the string
00316
         buffer[len] = 0x00;
00317
00318
          //do something with the generated string
00319
          return buffer; //for now
00320 }
00321
00322 template <tvpename NodeStorageType>
00323 void Markov::Model<NodeStorageType>::AdjustEdge(const NodeStorageType* payload, long int occurrence) {
00324
         NodeStorageType p = payload[0];
00325
          Markov::Node<NodeStorageType>* curnode = this->starterNode;
00326
         Markov::Edge<NodeStorageType>* e;
00327
         int i = 0;
00328
         if (p == 0) return;
00330
         while (p != 0) {
00331
           e = curnode->FindEdge(p);
             if (e == NULL) return;
00332
00333
             e->AdjustEdge(occurrence);
00334
             curnode = e->RightNode();
             p = payload[++i];
00335
00336
00337
00338
         e = curnode->FindEdge('\xff');
00339
          e->AdjustEdge(occurrence);
00340
          return:
00341 }
```

## 9.43 model 2gram.py File Reference

### **Namespaces**

model\_2gram

### **Variables**

• model 2gram.alphabet = string.printable

password alphabet

9.44 model\_2gram.py 229

```
    model_2gram.f = open('../../models/2gram.mdl', "wb")
    output file handle
```


# 9.44 model\_2gram.py

```
00001 #!/usr/bin/python3 00002 """
00003
        python script for generating a 2gram model
00004 """
00005
00006 import string
00007 import re
80000
00009
00010 alphabet = string.printable
00011 alphabet = re.sub('\s', ", alphabet)
00012 print(f"alphabet={alphabet}")
00013 #exit()
00014
00015
00016 f = open('../../models/2gram.mdl', "wb")
00017 #tie start nodes
00018 for sym in alphabet:
00019 f.write(b"\x00,1," + bytes(sym, encoding='ascii') + b"\n")
00020
00021 #tie terminator nodes
00022 for sym in alphabet:
00023
          f.write(bytes(sym, encoding='ascii')+ b",1,\xff\n")
00024
00025 #tie internals
00026 for src in alphabet:
           for target in alphabet:
                f.write(bytes(src, encoding='ascii') + b",1," + bytes(target, encoding='ascii') + b"\n")
```

# 9.45 modelMatrix.cpp File Reference

```
#include "modelMatrix.h"
#include <map>
#include <cstring>
#include <thread>
```

Include dependency graph for modelMatrix.cpp:



# 9.46 modelMatrix.cpp

```
00001 #include "modelMatrix.h"
00002 #include <map>
00003 #include <cstring>
00004 #include <thread>
00005
00005 Markov::API::ModelMatrix::ModelMatrix(){
```

```
00009
00010
00011 void Markov::API::ModelMatrix::ConstructMatrix() {
            this->matrixSize = this->StarterNode()->edgesV.size() + 2;
00012
00013
            this->matrixIndex = new char[this->matrixSize];
00015
            this->totalEdgeWeights = new long int[this->matrixSize];
00016
            this->edgeMatrix = new char*[this->matrixSize];
for(int i=0;i<this->matrixSize;i++) {
00017
00018
                 this->edgeMatrix[i] = new char[this->matrixSize];
00019
00020
00021
            this->valueMatrix = new long int*[this->matrixSize];
00022
            for(int i=0;i<this->matrixSize;i++) {
00023
                 this->valueMatrix[i] = new long int[this->matrixSize];
00024
00025
            std::map< char, Node< char > * > *nodes;
            nodes = this->Nodes();
00027
            int i=0;
00028
            for (auto const& [repr, node] : *nodes) {
                 tauto Consta [Tepf, Nodes] . *Nodes]{
if (repr!=0) this->matrixIndex[i] = repr;
else this->matrixIndex[i] = 199;
this->totalEdgeWeights[i] = node->TotalEdgeWeights();
for (int j=0; j<this->matrixSize; j++) {
   char val = node->NodeValue();
}
00029
00030
00031
00032
00033
00034
                       if(val < 0){</pre>
00035
                            for(int k=0;k<this->matrixSize;k++){
00036
                                 this->valueMatrix[i][k] = 0;
                                 this->edgeMatrix[i][k] = 255;
00037
00038
00039
                            break:
00040
00041
                       else if(node->NodeValue() == 0 && j>(this->matrixSize-3)){
                            this->valueMatrix[i][j] = 0;
this->edgeMatrix[i][j] = 255;
00042
00043
00044
                       }else if(j==(this->matrixSize-1))
                            this->valueMatrix[i][j] = 0;
00046
                            this->edgeMatrix[i][j] = 255;
00047
                       }else{
00048
                            this->valueMatrix[i][j] = node->edgesV[j]->EdgeWeight();
00049
                            this->edgeMatrix[i][j] = node->edgesV[j]->RightNode()->NodeValue();
00050
00051
00052
                 i++;
00053
00054
            }
00055
00056
            //this->DumpJSON();
00057 }
00059
00060 void Markov::API::ModelMatrix::DumpJSON() {
00061
            std::cout « "{\n \"index\": \"";
00062
            std::cout « "{\n \"index\": \"";
for(int i=0;i<this->matrixSize;i++) {
    if(this->matrixIndex[i]=='\"') std::cout « \"\\\";
    else if(this->matrixIndex[i]=='\\') std::cout « \"\\\";
    else if(this->matrixIndex[i]==0) std::cout « \"\\\x00";
    else if(i=0) std::cout « \"\\\xff";
    else if(this->matrixIndex[i]=='\n') std::cout « \"\\n";
00063
00065
00066
00067
00068
                 else std::cout « this->matrixIndex[i];
00069
00070
00071
            std::cout «
00072
00073
                 \"edgemap\": {\n";
00074
                 00075
            for(int i=0;i<this->matrixSize;i++){
00076
                                                                                  \"\\\\": [";
\"\\\x00\": [";
00078
00079
00080
00081
00082
00083
00084
00085
00086
00087
00088
00090
                 std::cout « "], \n";
00091
00092
            std::cout « "},\n";
00093
00094
            std::cout « "\" weightmap\": {\n";
```

9.46 modelMatrix.cpp 231


```
for(int i=0;i<this->matrixSize;i++) {
              if(this->matrixIndex[i]=='"') std::cout « " \"\\\"\": [";
else if(this->matrixIndex[i]=='\\') std::cout « " \"\\\\": [";
else if(this->matrixIndex[i]==0) std::cout « " \"\\\x00\": [";
else if(this->matrixIndex[i]=0) std::cout « " \"\\\xff\": [";
else std::cout « " \"" « this->matrixIndex[i] « "\": [";
00096
00097
00098
00099
               else std::cout « "
00100
00101
00102
                for(int j=0;j<this->matrixSize;j++){
00103
                   std::cout « this->valueMatrix[i][j];
                    if(j!=this->matrixSize-1) std::cout « ", ";
00104
00105
00106
                std::cout « "], \n";
00107
00108
           std::cout « " }\n}\n";
00109 }
00110
00111
00112 void Markov::API::ModelMatrix::FastRandomWalkThread(std::mutex *mlock, std::ofstream *wordlist,
       unsigned long int n, int minLen, int maxLen, int id, bool bFileIO) {
00113
           if(n==0) return;
00114
00115
           Markov::Random::Marsaglia MarsagliaRandomEngine;
00116
           char* e;
           char *res = new char[maxLen*n];
00117
00118
           int index = 0;
00119
           char next;
00120
           int len=0;
00121
           long int selection;
00122
           char cur;
           long int bufferctr = 0;
00123
00124
           for (int i = 0; i < n; i++) {</pre>
00125
               cur=199;
00126
                len=0;
00127
                while (true) {
00128
                    e = strchr(this->matrixIndex, cur);
00129
                    index = e - this->matrixIndex;
                    selection = MarsagliaRandomEngine.random() % this->totalEdgeWeights[index];
00130
                    for(int j=0;j<this->matrixSize;j++){
00131
00132
                        selection -= this->valueMatrix[index][j];
00133
                         if (selection < 0) {</pre>
00134
                             next = this->edgeMatrix[index][j];
00135
                             break:
00136
00137
                    }
00138
00139
                    if (len >= maxLen) break;
                    else if ((next < 0) && (len < minLen)) continue;
else if (next < 0) break;</pre>
00140
00141
00142
                    cur = next;
00143
                    res[bufferctr + len++] = cur;
00144
00145
                res[bufferctr + len++] = '\n';
00146
               bufferctr+=len;
00147
00148
00149
           if(bFileIO) {
              mlock->lock();
00151
                *wordlist « res;
00152
                mlock->unlock();
00153
           }else{
              mlock->lock();
00154
00155
               std::cout « res;
00156
               mlock->unlock();
00157
00158
           delete res;
00159
00160 }
00161
00162
00163 void Markov::API::ModelMatrix::FastRandomWalk(unsigned long int n, const char* wordlistFileName, int
       minLen, int maxLen, int threads, bool bFileIO) {
00164
00165
00166
           std::ofstream wordlist;
00167
           if (bFileIO)
00168
               wordlist.open(wordlistFileName);
00169
00170
           std::mutex mlock;
00171
           if (n<=50000000ull) return this->FastRandomWalkPartition (&mlock, &wordlist, n, minLen, maxLen,
       bFileIO, threads);
00172
          else{
00173
               int numberOfPartitions = n/50000000ull;
00174
                for(int i=0;i<numberOfPartitions;i++)</pre>
00175
                    this->FastRandomWalkPartition(&mlock, &wordlist, 50000000ull, minLen, maxLen, bFileIO,
        threads);
00176
00177
```

```
00178
00179 }
00180
00181
00182 void Markov::API::ModelMatrix::FastRandomWalkPartition(std::mutex *mlock, std::ofstream *wordlist,
                       unsigned long int n, int minLen, int maxLen, bool bFileIO, int threads) {
00183
00184
                                   int iterationsPerThread = n/threads;
00185
                                  int iterationsPerThreadCarryOver = n%threads;
00186
00187
                                  std::vector<std::thread*> threadsV;
00188
                                  int id = 0;
for(int i=0;i<threads;i++){</pre>
00189
00190
00191
                                               threads V.push\_back (\texttt{new std::thread}(\&Markov::API::ModelMatrix::FastRandomWalkThread, this, the statement of the stateme
                       mlock, wordlist, iterationsPerThread, minLen, maxLen, id, bFileIO));
00192
                                               id++;
00193
00194
00195
                                  threadsV.push_back(new std::thread(&Markov::API::ModelMatrix::FastRandomWalkThread, this, mlock,
                       wordlist, iterationsPerThreadCarryOver, minLen, maxLen, id, bFileIO));
00196
00197
                                  for(int i=0;i<threads;i++){</pre>
00198
                                               threadsV[i]->join();
00199
00200 }
```


## 9.47 modelMatrix.h File Reference

```
#include "markovPasswords.h"
#include <mutex>
```

Include dependency graph for modelMatrix.h:



This graph shows which files directly or indirectly include this file:



9.48 modelMatrix.h

#### **Classes**

class Markov::API::ModelMatrix

Class to flatten and reduce Markov::Model to a Matrix.

### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

## 9.48 modelMatrix.h

```
00001 #include "markovPasswords.h"
00002 #include <mutex>
00004 namespace Markov::API{
00005
00006
           /** @brief Class to flatten and reduce Markov::Model to a Matrix
00007
80000
            * Matrix level operations can be used for Generation events, with a significant performance
       optimization at the cost of O(N) memory complexity (O(1) memory space for slow mode)
00009
       \star To limit the maximum memory usage, each generation operation is partitioned into 50M chunks for allocation. Threads are sychronized and files are flushed every 50M operations.
00010
00011
00012
          class ModelMatrix : public Markov::API::MarkovPasswords{
00014
          public:
00015
               ModelMatrix();
00016
00017
               /** @brief Construct the related Matrix data for the model.
00018
00019
                \star This operation can be used after importing/training to allocate and populate the matrix
       content.
00020
00021
               * this will initialize:
               \star char** edgeMatrix -> a 2D array of mapping left and right connections of each edge.
00022
00023
               * long int **valueMatrix -> a 2D array representing the edge weights.
00024
               * int matrixSize -> Size of the matrix, aka total number of nodes.
00025
                \star char* matrixIndex -> order of nodes in the model
00026
                * long int *totalEdgeWeights -> total edge weights of each Node.
00027
00028
               void ConstructMatrix();
00029
00030
00031
               /** @brief Debug function to dump the model to a JSON file.
00032
00033
                \star Might not work 100%. Not meant for production use.
00034
00035
               void DumpJSON();
00036
00037
00038
               /** @brief Random walk on the Matrix-reduced Markov::Model
00039
00040
                \star This has an O(N) Memory complexity. To limit the maximum usage, requests with n>50M are
       partitioned using Markov::API::ModelMatrix::FastRandomWalkPartition.
00041
00042
                \star If n>50M, threads are going to be synced, files are going to be flushed, and buffers will
       be reallocated every 50M generations.
00043
                \star This comes at a minor performance penalty.
00044
                \star While it has the same functionality, this operation reduces
00045
       Markov::API::MarkovPasswords::Generate runtime by %96.5
00046
00047
                \star \  \, \text{This function has deprecated Markov::API::MarkovPasswords::Generate, and will eventually}
       replace it.
00048
00049
                * @param n - Number of passwords to generate.
                * @param wordlistFileName - Filename to write to
00050
00051
                * @param minLen - Minimum password length to generate
00052
                  @param maxLen - Maximum password length to generate
                * @param threads - number of OS threads to spawn
* @param bFileIO - If false, filename will be ignored and will output to stdout.
00053
00054
00055
00056
00057
                * @code{.cpp}
00058
                * Markov::API::ModelMatrix mp;
```


```
* mp.Import("models/finished.mdl");
00060
               * mp.FastRandomWalk(50000000,"./wordlist.txt",6,12,25, true);
00061
               * @endcode
00062
00063
00064
              void FastRandomWalk (unsigned long int n, const char* wordlistFileName, int minLen=6, int
       maxLen=12, int threads=20, bool bFileIO=true);
00065
00066
          protected:
00067
00068
              /** @brief A single partition of FastRandomWalk event
00069
00070
               * Since FastRandomWalk has to allocate its output buffer before operation starts and writes
       data in chunks,
00071
              * large n parameters would lead to huge memory allocations.
00072
               \star @b Without @b Partitioning:
               * - 50M results 12 characters max -> 550 Mb Memory allocation
00073
00074
00075
               \star - 5B results 12 characters max -> 55 Gb Memory allocation
00076
00077
               * - 50B results 12 characters max -> 550GB Memory allocation
00078
00079
               * Instead, FastRandomWalk is partitioned per 50M generations to limit the top memory need.
00080
00081
               * @param mlock - mutex lock to distribute to child threads
               * @param wordlist - Reference to the wordlist file to write to
00082
00083
               \star @param n - Number of passwords to generate.
00084
               * @param wordlistFileName - Filename to write to
00085
               * @param minLen - Minimum password length to generate
               * @param maxLen - Maximum password length to generate
00086
00087
               * @param threads - number of OS threads to spawn
00088
               * @param bFileIO - If false, filename will be ignored and will output to stdout.
00089
00090
00091
              void FastRandomWalkPartition(std::mutex *mlock, std::ofstream *wordlist, unsigned long int n,
00092
       int minLen, int maxLen, bool bFileIO, int threads);
00093
00094
              /** @brief A single thread of a single partition of FastRandomWalk
00095
00096
               * A FastRandomWalkPartition will initiate as many of this function as requested.
00097
00098
               * This function contains the bulk of the generation algorithm.
00099
00100
              * @param mlock - mutex lock to distribute to child threads
00101
               * @param wordlist - Reference to the wordlist file to write to
00102
               * @param n - Number of passwords to generate.
00103
               * @param wordlistFileName - Filename to write to
               * @param minLen - Minimum password length to generate  
* @param maxLen - Maximum password length to generate
00104
00105
                 @param id - @b DEPRECATED Thread id - No longer used
00106
00107
               * @param bFileIO - If false, filename will be ignored and will output to stdout.
00108
00109
00110
              void FastRandomWalkThread(std::mutex *mlock, std::ofstream *wordlist, unsigned long int n, int
00111
       minLen, int maxLen, int id, bool bFileIO);
00112
00113
00114
                 @brief 2-D Character array for the edge Matrix (The characters of Nodes)
              */
00115
00116
              char** edgeMatrix;
00117
00118
00119
                @brief 2-d Integer array for the value Matrix (For the weights of Edges)
00120
              long int **valueMatrix;
00121
00122
00123
              . @brief to hold Matrix size */
00124
00125
00126
              int matrixSize;
00127
00128
00129
                @brief to hold the Matrix index (To hold the orders of 2-D arrays')
00130
00131
              char* matrixIndex;
00132
00133
                 @brief Array of the Total Edge Weights
00134
00135
00136
              long int *totalEdgeWeights;
00137
00138
00139
00140
00141 };
```

9.49 node.h File Reference 235


## 9.49 node.h File Reference

```
#include <vector>
#include <map>
#include <assert.h>
#include <iostream>
#include <stdexcept>
#include "edge.h"
#include "random.h"
```

Include dependency graph for node.h:



This graph shows which files directly or indirectly include this file:



### **Classes**

class Markov::Node < storageType >

A node class that for the vertices of model. Connected with eachother using Edge.

## **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

## 9.50 node.h

00001 #pragma once 00002 #include <vector>

```
00003 #include <map>
00004 #include <assert.h>
00005 #include <iostream>
00006 #include <stdexcept> // To use runtime_error
00007 #include "edge.h"
00008 #include "random.h"
00009 namespace Markov {
00010
00011
          /\star\star @brief A node class that for the vertices of model. Connected with eachother using Edge
00012
00013
          * This class will later be templated to accept other data types than char*.
00014
00015
          template <typename storageType>
00016
          class Node {
00017
          public:
00018
              /\!\star\!\star @brief Default constructor. Creates an empty Node.
00019
00020
00021
              Node<storageType>();
00022
00023
              /** @brief Constructor. Creates a Node with no edges and with given NodeValue.
00024
               * @param _value - Nodes character representation.
00025
00026
               * @b Example @b Use: Construct nodes
00027
               * @code{.cpp}
00028
               * Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00029
               * Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00030
               * @endcode
00031
00032
              Node<storageType>(storageType _value);
00033
00034
              /** @brief Link this node with another, with this node as its source.
00035
               * Creates a new Edge.
00036
00037
               * @param target - Target node which will be the RightNode() of new edge.
00038
               * @return A new node with LeftNode as this, and RightNode as parameter target.
00039
              * @b Example @b Use: Construct nodes
00040
00041
               * @code{.cpp}
00042
               * Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00043
               * Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00044
               * Markov::Edge<unsigned char>* e = LeftNode->Link(RightNode);
00045
               * @endcode
00046
00047
              Edge<storageType>* Link(Node<storageType>*);
00048
00049
              /** @brief Link this node with another, with this node as its source.
00050
00051
               * *DOES NOT* create a new Edge.
               * @param Edge - Edge that will accept this node as its LeftNode.
00052
00053
               * @return the same edge as parameter target.
00054
00055
               * @b Example @b Use: Construct and link nodes
00056
               * @code{.cpp}
00057
               * Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00058
               * Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
               * Markov::Edge<unsigned char>* e = LeftNode->Link(RightNode);
00059
00060
               * LeftNode->Link(e):
00061
               * @endcode
00062
00063
              Edge<storageType>* Link(Edge<storageType>*);
00064
00065
               /** @brief Chose a random node from the list of edges, with regards to its EdgeWeight, and
       TraverseNode to that.
00066
00067
               * This operation is done by generating a random number in range of 0-this.total_edge_weights,
       and then iterating over the list of edges. 
 \star At each step, EdgeWeight of the edge is subtracted from the random number, and once it is
00068
       0, next node is selected.
00069
               \star @return Node that was chosen at EdgeWeight biased random.
00070
00071
               \star @b Example @b Use: Use randomNext to do a random walk on the model
00072
               * @code{.cpp}
00073
               * char* buffer[64];
00074
               * Markov::Model<char> model;
               * model.Import("model.mdl");
00075
00076
               * Markov::Node<char>* n = model.starterNode;
00077
                  int len = 0;
00078
               * Markov::Node<char>* temp_node;
00079
               * while (true) {
                     temp_node = n->RandomNext(randomEngine);
08000
00081
                      if (len >= maxSetting) {
00082
00083
00084
                      else if ((temp_node == NULL) && (len < minSetting)) {</pre>
00085
                          continue;
00086
                      }
```

9.50 node.h 237

```
00088
                         else if (temp_node == NULL) {
                             break;
00089
00090
00091
00092
                        n = temp node;
00093
00094
                        buffer[len++] = n->NodeValue();
00095
00096
                * @endcode
00097
00098
               Node<storageType>* RandomNext(Markov::Random::RandomEngine* randomEngine);
00099
00100
               /** @brief Insert a new edge to the this.edges.
00101
                * @param edge - New edge that will be inserted.
00102
                 \star @return true if insertion was successful, false if it fails.
00103
00104
                * @b Example @b Use: Construct and update edges
00105
                * @code{.cpp}
00106
00107
                * Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                * Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
* Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00108
00109
                * Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
* Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target2);
00110
00111
                * e1->AdjustEdge(25);
00112
00113
                * src->UpdateEdges(e1);
00114
                * e2->AdjustEdge(30);
00115
                * src->UpdateEdges(e2);
00116
                * @endcode
00117
00118
               bool UpdateEdges(Edge<storageType>*);
00119
00120
               /\!\star\!\star @brief Find an edge with its character representation.
00121
                 \star @param repr - character NodeValue of the target node.
00122
                * @return Edge that is connected between this node, and the target node.
00123
00124
                * @b Example @b Use: Construct and update edges
00125
00126
                * @code{.cpp}
00127
                * Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                * Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
* Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00128
00129
00130
                * Markov::Edge<unsigned char>* res = NULL;
00131
                * src->Link(target1);
00132
                * src->Link(target2);
00133
                 * res = src->FindEdge('b');
00134
00135
                * @endcode
00136
00137
00138
                Edge<storageType>* FindEdge(storageType repr);
00139
00140
               /\star\star @brief Find an edge with its pointer. Avoid unless neccessary because comptutational cost
       of find by character is cheaper (because of std::map)

* @param target - target node.
00141
00142
                * @return Edge that is connected between this node, and the target node.
00143
00144
                Edge<storageType>* FindEdge(Node<storageType>* target);
00145
                /** @brief Return character representation of this node.
00146
00147
               * @return character representation at _value.
00148
00149
                inline unsigned char NodeValue();
00150
00151
                /** @brief Change total weights with offset
00152
                \star @param offset to adjust the vertice weight with
00153
00154
               void UpdateTotalVerticeWeight(long int offset);
00155
00156
                /** @brief return edges
00157
00158
               inline std::map<storageType, Edge<storageType>*>* Edges();
00159
                /** @brief return total edge weights
00160
00161
00162
               inline long int TotalEdgeWeights();
00163
00164
               std::vector<Edge<storageType>*> edgesV;
00165
00166
           private:
00167
00168
00169
                   @brief Character representation of this node. 0 for starter, 0xff for terminator.
00170
                storageType _value;
00172
```


```
00174
                  Obrief Total weights of the vertices, required by RandomNext
00175
00176
              long int total_edge_weights;
00177
00178
00179
                  Obrief A map of all edges connected to this node, where this node is at the LeftNode.
00180
                   \star Map is indexed by unsigned char, which is the character representation of the node.
00181
00182
              std::map<storageType, Edge<storageType>*> edges;
00183
          };
00184 };
00185
00186
00187
00188
00189
00190
00191
00192
00193
00194 template <typename storageType>
00195 Markov::Node<storageType>::Node(storageType _value) {
00196
          this->_value = _value;
this->total_edge_weights = 0L;
00197
00198 };
00199
00200 template <typename storageType>
00201 Markov::Node<storageType>::Node() {
00202
          this->_value = 0;
00203
          this->total_edge_weights = 0L;
00204 };
00205
00206 template <typename storageType>
00207 inline unsigned char Markov::Node<storageType>::NodeValue() {
00208
          return _value;
00209 }
00210
00211 template <typename storageType>
00212 Markov::Edge<storageType>* Markov::Node<storageType>* n) {
00213
          Markov::Edge<storageType>* v = new Markov::Edge<storageType>(this, n);
00214
          this->UpdateEdges(v);
00215
          return v:
00216 }
00217
00218 template <typename storageType>
00219 Markov::Edge<storageType>* Markov::Node<storageType>::Link(Markov::Edge<storageType>* v) {
00220
          v->SetLeftEdge(this);
          this->UpdateEdges(v);
00221
00222
          return v:
00223 }
00224
00225 template <typename storageType>
00226 Markov::Node<storageType>* Markov::Node<storageType>::RandomNext(Markov::Random::RandomEngine*
       randomEngine) {
00227
00228
          //get a random NodeValue in range of total_vertice_weight
          long int selection = randomEngine->random() %
00229
       this->total_edge_weights;//distribution()(generator());// distribution(generator);
00230
         //make absolute, no negative modulus values wanted
          //selection = (selection >= 0) ? selection : (selection + this->total_edge_weights);
00231
          for (int i=0;i<this->edgesV.size();i++) {
00232
00233
              selection -= this->edgesV[i]->EdgeWeight();
00234
              if (selection < 0) return this->edgesV[i]->TraverseNode();
00235
00236
          //if this assertion is reached, it means there is an implementation error above std::cout « "This should never be reached (node failed to walk to next) \n"; //cant assert from
00237
00238
       child thread
00239
         assert(true && "This should never be reached (node failed to walk to next)");
00240
          return NULL;
00241 }
00242
00243 template <typename storageType>
00244 bool Markov::Node<storageType>::UpdateEdges(Markov::Edge<storageType>* v) {
00245
          this->edges.insert({ v->RightNode()->NodeValue(), v });
00246
          this->edgesV.push_back(v);
00247
          //this->total_edge_weights += v->EdgeWeight();
00248
          return v->TraverseNode();
00249 }
00250
00251 template <typename storageType>
00252 Markov::Edge<storageType>* Markov::Node<storageType>::FindEdge(storageType repr) {
00253
          auto e = this->edges.find(repr);
          if (e == this->edges.end()) return NULL;
00254
00255
          return e->second;
00256 };
```

```
00257
00258 template <typename storageType>
00259 void Markov::Node<storageType>::UpdateTotalVerticeWeight(long int offset) {
00260
        this->total_edge_weights += offset;
00261 }
00262
00263 template <typename storageType>
00264 inline std::map<storageType, Markov::Edge<storageType>*** Markov::Node<storageType>::Edges() {
00265
        return &(this->edges);
00266 }
00267
00268 template <typename storageType>
00269 inline long int Markov::Node<storageType>::TotalEdgeWeights() {
00270    return this->total_edge_weights;
00271 }
```

# 9.51 pch.cpp File Reference

```
#include "pch.h"
```

Include dependency graph for MarkovModel/src/pch.cpp:




# 9.52 MarkovModel/src/pch.cpp

```
00001 // pch.cpp: source file corresponding to the pre-compiled header
00002
00003 #include "pch.h"
00004
00005 // When you are using pre-compiled headers, this source file is necessary for compilation to succeed.
```

# 9.53 pch.cpp File Reference

```
#include "pch.h"
```

Include dependency graph for UnitTests/pch.cpp:




# 9.54 UnitTests/pch.cpp


```
00001 // pch.cpp: source file corresponding to the pre-compiled header
00002
00003 #include "pch.h"
00004
00005 // When you are using pre-compiled headers, this source file is necessary for compilation to succeed.
```

# 9.55 pch.h File Reference

```
#include "framework.h"
Include dependency graph for MarkovModel/src/pch.h:
```



This graph shows which files directly or indirectly include this file:




# 9.56 MarkovModel/src/pch.h

```
00001 // pch.h: This is a precompiled header file.
00002 // Files listed below are compiled only once, improving build performance for future builds.
00003 // This also affects IntelliSense performance, including code completion and many code browsing features.
00004 // However, files listed here are ALL re-compiled if any one of them is updated between builds.
00005 // Do not add files here that you will be updating frequently as this negates the performance advantage.
00006
00007 #ifndef PCH_H
00008 #define PCH_H
00009
00010 // add headers that you want to pre-compile here
00011 #include "framework.h"
00012
00013 #endif //PCH_H
```

# 9.57 pch.h File Reference

This graph shows which files directly or indirectly include this file:



# 9.58 UnitTests/pch.h

```
00001 // pch.h: This is a precompiled header file.
00002 // Files listed below are compiled only once, improving build performance for future builds.
00003 // This also affects IntelliSense performance, including code completion and many code browsing features.
00004 // However, files listed here are ALL re-compiled if any one of them is updated between builds.
00005 // Do not add files here that you will be updating frequently as this negates the performance advantage.
```

```
00006
00007 #ifndef PCH_H
00008 #define PCH_H
00009
00010 // add headers that you want to pre-compile here
00011
00012 #endif //PCH_H
```

# 9.59 random-model.py File Reference

## **Namespaces**

- · random-model
- random

#### **Variables**

• random-model.alphabet = string.printable

password alphabet

random-model.f = open('../../models/random.mdl', "wb")

output file handle


# 9.60 random-model.py

```
00001 #!/usr/bin/python3 00002 """
00003 python script for generating a 2gram model 00004 """
00005
00006 import string
00007 import re
80000
00009
00010 alphabet = string.printable 00011 alphabet = re.sub(' \ s', ", alphabet)
00012 print(f"alphabet={alphabet}")
00013 #exit()
00014
00015
00016 f = open('.../models/random.mdl', "wb") 00017 #tie start nodes
00018 for sym in alphabet:
          f.write(b"\x00,1," + bytes(sym, encoding='ascii') + b"\n")
00020
00021 #tie terminator nodes
00022 for sym in alphabet:
         f.write(bytes(sym, encoding='ascii') + b",1,\xff\n")
00023
00024
00025 #tie internals
00026 for src in alphabet:
00027 for target in alphabet:
               f.write(bytes(src, encoding='ascii') + b",1," + bytes(target, encoding='ascii') + b"\n")
00028
```


## 9.61 random.h File Reference

```
#include <random>
#include <iostream>
```

Include dependency graph for random.h:



This graph shows which files directly or indirectly include this file:



## **Classes**

- class Markov::Random::RandomEngine
  - An abstract class for Random Engine.
- class Markov::Random::DefaultRandomEngine
  - Implementation using Random.h default random engine.
- class Markov::Random::Marsaglia
  - Implementation of Marsaglia Random Engine.
- class Markov::Random::Mersenne
  - Implementation of Mersenne Twister Engine.

## **Namespaces**

- Markov
  - Namespace for the markov-model related classes. Contains Model, Node and Edge classes.
- Markov::Random

Objects related to RNG.

#### 9.62 random.h

```
00001
00002 #pragma once
00003 #include <random>
00004 #include <iostream>
00005
00006 /**
00007
         @brief Objects related to RNG
00008 */
00009 namespace Markov::Random{
00010
00011
          /** @brief An abstract class for Random Engine
00012
          \star This class is used for generating random numbers, which are used for random walking on the
00013
       graph.
00014
           * Main reason behind allowing different random engines is that some use cases may favor
00015
       performance,
00016
          * while some favor good random.
00017
00018
          * Mersenne can be used for truer random, while Marsaglia can be used for deterministic but fast
       random.
00019
00020
          class RandomEngine{
00022
          public:
00023
              virtual inline unsigned long random() = 0;
00024
00025
00026
00027
00028
          /** @brief Implementation using Random.h default random engine
00029
00030
          * This engine is also used by other engines for seeding.
00031
00032
00033
          * @b Example @b Use: Using Default Engine with RandomWalk
00034
          * @code{.cpp}
00035
          * Markov::Model<char> model;
00036
          * Model.import("model.mdl");
00037
          * char* res = new char[11];
00038
          * Markov::Random::DefaultRandomEngine randomEngine;
00039
          * for (int i = 0; i < 10; i++) {
                  this->RandomWalk(&randomEngine, 5, 10, res);
00040
                  std::cout « res « "\n";
00041
00042
00043
           * @endcode
00044
00045
          * @b Example @b Use: Generating a random number with Marsaglia Engine
00046
          * @code{.cpp}
00047
           * Markov::Random::DefaultRandomEngine de;
00048
           * std::cout « de.random();
00049
           * @endcode
00050
00051
          class DefaultRandomEngine : public RandomEngine{
00053
00054
              /** @brief Generate Random Number
00055
              \star @return random number in long range.
00056
              inline unsigned long random() {
    return this->distribution()(this->generator());
00057
00058
00059
00060
          protected:
00061
00062
              /** @brief Default random device for seeding
00063
00064
00065
              inline std::random_device& rd() {
00066
                  static std::random_device _rd;
00067
                  return _rd;
00068
00069
00070
              /** @brief Default random engine for seeding
00071
00072
00073
              inline std::default_random_engine& generator() {
00074
                  static std::default_random_engine _generator(rd()());
00075
                  return _generator;
00076
00077
00078
              /** @brief Distribution schema for seeding.
```

9.62 random.h 245


```
00079
00080
00081
              inline std::uniform_int_distribution<long long unsigned>& distribution() {
00082
                  static std::uniform_int_distribution<long long unsigned> _distribution(0, 0xfffffFFFF);
00083
                  return _distribution;
00084
00085
00086
00087
00088
00089
          /** @brief Implementation of Marsaglia Random Engine
00090
00091
           \star This is an implementation of Marsaglia Random engine, which for most use cases is a better fit
       than other solutions.
00092
          * Very simple mathematical formula to generate pseudorandom integer, so its crazy fast.
00093
          \star This implementation of the Marsaglia Engine is seeded by random.h default random engine.
00094
00095
          * RandomEngine is only seeded once so its not a performance issue.
00096
00097
          * @b Example @b Use: Using Marsaglia Engine with RandomWalk
00098
          * @code{.cpp}
00099
          * Markov::Model<char> model;
           * Model.import("model.mdl");
00100
00101
          * char* res = new char[111:
00102
           * Markov::Random::Marsaglia MarsagliaRandomEngine;
           * for (int i = 0; i < 10; i++) {
00103
00104
                  this->RandomWalk(&MarsagliaRandomEngine, 5, 10, res);
00105
                  std::cout « res « "\n";
00106
00107
           * @endcode
00108
00109
           * @b Example @b Use: Generating a random number with Marsaglia Engine
00110
          * @code{.cpp}
00111
           * Markov::Random::Marsaglia me;
00112
           * std::cout « me.random();
00113
           * @endcode
00114
00115
00116
          class Marsaglia : public DefaultRandomEngine{
00117
          public:
00118
00119
              /** @brief Construct Marsaglia Engine
00120
00121
              \star Initialize x,\gamma and z using the default random engine.
00122
00123
              Marsaglia() {
00124
                  this->x = this->distribution()(this->generator());
00125
                  this->y = this->distribution()(this->generator());
                  this->z = this->distribution()(this->generator());
00126
                  //std::cout « "x: " « x « ", y: " « y « ", z: " « z « "\n";
00127
00128
              }
00129
00130
00131
          inline unsigned long random() {
00132
              unsigned long t;
              x ^= x « 16;
x ^= x » 5;
00133
00134
00135
              x ^= x « 1;
00136
00137
              t = x;
              x = y;
00138
              y = z;
00139
00140
              z = t^x \times y;
00141
00142
              return z;
00143
          }
00144
00145
00146
              unsigned long x;
00147
              unsigned long y;
00148
              unsigned long z;
00149
00150
00151
00152
          /** @brief Implementation of Mersenne Twister Engine
00153
00154
           \star This is an implementation of Mersenne Twister Engine, which is slow but is a good
       implementation for high entropy pseudorandom.
00155
00156
00157
           * @b Example @b Use: Using Mersenne Engine with RandomWalk
00158
           * @code{.cpp}
00159
           * Markov::Model<char> model;
00160
           * Model.import("model.mdl");
00161
           * char* res = new char[11];
           * Markov::Random::Mersenne MersenneTwisterEngine;
* for (int i = 0; i < 10; i++) {
00162
00163
```

```
this->RandomWalk(&MersenneTwisterEngine, 5, 10, res);
00165
                  std::cout « res « "\n";
00166
           * @endcode
00167
00168
          * @b Example @b Use: Generating a random number with Marsaglia Engine * @code{.cpp}
00169
00170
00171
          * Markov::Random::Mersenne me;
00172
           * std::cout « me.random();
00173
00174
           * @endcode
00175
00176
          class Mersenne : public DefaultRandomEngine{
00177
00178
00179
00180
00181 };
```

# 9.63 README.md File Reference

# 9.64 term.cpp File Reference

```
#include "term.h"
#include <string>
Include dependency graph for term.cpp:
```



## **Functions**

• std::ostream & operator<< (std::ostream &os, const Terminal::color &c)

#### 9.64.1 Function Documentation

# 9.64.1.1 operator<<()

9.65 term.cpp 247


References Markov::API::CLI::Terminal::colormap.

# 9.65 term.cpp


```
00001 #pragma once
00002 #include "term.h"
00003 #include <string>
00004
00005 using namespace Markov::API::CLI;
00006
00007 //Windows text processing is different from unix systems, so use windows header and text attributes
00008 #ifdef _WIN32
00009
00010 HANDLE Terminal::_stdout;
00011 HANDLE Terminal::_stderr;
00012
00013 std::map<Terminal::color, DWORD> Terminal::colormap = {
00014
           {Terminal::color::BLACK, 0},
00015
           {Terminal::color::BLUE, 1},
           {Terminal::color::GREEN, 2},
00016
           {Terminal::color::CYAN, 3},
00017
00018
           {Terminal::color::RED, 4},
00019
           {Terminal::color::MAGENTA, 5},
           {Terminal::color::BROWN, 6},
00021
           {Terminal::color::LIGHTGRAY, 7},
00022
           {Terminal::color::DARKGRAY, 8},
           {Terminal::color::YELLOW, 14}, {Terminal::color::WHITE, 15},
00023
00024
00025
           {Terminal::color::RESET, 15},
00026 };
00027
00028
00029 Terminal::Terminal() {
           Terminal::_stdout = GetStdHandle(STD_OUTPUT_HANDLE);
Terminal::_stderr = GetStdHandle(STD_ERROR_HANDLE);
00030
00031
00033
00034 std::ostream& operator«(std::ostream& os, const Terminal::color& c) {
00035
          SetConsoleTextAttribute(Terminal::_stdout, Terminal::colormap.find(c)->second);
00036
           return os:
00037 }
00038
00039 #else
00040
00041 std::map<Terminal::color, int> Terminal::colormap = {
           {Terminal::color::BLACK, 30}, {Terminal::color::BLUE, 34},
00042
00043
00044
           {Terminal::color::GREEN, 32},
00045
           {Terminal::color::CYAN, 36},
00046
           {Terminal::color::RED, 31},
00047
           {Terminal::color::MAGENTA, 35},
00048
           {Terminal::color::BROWN, 0}, {Terminal::color::LIGHTGRAY, 0},
00049
00050
           {Terminal::color::DARKGRAY, 0},
00051
           {Terminal::color::YELLOW, 33},
00052
           {Terminal::color::WHITE, 37},
00053
           {Terminal::color::RESET, 0},
00054 };
00055
00056 Terminal::Terminal() {
00057
           /*this->; */
00058 }
00059
00060 std::ostream& operator«(std::ostream& os, const Terminal::color& c) {
          char buf[6];
sprintf(buf,"%d", Terminal::colormap.find(c)->second);
os « "\e[1;" « buf « "m";
00061
00062
00063
00064
           return os;
00065 }
00066
00067
00068
00069
00070 #endif
```

# 9.66 term.h File Reference

#include <iostream>
#include <map>
Include dependency graph for term.h:



This graph shows which files directly or indirectly include this file:



#### **Classes**

class Markov::API::CLI::Terminal
 pretty colors for Terminal. Windows Only.

# **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::CLI

Structure to hold parsed cli arguements.

# **Macros**

• #define TERM\_FAIL "[" << Markov::API::CLI::Terminal::color::RED << "+" << Markov::API::CLI::Terminal::color::RESET << "] "

9.67 term.h 249

• #define TERM\_INFO "[" << Markov::API::CLI::Terminal::color::BLUE << "+" << Markov::API::CLI::Terminal::color::RESET << "] "

- #define TERM\_WARN "[" << Markov::API::CLI::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::RESI << "1"</li>
- #define TERM\_SUCC "[" << Markov::API::CLI::Terminal::color::GREEN << "+" << Markov::API::CLI::Terminal::color::RESET << "] "

#### **Functions**

std::ostream & Markov::API::CLI::operator<< (std::ostream &os, const Markov::API::CLI::Terminal::color &c)</li>

#### 9.66.1 Macro Definition Documentation

#### 9.66.1.1 TERM FAIL

```
#define TERM_FAIL "[" << Markov::API::CLI::Terminal::color::RED << "+" << Markov::API::CLI::Terminal::color
<< "] "</pre>
```

Definition at line 10 of file term.h.

## 9.66.1.2 TERM INFO

```
#define TERM_INFO "[" << Markov::API::CLI::Terminal::color::BLUE << "+" << Markov::API::CLI::Terminal::color
<< "] "</pre>
```

Definition at line 11 of file term.h.

## 9.66.1.3 TERM\_SUCC

```
#define TERM_SUCC "[" << Markov::API::CLI::Terminal::color::GREEN << "+" << Markov::API::CLI::Terminal::color:
<< "] "</pre>
```

Definition at line 13 of file term.h.

## 9.66.1.4 TERM\_WARN

```
#define TERM_WARN "[" << Markov::API::CLI::Terminal::color::YELLOW << "+" </ Markov::API::CLI::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::Terminal::color::YELLOW << "+" << Markov::API::CLI::Terminal::color::Terminal::color::Terminal::color::Terminal::color::Terminal::color::Terminal::color::Terminal::color::Terminal::color::Terminal::CLI::Terminal::color::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Terminal::Termin
```

Definition at line 12 of file term.h.

## 9.67 term.h


```
00001 #pragma once
00003 #ifdef _WIN32
00004 #include <Windows.h>
00005 #endif
00006
00007 #include <iostream>
00008 #include <map>
00010 #define TERM_FAIL "[" \ll Markov::API::CLI::Terminal::color::RED \ll "+" \ll
Markov::API::CLI::Terminal::color::RESET « "] "
00011 #define TERM_INFO "[" « Markov::API::CLI::Terminal::color::BLUE « "+" «
Markov::API::CLI::Terminal::color::RESET « "] "

00012 #define TERM_WARN "[" « Markov::API::CLI::Terminal::color::YELLOW « "+" «
        Markov::API::CLI::Terminal::color::RESET « "] "
00013 #define TERM_SUCC "[" « Markov::API::CLI::Terminal::color::GREEN « "+" «
        Markov::API::CLI::Terminal::color::RESET « "]
00014
00015 namespace Markov::API::CLI{
00016
           /** @brief pretty colors for Terminal. Windows Only.
```

```
00018
          class Terminal {
00019
00020
00021
              /** Default constructor.
00022
              \star Get references to stdout and stderr handles.
00023
00024
              Terminal();
00025
              enum color { RESET, BLACK, RED, GREEN, YELLOW, BLUE, MAGENTA, CYAN, WHITE, LIGHTGRAY,
00026
      DARKGRAY, BROWN };
#ifdef _WIN32
static HANDLE _stdout;
00027
00028
00029
              static HANDLE _stderr;
00030
              static std::map<Markov::API::CLI::Terminal::color, DWORD> colormap;
00031
00032
              static std::map<Markov::API::CLI::Terminal::color, int> colormap;
00033
              #endif
00034
00035
00036
00037
              static std::ostream endl;
00038
00039
00040
          };
00041
00042
          /** overload for std::cout.
00043
00044
          std::ostream& operator«(std::ostream& os, const Markov::API::CLI::Terminal::color& c);
00045
00046 }
```

# 9.68 threadSharedListHandler.cpp File Reference

#include "threadSharedListHandler.h"
Include dependency graph for threadSharedListHandler.cpp:




# 9.69 threadSharedListHandler.cpp

```
00001 #include "threadSharedListHandler.h"
00002
00003
00004 Markov::API::Concurrency::ThreadSharedListHandler::ThreadSharedListHandler(const char* filename) {
00005
         this->listfile;
00006
          this->listfile.open(filename, std::ios_base::binary);
00007 }
80000
00009
00010 bool Markov::API::Concurrency::ThreadSharedListHandler::next(std::string* line){
00011
         bool res = false;
00012
         this->mlock.lock();
00013
         res = (std::getline(this->listfile, *line,'\n'))? true : false;
```


## 9.70 threadSharedListHandler.h File Reference

```
#include <string>
#include <fstream>
#include <mutex>
```

Include dependency graph for threadSharedListHandler.h:



This graph shows which files directly or indirectly include this file:



#### **Classes**

class Markov::API::Concurrency::ThreadSharedListHandler
 Simple class for managing shared access to file.

#### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::API

Namespace for the MarkovPasswords API.

Markov::API::Concurrency

Namespace for Concurrency related classes.

#### 9.71 threadSharedListHandler.h


```
00001 #include <string>
00002 #include <fstream>
00003 #include <mutex>
00004
00005 /** @brief Namespace for Concurrency related classes
00006 */
00007 namespace Markov::API::Concurrency(
80000
00009 /** @brief Simple class for managing shared access to file
00010
00011
       \star This class maintains the handover of each line from a file to multiple threads.
00012 ^{\star} 00013 ^{\star} When two different threads try to read from the same file while reading a line isn't completed, it
       can have unexpected results.
00014 * Line might be split, or might be read twice.
       * This class locks the read action on the list until a line is completed, and then proceeds with the
00015
00016 *
00017 */
00018 class ThreadSharedListHandler{
00019 public:
         /** @brief Construct the Thread Handler with a filename
00021
00022
           * Simply open the file, and initialize the locks.
00023
00024
           * @b Example @b Use: Simple file read
00025
           * @code{.cpp}
00026
           * ThreadSharedListHandler listhandler("test.txt");
00027
           * std::string line;
00028
           * std::cout « listhandler->next(&line) « "\n";
00029
           * @endcode
00030
00031
           * @b Example @b Use: Example use case from MarkovPasswords showing multithreaded access
00032
           * @code{.cpp}
00033
             void MarkovPasswords::Train(const char* datasetFileName, char delimiter, int threads)
00034
                   ThreadSharedListHandler listhandler(datasetFileName);
00035
                    auto start = std::chrono::high_resolution_clock::now();
00036
00037
                    std::vector<std::thread*> threadsV:
00038
                    for(int i=0;i<threads;i++){</pre>
00039
                        threadsV.push_back(new std::thread(&MarkovPasswords::TrainThread, this, &listhandler,
       datasetFileName, delimiter));
00040
00041
00042
                  for(int i=0;i<threads;i++){
                       threadsV[i]->join();
00043
00044
                        delete threadsV[i];
00045
00046
                    auto finish = std::chrono::high_resolution_clock::now();
                    std::chrono::duration<double> elapsed = finish - start;
std::cout « "Elapsed time: " « elapsed.count() « " s\n";
00047
00048
00049
00050
00051
               void MarkovPasswords::TrainThread(ThreadSharedListHandler *listhandler, const char*
00052
       datasetFileName, char delimiter) {
                    char format_str[] ="%ld,%s";
00053
00054
                    format str[2]=delimiter;
00055
                    std::string line;
                    while (listhandler->next(&line)) {
00056
00057
                        long int oc;
00058
                        if (line.size() > 100) {
00059
                             line = line.substr(0, 100);
00060
00061
                        char* linebuf = new char[line.length()+5];
                        chara Inhebut = hew Challette.tength() | 5);
sscanf_s(line._str(), format_str, &oc, linebuf, line.length()+5);
this->AdjustEdge((const char*)linebuf, oc);
00062
00063
00064
                        delete linebuf;
00065
00066
00067
           * @endcode
00068
00069
            * @param filename Filename for the file to manage.
00070
00071
           ThreadSharedListHandler(const char* filename);
00072
00073
           /** @brief Read the next line from the file.
00074
            \star This action will be blocked until another thread (if any) completes the read operation on the
00075
00076
00077
           * @b Example @b Use: Simple file read
00078
           * @code(.cpp)
00079
           * ThreadSharedListHandler listhandler("test.txt");
00080
           * std::string line;
```

9.72 Train.h File Reference 253

```
00081     * std::cout « listhandler->next(&line) « "\n";
00082     * @endcode
00083     *
00084     */
00085     bool next(std::string* line);
00086
00087 private:
00088     std::ifstream listfile;
00089     std::mutex mlock;
00090 };
00091
00092 };
```

## 9.72 Train.h File Reference

```
#include <QtWidgets/QMainWindow>
#include "ui_Train.h"
Include dependency graph for Train.h:
```



#### **Classes**

class Markov::GUI::Train
 QT Training page class.

#### **Namespaces**

Markov

Namespace for the markov-model related classes. Contains Model, Node and Edge classes.

Markov::GUI


namespace for MarkovPasswords API GUI wrapper

#### 9.73 Train.h

```
00001 #pragma once
00002 #include <QtWidgets/QMainWindow>
00003 #include "ui_Train.h"
00004
00005 namespace Markov::GUI{
00006
          /** @brief QT Training page class
00007
00008
00009
          class Train :public QMainWindow {
00010
          Q_OBJECT
00011
00012
              Train(QWidget* parent = Q_NULLPTR);
00013
00014
00015
          private:
              Ui::Train ui;
00016
00017
          public slots:
```

# 9.74 UnitTests.cpp File Reference

```
#include "pch.h"
#include "CppUnitTest.h"
#include "MarkovModel/src/model.h"
Include dependency graph for UnitTests.cpp:
```



## **Namespaces**

Testing

Namespace for Microsoft Native Unit Testing Classes.

• Testing::MVP

Testing Namespace for Minimal Viable Product.

• Testing::MVP::MarkovModel

Testing Namespace for MVP MarkovModel.

Testing::MVP::MarkovPasswords

Testing namespace for MVP MarkovPasswords.

· Testing::MarkovModel

Testing namespace for MarkovModel.

Testing::MarkovPasswords

Testing namespace for MarkovPasswords.

## **Functions**

• Testing::MVP::MarkovModel::TEST\_CLASS (Edge)

Test class for minimal viable Edge.

• Testing::MVP::MarkovModel::TEST\_CLASS (Node)

Test class for minimal viable Node.

• Testing::MVP::MarkovModel::TEST\_CLASS (Model)

Test class for minimal viable Model.

• Testing::MVP::MarkovPasswords::TEST\_CLASS (ArgParser)

Test Class for Argparse class.

Testing::MarkovModel::TEST\_CLASS (Edge)

9.75 UnitTests.cpp 255

Test class for rest of Edge cases.

Testing::MarkovModel::TEST\_CLASS (Node)

Test class for rest of Node cases.

Testing::MarkovModel::TEST\_CLASS (Model)

Test class for rest of model cases.

# 9.75 UnitTests.cpp

```
00001 #include "pch.h"
00002 #include "CppUnitTest.h"
00003 #include "MarkovModel/src/model.h"
00004
00005 using namespace Microsoft::VisualStudio::CppUnitTestFramework;
00006
00007
00008 /** @brief Namespace for Microsoft Native Unit Testing Classes
00009 */
00010 namespace Testing {
00011
00012
          /** @brief Testing Namespace for Minimal Viable Product
00013
00014
          namespace MVP {
00015
              /\star\star @brief Testing Namespace for MVP MarkovModel
00016
              namespace MarkovModel
00018
00019
                   /** @brief Test class for minimal viable Edge
00020
                  TEST_CLASS (Edge)
00021
00022
00023
                  public:
00024
00025
                       /** @brief test default constructor
00026
                       TEST_METHOD (default_constructor) {
00027
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>;
00028
00029
                           Assert::IsNull(e->LeftNode());
00030
                           Assert::IsNull(e->RightNode());
00031
                           delete e;
00032
00033
00034
                       /\!\star\!\star\,\text{@brief test linked constructor with two nodes}
00035
00036
                       TEST_METHOD(linked_constructor) {
00037
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00038
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00039
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(LeftNode,
       RightNode);
00040
                           Assert::IsTrue(LeftNode == e->LeftNode());
                           Assert::IsTrue(RightNode == e->RightNode());
00041
00042
                           delete LeftNode;
00043
                           delete RightNode;
00044
                           delete e;
00045
                       }
00046
00047
                       /** @brief test AdjustEdge function
00048
00049
                       TEST_METHOD (AdjustEdge) {
00050
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00051
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00052
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
       RightNode):
00053
                           e->AdjustEdge(15);
00054
                           Assert::AreEqual(15ull, e->EdgeWeight());
00055
                           e->AdjustEdge(15);
00056
                           Assert::AreEqual(30ull, e->EdgeWeight());
00057
                           delete LeftNode:
00058
                           delete RightNode;
00059
                           delete e;
00060
00061
00062
                       /** @brief test TraverseNode returning RightNode
00063
00064
                       TEST METHOD (TraverseNode) {
00065
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00066
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00067
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
       RightNode);
00068
                           Assert::IsTrue(RightNode == e->TraverseNode());
00069
                           delete LeftNode:
00070
                           delete RightNode;
                           delete e;
```

```
00073
00074
                      /** @brief test LeftNode/RightNode setter
00075
                       TEST_METHOD(set_left_and_right) {
00076
00077
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00078
00079
                           Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(LeftNode,
       RightNode);
00080
00081
                           Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>;
00082
                           e2->SetLeftEdge(LeftNode);
00083
                           e2->SetRightEdge(RightNode);
00084
00085
                           Assert::IsTrue(e1->LeftNode() == e2->LeftNode());
                           Assert::IsTrue(e1->RightNode() == e2->RightNode());
00086
00087
                           delete LeftNode:
00088
                           delete RightNode;
00089
                           delete e1;
00090
                           delete e2;
00091
00092
                      /** @brief test negative adjustments
00093
00094
00095
                       TEST_METHOD (negative_adjust) {
00096
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00097
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00098
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
       RightNode);
00099
                           e->AdjustEdge(15);
00100
                           Assert::AreEqual(15ull, e->EdgeWeight());
00101
                           e->AdjustEdge(-15);
00102
                           Assert::AreEqual(Oull, e->EdgeWeight());
00103
                           delete LeftNode;
00104
                           delete RightNode;
00105
                           delete e;
00106
                      }
00107
                  };
00108
00109
                   /** @brief Test class for minimal viable Node
00110
                  TEST_CLASS (Node)
00111
00112
00113
                  public:
00114
00115
                       /** @brief test default constructor
00116
00117
                      TEST_METHOD (default_constructor) {
                           Markov::Node<unsigned char>* n = new Markov::Node<unsigned char>();
00118
00119
                           Assert::AreEqual((unsigned char)0, n->NodeValue());
00120
                           delete n;
00121
00122
00123
                      /** @brief test custom constructor with unsigned char
00124
00125
                      TEST_METHOD (uchar_constructor) {
                           Markov::Node<unsigned char>* n = NULL;
00126
00127
                           unsigned char test_cases[] = { 'c', 0x00, 0xff, -32 };
00128
                           for (unsigned char tcase : test_cases)
00129
                               n = new Markov::Node<unsigned char>(tcase);
00130
                               Assert::AreEqual(tcase, n->NodeValue());
00131
                              delete n;
00132
                           }
00133
                      }
00134
00135
                       /** @brief test link function
00136
                       TEST_METHOD(link_left) {
00137
00138
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00139
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00140
00141
                          Markov::Edge<unsigned char>* e = LeftNode->Link(RightNode);
00142
                           delete LeftNode;
                           delete RightNode;
00143
00144
                           delete e;
00145
00146
00147
                       /** @brief test link function
00148
                       TEST METHOD (link right) {
00149
                           Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00150
00151
                           Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00152
00153
                           Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(NULL, RightNode);
                          LeftNode >>Link(e);
Assert::IsTrue(LeftNode == e->LeftNode());
00154
00155
00156
                           Assert::IsTrue(RightNode == e->RightNode());
```

9.75 UnitTests.cpp 257

```
00157
                           delete LeftNode;
                            delete RightNode;
00158
00159
                           delete e;
00160
                       }
00161
                       /** @brief test RandomNext with low values
00162
00163
00164
                       TEST_METHOD(rand_next_low) {
00165
                           Markov::Random::Marsaglia MarsagliaRandomEngine;
                           Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00166
00167
                           Markov::Edge<unsigned char>* e = src->Link(target1);
00168
00169
                            e->AdjustEdge(15);
00170
                            Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00171
                            Assert::IsTrue(res == target1);
                            delete src;
00172
00173
                           delete target1;
00174
                           delete e;
00175
00176
00177
00178
                       /** @brief test RandomNext with 32 bit high values
00179
                       TEST METHOD (rand_next_u32) {
00180
00181
                            Markov::Random::Marsaglia MarsagliaRandomEngine;
                            Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00182
00183
                            Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00184
                           Markov::Edge<unsigned char>* e = src->Link(target1);
00185
                            e->AdjustEdge(1 « 31);
00186
                           Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00187
                           Assert::IsTrue(res == target1);
00188
                           delete src;
00189
                            delete target1;
00190
                           delete e;
00191
00192
00193
00194
                       /** @brief random next on a node with no follow-ups
00195
00196
                       TEST_METHOD(rand_next_choice_1) {
00197
                            Markov::Random::Marsaglia MarsagliaRandomEngine;
                           Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00198
                            Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00199
                            Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00200
                            Markov::Edge<unsigned char>* e1 = src->Link(target1);
00201
00202
                           Markov::Edge<unsigned char>* e2 = src->Link(target2);
00203
                            e1->AdjustEdge(1);
00204
                            e2->AdjustEdge((unsigned long)(1ull « 31));
                           Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00205
00206
                           Assert::IsNotNull(res);
00207
                            Assert::IsTrue(res == target2);
00208
                            delete src;
00209
                            delete target1;
00210
                           delete e1;
00211
                           delete e2:
00212
                       }
00213
00214
                       /** @brief random next on a node with no follow-ups
00215
00216
                       TEST_METHOD(rand_next_choice_2) {
00217
                           Markov::Random::Marsaglia MarsagliaRandomEngine;
                            Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00218
00219
                            Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00220
                            Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00221
                           Markov::Edge<unsigned char>* e1 = src->Link(target1);
00222
                           Markov::Edge<unsigned char>* e2 = src->Link(target2);
00223
                           e2->AdjustEdge(1);
00224
                            e1->AdjustEdge((unsigned long)(1ull « 31));
00225
                           Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00226
                            Assert::IsNotNull(res);
00227
                            Assert::IsTrue(res == target1);
00228
                            delete src;
00229
                           delete target1;
00230
                           delete e1:
00231
                           delete e2;
00232
00233
00234
00235
                       /** @brief test updateEdges
00236
00237
                       TEST_METHOD (update_edges_count) {
00238
00239
                            Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00240
                            Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00241
                           Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
                           Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target2);
00242
00243
```

```
00244
                             e1->AdjustEdge(25);
00245
                             src->UpdateEdges(e1);
00246
                             e2->AdjustEdge(30);
00247
                             src->UpdateEdges(e2);
00248
00249
                             Assert::AreEqual((size_t)2, src->Edges()->size());
00250
00251
00252
                             delete target1;
00253
                             delete e1;
00254
                             delete e2:
00255
00256
00257
00258
                         /** @brief test updateEdges
00259
                         TEST_METHOD (update_edges_total) {
00260
00261
00262
                              Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00263
                              Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
                             Markov::Edge<unsigned char>* e1 = new Markov::Edge<unsigned char>(src, target1);
Markov::Edge<unsigned char>* e2 = new Markov::Edge<unsigned char>(src, target1);
00264
00265
00266
                             e1->AdjustEdge(25);
                             src->UpdateEdges(e1);
00267
00268
                             e2->AdjustEdge(30);
00269
                             src->UpdateEdges(e2);
00270
00271
                             //Assert::AreEqual(55ull, src->TotalEdgeWeights());
00272
00273
                             delete src:
00274
                             delete target1;
00275
                             delete e1;
00276
                              delete e2;
00277
00278
00279
00280
                         /** @brief test FindVertice
00281
00282
                         TEST_METHOD(find_vertice) {
00283
00284
                             Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                             Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00285
00286
00287
                             Markov::Edge<unsigned char>* res = NULL;
00288
                             src->Link(target1);
00289
                              src->Link(target2);
00290
00291
00292
                             res = src->FindEdge('b');
00293
                             Assert::IsNotNull(res);
00294
                             Assert::AreEqual((unsigned char)'b', res->TraverseNode()->NodeValue());
00295
                              res = src->FindEdge('c');
00296
                              Assert::IsNotNull(res);
00297
                             Assert::AreEqual((unsigned char)'c', res->TraverseNode()->NodeValue());
00298
00299
                             delete src;
00300
                             delete target1;
00301
                             delete target2;
00302
00303
00304
                         }
00305
00306
00307
                         /** @brief test FindVertice
00308
00309
                         TEST_METHOD(find_vertice_without_any) {
00310
00311
                             auto invalid next = [] {
00312
                                  Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00313
                                 Markov::Edge<unsigned char>* res = NULL;
00314
00315
                                  res = src->FindEdge('b');
00316
                                 Assert::IsNull(res);
00317
00318
                                  delete src;
00319
                             };
00320
00321
                              //Assert::ExpectException<std::logic_error>(_invalid_next);
00322
00323
00324
                         /** @brief test FindVertice
00325
00326
                         TEST_METHOD(find_vertice_nonexistent) {
00327
00328
                             Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
                             Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* target2 = new Markov::Node<unsigned char>('c');
00329
00330
```

9.75 UnitTests.cpp 259

```
00331
                           Markov::Edge<unsigned char>* res = NULL;
                           src->Link(target1);
00332
00333
                           src->Link(target2);
00334
                           res = src->FindEdge('D');
00335
00336
                           Assert::IsNull(res);
00337
00338
00339
                           delete target1;
00340
                           delete target2;
00341
00342
00343
                  };
00344
00345
                   /** @brief Test class for minimal viable Model
00346
                  TEST CLASS (Model)
00347
00348
00349
                  public:
00350
                       /** @brief test model constructor for starter node
00351
00352
                       TEST_METHOD (model_constructor) {
00353
                           Markov::Model<unsigned char> m;
                           Assert::AreEqual((unsigned char)'\0', m.StarterNode()->NodeValue());
00354
00355
00356
00357
                       /** @brief test import
00358
00359
                       TEST_METHOD(import_filename) {
00360
                           Markov::Model<unsigned char> m;
00361
                           Assert::IsTrue(m.Import("../MarkovPasswords/Models/2gram.mdl"));
00362
00363
00364
                       /** @brief test export
00365
                       TEST_METHOD(export_filename) {
00366
00367
                           Markov::Model<unsigned char> m;
                           Assert::IsTrue(m.Export("../MarkovPasswords/Models/testcase.mdl"));
00368
00369
00370
00371
                       /** @brief test random walk
00372
                       TEST_METHOD(random_walk) {
00373
00374
                           unsigned char* res = new unsigned char[12 + 5];
00375
                           Markov::Random::Marsaglia MarsagliaRandomEngine;
00376
                           Markov::Model<unsigned char> m;
00377
                           Assert::IsTrue(m.Import("../Models/finished2.mdl"));
00378
                           Assert::IsNotNull(m.RandomWalk(&MarsagliaRandomEngine,1,12,res));
00379
00380
                  };
00381
              }
00382
00383
               /** @brief Testing namespace for MVP MarkovPasswords
00384
00385
              namespace MarkovPasswords
00386
00387
                   /** @brief Test Class for Argparse class
00388
00389
                  TEST_CLASS (ArgParser)
00390
                  public:
00391
00392
                      /** @brief test basic generate
00393
00394
                       TEST_METHOD (generate_basic) {
00395
                           int argc = 8;
       char *argv[] = {"markov.exe", "generate", "-if", "model.mdl", "-of", "passwords.txt", "-n", "100"};
00396
00397
00398
                           /*ProgramOptions *p = Argparse::parse(argc, argv);
00399
                           Assert::IsNotNull(p);
00400
00401
                           Assert::AreEqual(p->bImport, true);
00402
                           Assert::AreEqual(p->bExport, false);
                           Assert::AreEqual(p->importname, "model.mdl");
00403
                           Assert::AreEqual(p->outputfilename, "passwords.txt");
00404
00405
                           Assert::AreEqual(p->generateN, 100); */
00406
00407
00408
                       /\star\star @brief test basic generate reordered params
00409
00410
00411
                       TEST_METHOD (generate_basic_reorder) {
00412
                           int argc = 8;
                           char *argv[] = { "markov.exe", "generate", "-n", "100", "-if", "model.mdl", "-of",
00413
       "passwords.txt" };
00414
00415
                           /*ProgramOptions* p = Argparse::parse(argc, argv);
```

```
Assert::IsNotNull(p);
00417
00418
                         Assert::AreEqual(p->bImport, true);
00419
                          Assert::AreEqual(p->bExport, false);
                          Assert::AreEqual(p->importname, "model.mdl");
00420
                          Assert::AreEqual(p->outputfilename, "passwords.txt");
00421
                          Assert::AreEqual(p->generateN, 100); */
00422
00423
00424
00425
                      /** @brief test basic generate param longnames
00426
                      TEST_METHOD(generate_basic_longname) {
00427
       00428
00430
00431
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00432
                         Assert::IsNotNull(p);
00433
00434
                          Assert::AreEqual(p->bImport, true);
00435
                          Assert::AreEqual(p->bExport, false);
                         Assert::AreEqual(p->importname, "model.mdl");
Assert::AreEqual(p->outputfilename, "passwords.txt");
00436
00437
00438
                          Assert::AreEqual(p->generateN, 100); */
00439
                      }
00440
00441
                      /** @brief test basic generate
00442
00443
                      TEST_METHOD(generate_fail_badmethod) {
       00444
00445
00446
00447
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00448
                          Assert::IsNull(p); */
                      }
00449
00450
00451
                      /** @brief test basic train
00452
00453
                      TEST_METHOD(train_basic) {
                         int argc = 4;
char *argv[] = { "markov.exe", "train", "-ef", "model.mdl" };
00454
00455
00456
00457
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00458
                         Assert::IsNotNull(p);
00459
00460
                         Assert::AreEqual(p->bImport, false);
00461
                          Assert::AreEqual(p->bExport, true);
                          Assert::AreEqual(p->exportname, "model.mdl"); */
00462
00463
00464
                      }
00465
00466
                      /** @brief test basic generate
00467
                      TEST_METHOD(train_basic_longname) {
00468
00469
                          int argc = 4;
00470
                          char *argv[] = { "markov.exe", "train", "--exportfilename", "model.mdl" };
00471
00472
                          /*ProgramOptions* p = Argparse::parse(argc, argv);
00473
                          Assert::IsNotNull(p);
00474
                         Assert::AreEqual(p->bImport, false);
Assert::AreEqual(p->bExport, true);
00475
00476
00477
                          Assert::AreEqual(p->exportname, "model.mdl"); */
00478
00479
00480
00481
00482
                 };
00483
00484
00485
00486
00487
00488
          /** @brief Testing namespace for MarkovModel
00489
00490
          namespace MarkovModel {
00491
00492
              /** @brief Test class for rest of Edge cases
00493
              TEST_CLASS(Edge)
00494
00495
00496
              public:
                /** @brief send exception on integer underflow
00497
00498
                  TEST_METHOD(except_integer_underflow) {
00499
00500
                      auto _underflow_adjust = [] {
```

9.75 UnitTests.cpp 261

```
00501
                            Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
00502
                            Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00503
                            Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
       RightNode);
00504
                            e->AdjustEdge(15);
00505
                            e->AdiustEdge(-30);
                            delete LeftNode;
00506
00507
                            delete RightNode;
00508
                            delete e;
00509
00510
                        Assert::ExpectException<std::underflow_error>(_underflow_adjust);
00511
                   }
00512
00513
                   /** @brief test integer overflows
00514
                   TEST_METHOD(except_integer_overflow) {
00515
00516
                        auto _overflow_adjust = [] {
                            Markov::Node<unsigned char>* LeftNode = new Markov::Node<unsigned char>('1');
Markov::Node<unsigned char>* RightNode = new Markov::Node<unsigned char>('r');
00517
00518
00519
                            Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char> (LeftNode,
       RightNode);
00520
                            e->AdjustEdge(~0ull);
00521
                            e->AdjustEdge(1);
                            delete LeftNode:
00522
00523
                            delete RightNode;
00524
                            delete e;
00525
00526
                        Assert::ExpectException<std::underflow_error>(_overflow_adjust);
00527
                   }
00528
               };
00529
00530
               /** @brief Test class for rest of Node cases
00531
00532
               TEST_CLASS (Node)
00533
               public:
00534
00535
00536
                   /** @brief test RandomNext with 64 bit high values
00537
00538
                   TEST_METHOD(rand_next_u64) {
00539
                        Markov::Random::Marsaglia MarsagliaRandomEngine;
                       Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00540
00541
                        Markov::Edge<unsigned char>* e = src->Link(target1);
00542
00543
                        e->AdjustEdge((unsigned long)(1ull « 63));
00544
                        Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00545
                        Assert::IsTrue(res == target1);
00546
                        delete src;
00547
                        delete target1;
00548
                       delete e:
00549
00550
00551
00552
                   /** @brief test RandomNext with 64 bit high values
00553
                   TEST_METHOD(rand_next_u64_max) {
00554
00555
                        Markov::Random::Marsaglia MarsagliaRandomEngine;
00556
                        Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00557
                        Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00558
                        Markov::Edge<unsigned char>* e = src->Link(target1);
00559
                        e->AdjustEdge((0xffffFFFF));
00560
                       Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00561
                        Assert::IsTrue(res == target1);
00562
                        delete src;
00563
                        delete target1;
00564
                        delete e;
00565
00566
                   }
00567
00568
                   /** @brief randomNext when no edges are present
00569
00570
                   TEST_METHOD(uninitialized_rand_next) {
00571
                        auto invalid_next = [] {
00572
00573
                            Markov::Random::Marsaglia MarsagliaRandomEngine;
00574
                            Markov::Node<unsigned char>* src = new Markov::Node<unsigned char>('a');
00575
                            Markov::Node<unsigned char>* target1 = new Markov::Node<unsigned char>('b');
00576
                            Markov::Edge<unsigned char>* e = new Markov::Edge<unsigned char>(src, target1);
00577
                            Markov::Node<unsigned char>* res = src->RandomNext(&MarsagliaRandomEngine);
00578
00579
                            delete src;
00580
                            delete target1;
00581
                            delete e;
00582
                        };
00583
00584
                        Assert::ExpectException<std::logic_error>(_invalid_next);
00585
                   }
```

```
00587
00588
                 };
00589
                 /** @brief Test class for rest of model cases
00590
00591
00592
                 TEST_CLASS (Model)
00593
00594
                 public:
00595
                      TEST_METHOD(functional_random_walk) {
00596
                           unsigned char* res2 = new unsigned char[12 + 5];
                           Markov::Random::Marsaglia MarsagliaRandomEngine;
00597
00598
                           Markov::Model<unsigned char> m;
00599
                           Markov::Node<unsigned char>* starter = m.StarterNode();
                           Markov::Node<unsigned char>* a = new Markov::Node<unsigned char>('a');
Markov::Node<unsigned char>* b = new Markov::Node<unsigned char>('b');
Markov::Node<unsigned char>* c = new Markov::Node<unsigned char>('c');
Markov::Node<unsigned char>* end = new Markov::Node<unsigned char>(0xff);
00600
00601
00602
00603
                           starter->Link(a)->AdjustEdge(1);
00604
00605
                           a->Link(b)->AdjustEdge(1);
00606
                           b->Link(c)->AdjustEdge(1);
00607
                           c->Link(end)->AdjustEdge(1);
00608
                           char* res = (char*)m.RandomWalk(&MarsagliaRandomEngine,1,12,res2);
Assert::IsFalse(strcmp(res, "abc"));
00609
00610
00611
00612
                      TEST_METHOD(functionoal_random_walk_without_any) {
00613
                           Markov::Model<unsigned char> m;
                           Markov::Node<unsigned char>* starter = m.StarterNode();
Markov::Node<unsigned char>* a = new Markov::Node<unsigned char>('a');
00614
00615
                           Markov::Node<unsigned char>* b = new Markov::Node<unsigned char>('b');
00616
00617
                           Markov::Node<unsigned char>* c = new Markov::Node<unsigned char>('c');
00618
                           Markov::Node<unsigned char>* end = new Markov::Node<unsigned char>(0xff);
00619
                           Markov::Edge<unsigned char>* res = NULL;
00620
                           starter->Link(a)->AdjustEdge(1);
                           a->Link(b)->AdjustEdge(1);
b->Link(c)->AdjustEdge(1);
00621
00622
00623
                           c->Link(end)->AdjustEdge(1);
00624
00625
                           res = starter->FindEdge('D');
00626
                           Assert::IsNull(res);
00627
00628
                      }
                 };
00629
00630
00631
            }
00632
            /** @brief Testing namespace for MarkovPasswords
00633
00634
00635
            namespace MarkovPasswords {
00636
00637
00638
00639 }
```

# Index

_left	markopy.cpp, 210
Markov::Edge < NodeStorageType >, 97	BROWN
_right	Markov::API::CLI::Terminal, 179
Markov::Edge < NodeStorageType >, 97	bulk
_value	markopy_cli, 19
Markov::Node< storageType >, 175	
_weight	CLI
Markov::Edge < NodeStorageType >, 97	Markov::GUI::CLI, 53
MarkovLuge< NodeStorage Type >, 97	CLI.h, 193, 194
about	cli_generate
Markov::GUI::about, 46	markopy cli, 17
Markov::GUI::CLI, 53	• • —
	cli_init
Markov::GUI::menu, 131	markopy_cli, 18
about.h, 187	cli_train
action	markopy_cli, 18
markopy_cli, 19	color
AdjustEdge	Markov::API::CLI::Terminal, 179
Markov::API::CUDA::CUDAModelMatrix, 64	colormap
Markov::API::MarkovPasswords, 101	Markov::API::CLI::Terminal, 179
Markov::API::ModelMatrix, 149	ConstructMatrix
Markov::Edge < NodeStorageType >, 95	Markov::API::CUDA::CUDAModelMatrix, 65
Markov::Model < NodeStorageType >, 138	Markov::API::ModelMatrix, 150
AllocVRAMOutputBuffer	corpus_list
Markov::API::CUDA::CUDAModelMatrix, 65	markopy_cli, 19
alphabet	CudaCheckNotifyErr
model_2gram, 27	Markov::API::CUDA::CUDADeviceController, 56
random-model, 27	Markov::API::CUDA::CUDAModelMatrix, 66
	Markov::API::CUDA::Random::Marsaglia, 117
Argparse	•
Markov::API::CLI::Argparse, 48	cudaDeviceController.h, 194, 195
argparse.cpp, 188	CudaMalloc2DToFlat
argparse.h, 188, 190	Markov::API::CUDA::CUDADeviceController, 56
BOOST_ALL_DYN_LINK, 190	Markov::API::CUDA::CUDAModelMatrix, 67
args	Markov::API::CUDA::Random::Marsaglia, 117
markopy_cli, 19	CudaMemcpy2DToFlat
	Markov::API::CUDA::CUDADeviceController, 57
bExport	Markov::API::CUDA::CUDAModelMatrix, 68
Markov::API::CLI::_programOptions, 43	Markov::API::CUDA::Random::Marsaglia, 118
bFailure	CudaMigrate2DFlat
Markov::API::CLI::_programOptions, 43	Markov::API::CUDA::CUDADeviceController, 58
bImport	Markov::API::CUDA::CUDAModelMatrix, 69
Markov::API::CLI::_programOptions, 43	Markov::API::CUDA::Random::Marsaglia, 119
BLACK	cudaModelMatrix.h, 197, 198
Markov::API::CLI::Terminal, 179	cudarandom.h, 199, 200
BLUE	CYAN
Markov::API::CLI::Terminal, 179	Markov::API::CLI::Terminal, 179
BOOST_ALL_DYN_LINK	MarkovAFIGLITerminal, 179
argparse.h, 190	DARKGRAY
<b>5.</b>	
BOOST_PYTHON_MODULE	Markov::API::CLI::Terminal, 179
Markov::Markopy, 25	datasetFile
BOOST_PYTHON_STATIC_LIB	Markov::API::CUDA::CUDAModelMatrix, 85

Markov::API::MarkovPasswords, 111	f
Markov::API::ModelMatrix, 165	model_2gram, 27
datasetname	random-model, 27
Markov::API::CLI::_programOptions, 43	FastRandomWalk
default	Markov::API::CUDA::CUDAModelMatrix, 72
markopy_cli, 19	Markov::API::ModelMatrix, 153
device_edgeMatrix	FastRandomWalkCUDAKernel
Markov::API::CUDA::CUDAModelMatrix, 85	Markov::API::CUDA, 23
device_matrixIndex	FastRandomWalkPartition
Markov::API::CUDA::CUDAModelMatrix, 85	Markov::API::CUDA::CUDAModelMatrix, 73
device_outputBuffer	Markov::API::ModelMatrix, 154
Markov::API::CUDA::CUDAModelMatrix, 85	FastRandomWalkThread
device_totalEdgeWeights	Markov::API::CUDA::CUDAModelMatrix, 75
Markov::API::CUDA::CUDAModelMatrix, 85	Markov::API::ModelMatrix, 155
device_valueMatrix	FindEdge
Markov::API::CUDA::CUDAModelMatrix, 85	Markov::Node < storageType >, 171
devrandom	flatEdgeMatrix
Markov::API::CUDA::Random, 24	Markov::API::CUDA::CUDAModelMatrix, 86
distribution	FlattenMatrix
Markov::API::CUDA::Random::Marsaglia, 120	Markov::API::CUDA::CUDAModelMatrix, 76
Markov::Random::DefaultRandomEngine, 90	flatValueMatrix
Markov::Random::Marsaglia, 126	Markov::API::CUDA::CUDAModelMatrix, 86
Markov::Random::Mersenne, 134	framework.h, 205
dllmain.cpp, 201	WIN32_LEAN_AND_MEAN, 205
DumpJSON	,,,,,,
Markov::API::CUDA::CUDAModelMatrix, 70	Generate
Markov::API::ModelMatrix, 151	Markov::API::CUDA::CUDAModelMatrix, 76
, , , , , , , , , , , , , , , , , , , ,	Markov::API::MarkovPasswords, 103
Edge	Markov::API::ModelMatrix, 157
Markov::Edge < NodeStorageType >, 94	generateN
edge.h, 202, 203	Markov::API::CLI::_programOptions, 44
edgeMatrix	GenerateThread
Markov::API::CUDA::CUDAModelMatrix, 85	Markov::API::CUDA::CUDAModelMatrix, 77
Markov::API::ModelMatrix, 165	Markov::API::MarkovPasswords, 104
Edges	Markov::API::ModelMatrix, 158
Markov::API::CUDA::CUDAModelMatrix, 71	generator
Markov::API::MarkovPasswords, 102	Markov::API::CUDA::Random::Marsaglia, 121
Markov::API::ModelMatrix, 152	Markov::Random::DefaultRandomEngine, 90
Markov::Model < NodeStorageType >, 139	Markov::Random::Marsaglia, 127
Markov::Node < storageType >, 171	Markov::Random::Mersenne, 134
edges	getProgramOptions
Markov::API::CUDA::CUDAModelMatrix, 86	Markov::API::CLI::Argparse, 50
Markov::API::MarkovPasswords, 111	GREEN
Markov::API::ModelMatrix, 165	Markov::API::CLI::Terminal, 179
Markov::Model < NodeStorageType >, 145	MarkovAi IOLITerrilinai, 173
Markov::Node< storageType >, 175	help
edgesV	markopy_cli, 19
Markov::Node< storageType >, 175	Markov::API::CLI::Argparse, 50
EdgeWeight	home
Markov::Edge < NodeStorageType >, 95	Markov::GUI::Train, 185
endl	Markovdoi Italii, 100
Markov::API::CLI::Terminal, 180	Import
Export	Markov::API::CUDA::CUDAModelMatrix, 78, 79
Markov::API::CUDA::CUDAModelMatrix, 71	Markov::API::MarkovPasswords, 105
Markov::API::MarkovPasswords, 102, 103	Markov::API::ModelMatrix, 159
Markov::API::ModelMatrix, 152, 153	Markov::Model< NodeStorageType >, 141
Markov::Model < NodeStorageType >, 139, 140	importname
exportname	Markov::API::CLI::_programOptions, 44
Markov::API::CLI::_programOptions, 44	intHandler
ivia nov ii ioei programopilons, ++	interiorior

markovPasswords.cpp, 214	importname, 44
	outputfilename, 44
keepRunning	seperator, 44
markovPasswords.cpp, 214	wordlistname, 44
LeftNode	Markov::API::CLI::Argparse, 46
Markov::Edge< NodeStorageType >, 95	Argparse, 48
LIGHTGRAY	getProgramOptions, 50
Markov::API::CLI::Terminal, 179	help, 50
Link	parse, 51
Markov::Node < storageType >, 172	po, 52
ListCudaDevices	setProgramOptions, 51 Markov::API::CLI::Terminal, 177
Markov::API::CUDA::CUDADeviceController, 59	BLACK, 179
Markov::API::CUDA::CUDAModelMatrix, 80	BLUE, 179
Markov::API::CUDA::Random::Marsaglia, 121	BROWN, 179
listfile	color, 179
Markov::API::Concurrency::ThreadSharedListHandle	r, colormap, 179
183	CYAN, 179
MACENTA	DARKGRAY, 179
MAGENTA  Markey WA Plu CL lu Tarminal 170	endl, 180
Markov::API::CLI::Terminal, 179 main	GREEN, 179
src/main.cpp, 206	LIGHTGRAY, 179
Ul/src/main.cpp, 208	MAGENTA, 179
main.cpp, 205, 207, 209	RED, 179
markopy.cpp, 209, 210	RESET, 179
BOOST_PYTHON_STATIC_LIB, 210	Terminal, 179
markopy_cli, 17	WHITE, 179
action, 19	YELLOW, 179
args, 19	Markov::API::Concurrency, 22
bulk, 19	Markov::API::Concurrency::ThreadSharedListHandler,
cli_generate, 17	180
cli_init, 18	listfile, 183
cli_train, 18	mlock, 183
corpus_list, 19	next, 183
default, 19	ThreadSharedListHandler, 182
help, 19	Markov::API::CUDA, 22
model, 19	FastRandomWalkCUDAKernel, 23
model_base, 19	strchr, 24
model_extension, 19	Markov::API::CUDA::CUDADeviceController, 54
model_list, 20	CudaCheckNotifyErr, 56
output, 20	CudaMalloc2DToFlat, 56 CudaMemcpy2DToFlat, 57
output_file_name, 20	CudaMigrate2DFlat, 58
output_forced, 20	ListCudaDevices, 59
parser, 20 True, 20	Markov::API::CUDA::CUDAModelMatrix, 60
markopy cli.py, 210, 211	AdjustEdge, 64
Markov, 20	AllocVRAMOutputBuffer, 65
Markov::API, 21	ConstructMatrix, 65
Markov::API::CLI, 21	CudaCheckNotifyErr, 66
operator<<, 22	CudaMalloc2DToFlat, 67
ProgramOptions, 22	CudaMemcpy2DToFlat, 68
Markov::API::CLI::_programOptions, 41	CudaMigrate2DFlat, 69
bExport, 43	datasetFile, 85
bFailure, 43	device_edgeMatrix, 85
blmport, 43	device_matrixIndex, 85
datasetname, 43	device_outputBuffer, 85
exportname, 44	device_totalEdgeWeights, 85
generateN, 44	device_valueMatrix, 85

DumpJSON, 70	modelSavefile, 111
edgeMatrix, 85	Nodes, 106
Edges, 71	nodes, 111
edges, 86	OpenDatasetFile, 106
Export, 71	outputFile, 111
FastRandomWalk, 72	RandomWalk, 107
FastRandomWalkPartition, 73	Save, 108
FastRandomWalkThread, 75	StarterNode, 109
flatEdgeMatrix, 86	starterNode, 112
FlattenMatrix, 76	Train, 109
flatValueMatrix, 86	TrainThread, 110
Generate, 76	Markov::API::ModelMatrix, 145
GenerateThread, 77	AdjustEdge, 149
Import, 78, 79	ConstructMatrix, 150
ListCudaDevices, 80	datasetFile, 165
matrixIndex, 86	DumpJSON, 151
matrixSize, 86	edgeMatrix, 165
MigrateMatrix, 80 modelSavefile, 86	Edges, 152 edges, 165
Nodes, 80	Export, 152, 153
nodes, 86	FastRandomWalk, 153
OpenDatasetFile, 80	FastRandomWalkPartition, 154
outputBuffer, 86	FastRandomWalkThread, 155
outputFile, 87	Generate, 157
RandomWalk, 81	GenerateThread, 158
Save, 82	Import, 159
StarterNode, 82	matrixIndex, 165
starterNode, 87	matrixSize, 165
totalEdgeWeights, 87	ModelMatrix, 149
Train, 83	modelSavefile, 166
TrainThread, 84	Nodes, 160
valueMatrix, 87	nodes, 166
Markov::API::CUDA::Random, 24	OpenDatasetFile, 160
devrandom, 24	outputFile, 166
Markov::API::CUDA::Random::Marsaglia, 114	RandomWalk, 161
CudaCheckNotifyErr, 117	Save, 162
CudaMalloc2DToFlat, 117	StarterNode, 163
CudaMemcpy2DToFlat, 118	starterNode, 166
CudaMigrate2DFlat, 119	totalEdgeWeights, 166
distribution, 120	Train, 163
generator, 121	TrainThread, 164
ListCudaDevices, 121	valueMatrix, 166
MigrateToVRAM, 122	Markov::Edge < NodeStorageType >, 92
random, 122	_left, 97
rd, 123	_right, 97
x, 123	_weight, 97
y, 123	AdjustEdge, 95
z, 123 Markov::API::MarkovPasswords, 97	Edge, 94 EdgeWeight, 95
AdjustEdge, 101	LeftNode, 95
datasetFile, 111	RightNode, 96
Edges, 102	SetLeftEdge, 96
edges, 111	SetRightEdge, 96
Export, 102, 103	TraverseNode, 97
Generate, 103	Markov::GUI, 25
GenerateThread, 104	Markov::GUI::about, 45
Import, 105	about, 46
MarkovPasswords, 101	ui, 46
·	

Markov::GUI::CLI, 52	rd, 91
about, 53	Markov::Random::Marsaglia, 124
CLI, 53	distribution, 126
start, 54	generator, 127
statistics, 54	Marsaglia, 126
ui, 54	random, 127
Markov::GUI::MarkovPasswordsGUI, 112	rd, 128
MarkovPasswordsGUI ::pass, 114	x, 128
MarkovPasswordsGUI::benchmarkSelected, 114	y, 128
MarkovPasswordsGUI::comparisonSelected, 114	z, 129
MarkovPasswordsGUI::home, 114	Markov::Random::Mersenne, 131
MarkovPasswordsGUI::model, 114	distribution, 134
MarkovPasswordsGUI::modelvisSelected, 114	generator, 134
MarkovPasswordsGUI::visualDebugSelected, 114	random, 135
ui, 114	rd, 135
Markov::GUI::menu, 129	Markov::Random::RandomEngine, 176
about, 131	random, 177
menu, 130	MarkovPasswords
ui, 131	Markov::API::MarkovPasswords, 101
visualization, 131	markovPasswords.cpp, 213, 215
Markov::GUI::Train, 184	intHandler, 214
home, 185	keepRunning, 214
Train, 185	markovPasswords.h, 216, 217
train, 185	MarkovPasswordsGUI ::pass
ui, 185	Markov::GUI::MarkovPasswordsGUI, 114
Markov::Markopy, 25	MarkovPasswordsGUI.cpp, 219
BOOST_PYTHON_MODULE, 25	MarkovPasswordsGUI.h, 220, 221
Markov::Model< NodeStorageType >, 136	MarkovPasswordsGUI::benchmarkSelected
AdjustEdge, 138	Markov::GUI::MarkovPasswordsGUI, 114
Edges, 139	MarkovPasswordsGUI::comparisonSelected
edges, 145	Markov::GUI::MarkovPasswordsGUI, 114
Export, 139, 140	MarkovPasswordsGUI::home
Import, 141	Markov::GUI::MarkovPasswordsGUI, 114
Model, 138	MarkovPasswordsGUI::model
Nodes, 143	Markov::GUI::MarkovPasswordsGUI, 114
nodes, 145	MarkovPasswordsGUI::modelvisSelected
RandomWalk, 143	Markov::GUI::MarkovPasswordsGUI, 114
StarterNode, 144	MarkovPasswordsGUI::visualDebugSelected
starterNode, 145	Markov::GUI::MarkovPasswordsGUI, 114
Markov::Node < storageType >, 166	Marsaglia
_value, 175	Markov::Random::Marsaglia, 126
Edges, 171	matrixIndex
edges, 175	Markov::API::CUDA::CUDAModelMatrix, 86
edgesV, 175	Markov::API::ModelMatrix, 165
FindEdge, 171	matrixSize
Link, 172	Markov::API::CUDA::CUDAModelMatrix, 86
Node, 169	Markov::API::ModelMatrix, 165
NodeValue, 173	menu
RandomNext, 173	Markov::GUI::menu, 130
total_edge_weights, 175	menu.cpp, 221
TotalEdgeWeights, 174	menu.h, 222, 223
UpdateEdges, 174	MigrateMatrix
UpdateTotalVerticeWeight, 175	Markov::API::CUDA::CUDAModelMatrix, 80
Markov::Random, 26	MigrateToVRAM
Markov::Random::DefaultRandomEngine, 87	Markov::API::CUDA::Random::Marsaglia, 122
distribution, 90	mlock
generator, 90	Markov::API::Concurrency::ThreadSharedListHandle
random, 91	183

Model	Markov::API::CUDA::CUDAModelMatrix, 87
Markov::Model < NodeStorageType >, 138	Markov::API::MarkovPasswords, 111
model	Markov::API::ModelMatrix, 166
markopy_cli, 19	outputfilename
model.h, 223, 224	Markov::API::CLI::_programOptions, 44
model_2gram, 26	marior in a mozini_program optiono, Tr
alphabet, 27	parse
f, 27	Markov::API::CLI::Argparse, 51
model 2gram.py, 228, 229	parser
model base	markopy_cli, 20
markopy cli, 19	pch.cpp, 239, 240
model extension	pch.h, 240, 241
markopy_cli, 19	po
	Markov::API::CLI::Argparse, 52
model_list markopy_cli, 20	ProgramOptions
ModelMatrix	Markov::API::CLI, 22
	Walker I. Oct, 22
Markov::API::ModelMatrix, 149	random, 27
modelMatrix.cpp, 229	Markov::API::CUDA::Random::Marsaglia, 122
modelMatrix.h, 232, 233	Markov::Random::DefaultRandomEngine, 91
modelSavefile	Markov::Random::Marsaglia, 127
Markov::API::CUDA::CUDAModelMatrix, 86	Markov::Random::Mersenne, 135
Markov::API::MarkovPasswords, 111	, ·
Markov::API::ModelMatrix, 166	Markov::Random::RandomEngine, 177
	random-model, 27
next	alphabet, 27
Markov::API::Concurrency::ThreadSharedListHandle	
183	random-model.py, 242
Node	random.h, 242, 244
Markov::Node < storageType >, 169	RandomNext
node.h, 235	Markov::Node < storageType >, 173
Nodes	RandomWalk
Markov::API::CUDA::CUDAModelMatrix, 80	Markov::API::CUDA::CUDAModelMatrix, 81
Markov::API::MarkovPasswords, 106	Markov::API::MarkovPasswords, 107
Markov::API::ModelMatrix, 160	Markov::API::ModelMatrix, 161
Markov::Model < NodeStorageType >, 143	Markov::Model < NodeStorageType >, 143
nodes	rd
Markov::API::CUDA::CUDAModelMatrix, 86	Markov::API::CUDA::Random::Marsaglia, 123
Markov::API::MarkovPasswords, 111	Markov::Random::DefaultRandomEngine, 91
Markov::API::ModelMatrix, 166	Markov::Random::Marsaglia, 128
Markov::Model< NodeStorageType >, 145	Markov::Random::Mersenne, 135
Node Value	README.md, 246
Markov::Node < storageType >, 173	RED
market intode Colorage type > , The	Markov::API::CLI::Terminal, 179
OpenDatasetFile	RESET
Markov::API::CUDA::CUDAModelMatrix, 80	Markov::API::CLI::Terminal, 179
Markov::API::MarkovPasswords, 106	RightNode
Markov::API::ModelMatrix, 160	Markov::Edge < NodeStorageType >, 96
operator<<	MarkovLuge \ NoueStorage Type >, 90
Markov::API::CLI, 22	Save
term.cpp, 246	Markov::API::CUDA::CUDAModelMatrix, 82
output	Markov::API::MarkovPasswords, 108
•	Markov::API::ModelMatrix, 162
markopy_cli, 20	
output_file_name	Seperator  Markov: API::Cl.I:: programOptions 44
markopy_cli, 20	Markov::API::CLI::_programOptions, 44
output_forced	SetLeftEdge
markopy_cli, 20	Markov::Edge < NodeStorageType >, 96
outputBuffer	setProgramOptions
Markov::API::CUDA::CUDAModelMatrix, 86	Markov::API::CLI::Argparse, 51
outputFile	SetRightEdge

Markov::Edge < NodeStorageType >, 96 src/main.cpp main, 206	totalEdgeWeights  Markov::API::CUDA::CUDAModelMatrix, 87  Markov::API::ModelMatrix, 166
start	Train
Markov::GUI::CLI, 54 StarterNode	Markov::API::CUDA::CUDAModelMatrix, 83 Markov::API::MarkovPasswords, 109
Markov::API::CUDA::CUDAModelMatrix, 82 Markov::API::MarkovPasswords, 109	Markov::API::ModelMatrix, 163 Markov::GUI::Train, 185
Markov::API::ModelMatrix, 163	train
Markov::Model < NodeStorageType >, 144	Markov::GUI::Train, 185
starterNode	Train.h, 253
Markov::API::CUDA::CUDAModelMatrix, 87	TrainThread
Markov::API::MarkovPasswords, 112	Markov::API::CUDA::CUDAModelMatrix, 84
Markov::API::ModelMatrix, 166	Markov::API::MarkovPasswords, 110
Markov::Model < NodeStorageType >, 145 statistics	Markov::API::ModelMatrix, 164 TraverseNode
Markov::GUI::CLI, 54	Markov::Edge < NodeStorageType >, 97
strchr	True
Markov::API::CUDA, 24	markopy_cli, 20
term.cpp, 246, 247	ui
operator<<, 246	Markov::GUI::about, 46
term.h, 248, 249	Markov::GUI::CLI, 54
TERM_FAIL, 249	Markov::GUI::MarkovPasswordsGUI, 114
TERM_INFO, 249	Markov::GUI::menu, 131
TERM_SUCC, 249	Markov::GUI::Train, 185
TERM_WARN, 249 TERM FAIL	Ul/src/main.cpp
term.h, 249	main, 208
TERM INFO	UnitTests.cpp, 254, 255 UpdateEdges
term.h, 249	Markov::Node < storageType >, 174
TERM SUCC	UpdateTotalVerticeWeight
term.h, 249	Markov::Node< storageType >, 175
TERM_WARN	
term.h, 249	valueMatrix
Terminal	Markov::API::CUDA::CUDAModelMatrix, 87
Markov::API::CLI::Terminal, 179	Markov::API::ModelMatrix, 166
TEST_CLASS	visualization
Testing::MarkovModel, 28–30	Markov::GUI::menu, 131
Testing::MVP::MarkovModel, 32–34	WHITE
Testing::MVP::MarkovPasswords, 37	Markov::API::CLI::Terminal, 179
Testing, 28	WIN32_LEAN_AND_MEAN
Testing::MarkovModel, 28 TEST CLASS, 28–30	framework.h, 205
Testing::MarkovPasswords, 31	wordlistname
Testing::MVP, 31	Markov::API::CLI::_programOptions, 44
Testing::MVP::MarkovModel, 31	
TEST_CLASS, 32–34	X
Testing::MVP::MarkovPasswords, 37	Markov::API::CUDA::Random::Marsaglia, 123
TEST_CLASS, 37	Markov::Random::Marsaglia, 128
ThreadSharedListHandler	у
Markov::API::Concurrency::ThreadSharedListHandle	Markov::API::CUDA::Random::Marsaglia, 123 Markov::Random::Marsaglia, 128
threadSharedListHandler.cpp, 250	YELLOW
threadSharedListHandler.h, 251, 252	Markov::API::CLI::Terminal, 179
total_edge_weights	•
Markov::Node < storageType >, 175	Z
TotalEdgeWeights	Markov::API::CUDA::Random::Marsaglia, 123
Markov::Node < storageType >, 174	Markov::Random::Marsaglia, 129