


# Packet Tracer - Configure VLANs, VTP and DTP

# **Topology**



## **Addressing Table**

Device	Interface	IP Address	Subnet Mask
PC0	NIC	192.168.10.1	255.255.255.0
PC1	NIC	192.168.20.1	255.255.255.0
PC2	NIC	192.168.30.1	255.255.255.0
PC3	NIC	192.168.30.2	255.255.255.0
PC4	NIC	192.168.20.2	255.255.255.0
PC5	NIC	192.168.10.2	255.255.255.0
S1	VLAN 99	192.168.99.1	255.255.255.0
S2	VLAN 99	192.168.99.2	255.255.255.0
S3	VLAN 99	192.168.99.3	255.255.255.0

### **Objectives**

Part 1: Configure and Verify DTP Part 2: Configure and Verify VTP

# **Background / Scenario**

As the number of switches in a network increases, the administration necessary to manage the VLANs and trunks can be challenging. To ease some of the VLAN and trunking configurations, VLAN trunking protocol (VTP) allows a network administration to automate the management of VLANs. Trunk negotiation between network devices is managed by the Dynamic Trunking Protocol (DTP), and is automatically enabled on Catalyst 2960 and Catalyst 3560 switches.

In this activity, you will configure trunk links between the switches. You will configure a VTP server and VTP clients in the same VTP domain. You will also observe the VTP behavior when a switch is in VTP transparent mode. You will assign ports to VLANs and verify end-to-end connectivity with the same VLAN.

# Part 1: Configure and Verify DTP

In Part 1, you will configure trunk links among the switches, and you will configure VLAN 999 as the native VLAN.

### Step 1: Verify VLAN configuration.

Verify the configured VLANs on the switches.

a. On S1, click the **CLI** tab. At the prompt, enter **enable** and enter the **show vlan brief** command to verify the configured VLANs on S1.

S1# show vlan brief

VLAN Name	Status	Ports
1 default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gig0/1, Gig0/2
99 Management	active	
999 VLAN0999	active	
1002 fddi-default	active	
1003 token-ring-default	active	
1004 fddinet-default	active	
1005 trnet-default	active	

b. Repeat step a. on S2 and S3. What VLANs are configured on the switches?

### Step 2: Configure Trunks on S1, S2, and S3.

Dynamic trunking protocol (DTP) manages the trunk links between Cisco switches. Currently all the switchports are in the default trunking mode, which is dynamic auto. In this step, you will change the trunking mode to dynamic desirable for the link between switches S1 and S2. For the link between switches S1 and S3, the link will be set as a static trunk. Use VLAN 999 as the native VLAN in this topology.

a. On S1, configure the trunk link to dynamic desirable on the GigabitEthernet 0/1 interface.

```
S1(config) # interface g0/1
S1(config-if) # switchport mode dynamic desirable
```

b. For the trunk link between S1 and S3, configure a static trunk link on the GigabitEthernet 0/2 interface.

```
S1(config) # interface g0/2
S1(config-if) # switchport mode trunk
S3(config) # interface g0/2
S3(config-if) # switchport mode trunk
```

c. Verify trunking is enabled on all the switches using the show interfaces trunk command.

#### S1# show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Gig0/1	desirable	n-802.1q	trunking	1
Gig0/2	on	802.1q	trunking	1
Port	Vlans allowe	ed on trunk		
Gig0/1	1-1005			
Gig0/2	1-1005			
Port	Vlans allowe	ed and active in	management do	omain
Gig0/1	1,99,999			
Gig0/2	1,99,999			
Port	Vlans in spa	nning tree forw	arding state a	and not pruned
Gig0/1	none			
Giq0/2	none			
0190/1	110116			

What is the native VLAN for these trunks currently?

d. Configure VLAN 999 as the native VLAN for the trunk links on S1.

```
S1(config) # interface range g0/1 - 2
S1(config-if-range) # switchport trunk native vlan 999
```

What messages did you receive on S1? How would you correct it?

- e. On S2 and S3, configure VLAN 999 as the native VLAN.
- f. Verify trunking is successfully configured on all the switches. You should be able ping one switch from another switch in the topology using the IP addresses configured on the SVI.

# Part 2: Configure and Verify VTP

S1 will be configured as the VTP server and S2 will be configured as VTP clients. All the switches will be configured to be in the VTP domain **CCNA** and use the VTP password **cisco**.

VLANs can be created on the VTP server and distributed to other switches in the VTP domain. In this part, you will create 3 new VLANs on the VTP server, S1. These VLANs will be distributed to S2 using VTP. Observe how the transparent VTP mode behaves.

### Step 1: Configure S1 as VTP server.

Configure S1 as the VTP server in the **CCNA** domain with the password **cisco**.

a. Configure S1 as a VTP server.

```
S1(config)# vtp mode server
Setting device to VTP SERVER mode.
```

b. Configure **CCNA** as the VTP domain name.

```
S1(config)# vtp domain CCNA
Changing VTP domain name from NULL to CCNA
```

c. Configure cisco as the VTP password.

```
S1(config)# vtp password cisco
Setting device VLAN database password to cisco
```

### Step 2: Verify VTP on S1.

a. Use the **show vtp status** command on the switches to confirm that the VTP mode and domain are configured correctly.

```
S1# show vtp status
VTP Version
                               : 2
Configuration Revision
Maximum VLANs supported locally: 255
Number of existing VLANs
VTP Operating Mode
                              : Server
VTP Domain Name
                              : CCNA
VTP Pruning Mode
                              : Disabled
VTP V2 Mode
                               : Disabled
VTP Traps Generation
                             : Disabled
                               : 0x8C 0x29 0x40 0xDD 0x7F 0x7A 0x63 0x17
MD5 digest
Configuration last modified by 0.0.0.0 at 0-0-00 00:00:00
Local updater ID is 192.168.99.1 on interface V199 (lowest numbered VLAN interface
found)
```

b. To verify the VTP password, use the **show vtp password** command.

```
S1# show vtp password
VTP Password: cisco
```

### Step 3: Add S2 and S3 to the VTP domain.

Before S2 and S3 will accept VTP advertisements from S1, they must belong to the same VTP domain. Configure S2 and S3 as VTP clients with **CCNA** as the VTP domain name and **cisco** as the VTP password. Remember that VTP domain names are case sensitive.

a. Configure S2 as a VTP client in the CCNA VTP domain with the VTP password cisco.

```
S2(config)# vtp mode client
Setting device to VTP CLIENT mode.
S2(config)# vtp domain CCNA
Changing VTP domain name from NULL to CCNA
S2(config)# vtp password cisco
Setting device VLAN database password to cisco
```

b. To verify the VTP password, use the **show vtp password** command.

```
S2# show vtp password
VTP Password: cisco
```

c. Configure S3 to be in the **CCNA** VTP domain with the VTP password **cisco**. Switch S3 will stay in VTP transparent mode.

```
S3(config) # vtp domain CCNA
Changing VTP domain name from NULL to CCNA
S3(config) # vtp password cisco
```

Setting device VLAN database password to cisco

d. Enter **show vtp status** command on all the switches to answer the following question.

Notice that the configuration revision number is 0 on all three switches. Explain.

### Step 4: Create more VLANs on S1.

a. On S1, create VLAN 10 and name it Red.

```
S1(config) # vlan 10
S1(config-vlan) # name Red
```

b. Create VLANs 20 and 30 according to the table below.

VLAN Number	VLAN Name
10	Red
20	Blue
30	Yellow

c. Verify the addition of the new VLANs. Enter show vlan brief at the privileged EXEC mode.

Which VLANs are configured on S1?

d. Confirm configuration changes using the **show vtp status** command on S1 and S2 to confirm that the VTP mode and domain are configured correctly. Output for S2 is shown here:

#### S2# show vtp status

```
VTP Version
                        : 2
Configuration Revision
Maximum VLANs supported locally : 255
Number of existing VLANs : 10
VTP Operating Mode
                       : Client
                       : CCNA
VTP Domain Name
VTP Pruning Mode
VTP V2 Mode
                       : Disabled
```

: 0xE6 0x56 0x05 0xE0 0x7A 0x63 0xFB 0x33

Configuration last modified by 192.168.99.1 at 3-1-93 00:21:07

How many VLANs are configured on S2? Does S2 have the same VLANs as S1? Explain.

### **Step 5: Observe VTP transparent mode.**

S3 is currently configured as VTP transparent mode.

a. Use **show vtp status** command to answer the following question.

How many VLANs are configured on S3 currently? What is the configuration revision number? Explain your answer.

How would you change the number of VLANs on S3?

b. Change VTP mode to client on S3.

Use show commands to verify the changes on VTP mode. How many VLANs exists on S3 now?

**Note**: VTP advertisements are flooded throughout the management domain every five minutes, or whenever a change occurs in VLAN configurations. To accelerate this process, you can switch between Realtime mode and Simulation mode until the next round of updates. However, you may have to do this multiple times because this will only forward Packet Tracer's clock by 10 seconds each time. Alternatively, you can change one of the client switches to transparent mode and then back to client mode.

### Step 6: Assign VLANs to Ports

Use the **switchport mode access** command to set access mode for the access links. Use the **switchport access vlan** *vlan-id* command to assign a VLAN to an access port.

Ports	Assignments	Network
S1 F0/1 – 8 S2 F0/1 – 8	VLAN 10 (Red)	192.168.10.0 /24
S1 F0/9 – 16 S2 F0/9 – 16	VLAN 20 (Blue)	192.168.20.0 /24
S1 F0/17 – 24 S2 F0/17 – 24	VLAN 30 (Yellow)	192.168.30.0 /24

a. Assign VLANs to ports on S2 using assignments from the table above.

```
S2(config-if)# interface range f0/1 - 8
S2(config-if-range)# switchport mode access
S2(config-if-range)# switchport access vlan 10
S2(config-if-range)# interface range f0/9 -16
S2(config-if-range)# switchport mode access
S2(config-if-range)# switchport access vlan 20
S2(config-if-range)# interface range f0/17 - 24
S2(config-if-range)# switchport mode access
S2(config-if-range)# switchport mode access
S2(config-if-range)# switchport access vlan 30
```

b. Assign VLANs to ports on S3 using assignment from the table above.

#### Step 7: Verify end to end connectivity.

- a. From PC0 ping PC5.
- b. From PC1 ping PC4.

c. From PC2 ping PC3.