

Chapter: CPU/ Process Scheduling

P U

Basic Concept

CPU Scheduling is basis of Multi-programmed OS

Objective of Multi-programming is to have some processes running all the time to maximize CPU Utilization.



Sequence of CPU and I/O Bursts


■ CPU Burst- when process is executed in CPU

- CPU Burst Time: The amount of time the process uses the processor
- Types of **CPU bursts**:
 - Long bursts -- process is CPU bound (spend max. time with CPU
 - Short bursts -- process is I/O bound (spend max. time with I/O)

■ I/O Burst- when CPU is waiting for I/O completion for further execution.



Sequence of CPU and I/O Bursts





CPU Scheduling Decisions

- When process switches from Running State to Waiting State (i/o request or wait)
- 2. When process switches from Running to Ready State (interrupt)
- 3. When process switches from Waiting State to Ready State (at completion of i/o)
- 4. When a process terminates

1. Non-preemptive


2. Pre-emptive

3. Pre-emptive

4. Non-Preemptive (allow)



Process States





Scheduling

Non-Preemptive

Preemptive

Non-Preemptive or Cooperative Scheduling

- Once the CPU is allocated to a process, process keeps the CPU until:
 - it releases when it completes
 - by switching to waiting state
 - E.g: 1. Windows 3.x and Apple Macintosh operating systems uses non-preemptive scheduling
 - 2. Windows (also 10) uses a round-robin technique with a *multi-level feedback queue* for priority scheduling
- Process is executed till completion. It cannot be interrupted.
 - Eg First In First Out





Preemptive Scheduling

■ The running process is interrupted for some time and resumed later on, when the priority task has finished its execution.

CPU /resources is/are taken away from the process when some high priority process needs execution.



Dispatcher

- A module that gives control of CPU to the process selected by short-term scheduler.
- Functions:
 - Switching Context
 - Switching to User mode
 - Jumping to proper location to restart the program.
- The dispatcher should be as fast as possible, given that it is invoked during every process switch
- Dispatch Latency:
 - Time taken for the dispatcher to stop one process and start another running.



Scheduling Criteria

- Which algorithm to use in a particular situation
- 1. CPU Utilization: CPU should be busy to the fullest

- **2. Throughput:** No. of processes completed per unit of time.
- **Turnaround Time:** The time interval from submitting a process to the time of completion.

Turnaround Time= Time spent to get into memory + waiting in ready queue + doing I/O + executing on CPU

(It is the amount of time taken to execute a particular process)



Scheduling Criteria

- 4. Waiting Time: Time a process spends in ready queue.
- Amount of time a process has been waiting in the ready queue to acquire control on the CPU.

5. **Response Time:** Time from the submission of a request to the first response, Not Output

6. Load Average: It is the average number of processes residing in the ready queue waiting for their turn to get into the CPU.



Scheduling Algorithm Optimization Criteria

- Max CPU utilization
- Max throughput
- Min turnaround time
- Min waiting time
- Min response time

First-Come, First-Served (FCFS)



Processes that request CPU first, are allocated the CPU first

FCFS is implemented with FIFO queue.

A process is allocated the CPU according to their arrival times.

When process enters the ready queue, its PCB is attached to the Tail of queue, When CPU is free, it is allocated to the process selected from Head/Front of queue.

First-Come, First-Served (FCFS)





- "Run until Completed:" FIFO algorithm
- Example: Three processes arrive in order P1, P2, P3.
 - P1 burst time: 24
 - P2 burst time: 3
 - P3 burst time: 3
- Draw the Gantt Chart and compute Average Waiting Time and Average Turn Around Time/Completion Time.


Sol: As arrival time is not given assume order of arrival as: P1,P2,P3



First-Come, First-Served (FCFS)



- Example: Three processes arrive in order P1, P2, P3.
 - P1 burst time: 24
 - P2 burst time: 3
 - P3 burst time: 3
- Waiting Time
 - P1: 0
 - P2: 24
 - P3: 27



- Turnaround Time/Completion Time:
 - P1: 24
 - P2: 27
 - P3: 30
- Average Waiting Time: (0+24+27)/3 = (51/3) = 17 milliseconds
- Average Completion Time: (24+27+30)/3 = 81/3=27 milliseconds

Example: First-Come, First-Served (FCFS)





PROCESS	BURST TIME
P1	21
P2	3
P3	6
P4	2



The average waiting time will be = (0 + 21 + 24 + 30)/4 = 18.75 ms

	P1		P2	P3		P4	
0		21	2	24	3() 3	2

This is the GANTT chart for the above processes

First Come First Serve



Process id	AT	ВТ		
1	0	2		
2	3	1		
3	5	6		

First Come First Serve (Convoy Effect



Solve: FCFS Arrival Time

Process	AT	ВТ		
P1	0	4		
P2	1	3		
P3	2	1		
P4	3	2		
P5	4	5		

Shortest Job First



- Processes with least execution time are selected first.
- CPU is assigned to process with less CPU burst time.
- SJF:
 - Non-Preemption: CPU is always allocated to the process with least burst time and Process Keeps CPU with it until it is completed.
 - Pre-Emption: When a new process enters the queue, scheduler checks its execution time and compare with the already running process.
 - If Execution time of running process is more, CPU is taken from it and given to new process.

Shortest Job First(Preemptive)



Q1. Consider foll. Processes with A.T and B.T.

Process A.T B.T

P1 0 9

P2 1 4

P3 2 9

Cal. Completion time, turn around time and avg. waiting time.

SJF(Pre-emptive)-> SRTF

Shortest Job First(Preemptive)



Q1. Consider foll. Processes with A.T and B.T.

Process	A.I	B.I
P1	0	5
P2	1	3
P3	2	3

P4

Cal. Completion time, turn around time and avg. waiting time.

Shortest Job First(Non-Preemptiv

P

Q1. Consider foll. Processes with A.T and B.T.

Process	A.T	B.T
P1	1	7
P2	2	5
P3	3	1
P4	4	2
P5	5	8

Cal. Completion time, turn around time and avg. waiting time.

Practice: Shortest Job First (Notes) Preemption)

- P1 burst time: 15
- P2 burst time: 8
- P3 burst time: 10
- P4 burst time: 3



Practice: Shortest Job First (Preemption)

Process	Arrival Time	Burst Time		
P1	0	8		
P2	1	4		
P3	2	9		
P4	3	5		



Practice: Shortest Job First (Preemption)

Process	Arrival Time	Burst Time	СТ	Turn around time	Waiting Time
P1	0	7	16		
P2	2	4	7		
P3	4	1	5		
P4	5	4	11		

Priority Scheduling



- Priority is associated with each process.
- CPU is allocated to the process with highest priority.
- If 2 processes have same priority → FCFS

Disadvantage: **Starvation** (Low priority Processes wait for long)

Solution of Starvation: Aging

Aging: Priority of process is increased gradually (e.g after every 5 min priority is incremented by 1)



Priority Scheduling (Preemptive)

Process	Arrival Time	Priority	Burst Time	Completion Time
P1	1	5	4	
P2	2	7	2	
P3	3	4	3	

Consider 4 as
Highest and 7
as Lowest
Priority



Priority Scheduling (Preemptive)

Process	Arrival Time	Priority	Burst Time	Completion Time
P1	0	2	10	
P2	2	1	5	
P3	3	0	2	
P4	5	3	20	

Consider 3 as Lowest and 0 as Highest Priority



Priority Scheduling (Preemptive)

Process	Arrival Time	Priority	Burst Time	Completion Time
P1	1	4	4	
P2	2	5	2	
P3	2	7	3	
P4	3	8	5	
P5	3	5	1	
P6	4	6	2	

Consider 4 as Lowest and 8 as Highest Priority

Round Robin Scheduling

A Time Quantum is associated to all processes

Time Quantum: Maximum amount of time for which process can run once it is scheduled.

RR scheduling is always Pre-emptive.



Round Robin

TQ: 2

Process	Arrival Time	Burst Time	Completion Time
P1	0	5	10
P2	1	7	13
P3	2	1	5

Process	Arrival Time	Burst Time	Completion Time
P1	0	3	
P2	3	4	
P3	4	6	





Round Robin

TQ: 2

Process	Arrival Time	Burst Time	Completion Time
P1	0	4	
P2	1	5	
P3	2	2	
P4	3	1	
P5	4	6	
P6	6	3	



A multilevel queue scheduling algorithm partitions the ready queue into several separate queues.

For Example: a multilevel queue scheduling algorithm with five queues, listed below in order of priority:

- 1. System processes
- 2. Interactive processes
- 3. Interactive editing processes
- 4. Batch processes
- 5. Student/ user processes



- A process can move between various queues
- Multilevel Queue Scheduler defined by the following parameters:
 - No. of queues
 - Scheduling algorithms for each queue
 - Method used to determine when to upgrade / demote a process
 - Method used to determine which queue a process will enter and when that process needs service.




Example:

- No process in the batch queue, could run unless the queues for system processes, interactive processes, and interactive editing processes were all empty.
- If an interactive editing process entered the ready queue while a batch process was running, the batch process would be preempted.



- Processes can be :
 - Foreground Process: processes that are running currently → RR Scheduling is applied
 - Background Process: Processes that are running in the background but its effects are not visible to user. →FCFS
- Multilevel queue scheduling divides ready queue into several queues.
- Processes are permanently assigned to one queue on some property like memory size, process priority, process type.
- Each queue has its own scheduling algorithm





P U

Multilevel Queue

As different type of processes are there so all cant be put into same queue and apply same scheduling algorithm.

Disadvantages:

- 1. Until high priority queue is not empty, No process from lower priority queues will be selected.
- 2. Starvation for lower priority processes

Advantage:

Can apply separate scheduling algorithm for each queue.



Practice: Multilevel Queue

Process	Arrival Time	Burst Time	Queue
P1	0	4	1
P2	0	3	1
P3	0	8	2
P4	10	5	1

Priority of queue 1 is greater than queue 2. queue 1 uses Round Robin (Time Quantum = 2) and queue 2 uses FCFS.



P1	Р	2	P1	P2	P3	P4	P3
0	2	4	(6	7 1	10 1	5 20

P U

- Solution is: Multilevel Feedback Queue
- If a process is taking too long to execute.. Pre-empt it send it to low priority queue.
- Don't allow a low priority process to wait for long.
- After some time move a least priority process to high priority queue → Aging



- ✓ Allows a process to move between queues.
- √The idea is to separate processes according to the characteristics of their CPU bursts.
- ✓ If a process uses too much CPU time, it will be moved to a lower-priority queue.
- √This scheme leaves I/O-bound and interactive processes in the higher-priority queues.
- ✓In addition, a process that waits too long in a lower-priority queue may be moved to a higher-priority queue. This form of aging prevents starvation.







Figure - Multilevel Feedback Queue Scheduling





Multi-processor Scheduling



Concerns:

- If multiple CPUs are available, load sharing becomes possible.
 - Concentration is on systems in which the processors are identical—homogeneous in terms of their functionality.
 - Use any available processor to run any process in the queue

There are also different types of limitations:

 A system with an I/O device attached to a private bus of one processor. Processes that wish to use that device must be scheduled to run on that processor







■ 1. Asymmetric multiprocessing

All scheduling decisions, I/O processing, and other system activities handled by a single processor—the master server. The other processors execute only user code.

 Only one processor accesses the system data structures, reducing the need for data sharing.

Approaches to Multiple-Processor Scheduling



- •Each processor is self-scheduling.
- •All processes may be in a **common ready queue**, or each processor may have its **own private queue** of ready processes.
- •Scheduling proceeds by having the scheduler for each processor examine the ready queue and select a process to execute.

Virtually all modern operating systems support SMP, including Windows, Linux, and Mac OS X



- 1. Processor Affinity (a process has an affinity for the processor on which it is currently running.)
- Consider what happens to cache memory when a process has been running on a specific processor?

The data most recently accessed by the process populate the cache for the processor. As a result, successive memory accesses by the process are often satisfied in cache memory.



1. Processor Affinity

- If the process migrates to another processor.
- The contents of cache memory must be invalidated for the first processor, and the cache for the second processor must be repopulated.



■ 1. Processor Affinity

Because of the high cost of invalidating and repopulating caches, most SMP systems try to avoid migration of processes from one processor to another and instead attempt to keep a process running on the same processor.

This is known as processor affinity—that is, a process has an affinity for the processor on which it is currently running.



Forms of Processor Affinity

1. Soft affinity

When an operating system has a policy of attempting to keep a process running on the same processor—but not guaranteeing that it will do so—we have a situation known as soft affinity.

2. Hard affinity

Operating system will attempt to **keep a process on a single processor**, it is possible for a process to migrate between processors.



Hard affirnity

Example:

Many systems provide both soft and hard affinity.

For example, Linux implements soft affinity, but it also provides the **schedsetaffinity()** system call, which supports hard affinity.



2. Load Balancing

On SMP systems, it is important to keep the workload balanced among all processors to fully utilize the benefits of having more than one processor.

Need of Load Balancing

One or more processors may sit idle while other processors have high workloads, along with lists of processes awaiting the CPU.



2. Load Balancing

Load balancing is necessary only on systems where each processor has its own private queue of eligible processes to execute.

On systems with a common run queue, load balancing is often unnecessary, because once a processor becomes idle, it immediately extracts a run able process from the common run queue.

In most operating systems that support SMP, each processor have a private queue of eligible processes.



2. Load Balancing

Two approaches to load balancing: **push migration and pull migration.**

- 1. Push migration: a specific task periodically checks the load on each processor and—if it finds an imbalance—evenly distributes the load by moving (or pushing) processes from overloaded to idle or less-busy processors.
- 2. Pull migration: occurs when an idle processor pulls a waiting task from a busy processor.

P U

Issues concerning SMP systems

3. Multicore Processors

- A multi-core processor is a single computing component with two or more independent processing units called cores, which read and execute program instructions.
- ➤ A processor, or more commonly a CPU, is an individual processing device. It may contain multiple cores.
- >A core is a bank of registers and dedicated cache
- Core is a structure that performs all of a processor's tasks, but is not an entire processor.



3. Multicore Processors

A multi-core processor is a single computing component with two or more independent processing units called cores, which read and execute program instructions.

The instructions are ordinary CPU instructions (such as add, move data, and branch) but the single processor can run multiple instructions on separate cores at the same time, increasing overall speed for programs.

Manufacturers typically integrate the cores onto a single integrated circuit



3. Multicore Processors

SMP systems have allowed several threads to run concurrently by providing multiple physical processors.

In computer system, multiple processor cores are placed on the same physical chip, resulting in a multicore processor.

Each core maintains its architectural state and appears to the operating system to be a separate physical processor.



3. Multicore Processors

Multicore processors may complicate scheduling issues:


When a processor accesses memory, it spends a significant amount of time waiting for the data to become available. This situation, known as a **memory stall.**

Memory Stall may occur due to a cache miss (accessing data that are not in cache memory).






Memory Stall



the processor can spend up to 50 percent of its time waiting for data to become available from memory.



Memory Stall



the processor can spend up to 50 percent of its time waiting for data to become available from memory.



Solution to Memory Stall Problem

To remedy this situation, hardware designs have implemented multithreaded processor cores in which two (or more) hardware threads are assigned to each core.

If one thread stalls while waiting for memory, the core can switch to another thread.

P U

Real Time Scheduling

Analysis and testing of the scheduler system and the algorithms used in real-time applications

- a) soft real-time systems b) hard real-time systems
- a) Soft real-time systems provide no guarantee as to when a critical real-time process will be scheduled. They guarantee only that the process will be given preference over noncritical processes.
- b) Hard real-time systems have stricter requirements. A task must be serviced by its deadline;
- Service after the deadline has expired is the same as no service at all.

P U

Priority based real-time scheduling

- priority-based scheduling algorithms assign each process a priority based on its importance;
- >more important tasks are assigned higher priorities than less important.
- ➤If the scheduler also supports preemption, a process currently running on the CPU will be preempted if a higher-priority process becomes available to run.
- ➤ A preemptive, priority-based scheduler only guarantees soft real-time functionality.



Priority based real-time scheduling

Example

Linux, Windows, and Solaris operating systems assign real-time processes the highest scheduling priority.

For example Windows has 32 different priority levels. The highest levels—priority values 16 to 31—are reserved for real-time processes.

Priority based scheduling for hard realtime



- ➤ Hard real-time systems must guarantee that real-time tasks will be serviced in accord with their deadline requirements.
- ➤ Characteristics of the processes that are to be scheduled:
- 1. The processes are considered **periodic**.
- i.e They require the CPU at constant intervals (periods).

Priority based scheduling for hard realtime



➤Once a periodic process has acquired the CPU, it has a fixed processing time *t*, a deadline *d* by which it must be serviced by the CPU, and a period *p*.

The relationship of the processing time, the deadline, and the period can be expressed as $0 \le t \le d \le p$.

The rate of a periodic task is 1/p.

Priority based scheduling for hard realtime



- 1. Schedulers assign priorities according to a process's deadline or rate requirements.
- 2. A process may have to announce its deadline requirements to the scheduler.
- Scheduler uses an admission-control algorithm to perform following:
 - 1. It either admits the process, guaranteeing that the process will complete on time.
 - 2. Rejects the request as impossible if it cannot guarantee that the task will be serviced by its deadline.



- The rate-monotonic scheduling algorithm schedules periodic tasks using a static priority policy with preemption.
- rate-monotonic scheduling (RMS) is a priority assignment algorithm used in real-time operating systems (RTOS) with a static-priority scheduling class.
- The static priorities are assigned according to the cycle duration of the job, so a shorter cycle duration results in a higher job priority



- ➤If a lower-priority process is running and a higher-priority process becomes available to run, it will preempt the lower-priority process.
- ➤ Upon entering the system, each periodic task is assigned a priority inversely based on its period. The shorter the period, the higher the priority; the longer the period, the lower the priority.
- ➤ Assign a higher priority to tasks that require the CPU more often (less)



rate-monotonic scheduling assumes that the processing time of a periodic process is the same for each CPU burst.

For example

Consider P1, P2 with time period 50,100 resp. and B.T 20,35 resp.

Cal. CPU utilization of each process and total CPU utilization.

Sol:

CPU utilization=(Burst time/Time period)= (Ti/Pi)

For P1: (20/50)=0.40 i.e 40%

For P2: (35/100)=0.35 i.e 35%

Total CPU utilization is 75%



rate-monotonic scheduling assumes that the processing time of a periodic process is the same for each CPU burst.

For example Consider t1,t2,t3 with time period 4,5,20 resp. and B.T 1,2,5 resp.



Consider 2 processes P1, P2. Time Period: 50,100 resp. Burst time: 20,35. Schedule processes using Rate monotonic scheduling

Note: if CPU utilization is less than 80% only then it can be scheduled by rate monotonic scheduling. So before scheduling find Over all CPU utilization.

Consider 2 processes P1, P2. Time Period: 50,70 resp. Burst time: 20,35. Schedule processes using Rate monotonic scheduling





Rate-monotonic scheduling has a limitation:

CPU utilization is bounded, and it is not always possible fully to maximize CPU resources.

The worst-case CPU utilization for scheduling *N processes is* $N(2^1/N - 1)$



Earliest Deadline First Scheduling

Earliest-deadline-first (EDF) scheduling dynamically assigns priorities according to deadline.

The earlier the deadline, the higher the priority the later the deadline, the lower the priority.

Under the EDF policy, when a process becomes runnable, it must announce its deadline requirements to the system. Priorities may have to be adjusted to reflect the deadline of the newly runnable process.



Earliest Deadline First Scheduling

Consider 2 processes P1, P2. Time Period: 50,100 resp.

Burst time: 20,35.

