
# **QVector3**

#### Diagrams



#### **Knowledge Requirements**

- Math
- See: Introduction to 3D Game Programming with DirectX 9.0, Part I.
- See: <Program Files Folder>\Microsoft DirectX SDK (June 2010)\Documentation\DirectX9\windows\_graphics.chm, from DirectX SDK. Search for D3DXVECTOR3 and D3DXVec3 in "Index" tab.
- See: http://www.zator.com/Cpp/E4 9 18.htm to refresh operators overloading knowledge.

#### **Functional Specifications**

- Override default constructor. Sets attributes to zero.
- Override copy constructor.
- Implement constructor that receives a QBaseVector3 type.
- Implement constructor that receives 3 FloatTypes, one for each vector components.
- Implement constructor that receives only 1 FloatType. Set all attributes to that value.
- Implement constructor that receives a 3-FloatTypes array.
- Implement constructor that receives a pointer-to-FloatType. The pointer should point to a dynamically allocated 3-FloatTypes array.
- Implement constructor that receives a V4x32-FLOAT.
- It is not necessary to override default destructor.



Quimera Engine: Kinesis Development Team

## **QVector3**

- It is not necessary to override assign operator.
- Operator\* must offer an overload that receives a FloatType (product by scalar).
- Operator\* must offer an overload that receives a QBaseVector3. Each vector component will be multiplied by the other vector's component.
- Operator/ must offer an overload that receives a FloatType (division by scalar).
- Operator/ must offer an overload that receives a QBaseVector3. Each vector component will be divided by the other vector's component.
- A global operator\* must be implemented in order to let a FloatType be multiplied by a QVector3. It's not the same QVector3 \* FloatType than FloatType \* QVector3.
- A global operator/ must be implemented in order to let a FloatType be multiplied by a QVector3. It's not the same QVector3 / FloatType than FloatType / QVector3.
- ResetToOne sets all vector's components to 1.
- GetLength calculates vector module.
- When implementing CrossProduct, be aware of Quimera Engine uses a left-handed convention and that affects directly to the resulting vector.
- Lerp must receive a FloatType value between 0 and 1. When it receives 1, the vector keeps its length; when it receives 0.5, the vector length is reduced to its half, etc. If it receives 2, its length becomes double.
- Distance calculates the length of the difference between 2 vectors.
- Intersection must offer an overload that receives a QBaseVector3 and returns a boolean type. If the vector intersects with the supplied vector, then return TRUE.
- Intersection must offer an overload that receives an input QBaseVector3, an output QBaseVector3 and returns a boolean type. If the vector intersects with the supplied input vector, then the output vector is filled with the intersection position and the method returns TRUE.
- ToString format: "V3( X, Y, Z )". Use STL string.

#### Design / Technical Requirements

- Use member initialization lists.
- Remember using "explicit" when constructors receive only one parameter.
- No virtual methods.
- Use by-reference parameters always.
- Operator== and Operator!= must have Epsilon value into account.
- Use FloatType constants to store values like 1.
- Try to avoid square roots.
- All methods should be inline.
- No exceptions.
- No error codes.
- No profiling.
- Check for division by zero. Use asserts.
- Respect diagram names.

### Support People

Thund.

o Ne

Quimera Engine: Kinesis Development Team