Infohazard.Core

Generated by Doxygen 1.9.5

1	Infohazard.Core Documentation	1
	1.1 Table of Contents	. 1
	1.2 Introduction	. 1
	1.3 License	. 2
	1.4 Installation	. 2
	1.4.1 Method 1 - Package Manager	. 2
	1.4.2 Method 2 - Git Submodule	. 2
	1.4.3 Method 3 - Add To Assets	. 3
	1.4.4 Method 4 - Asset Store	. 3
	1.5 Setup	. 3
	1.6 Features Guide	. 3
	1.6.1 Attributes	. 3
	1.6.2 Data Structures	. 4
	1.6.3 Pooling	. 4
	1.6.4 Timing	. 4
	1.6.5 Tags	. 5
	1.6.6 Unique Names	. 5
	1.6.7 Utility	. 6
	1.6.8 Miscellaneous	. 6
2	Changelog	7
	2.1 [Unreleased]	. 7
	2.2 [1.0.0] - 2022-10-08	. 7
	2.2.1 Added	. 7
3	Hierarchical Index	7
	3.1 Class Hierarchy	. 7
4	Class Index	9
	4.1 Class List	. 9
5	Namespace Documentation	11
	5.1 Infohazard Namespace Reference	. 11
	5.2 Infohazard.Core Namespace Reference	. 11
	5.3 Infohazard.Core.Editor Namespace Reference	. 12
6	Class Documentation	13
	6.1 Infohazard.Core.AssetDropdownAttribute Class Reference	. 13
	6.1.1 Detailed Description	. 13
	6.2 Infohazard.Core.ComponentID Struct Reference	. 13
	6.2.1 Detailed Description	. 14
	6.2.2 Constructor & Destructor Documentation	. 14
	6.2.3 Member Function Documentation	. 14
	6.2.4 Member Data Documentation	. 15

6.2.5 Property Documentation	. 15
6.3 Infohazard.Core.ConditionalDrawAttribute Class Reference	. 16
6.3.1 Detailed Description	. 16
6.3.2 Constructor & Destructor Documentation	. 16
6.3.3 Property Documentation	. 17
6.4 Infohazard.Core.Editor.CoreEditorUtility Class Reference	. 17
6.4.1 Detailed Description	. 18
6.4.2 Member Function Documentation	. 18
6.4.3 Member Data Documentation	. 23
6.5 Infohazard.Core.DebugUtility Class Reference	. 24
6.5.1 Detailed Description	. 24
6.5.2 Member Function Documentation	. 24
6.6 Infohazard.Core.DrawSingleChildPropertyAttribute Class Reference	. 25
6.6.1 Detailed Description	. 26
6.6.2 Constructor & Destructor Documentation	. 26
6.6.3 Property Documentation	. 26
6.7 Infohazard.Core.EditNameOnlyAttribute Class Reference	. 26
6.7.1 Detailed Description	. 26
6.8 Infohazard.Core.EnumerableUtility Class Reference	. 27
6.8.1 Detailed Description	. 27
6.8.2 Member Function Documentation	. 27
6.9 Infohazard.Core.ExpandableAttribute Class Reference	. 28
6.9.1 Detailed Description	. 29
6.9.2 Constructor & Destructor Documentation	. 29
6.9.3 Property Documentation	. 29
6.10 Infohazard.Core.GameObjectUtility Class Reference	. 30
6.10.1 Detailed Description	. 31
6.10.2 Member Function Documentation	. 31
6.11 Infohazard.Core.IPersistedInstance Interface Reference	. 36
6.11.1 Detailed Description	. 36
6.11.2 Member Function Documentation	. 37
$6.12\ Infohazard. Core. List Queue < T > Class\ Template\ Reference\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\$. 37
6.12.1 Detailed Description	. 38
6.12.2 Constructor & Destructor Documentation	. 38
6.12.3 Member Function Documentation	. 40
6.12.4 Property Documentation	. 43
6.13 Infohazard.Core.MathUtility Class Reference	. 43
6.13.1 Detailed Description	. 46
6.13.2 Member Function Documentation	. 46
6.13.3 Member Data Documentation	. 59
6.14 Infohazard.Core.PassiveTimer Struct Reference	. 60
6.14.1 Detailed Description	. 62

6.14.2 Member Enumeration Documentation	62
6.14.3 Constructor & Destructor Documentation	62
6.14.4 Member Function Documentation	63
6.14.5 Member Data Documentation	63
6.14.6 Property Documentation	64
6.15 Infohazard.Core.Pause Class Reference	66
6.15.1 Detailed Description	67
6.15.2 Property Documentation	67
6.15.3 Event Documentation	67
$\textbf{6.16 Infohazard.Core.Pool} < T > Class\ Template\ Reference\ \dots \dots$	68
6.16.1 Detailed Description	68
6.16.2 Constructor & Destructor Documentation	68
6.16.3 Member Function Documentation	69
6.16.4 Property Documentation	70
6.17 Infohazard.Core.PooledParticleEffect Class Reference	70
6.17.1 Detailed Description	71
6.17.2 Member Data Documentation	71
6.18 Infohazard.Core.PooledTrail Class Reference	71
6.18.1 Detailed Description	71
6.19 Infohazard.Core.PoolManager Class Reference	71
6.19.1 Detailed Description	72
6.19.2 Member Function Documentation	72
6.19.3 Property Documentation	72
6.20 Infohazard.Core.ProgressBar Class Reference	72
6.20.1 Detailed Description	73
6.20.2 Member Data Documentation	73
6.20.3 Property Documentation	73
6.21 Infohazard.Core.RandomUtility Class Reference	74
6.21.1 Detailed Description	74
6.21.2 Member Function Documentation	74
6.22 Infohazard.Core.SceneControl Class Reference	75
6.22.1 Detailed Description	75
6.22.2 Member Function Documentation	75
$ \textbf{6.23 Infohazard.Core.Singleton} < \textbf{T} > \textbf{Class Template Reference} \dots \dots \dots \dots \dots \dots \dots \dots \dots $	76
6.23.1 Detailed Description	76
6.23.2 Property Documentation	76
$\textbf{6.24 Infohazard.Core.SingletonAsset} < T > Class Template \ Reference \dots \dots \dots \dots \dots \dots \dots \dots \dots $	77
6.24.1 Detailed Description	77
6.24.2 Property Documentation	77
6.25 Infohazard.Core.SingletonAssetBase Class Reference	78
6.25.1 Detailed Description	78
6.25.2 Property Documentation	78

6.26 Infohazard.Core.Spawnable Class Reference	78
6.26.1 Detailed Description	79
6.26.2 Member Function Documentation	79
6.26.3 Property Documentation	82
6.26.4 Event Documentation	82
6.27 Infohazard.Core.StringUtility Class Reference	82
6.27.1 Detailed Description	83
6.27.2 Member Function Documentation	83
6.28 Infohazard.Core.Tag Class Reference	83
6.28.1 Detailed Description	84
6.28.2 Member Data Documentation	84
6.28.3 Property Documentation	85
6.29 Infohazard.Core.TagMask Struct Reference	86
6.29.1 Detailed Description	87
6.29.2 Constructor & Destructor Documentation	87
6.29.3 Member Function Documentation	87
6.29.4 Member Data Documentation	91
6.29.5 Property Documentation	92
6.30 Infohazard.Core.TagMaskUtility Class Reference	93
6.30.1 Detailed Description	93
6.30.2 Member Function Documentation	93
6.31 Infohazard.Core.Editor.TagsGenerator Class Reference	96
6.31.1 Detailed Description	97
6.31.2 Member Function Documentation	97
6.32 Infohazard.Core.TimeToLive Class Reference	97
6.32.1 Detailed Description	98
6.32.2 Member Data Documentation	98
6.32.3 Property Documentation	98
6.33 Infohazard.Core.TriggerVolume.TriggerEvents Class Reference	98
6.33.1 Detailed Description	99
6.33.2 Member Data Documentation	99
6.33.3 Property Documentation	99
6.34 Infohazard.Core.TriggerVolume Class Reference	100
6.34.1 Detailed Description	101
6.34.2 Member Data Documentation	101
6.34.3 Property Documentation	101
6.34.4 Event Documentation	101
6.35 Infohazard.Core.TypeSelectAttribute Class Reference	102
6.35.1 Detailed Description	102
6.35.2 Constructor & Destructor Documentation	102
6.35.3 Property Documentation	103
6.36 Infohazard Core Type Utility Class Reference	103

	6.36.1 Detailed Description	104
	6.36.2 Member Function Documentation	104
	6.36.3 Property Documentation	104
6.37	Infohazard.Core.UniqueNamedObject Class Reference	105
	6.37.1 Detailed Description	105
	6.37.2 Member Function Documentation	105
	6.37.3 Member Data Documentation	106
	6.37.4 Property Documentation	106
6.38	Infohazard.Core.UniqueNameList Class Reference	107
	6.38.1 Detailed Description	107
	6.38.2 Member Data Documentation	107
	6.38.3 Property Documentation	107
6.39	Infohazard.Core.UniqueNameListEntry Class Reference	107
	6.39.1 Detailed Description	107

1 Infohazard.Core Documentation

1.1 Table of Contents

- · Infohazard.Core Documentation
 - Table of Contents
 - Introduction
 - License
 - Installation
 - * Method 1 Package Manager
 - * Method 2 Git Submodule
 - * Method 3 Add To Assets
 - * Method 4 Asset Store
 - Setup
 - Features Guide
 - * Attributes
 - * Data Structures
 - * Pooling
 - * Timing
 - * Tags
 - * Unique Names
 - * Utility
 - * Miscellaneous

1.2 Introduction

Infohazard.Core is a collection of systems and utilities that I've found super helpful in making many different kinds of games, so I hope you find it helpful too! This document will cover setup and basic usage of the code in Infohazard.Core. You can find full API documentation here and in the code.

1.3 License

If Infohazard.Core is acquired from the Unity Asset Store, you must follow the Unity Asset Store license. The open-source repository uses the MIT license. You are welcome to have your own packages or assets depend on this package.

1.4 Installation

1.4.1 Method 1 - Package Manager

Using the Package Manager is the easiest way to install HyperNav to your project. Simply install the project as a git URL. Note that if you go this route, you will not be able to make any edits to the package.

- 1. In Unity, open the Package Manager (Window > Package Manager).
- 2. Click the '+' button in the top right of the window.
- 3. Click "Add package from git URL...".
- 4. Paste in https://github.com/infohazardgames/Infohazard.Core.git.
- 5. Click Add.

1.4.2 Method 2 - Git Submodule

Using a git submodule is an option if you are using git for your project source control. This method will enable you to make changes to the package, but those changes will need to be tracked in a separate git repository.

- 1. Close the Unity Editor.
- 2. Using your preferred git client or the command line, add https://github.com/infohazardgames/\leftarrow
 Infohazard.Core.git as a submodule in your project's Packages folder.
- 3. Re-open the Unity Editor.

If you wish to make changes when you use this method, you'll need to fork the HyperNav repo. Once you've made your changes, you can submit a pull request to get those changes merged back to this repository if you wish.

- 1. Fork this repository. Open your newly created fork, and copy the git URL.
- 2. In your project's Packages folder, open the HyperNav repository.
- 3. Change the origin remote to the copied URL.
- 4. Make your changes, commit, and push.
- 5. (Optional) Open your fork again, and create a pull request.

1.5 Setup 3

1.4.3 Method 3 - Add To Assets

If you wish to make changes to the library without dealing with a git submodule (or you aren't using git), you can simply copy the files into your project's Assets folder.

- 1. In the main page for this repo, click on Code > Download Zip.
- 2. Extract the zip on your computer.
- 3. Make a HyperNav folder under your project's Assets folder.
- 4. Copy the Editor and Runtime folders from the extracted zip to the newly created HyperNav folder.

1.4.4 Method 4 - Asset Store

If you'd rather use the asset store than the package manager, you can get the project at LINK TBD. Simply add it to the project as you would any other asset.

1.5 Setup

The only setup required beyond installation is to add references to the Infohazard.Core assembly if you are using an assembly definition. If you are using the default assemblies (such as Assembly-CSharp), nothing is needed here. You may also wish to have your editor assembly (if you have one) reference Infohazard.Core.Editor.

1.6 Features Guide

1.6.1 Attributes

The package provides several PropertyAttributes that you can use in your scripts to customize how serialized fields are drawn in the inspector. To use any of these attributes, simply add [AttributeName] in front of a serialized field in a script. You can also check out the drawers for these attributes in the Editor/Attributes directory.

- **1.6.1.1 AssetDropdown** The [AssetDropdown] attribute is used to show a dropdown menu on a field whose type is a UnityEngine.Object reference. It will find all assets in your project that match this type and display them as options in the dropdown. The standard drag/drop interface still works as well.
- **1.6.1.2 ConditionalDraw** The [ConditionalDraw] attribute is used to conditionally hide a serialized field in the inspector depending on some other condition. The supplied condition should be the name of another serialized field in the same script. You can also optionally pass in a value to compare that condition field with, and whether they must be equal or unequal to display the field.
- **1.6.1.3 DrawSingleChildProperty** The [DrawSingleChildProperty] attribute is used to render a hierarchy of fields as just a single value. Say you have a struct called Data with a string field called _name. Adding [Draw← SingleChildProperty("_name")] to a field of type Data would cause just the _name field to be drawn in the inspector.

- **1.6.1.4 EditNameOnlyAttribute** The [EditNameOnly] attribute displays a Unity Object reference field as a text entry, which is used to control the name of the referenced object. If the reference is set to null, the standard drag-drop box is used.
- **1.6.1.5 ExpandableAttribute** The [Expandable] attribute is used to optionally draw the child properties of a Unity Object reference field, such that the referenced object can be edited without changing the inspector context. If the type of the field is a ScriptableObject, new instances can also be created from the inspector.
- **1.6.1.6 TypeSelectAttribute** The [TypeSelect] attribute is used on a string field to show a dropdown where any valid C# type can be selected. The selected type is saved in the string as its full class name. This attribute is useful with the TypeUtility class to find the selected type.

1.6.2 Data Structures

1.6.2.1 ListQueue The ListQueue<T> class is an implementation of a queue data structure similar to C::'s Queue class. The main difference is that a ListQueue implements the IList interface and allows you to access any element of the queue whenever you want, while still maintaining O(1) performance for normal Enqueue and Dequeue operations (as long as there is capacity available).

1.6.3 Pooling

The library provides a simple object pooling system under the Pooling directory. Object pooling means that instead of instantiating and destroying GameObjects as needed, we deactivate them and reactivate them to avoid constantly allocating and deallocating memory.

- 1.6.3.1 Spawnable To start working with the pooling system, simply add the Spawnable script to your prefabs and then instantiate/destroy them using Spawnable.Spawn and Spawnable.Despawn. Note that Awake/OnDestroy will only be called when the objects are actually created and destroyed; if you want an event when the object is spawned, use the OnSpawned and OnDespawned messages. Note that if a prefab does not contain a Spawnable script, using Spawnable.Spawn and Spawnable.Despawn is the same as Instantiate and Destroy. This allows you to spawn and despawn objects without worrying about whether they're pooled or not. All of my libraries use this system, so they are compatible with pooling.
- **1.6.3.2 PoolManager** The pooling system needs a PoolManager to work. You can either place one Pool ← Manager per scene, have a global instance that is never destroyed, or simply let the system create the manager itself. To create it manually, just add this script to an empty GameObject and you're good to go. You can use the ClearInactiveObjects() method on PoolManager.Instance to destroy any inactive pooled objects, such as when you change scenes. PooledTrail, PooledParticleEffect Attach these scripts to TrailRenderer and ParticleSystem GameObjects to make them play nicely with the pooling system.

1.6.4 Timing

The Timing directory contains some useful utilities to deal with in-game time.

1.6.4.1 PassiveTimer PassiveTimer is a serializable data type used to create timers in your scripts. You can use it to create ability cooldowns and durations, weapon reloads, and other common game functionality. Simply call Initialize() when your script initializes, then use the timer's various methods. See the API docs for more info.

1.6 Features Guide 5

1.6.4.2 Pause The Pause system is built to do exactly that - pause the game. Just set Pause.IsPaused to true and time will freeze, then set it to false to resume time at its previous speed. The game will automatically unpause if you change scenes. You should avoid running game logic if the game is paused.

1.6.4.3 TimeToLive This script destroys or despawns an object some number of seconds after it is spawned. It is compatible with the pooling system.

1.6.5 Tags

This system is meant to make working with GameObject tags in your scripts much easier and less error-prone.

- **1.6.5.1 Tag** This class provides string constants for all default tags. So instead of writing target.CompareTag("← Player") you could write target.CompareTag(Tag.Player).
- **1.6.5.2 TagMask** Using a serialized field of type TagMask allows users to pick tags in the editor from a dropdown instead of typing them, just like the Unity-provided LayerMask.. It also allows selecting multiple tags without using an array. Extension methods are provided for common tag operations so that a TagMask can be used in place of a string tag. For example, you can say target.CompareTag(tagMask), which will return true if target's tag is equal to any of the tags in tagMask.
- **1.6.5.3 GameTag** This file is generated based on your custom tags, and lives in your project rather than in the package. You should be prompted to generate it if the system detects you have custom tags, or you can use the Infohazard/Generate/Update GameTag.cs command. Once this file is generated, your game tags will automatically be available for selection in a TagMask, and you can refer to them as constants in code through the generated GameTag class (you will need to reference the Infohazard.Core.Data assembly if you are using assembly definitions).

1.6.6 Unique Names

The UniqueName system enables you to assign names to objects that can be referenced across scenes and assets. You can then easily find the active object using that name (if one exists). This system uses ScriptableObjects to store the names so that you can easily see what names are available to reference, and can avoid having to type out the names and potentially make mistakes. Furthermore, these unique names can be changed without breaking references, since they are stored as object references.

- **1.6.6.1 UniqueNameList** A UniqueNameList asset is how you start creating a list of unique names. You can have multiple UniqueNameLists in your project, or you can use just one. This is purely for organizational purposes. You can create a UniqueNameList using Assets/Create/Infohazard/Unique Name List.
- **1.6.6.2 UniqueNameListEntry** A UniqueNameListEntry is the actual unique name, which is organized under a UniqueNameList and used both by objects with unique names and objects using the system to find named objects. UniqueNameListEntries should be created through the UniqueNameList inspector.
- **1.6.6.3 UniqueNamedObject** Attach this script to a GameObject to assign a unique name to it, and make it findable in the system. You can find one of these objects using the static method UniqueNamedObject.TryGet← Object, passing in either a string or a UniqueNameListEntry.

1.6.7 Utility

The Utility section contains a bunch of static methods to help with all kinds of common operations. See the API docs for each file for more info.

- **1.6.7.1 DebugUtility** Contains methods to draw a cube using Debug.DrawLine, and to pause the editor after a certain number of frames.
- **1.6.7.2 EnumerableUtility** Contains methods that combine common LINQ calls such as Select and Where into a single enumeration for better code optimization.
- **1.6.7.3 GameObjectUtility** Contains various methods for working with GameObjects and Transforms, such as destroying all the children of an object, setting an object's layer recursively, and getting a path containing an object's ancestor names.
- **1.6.7.4 MathUtility** Contains many useful math operations, such as constructing a Quaternion from any two axes, getting a vector with one component changed, solving polynomials up to degree 4 (quartic), and getting the point where two lines are closest to each other.
- **1.6.7.5 RandomUtility** Contains extension methods to System.Random such as generating 64-bit numbers. StringUtility String processing methods such as splitting a CamelCase string to have spaces between words.
- **1.6.7.6 TypeUtility** Provides methods to get a list of all loaded types using reflection, and to find a type based on its name.

1.6.8 Miscellaneous

The remaining functionality provided by Infohazard.Core doesn't fall nicely into one of the previous categories, but was still useful enough to include.

- **1.6.8.1 ProgressBar** Used to create health bars and other types of progress bars without using a Slider. It supports images that fill the bar using either the "filled" image type or by manipulating the RectTransform anchors.
- **1.6.8.2 SceneControl** Provides a static method to quit the game that works in a standalone build as well as in the editor. Also provides some methods to navigate to scenes. This is useful if you're building a super quick main menu (such as in the last half hour of a game jam) and need to hook up your buttons as fast as possible.
- **1.6.8.3 SceneRef** A serializable type that allows you to have assignable scene references in your scripts without making the user type the scene name. Instead, they can simply drag in a scene asset. At runtime, you still access the scene by its name. Using a SceneRef also enables the reference to be maintained if a scene is renamed.
- **1.6.8.4 Singleton** You can inherit from this script in managers or other scripts that need to exist in the scene exactly once. A static Instance accessor is automatically provided, which will do a lazy search for the correct instance the first time it is used, or if the previous instance was destroyed. After that it will just return a cached instance.

2 Changelog 7

1.6.8.5 SingletonAsset Similar to Singleton, but for ScriptableObjects. You specify a path in your subclass where the instance should live (this must be under a Resources folder) and the editor will automatically handle loading and even creating this asset for you when needed.

1.6.8.6 TriggerVolume A script that makes it easy to add events to a trigger collider. Provides both UnityEvents (assignable in the inspector) and normal C# events for when an object enters or leaves the trigger, and when all objects have left the trigger.

Changelog

All notable changes to this project will be documented in this file.

The format is based on Keep a Changelog, and this project adheres to Semantic Versioning.

2.1 [Unreleased]

2.2 [1.0.0] - 2022-10-08

2.2.1 Added

· Initial commit, all files and documentation added.

Into bearing Onco Asset Due to decima Attailbeats

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Infohazard.Core.AssetDropdownAttribute	13
Infohazard.Core.ComponentID	13
Infohazard.Core.ConditionalDrawAttribute	16
Infohazard.Core.Editor.CoreEditorUtility	17
Infohazard.Core.DebugUtility	24
Infohazard.Core.DrawSingleChildPropertyAttribute	25
Infohazard.Core.EditNameOnlyAttribute	26
Infohazard.Core.EnumerableUtility	27
Infohazard.Core.ExpandableAttribute	28
Infohazard.Core.GameObjectUtility	30
Infohazard.Core.IPersistedInstance	36

Infohazard.Core.ListQueue< T >	37
Infohazard.Core.MathUtility	43
Infohazard.Core.PassiveTimer	60
Infohazard.Core.Pause	66
Infohazard.Core.Pool < T >	68
${\sf Infohazard.Core.Pool} {< \sf Infohazard.Core.Spawnable > }$	68
Infohazard.Core.PooledParticleEffect	70
Infohazard.Core.PooledTrail	71
Infohazard.Core.PoolManager	71
Infohazard.Core.ProgressBar	72
Infohazard.Core.RandomUtility	74
Infohazard.Core.SceneControl	75
Infohazard.Core.Singleton< T >	76
Infohazard.Core.SingletonAssetBase	78
${\bf Infohazard.Core.SingletonAsset} < {\bf T} >$	77
Infohazard.Core.Spawnable	78
Infohazard.Core.StringUtility	82
Infohazard.Core.Tag	83
Infohazard.Core.TagMask	86
Infohazard.Core.TagMaskUtility	93
Infohazard.Core.Editor.TagsGenerator	96
Infohazard.Core.TimeToLive	97
Infohazard.Core.TriggerVolume.TriggerEvents	98
Infohazard.Core.TriggerVolume	100
Infohazard.Core.TypeSelectAttribute	102
Infohazard.Core.TypeUtility	103
Infohazard.Core.UniqueNamedObject	105
Infohazard.Core.UniqueNameList	107
Infohazard.Core.UniqueNameListEntry	107

4 Class Index 9

4 Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Infohazard.Core.AssetDropdownAttribute Attribute that draws an object reference as a dropdown that searches through the project.	13
Infohazard.Core.ComponentID A serializable type used to uniquely identify a component relative to a root GameObject.	13
Infohazard.Core.ConditionalDrawAttribute Attribute draws a property when a given condition is true.	16
Infohazard.Core.Editor.CoreEditorUtility Contains several editor-only utilities.	17
Infohazard.Core.DebugUtility Contains various static methods relating to debugging and diagnostics.	24
Infohazard.Core.DrawSingleChildPropertyAttribute Attribute draws only a single child property of a property.	25
Infohazard.Core.EditNameOnlyAttribute Attribute that draws only the name of an Object reference field.	26
Infohazard.Core.EnumerableUtility Contains various static methods for working with sequences, extending the functionality of LINQ.	27
Infohazard.Core.ExpandableAttribute Attribute that enables editing properties of a referenced object.	28
Infohazard.Core.GameObjectUtility Contains utility methods for dealing with GameObjects and Transforms.	30
Infohazard.Core.IPersistedInstance This is a hack so that PoolManager can send messages to PersistedGameObjects.	36
Infohazard.Core.ListQueue < T > A FIFO data structure similar to a Queue, except that it implements all List operations.	37
Infohazard.Core.MathUtility Contains utility methods for working with mathematical types and solving math equations.	43
Infohazard.Core.PassiveTimer A lightweight timer that does not need to be updated each frame.	60
Infohazard.Core.Pause Manages pausing and unpausing of the game.	66
Infohazard.Core.Pool < T > Provides a simple pool with an interface similar to the official Unity pool added in 2021.	68
Infohazard.Core.PooledParticleEffect A component that can be attached to ParticleSystem GameObjects to make them work correctly with pooling.	70

Infohazard.Core.PooledTrail	
A component that can be attached to TrailRenderer GameObjects to make them work correctly with pooling.	71
Infohazard.Core.PoolManager The singleton manager class that handles object pooling.	71
Infohazard.Core.ProgressBar Used to create health bars and other types of progress bars without using a Slider.	72
Infohazard.Core.RandomUtility Contains extensions to builtin randomization functionality.	74
Infohazard.Core.SceneControl Provides some methods to navigate to scenes.	75
Infohazard.Core.Singleton< T > Base class that makes it easier to write scripts that always have exactly one instance.	76
Infohazard.Core.SingletonAsset< T > Base class that makes it easier to write ScriptableObjects that always have exactly one instance in your project.	77
Infohazard.Core.SingletonAssetBase Base class of SingletonAsset <t>. For internal use only.</t>	78
Infohazard.Core.Spawnable Attach this component to a prefab to enable it to use the pooling system.	78
Infohazard.Core.StringUtility Contains string processing utilities.	82
Infohazard.Core.Tag Provides string constants for builtin Unity tags.	83
Infohazard.Core.TagMask Used to select tags in the inspector, including the ability to select multiple tags.	86
Infohazard.Core.TagMaskUtility Static operations on Tag enum values.	93
Infohazard.Core.Editor.TagsGenerator Class used to generate the GameTag.cs file to use your custom tags in code.	96
Infohazard.Core.TimeToLive Despawns a GameObject after a set amount of time.	97
Infohazard.Core.TriggerVolume.TriggerEvents Class that stores the UnityEvents used by a TriggerVolume.	98
Infohazard.Core.TriggerVolume A script that makes it easy to add events to a trigger collider.	100
Infohazard.Core.TypeSelectAttribute Attribute that draws string fields as a dropdown where a Type can be selected.	102
Infohazard.Core.TypeUtility Contains utilities for working with C# reflection types and getting a type by its name.	103

107

Infohazard.Core.UniqueNamedObject This script is used to assign a unique name to an object, which can then be used to find that object.	10
Infohazard.Core.UniqueNameList	
A list used to organize unique names used by objects.	10
Infohazard.Core.UniqueNameListEntry	

5 Namespace Documentation

5.1 Infohazard Namespace Reference

5.2 Infohazard.Core Namespace Reference

Classes

· class AssetDropdownAttribute

Attribute that draws an object reference as a dropdown that searches through the project.

struct ComponentID

A serializable type used to uniquely identify a component relative to a root GameObject.

· class ConditionalDrawAttribute

Attribute draws a property when a given condition is true.

A unique name asset, usable by a UniqueNamedObject.

· class DebugUtility

Contains various static methods relating to debugging and diagnostics.

• class DrawSingleChildPropertyAttribute

Attribute draws only a single child property of a property.

class EditNameOnlyAttribute

Attribute that draws only the name of an Object reference field.

class EnumerableUtility

Contains various static methods for working with sequences, extending the functionality of LINQ.

· class ExpandableAttribute

Attribute that enables editing properties of a referenced object.

class GameObjectUtility

Contains utility methods for dealing with GameObjects and Transforms.

• interface IPersistedInstance

This is a hack so that PoolManager can send messages to PersistedGameObjects.

class ListQueue

A FIFO data structure similar to a Queue, except that it implements all List operations.

· class MathUtility

Contains utility methods for working with mathematical types and solving math equations.

struct PassiveTimer

A lightweight timer that does not need to be updated each frame.

class Pause

Manages pausing and unpausing of the game.

class Pool

Provides a simple pool with an interface similar to the official Unity pool added in 2021.

class PooledParticleEffect

A component that can be attached to ParticleSystem GameObjects to make them work correctly with pooling.

class PooledTrail

A component that can be attached to TrailRenderer GameObjects to make them work correctly with pooling.

· class PoolManager

The singleton manager class that handles object pooling.

class ProgressBar

Used to create health bars and other types of progress bars without using a Slider.

class RandomUtility

Contains extensions to builtin randomization functionality.

class SceneControl

Provides some methods to navigate to scenes.

class Singleton

Base class that makes it easier to write scripts that always have exactly one instance.

class SingletonAsset

Base class that makes it easier to write ScriptableObjects that always have exactly one instance in your project.

· class SingletonAssetBase

Base class of SingletonAsset<T>. For internal use only.

· class Spawnable

Attach this component to a prefab to enable it to use the pooling system.

· class StringUtility

Contains string processing utilities.

class Tag

Provides string constants for builtin Unity tags.

struct TagMask

Used to select tags in the inspector, including the ability to select multiple tags.

class TagMaskUtility

Static operations on Tag enum values.

class TimeToLive

Despawns a GameObject after a set amount of time.

class TriggerVolume

A script that makes it easy to add events to a trigger collider.

class TypeSelectAttribute

Attribute that draws string fields as a dropdown where a Type can be selected.

class TypeUtility

Contains utilities for working with C# reflection types and getting a type by its name.

class UniqueNamedObject

This script is used to assign a unique name to an object, which can then be used to find that object.

· class UniqueNameList

A list used to organize unique names used by objects.

class UniqueNameListEntry

A unique name asset, usable by a UniqueNamedObject.

5.3 Infohazard.Core.Editor Namespace Reference

Classes

· class CoreEditorUtility

Contains several editor-only utilities.

class TagsGenerator

Class used to generate the GameTag.cs file to use your custom tags in code.

6 Class Documentation 13

6 Class Documentation

6.1 Infohazard.Core.AssetDropdownAttribute Class Reference

Attribute that draws an object reference as a dropdown that searches through the project.

6.1.1 Detailed Description

Attribute that draws an object reference as a dropdown that searches through the project.

The documentation for this class was generated from the following file:

• Runtime/Attributes/AssetDropdownAttribute.cs

6.2 Infohazard.Core.ComponentID Struct Reference

A serializable type used to uniquely identify a component relative to a root GameObject.

Public Member Functions

- ComponentID (Transform root, Component target)
 - Construct a ComponentID with the given root and target by calculating the path to the target.
- override string ToString ()
- T Get< T > (Transform root)

Get the referenced component.

- bool Equals (ComponentID other)
- override bool Equals (object obj)
- · override int GetHashCode ()

Properties

• string Path [get]

Path from this GameObject to the GameObject that holds the referenced component.

• string Type [get]

Type name of the referenced component.

Private Attributes

• string _path

(Serialized) Path from this GameObject to the GameObject that holds the referenced component.

• string _type

(Serialized) Type name of the referenced component.

6.2.1 Detailed Description

A serializable type used to uniquely identify a component relative to a root GameObject.

The root GameObject that holds the ComponentID may not be an actual transform.root, but rather just an ancestor of the referenced component. This type is mostly used in order to persist the states of individual components, keyed by their ID.

6.2.2 Constructor & Destructor Documentation

```
6.2.2.1 ComponentID() Infohazard.Core.ComponentID.ComponentID (

Transform root,

Component target )
```

Construct a ComponentID with the given root and target by calculating the path to the target.

Parameters

roc	ot	The GameObject from which the reference originates.
tar	get	The component that is being referenced.

6.2.3 Member Function Documentation

```
6.2.3.1 Equals() [1/2] bool Infohazard.Core.ComponentID.Equals (

ComponentID other)
```

```
6.2.3.2 Equals() [2/2] override bool Infohazard.Core.ComponentID.Equals ( object obj )
```

```
6.2.3.3 Get< T>() T Infohazard.Core.ComponentID.Get< T> ( Transform root )
```

Get the referenced component.

Parameters

root	The GameObject from which the reference originates.

Template Parameters

T Type to cast the component to.

Returns

The referenced component, or null if not found.

Type Constraints

T: Component

6.2.3.4 GetHashCode() override int Infohazard.Core.ComponentID.GetHashCode ()

6.2.3.5 ToString() override string Infohazard.Core.ComponentID.ToString ()

6.2.4 Member Data Documentation

6.2.4.1 _path string Infohazard.Core.ComponentID._path [private]

(Serialized) Path from this GameObject to the GameObject that holds the referenced component.

6.2.4.2 _type string Infohazard.Core.ComponentID._type [private]

(Serialized) Type name of the referenced component.

6.2.5 Property Documentation

6.2.5.1 Path string Infohazard.Core.ComponentID.Path [get]

Path from this GameObject to the GameObject that holds the referenced component.

```
6.2.5.2 Type string Infohazard.Core.ComponentID.Type [get]
```

Type name of the referenced component.

The documentation for this struct was generated from the following file:

• Runtime/Misc/ComponentID.cs

6.3 Infohazard.Core.ConditionalDrawAttribute Class Reference

Attribute draws a property when a given condition is true.

Public Member Functions

ConditionalDrawAttribute (string boolCondition)

ConditionalAttribute that requires a serialized boolean field to be true.

• ConditionalDrawAttribute (string condition, object value, bool isEqual=true)

Conditional Attribute that requires a serialized field named condition to be equal or not equal to value.

Properties

```
• string Condition [get]
```

The serialized field to check.

• object Value [get]

The value to compare the Condition field to.

• bool IsEqual [get]

Whether the value of the condition field should be equal to the given value in order to draw.

6.3.1 Detailed Description

Attribute draws a property when a given condition is true.

6.3.2 Constructor & Destructor Documentation

```
6.3.2.1 ConditionalDrawAttribute() [1/2] Infohazard.Core.ConditionalDrawAttribute.Conditional ← DrawAttribute (

string boolCondition)
```

Conditional Attribute that requires a serialized boolean field to be true.

Parameters

boolCondition	The name of a boolean field.

6.3.2.2 ConditionalDrawAttribute() [2/2] Infohazard.Core.ConditionalDrawAttribute.Conditional← DrawAttribute (string condition, object value, bool isEqual = true)

Conditional Attribute that requires a serialized field named condition to be equal or not equal to value.

Parameters

condition	The name of a field.
value	The value to compare to.
isEqual	Whether to check for equality or inequality.

6.3.3 Property Documentation

 $\textbf{6.3.3.1} \quad \textbf{Condition} \quad \texttt{string Infohazard.Core.ConditionalDrawAttribute.Condition} \quad \texttt{[get]}$

The serialized field to check.

6.3.3.2 IsEqual bool Infohazard.Core.ConditionalDrawAttribute.IsEqual [get]

Whether the value of the condition field should be equal to the given value in order to draw.

6.3.3.3 Value object Infohazard.Core.ConditionalDrawAttribute.Value [get]

The value to compare the Condition field to.

The documentation for this class was generated from the following file:

· Runtime/Attributes/ConditionalDrawAttribute.cs

6.4 Infohazard.Core.Editor.CoreEditorUtility Class Reference

Contains several editor-only utilities.

Static Public Member Functions

static object GetValue (this SerializedProperty property)

Get the value of a SerializedProperty of any type. Does not work for serializable objects or gradients. Enum values are returned as ints.

static object FindValue (this SerializedProperty prop)

Find the value of a given property using reflection and reading the field directly.

static T FindValue< T > (this SerializedProperty prop)

Find the value of a given property using Reflection and reading the field directly.

static List< string > GetDefinesList (BuildTargetGroup group)

Get the Unity PlayerSettings list of #define symbols for the given build target.

• static void SetSymbolDefined (string symbol, bool value, BuildTargetGroup group)

Sets whether the given symbol is defined in the PlayerSettings for the given build target.

static string GetResourcePath (Object obj)

Get the path an object lives in relative to a resource folder.

static string GetResourcePath (string path)

Get the given path relative to a resource folder.

• static string GetPathRelativeToAssetsFolder (string path)

Convert the given path to be relative to the Assets folder.

static void DoLazyDropdown< T > (Rect position, GUIContent content, Func< T[]> optionsFunc, Func< T, string > stringifier, Action< T > setter)

Create a dropdown button in the IMGUI, whose options will not be calculated until it is clicked.

static IEnumerable < T > GetAssetsOfType < T > ()

Find all the assets of the given type in the project.

static IEnumerable < Object > GetAssetsOfType (string type)

Find all the assets of the given type in the project.

static string GetTypeName (this SerializedProperty property)

Get the type full name (including assembly) of the type of the underlying field for the given property.

static void EnsureDataFolderExists ()

Ensure that the DataFolder directory exists in your project, and contains an assembly definition.

• static bool ExecuteProcess (string command, string args, bool showMessages)

Launch an external process using the given command and arguments, and wait for it to complete.

Static Public Attributes

const string DataFolder = "Assets/Infohazard.Core.Data/"

Folder where all generated files used by the Infohazard libraries should live.

6.4.1 Detailed Description

Contains several editor-only utilities.

6.4.2 Member Function Documentation

Create a dropdown button in the IMGUI, whose options will not be calculated until it is clicked.

For a normal dropdown, you'd need to know all of the options before the button was clicked. With lazy dropdown, they are not evaluated until needed. They are also re-evaluated every time the dropdown is opened, preventing the need for cache invalidation.

Parameters

position	Position to draw the dropdown button.
content	Current value to show in the dropdown button (when not selected).
optionsFunc	Function that will calculate and return the options.
stringifier	Function that converts options to strings for display.
setter	Function that sets the value when an option is chosen.

Template Parameters

```
T Type of the options before they are converted to strings.
```

```
6.4.2.2 EnsureDataFolderExists() static void Infohazard.Core.Editor.CoreEditorUtility.Ensure← DataFolderExists ( ) [static]
```

Ensure that the DataFolder directory exists in your project, and contains an assembly definition.

```
6.4.2.3 ExecuteProcess() static bool Infohazard.Core.Editor.CoreEditorUtility.ExecuteProcess ( string command, string args, bool showMessages ) [static]
```

Launch an external process using the given command and arguments, and wait for it to complete.

Parameters

command	The command (executable file) to run.
args	The argument string to pass to the command.
showMessages	Whether to display a dialog box if the command fails.

Returns

Whether the command succeeded.

```
6.4.2.4 FindValue() static object Infohazard.Core.Editor.CoreEditorUtility.FindValue ( this SerializedProperty prop ) [static]
```

Find the value of a given property using reflection and reading the field directly.

Parameters

```
prop The property to read.
```

Returns

The value of the property.

```
6.4.2.5 FindValue < T >() static T Infohazard.Core.Editor.CoreEditorUtility.FindValue < T > ( this SerializedProperty prop ) [static]
```

Find the value of a given property using Reflection and reading the field directly.

Template Parameters

```
T The type to cast the value to.
```

Parameters

```
prop The property to read
```

Returns

The value of the property.

```
6.4.2.6 GetAssetsOfType() static <code>IEnumerable< Object > Infohazard.Core.Editor.CoreEditor \leftarrow Utility.GetAssetsOfType ( string type ) [static]</code>
```

Find all the assets of the given type in the project.

Only assets whose root object is the given type are included.

Parameters

type	The type name of assets to find.
type	I he type name of assets to find

Returns

A sequence of all the found assets.

6.4.2.7 GetAssetsOfType< **T**>() static IEnumerable< T> Infohazard.Core.Editor.CoreEditorUtility.GetAssetsOfTy T> () [static]

Find all the assets of the given type in the project.

Only assets whose root object is the given type are included.

Template Parameters

T

Returns

A sequence of all the found assets.

Type Constraints

T: Object

```
6.4.2.8 GetDefinesList() static List< string > Infohazard.Core.Editor.CoreEditorUtility.Get \leftarrow DefinesList (

BuildTargetGroup group ) [static]
```

Get the Unity PlayerSettings list of #define symbols for the given build target.

Parameters

group	The build target.

Returns

A list of all defined symbols for that group.

6.4.2.9 GetPathRelativeToAssetsFolder() static string Infohazard.Core.Editor.CoreEditorUtility. \leftarrow GetPathRelativeToAssetsFolder (string path) [static]

Convert the given path to be relative to the Assets folder.

Accepts absolute paths, paths staring with "Assets/", and paths starting with "/""". </remarks> <param name="path">

Returns

```
6.4.2.10 GetResourcePath() [1/2] static string Infohazard.Core.Editor.CoreEditorUtility.Get\leftrightarrow ResourcePath ( Object obj ) [static]
```

Get the path an object lives in relative to a resource folder.

The result path can be used with Resources.Load.

Parameters

obj The object to get the path for.

Returns

The path relative to a resource folder, or null.

```
6.4.2.11 GetResourcePath() [2/2] static string Infohazard.Core.Editor.CoreEditorUtility.Get\leftrightarrow ResourcePath ( string path ) [static]
```

Get the given path relative to a resource folder.

The result path can be used with Resources.Load.

Parameters

```
path The path to search for.
```

Returns

The path relative to a resource folder, or null.

```
6.4.2.12 GetTypeName() static string Infohazard.Core.Editor.CoreEditorUtility.GetTypeName ( this SerializedProperty property ) [static]
```

Get the type full name (including assembly) of the type of the underlying field for the given property.

Parameters

```
property
```

Returns

```
6.4.2.13 GetValue() static object Infohazard.Core.Editor.CoreEditorUtility.GetValue ( this SerializedProperty property ) [static]
```

Get the value of a SerializedProperty of any type. Does not work for serializable objects or gradients. Enum values are returned as ints.

Parameters

property	The property to read.
----------	-----------------------

Returns

The value of the property, or null if not readable.

Sets whether the given symbol is defined in the PlayerSettings for the given build target.

Parameters

symbol	The symbol to set.
value	Whether the symbol should be defined.
group	The build target.

6.4.3 Member Data Documentation

6.4.3.1 DataFolder const string Infohazard.Core.Editor.CoreEditorUtility.DataFolder = "Assets/Infohazard.← Core.Data/" [static]

Folder where all generated files used by the Infohazard libraries should live.

Call EnsureDataFolderExists to make sure this folder exists before using it.

The documentation for this class was generated from the following file:

· Editor/Utility/CoreEditorUtility.cs

6.5 Infohazard.Core.DebugUtility Class Reference

Contains various static methods relating to debugging and diagnostics.

Static Public Member Functions

- static void DrawDebugBounds (Bounds bounds, Color color, float duration=0.0f, bool depthTest=true)

 Draw the given Bounds in the scene view.
- static void DebugBreakAfterFrames (this MonoBehaviour cmp, int frames)
 - Pause the editor after a given number of frames, using a Coroutine and Debug.Break().
- static bool CheckPlaying (bool propertySet=false, [CallerMemberName] string callerName="")

 Checks whether in play mode (including standalone), and prints an error if it is.

6.5.1 Detailed Description

Contains various static methods relating to debugging and diagnostics.

6.5.2 Member Function Documentation

```
6.5.2.1 CheckPlaying() static bool Infohazard.Core.DebugUtility.CheckPlaying ( bool propertySet = false,  
[CallerMemberName] string callerName = "") [static]
```

Checks whether in play mode (including standalone), and prints an error if it is.

Used to ensure certain properties are not edited while playing.

Parameters

propertySet	Whether the caller is a property set accessor (changes error log).
callerName	Set automatically, do not supply a value for this parameter.

Returns

True if in play mode.

```
6.5.2.2 DebugBreakAfterFrames() static void Infohazard.Core.DebugUtility.DebugBreakAfterFrames (

this MonoBehaviour cmp,

int frames ) [static]
```

Pause the editor after a given number of frames, using a Coroutine and Debug.Break().

Only works in play mode. Will not cause errors if used in a standalone build, but will do unnecessary work.

Parameters

стр	Component to attach the Coroutine to.
frames	Number of frames to wait before pausing.

Draw the given Bounds in the scene view.

Parameters

bounds	Bounds to draw.
color	Color to use.
duration	Time, in seconds, to draw the lines for.
depthTest	Whether to depth dest the drawn lines.

The documentation for this class was generated from the following file:

• Runtime/Utility/DebugUtility.cs

6.6 Infohazard.Core.DrawSingleChildPropertyAttribute Class Reference

Attribute draws only a single child property of a property.

Public Member Functions

DrawSingleChildPropertyAttribute (string propertyName)
 DrawSingleChildPropertyAttribute that will draw only the specified property.

Properties

• string PropertyName [get]

The child property to draw.

6.6.1 Detailed Description

Attribute draws only a single child property of a property.

6.6.2 Constructor & Destructor Documentation

DrawSingleChildPropertyAttribute that will draw only the specified property.

Parameters

propertyName	The child property to draw.	
--------------	-----------------------------	--

6.6.3 Property Documentation

6.6.3.1 PropertyName string Infohazard.Core.DrawSingleChildPropertyAttribute.PropertyName [get]

The child property to draw.

The documentation for this class was generated from the following file:

Runtime/Attributes/DrawSingleChildPropertyAttribute.cs

6.7 Infohazard.Core.EditNameOnlyAttribute Class Reference

Attribute that draws only the name of an Object reference field.

6.7.1 Detailed Description

Attribute that draws only the name of an Object reference field.

The documentation for this class was generated from the following file:

Runtime/Attributes/EditNameOnlyAttribute.cs

6.8 Infohazard.Core.EnumerableUtility Class Reference

Contains various static methods for working with sequences, extending the functionality of LINQ.

Public Member Functions

delegate bool SelectWhereDelegate < in T1, T2 > (T1 input, out T2 output)
 Delegate for functions that perform both a select/map and where/filter operation.

Static Public Member Functions

static IEnumerable < T2 > SelectWhere < T1, T2 > (this IEnumerable < T1 > input, SelectWhereDelegate < T1, T2 > selectionDelegate)

Perform select/map and where/filter operations on a sequence with a single function.

static T2 FirstOrDefaultWhere< T1, T2 > (this IEnumerable< T1 > input, SelectWhereDelegate< T1, T2 > selectionDelegate)

Perform select/map and where/filter operations on a sequence with a single function, and returns the result of the select operation for the first passing element.

6.8.1 Detailed Description

Contains various static methods for working with sequences, extending the functionality of LINQ.

6.8.2 Member Function Documentation

```
6.8.2.1 FirstOrDefaultWhere<br/>
T1, T2 >() static T2 Infohazard.Core.EnumerableUtility.FirstOr<br/>
DefaultWhere<br/>
T1, T2 > (<br/>
this IEnumerable<br/>
T1 > input,<br/>
SelectWhereDelegate<br/>
T1, T2 > selectionDelegate) [static]
```

Perform select/map and where/filter operations on a sequence with a single function, and returns the result of the select operation for the first passing element.

Parameters

input	The input sequence.
selectionDelegate	The delegate to use.

Template Parameters

T1	Input type of the delegate.
T2	Output type of the select operation.

Returns

The result of the select operation for the first passing element.

```
6.8.2.2 SelectWhere < T1, T2 > () static IEnumerable < T2 > Infohazard.Core.EnumerableUtility. <math>\leftarrow SelectWhere < T1, T2 > ( this IEnumerable < T1 > input, SelectWhereDelegate < T1, T2 > selectionDelegate ) [static]
```

Perform select/map and where/filter operations on a sequence with a single function.

Parameters

input	The input sequence.
selectionDelegate	The delegate to use.

Template Parameters

T1	Input type of the delegate.
T2	Output type of the select operation.

Returns

The resulting sequence.

Delegate for functions that perform both a select/map and where/filter operation.

Template Parameters

T1	Input type of the function.
T2	Output type of the select operation.

The documentation for this class was generated from the following file:

• Runtime/Utility/EnumerableUtility.cs

6.9 Infohazard.Core.ExpandableAttribute Class Reference

Attribute that enables editing properties of a referenced object.

Public Member Functions

• ExpandableAttribute (bool alwaysExpanded=false, string savePath=null, bool showNewButton=true) Construct a new ExpandableAttribute.

Properties

```
• bool AlwaysExpanded [get]
```

Whether the attribute is always expanded.

bool ShowNewButton [get]

Whether to show a "New" button to create new instances.

• string SavePath [get]

The default path to save newly created ScriptableObjects at.

6.9.1 Detailed Description

Attribute that enables editing properties of a referenced object.

Normally, to edit a referenced object, you'd have to change the inspector context. With an ExpandableAttribute, you can just expand the property and edit the referenced object inline. If the type of the reference field is a Scriptable Object, the ExpandableAttribute also allows creating new instances in the inspector.

6.9.2 Constructor & Destructor Documentation

```
6.9.2.1 ExpandableAttribute() Infohazard.Core.ExpandableAttribute.ExpandableAttribute (
bool alwaysExpanded = false,
string savePath = null,
bool showNewButton = true )
```

Construct a new ExpandableAttribute.

Parameters

alwaysExpanded	Whether the attribute is always expanded.
savePath	Whether to show a "New" button to create new instances.
showNewButton	The default path to save newly created ScriptableObjects at.

6.9.3 Property Documentation

6.9.3.1 AlwaysExpanded bool Infohazard.Core.ExpandableAttribute.AlwaysExpanded [get]

Whether the attribute is always expanded.

If false, will show the expander.

6.9.3.2 SavePath string Infohazard.Core.ExpandableAttribute.SavePath [get]

The default path to save newly created ScriptableObjects at.

If unset, this will use the same path as the containing object if it is an asset.

6.9.3.3 ShowNewButton bool Infohazard.Core.ExpandableAttribute.ShowNewButton [get]

Whether to show a "New" button to create new instances.

This only works if the type of the field is a ScriptableObject.

The documentation for this class was generated from the following file:

· Runtime/Attributes/ExpandableAttribute.cs

6.10 Infohazard.Core.GameObjectUtility Class Reference

Contains utility methods for dealing with GameObjects and Transforms.

Static Public Member Functions

 static void GetCapsuleInfo (float radius, float height, Vector3 center, int direction, Transform transform, out Vector3 point1, out Vector3 point2, out float worldRadius, out float worldHeight)

Converts capsule info in transform/height/radius form to two-point form for use with Physics.CapsuleCast.

• static void GetCapsuleInfo (this CharacterController capsule, out Vector3 point1, out Vector3 point2, out float worldRadius, out float worldHeight)

Converts capsule info in a CharacterController to two-point form for use with Physics.CapsuleCast.

• static void GetCapsuleInfo (this CapsuleCollider capsule, out Vector3 point1, out Vector3 point2, out float worldRadius, out float worldHeight)

Converts capsule info in a CapsuleCollider to two-point form for use with Physics.CapsuleCast.

• static void SetParentAndReset (this Transform transform, Transform parent)

Set the parent of the given transform, and reset it's local position, rotation, and scale.

• static void Initialize (this Transform transform, Transform parent, Vector3? position=null, Quaternion? rotation=null, Vector3? scale=null, bool inWorldSpace=false, Scene? scene=null)

Initialize the transform with the given parent, position, rotation, and scale.

static void DestroyChildren (this Transform transform)

Destroy all of the child GameObjects of a Transform at the end of this frame.

static void DestroyChildrenImmediate (this Transform transform)

Destroy all of the child GameObjects of a Transform immediately.

static void DespawnChildren (this Transform transform)

Despawn all of the child GameObjects of a Transform.

static bool TryGetComponentInParent< T > (this GameObject obj, out T result)

Like GetComponentInParent, but more convenient if using in conditionals and also using the component value.

• static bool TryGetComponentInChildren< T > (this GameObject obj, out T result, bool includeInactive=false)

Like GetComponentInChildren, but more convenient if using in conditionals and also using the component value.

• static bool TryGetComponentInParent< T > (this Component cmp, out T result)

Like GetComponentInParent, but more convenient if using in if statements and also using the component value.

 $\bullet \ \ \text{static bool } \\ \hline \text{TryGetComponentInChildren} < \\ \hline \text{T} > \text{(this Component cmp, out T result)} \\$

Like GetComponentInChildren, but more convenient if using in if statements and also using the component value.

• static string GetRelativeTransformPath (this Transform from, Transform to)

Get the path from one transform to another (object names separated by slashes).

• static Transform GetTransformAtRelativePath (this Transform from, string path)

Parses a slash-separated Transform path from a parent object to find a child.

static void SetLayerRecursively (this GameObject obj, int layer)

Sets the layer of a GameObject and all of its children.

Static Private Member Functions

• static void Initialize (this Transform transform, Vector3? position, Quaternion? rotation, Vector3? scale)

Set's the transform's position, and rotation, and scale (if they are specified).

6.10.1 Detailed Description

Contains utility methods for dealing with GameObjects and Transforms.

6.10.2 Member Function Documentation

```
6.10.2.1 DespawnChildren() static void Infohazard.Core.GameObjectUtility.DespawnChildren ( this Transform transform ) [static]
```

Despawn all of the child GameObjects of a Transform.

Parameters

transform	Transform to despawn children of.
-----------	-----------------------------------

```
6.10.2.2 DestroyChildren() static void Infohazard.Core.GameObjectUtility.DestroyChildren ( this Transform transform ) [static]
```

Destroy all of the child GameObjects of a Transform at the end of this frame.

Parameters

transform	Transform to destroy children of.
-----------	-----------------------------------

6.10.2.3 DestroyChildrenImmediate() static void Infohazard.Core.GameObjectUtility.Destroy← ChildrenImmediate (this Transform transform) [static]

Destroy all of the child GameObjects of a Transform immediately.

Parameters

transform	Transform to destroy children of.

Converts capsule info in transform/height/radius form to two-point form for use with Physics.CapsuleCast.

Also tells you the radius and height of the capsule in world space.

out float worldHeight) [static]

Parameters

radius	Radius of the capsule in local space.	
height	Height of the capsule in local space.	
center	Center of the capsule in local space.	
direction	On which axis the capsule extends $(0 = x, 1 = y, 2 = z)$.	
transform	Transform that the capsule is parented to.	
point1	The first point of the capsule in world space.	
point2	The second point of the capsule in world space.	
worldRadius	The radius of the capsule in world space.	
worldHeight	The height of the capsule in world space.	

Converts capsule info in a CapsuleCollider to two-point form for use with Physics.CapsuleCast.

Also tells you the radius and height of the capsule in world space.

Parameters

capsule	The CapsuleCollider to read.	
point1	The first point of the capsule in world space.	
point2	The second point of the capsule in world space.	
worldRadius	The radius of the capsule in world space.	
worldHeight	The height of the capsule in world space.	

6.10.2.6 GetCapsuleInfo() [3/3] static void Infohazard.Core.GameObjectUtility.GetCapsuleInfo (this CharacterController *capsule*,

```
out Vector3 point1,
out Vector3 point2,
out float worldRadius,
out float worldHeight) [static]
```

Converts capsule info in a CharacterController to two-point form for use with Physics.CapsuleCast.

Also tells you the radius and height of the capsule in world space.

Parameters

capsule	The CharacterController to read.	
point1	The first point of the capsule in world space.	
point2	The second point of the capsule in world space.	
worldRadius	The radius of the capsule in world space.	
worldHeight	Height The height of the capsule in world space.	

```
6.10.2.7 GetRelativeTransformPath() static string Infohazard.Core.GameObjectUtility.GetRelative←

TransformPath (
this Transform from,
Transform to ) [static]
```

Get the path from one transform to another (object names separated by slashes).

The parameter to must be a direct descendent of from, or an error is logged. The returned path contains the name of to but not from. This path can be turned back to an object reference using GetTransformAtRelativePath.

Parameters

from	The parent Transform to get the path from.	
to	The Transform to get the path to.	

Returns

The path relative transform path separated by slashes.

Parses a slash-separated Transform path from a parent object to find a child.

This can be used to turn a path created by GetRelativeTransformPath back to an object reference.

Parameters

from	The parent Transform to search from.	
path The slash-separated path to search for		

Returns

The found child Transform, or null if not found.

Initialize the transform with the given parent, position, rotation, and scale.

Parameters

transform	The transform to initialize.	
parent	The parent to attach to.	
position	The position (if null, do not set).	
rotation	The rotation (if null, do not set).	
scale	The scale (if null, do not set).	
inWorldSpace	Whether the given position, rotation, and scale should be considered global.	
scene	An optional scene to move the object to.	

Set's the transform's position, and rotation, and scale (if they are specified).

transform	The transform to initialize.	
position	The position (if null, do not set).	
rotation	The rotation (if null, do not set).	
scale	The scale (if null, do not set).	

Sets the layer of a GameObject and all of its children.

Parameters

obj	The GameObject to set the layer on.	
layer	The layer index to set.	

```
6.10.2.12 SetParentAndReset() static void Infohazard.Core.GameObjectUtility.SetParentAndReset (
this Transform transform,
Transform parent) [static]
```

Set the parent of the given transform, and reset it's local position, rotation, and scale.

Parameters

transform	The transform to reset.	
parent	The transform to parent it to (can be null).	

Like GetComponentInChildren, but more convenient if using in if statements and also using the component value.

Like GetComponentInChildren, but more convenient if using in conditionals and also using the component value.

Like GetComponentInParent, but more convenient if using in if statements and also using the component value.

Like GetComponentInParent, but more convenient if using in conditionals and also using the component value.

Parameters

obj	The object to search from.	
result The found component or r		

Template Parameters

T	The type of component to search for.
---	--------------------------------------

Returns

Whether a component of the given type was found.

The documentation for this class was generated from the following file:

• Runtime/Utility/GameObjectUtility.cs

6.11 Infohazard.Core.IPersistedInstance Interface Reference

This is a hack so that PoolManager can send messages to PersistedGameObjects.

Public Member Functions

void SetupDynamicInstance (ulong persistedInstanceID)

Initialize the current object as a new persisted instance with the given ID.

void RegisterDestroyed ()

Remove the current object from persistence.

6.11.1 Detailed Description

This is a hack so that PoolManager can send messages to PersistedGameObjects.

There is likely no need to use this interface yourself.

6.11.2 Member Function Documentation

6.11.2.1 RegisterDestroyed() void Infohazard.Core.IPersistedInstance.RegisterDestroyed ()

Remove the current object from persistence.

6.11.2.2 SetupDynamicInstance() void Infohazard.Core.IPersistedInstance.SetupDynamicInstance (ulong persistedInstanceID)

Initialize the current object as a new persisted instance with the given ID.

Parameters

persistedInstanceID	The instance ID to use.
---------------------	-------------------------

The documentation for this interface was generated from the following file:

· Runtime/Pooling/IPersistedInstance.cs

6.12 Infohazard.Core.ListQueue < T > Class Template Reference

A FIFO data structure similar to a Queue, except that it implements all List operations.

Public Member Functions

ListQueue (int initialCapacity=32)

Construct a new ListQueue with the given capacity.

ListQueue (IEnumerable < T > enumerable)

Construct a new ListQueue containing all the elements of the given sequence.

void Enqueue (T item)

Add an item to the front of the queue.

void EnsureCapacity (int capacity)

Ensures that the capacity of the queue is at least the given value, and grows if not.

• T Peek ()

Returns the element at the front of the queue without removing it.

bool TryPeek (out T item)

Get the element at the front of the queue if it is not empty, and return whether this was successful.

• T Dequeue ()

Removes and returns the element at the front of the queue.

bool TryDequeue (out T item)

Get the element at the front of the queue if it is not empty, remove it, and return whether this was successful.

- IEnumerator < T > GetEnumerator ()
- void Add (T item)

- void Clear ()
- bool Contains (T item)
- void CopyTo (T[] array, int arrayIndex)
- bool Remove (Titem)
- int IndexOf (T item)
- void Insert (int index, T item)
- void RemoveAt (int index)
- void RemoveRange (int index, int count)

Removes a range of items from the queue.

Properties

```
    int Count [get, private set]
    int Capacity [get]
        Current capacity, which will be automatically expanded when needed.

    bool IsReadOnly [get]
    T this[int index] [get, set]
```

6.12.1 Detailed Description

A FIFO data structure similar to a Queue, except that it implements all List operations.

This enables much greater flexibility than the builtin .NET Queue class. Unlike a List, it has O(1) performance for both Enqueue and Dequeue operations (assuming there is enough room).

Template Parameters

```
T | Type of elements in the structure.
```

6.12.2 Constructor & Destructor Documentation

Construct a new ListQueue with the given capacity.

```
initialCapacity Initial capacity, which will be expanded as needed.
```

```
6.12.2.2 ListQueue() [2/2] Infohazard.Core.ListQueue< T >.ListQueue ( IEnumerable< T > enumerable )
```

Construct a new ListQueue containing all the elements of the given sequence.		

Parameters

enumerable	Sequence to initialize the queue.
------------	-----------------------------------

6.12.3 Member Function Documentation

```
\textbf{6.12.3.2} \quad \textbf{Clear()} \quad \text{void Infohazard.Core.ListQueue} < \text{T} > . \text{Clear ()}
```

```
6.12.3.4 CopyTo() void Infohazard.Core.ListQueue< T >.CopyTo ( T[] array, int arrayIndex )
```

```
6.12.3.5 Dequeue() T Infohazard.Core.ListQueue< T >.Dequeue ( )
```

Removes and returns the element at the front of the queue.

Returns

The item at the front of the queue.

Exceptions

```
InvalidOperationException If the queue is empty.
```

```
6.12.3.6 Enqueue() void Infohazard.Core.ListQueue< T >.Enqueue ( T item )
```

Add an item to the front of the queue.

The capacity of the queue will be grown if needed.

Parameters

```
item The item to add.
```

```
6.12.3.7 EnsureCapacity() void Infohazard.Core.ListQueue< T >.EnsureCapacity ( int capacity )
```

Ensures that the capacity of the queue is at least the given value, and grows if not.

Parameters

```
capacity The capacity to ensure.
```

```
\textbf{6.12.3.8} \quad \textbf{GetEnumerator()} \quad \texttt{IEnumerator} < \texttt{T} > \texttt{Infohazard.Core.ListQueue} < \texttt{T} > .\texttt{GetEnumerator} \ ( \ )
```

```
6.12.3.9 IndexOf() int Infohazard.Core.ListQueue< T >.IndexOf ( T item )
```

```
6.12.3.11 Peek() T Infohazard.Core.ListQueue< T >.Peek ( )
```

Returns the element at the front of the queue without removing it.

Returns

The item at the front of the queue.

Exceptions

InvalidOperationException If the queue
--

```
6.12.3.12 Remove() bool Infohazard.Core.ListQueue< T >.Remove ( T item )
```

Removes a range of items from the queue.

Parameters

index	The first index to remove.	
count	The number of items to remove.	l

Get the element at the front of the queue if it is not empty, remove it, and return whether this was successful.

Parameters

item	The item at the front of the queue.
	•

Returns

Whether an item was available to dequeue.

Get the element at the front of the queue if it is not empty, and return whether this was successful.

item	The item at the front of the queue.

Whether an item was available to peek.

6.12.4 Property Documentation

```
6.12.4.1 Capacity int Infohazard.Core.ListQueue< T >.Capacity [get]
```

Current capacity, which will be automatically expanded when needed.

Expanding capacity is an O(n) operation, so it should be avoided when possible.

```
6.12.4.2 Count int Infohazard.Core.ListQueue< T >.Count [get], [private set]
```

```
6.12.4.3 IsReadOnly bool Infohazard.Core.ListQueue< T >.IsReadOnly [get]
```

```
\textbf{6.12.4.4} \quad \textbf{this[int index]} \quad \texttt{T Infohazard.Core.ListQueue} < \texttt{T} > .\texttt{this[int index]} \quad \texttt{[get], [set]}
```

The documentation for this class was generated from the following file:

• Runtime/DataStructures/ListQueue.cs

6.13 Infohazard.Core.MathUtility Class Reference

Contains utility methods for working with mathematical types and solving math equations.

Static Public Member Functions

static float RoundToNearest (float value, float factor)

Round a value to the nearest multiple of a given factor.

static float SignZero (float value)

Same as Mathf. Sign, except that if the input is zero, it returns zero.

• static float NormalizeAngle (float angle)

Normalize an angle to a value between 0 and 360.

• static Vector3 NormalizeAngles (Vector3 angles)

Normalize a set of euler angles to values between 0 and 360.

static float NormalizeInnerAngle (float angle)

Normalize an angle to a value between -180 and 180.

static Vector3 NormalizeInnerAngles (Vector3 angles)

Normalize a set of euler angles to values between -180 and 180.

static float ClampInnerAngle (float angle, float min, float max)

Normalize an angle to a value between -180 and 180, then clamp it in the given range.

static Vector3 ClampInnerAngles (Vector3 angles, Vector3 min, Vector3 max)

Normalize a set of euler angles to values between -180 and 180, then clamp them in the given ranges.

• static Vector3 Multiply (Vector3 left, Vector3 right)

Multiply the components of left by the components of right.

• static Vector3 Divide (Vector3 left, Vector3 right)

Divide the components of left by the components of right.

static Vector3 Reciprocal (Vector3 vector)

Take the reciprocal of each component of a vector.

static Vector3 Divide (float left, Vector3 right)

Divide a float by each component of a vector.

static Vector3 RoundToNearest (Vector3 vector, float factor)

Round a each component of a vector to the nearest multiple of a given factor.

static bool GetNearestPointOnLines (Ray line1, Ray line2, out float t1, out float t2)

Find the point along each line where the lines come closest to each other.

static float GetNearestPointOnLine (Ray line, Vector3 p)

Get the point on a line where it is nearest to a position.

- static bool GetNearestPointOnSegment (Vector3 v1, Vector3 v2, Vector3 point, out Vector3 pointOnSegment)

 Find the point on a bounded line segment where it is nearest to a position, and return whether that point is in the segment's bounds.
- static Vector3 GetNearestPointOnTriangleIncludingBounds (Vector3 v1, Vector3 v2, Vector3 v3, Vector3 point)

 Find the point on a triangle (including its bounds) where it is nearest to a position.
- static bool GetNearestPointOnTriangle (Vector3 v1, Vector3 v2, Vector3 v3, Vector3 point, out Vector3 point ← OnTriangle)

Find the point on a triangle where it is nearest to a position, and return whether that point is in the triangle's bounds.

• static bool IsPointInsideBound (Vector3 v1, Vector3 v2, Vector3 normal, Vector3 point)

Returns true if a given point is on the inner side (defined by a given normal) of a segment.

 static bool DoesSegmentIntersectTriangle (Vector3 v1, Vector3 v2, Vector3 v3, Vector3 s1, Vector3 s2, out float t)

Raycast a line segment against a triangle, and return whether they intersect.

• static Vector3 WorldToCanvasPoint (this Camera camera, Canvas canvas, Vector3 point)

Projects a point in the world onto a canvas in camera or overlay space.

static int Dot (Vector3Int v1, Vector3Int v2)

Dot product of two int vectors.

• static Vector3 WithX (this Vector3 v, float x)

Replace the X component of a vector.

static Vector3 WithY (this Vector3 v, float y)

Replace the Y component of a vector.

static Vector3 WithZ (this Vector3 v, float z)

Replace the Z component of a vector.

static Vector2 WithX (this Vector2 v, float x)

Replace the X component of a vector.

• static Vector2 WithY (this Vector2 v, float y)

Replace the Y component of a vector.

static Vector3 WithZ (this Vector2 v, float z)

Convert a Vector2 to a Vector3 with the given Z.

• static Vector3 AsXY (this Vector2 v)

Get a Vector3 with the components (x, y, 0).

static Vector3 AsYX (this Vector2 v)

Get a Vector3 with the components (y, x, 0).

• static Vector3 AsXZ (this Vector2 v)

```
Get a Vector3 with the components (x, 0, y).

static Vector3 AsZX (this Vector2 v)

Get a Vector3 with the components (y, 0, x).

static Vector3 AsYZ (this Vector2 v)

Get a Vector3 with the components (0, x, y).

static Vector3 AsZY (this Vector2 v)

Get a Vector3 with the components (0, y, x).

static Vector2 ToXY (this Vector3 v)

Get a Vector2 with the components (x, y).

static Vector2 ToYX (this Vector3 v)

Get a Vector2 with the components (y, x).

static Vector2 ToXZ (this Vector3 v)

Get a Vector2 with the components (x, z).
```

static Vector2 ToZX (this Vector3 v)

Get a Vector2 with the components (z, x).

static Vector2 ToYZ (this Vector3 v)

Get a Vector2 with the components (y, z).

static Vector2 ToZY (this Vector3 v)

Get a Vector2 with the components (z, y).

static Vector4 ToV4Pos (this Vector3 vector)

Get a Vector4 with the components (x, y, z, 1).

static Vector4 ToV4 (this Vector3 vector)

Get a Vector4 with the components (x, y, z, 0).

static Quaternion XYRotation (Vector3 right, Vector3 upHint)

Get a quaternion based on a right vector and approximate up vector.

static Quaternion YXRotation (Vector3 up, Vector3 rightHint)

Get a quaternion based on a up vector and approximate right vector.

static Quaternion XZRotation (Vector3 right, Vector3 forwardHint)

Get a quaternion based on a right vector and approximate forward vector.

static Quaternion ZXRotation (Vector3 forward, Vector3 rightHint)

Get a quaternion based on a forward vector and approximate right vector.

static Quaternion YZRotation (Vector3 up, Vector3 forwardHint)

Get a quaternion based on a up vector and approximate forward vector.

static Quaternion ZYRotation (Vector3 forward, Vector3 upHint)

Get a quaternion based on a forward vector and approximate up vector.

static void GetCorners (this Bounds bounds, Vector3[] corners)

Get the eight corners of a bounding box and save them in the given array.

static bool BoundsToScreenRect (Transform transform, Bounds bounds, Func< Vector3, Vector3 > world
 —
 ToScreen, out Rect rect)

Get a screen rect that encapsulates the given bounds.

• static void SplitHorizontal (Rect rect, float gap, out Rect out1, out Rect out2, float div=0.5f)

Split a rect into two halves horizontally, with given gap between the halves.

• static void SplitHorizontal (Rect rect, float gap, out Rect out1, out Rect out2, out Rect out3, float div1=1.0f/3.0f, float div2=2.0f/3.0f)

Split a rect into three thirds horizontally, with given gap between the thirds.

Static Public Attributes

• static Complex

Evaluate all cubic roots of this Complex.

static Complex r1

Solve a quadratic equation (find x such that the result is zero) in the form $ax^2 + bx + c = 0$.

• static readonly Vector3[] BoundsCornerArray = new Vector3[8]

A static array that can be used to store the output of GetCorners, as long as the values are copied from the array right away.

6.13.1 Detailed Description

Contains utility methods for working with mathematical types and solving math equations.

6.13.2 Member Function Documentation

```
6.13.2.1 AsXY() static Vector3 Infohazard.Core.MathUtility.AsXY ( this Vector2 v ) [static]
```

Get a Vector3 with the components (x, y, 0).

```
6.13.2.2 AsXZ() static Vector3 Infohazard.Core.MathUtility.AsXZ ( this Vector2 v ) [static]
```

Get a Vector3 with the components (x, 0, y).

```
6.13.2.3 AsYX() static Vector3 Infohazard.Core.MathUtility.AsYX ( this Vector2 v ) [static]
```

Get a Vector3 with the components (y, x, 0).

```
6.13.2.4 AsYZ() static Vector3 Infohazard.Core.MathUtility.AsYZ ( this Vector2 v ) [static]
```

Get a Vector3 with the components (0, x, y).

```
6.13.2.5 AsZX() static Vector3 Infohazard.Core.MathUtility.AsZX ( this Vector2 v ) [static]
```

Get a Vector3 with the components (y, 0, x).

```
6.13.2.6 AsZY() static Vector3 Infohazard.Core.MathUtility.AsZY ( this Vector2 v ) [static]
```

Get a Vector3 with the components (0, y, x).

Get a screen rect that encapsulates the given bounds.

Parameters

transform	Parent that the bounds are attached to (can be null).
bounds	The input bounds.
worldToScreen	A function that converts world points to screen points, such as Camera. WorldToScreenPoint.
rect	A screen rect that encapsulates the bounds.

Returns

Whether a screen rect could be calculated (false if completely off screen).

Normalize an angle to a value between -180 and 180, then clamp it in the given range.

angle	Input angle.
min	Min clamp value (applied after normalize).
max	Max Clamp value (applied after normalize).

Angle between min and max.

Normalize a set of euler angles to values between -180 and 180, then clamp them in the given ranges.

Parameters

angles	Input angles.
min	Min clamp values (applied after normalize).
max	Max Clamp values (applied after normalize).

Returns

Angles between min and max.

```
6.13.2.10 Divide() [1/2] static Vector3 Infohazard.Core.MathUtility.Divide ( float left, Vector3 right ) [static]
```

Divide a float by each component of a vector.

```
6.13.2.11 Divide() [2/2] static Vector3 Infohazard.Core.MathUtility.Divide ( Vector3 left, Vector3 right ) [static]
```

Divide the components of left by the components of right.

out float t) [static]

Raycast a line segment against a triangle, and return whether they intersect.

Parameters

v1	The first triangle point.
v2	The second triangle point.
v3	The third triangle point.
s1	The start of the segment.
s2	The end of the segment.
t	The point along the input segment where it intersects the triangle, or -1.

Returns

Whether the segment intersects the triangle.

Dot product of two int vectors.

```
6.13.2.14 GetCorners() static void Infohazard.Core.MathUtility.GetCorners ( this Bounds bounds, Vector3[] corners ) [static]
```

Get the eight corners of a bounding box and save them in the given array.

You can use BoundsCornerArray to avoid allocating here.

Parameters

bounds	The input bounds.
corners	Array to save the values in.

Get the point on a line where it is nearest to a position.

line	The input line.
p	The input position.

THe point along the line where it is nearest to the position.

Find the point along each line where the lines come closest to each other.

If the lines are parallel, then return false.

Parameters

line1	The first line.	
line2	The second line.	
t1	The point along the first line where they are closest to intersecting.	
t2	The point along the second line where they are closest to intersecting.	

Returns

False if the lines are parallel, true otherwise.

Find the point on a bounded line segment where it is nearest to a position, and return whether that point is in the segment's bounds.

Does not return points on the ends of the segment. If the nearest point on the segment's line is outside the segment, will fail and not return a valid point.

v1	The start of the segment.
v2	The end of the segment.
point	The point to search for.
pointOnSegment	The point on the segment closest to the input point.

Whether the nearest point is within the segment's bounds.

Find the point on a triangle where it is nearest to a position, and return whether that point is in the triangle's bounds.

Does not return points on the edge of the triangle. If the nearest point on the triangle's plane is outside the triangle, will fail and not return a valid point.

Parameters

v1	The first triangle point.
v2	The second triangle point.
v3	The third triangle point.
point	The point to search for.
pointOnTriangle	The point on the triangle closest to the input point.

Returns

Whether the nearest point is within the triangle's bounds.

Find the point on a triangle (including its bounds) where it is nearest to a position.

If nearest point is on the triangle's bounds, that point will be returned, unlike GetNearestPointOnTriangle.

v1	The first triangle point.
v2	The second triangle point.
v3	The third triangle point.
point	The point to search for.

The nearest point on the triangle to the given point.

```
6.13.2.20 IsPointInsideBound() static bool Infohazard.Core.MathUtility.IsPointInsideBound (

Vector3 v1,

Vector3 v2,

Vector3 normal,

Vector3 point ) [static]
```

Returns true if a given point is on the inner side (defined by a given normal) of a segment.

Parameters

v1	The start of the segment.
v2	The end of the segment.
normal	The normal, defining which side is inside.
point	The point to search for.

Returns

Whether the point is on the inner side.

Multiply the components of left by the components of right.

```
6.13.2.22 NormalizeAngle() static float Infohazard.Core.MathUtility.NormalizeAngle ( float angle ) [static]
```

Normalize an angle to a value between 0 and 360.

Parameters

angle	Input angle.

Returns

Angle between 0 and 360.

```
6.13.2.23 NormalizeAngles() static Vector3 Infohazard.Core.MathUtility.NormalizeAngles ( Vector3 angles ) [static]
```

Normalize a set of euler angles to values between 0 and 360.

Parameters

angles	Input angles.
--------	---------------

Returns

Angles between 0 and 360.

6.13.2.24 NormalizeInnerAngle() static float Infohazard.Core.MathUtility.NormalizeInnerAngle (float angle) [static]

Normalize an angle to a value between -180 and 180.

Parameters

angle	Input angle.
-------	--------------

Returns

Angle between -180 and 180.

Normalize a set of euler angles to values between -180 and 180.

Parameters

```
angles Input angles.
```

Returns

Angles between -180 and 180.

```
6.13.2.26 Reciprocal() static Vector3 Infohazard.Core.MathUtility.Reciprocal ( Vector3 vector) [static]
```

Take the reciprocal of each component of a vector.

```
6.13.2.27 RoundToNearest() [1/2] static float Infohazard.Core.MathUtility.RoundToNearest ( float value, float factor) [static]
```

Round a value to the nearest multiple of a given factor.

Parameters

value	Input value.
factor	Value to round to a multiple of.

Returns

Rounded value.

```
6.13.2.28 RoundToNearest() [2/2] static Vector3 Infohazard.Core.MathUtility.RoundToNearest ( Vector3 vector, float factor ) [static]
```

Round a each component of a vector to the nearest multiple of a given factor.

Parameters

vector	Input values.
factor	Value to round to a multiple of.

Returns

Rounded values.

```
6.13.2.29 SignZero() static float Infohazard.Core.MathUtility.SignZero ( float value ) [static]
```

Same as Mathf.Sign, except that if the input is zero, it returns zero.

Parameters

value	A number to get the sign of.
-------	------------------------------

Returns

1 if the number is positive, -1 if the number is negative, 0 if the number is 0.

```
6.13.2.30 SplitHorizontal() [1/2] static void Infohazard.Core.MathUtility.SplitHorizontal ( Rect rect, float gap, out Rect out1, out Rect out2, float div = 0.5f) [static]
```

Split a rect into two halves horizontally, with given gap between the halves.

Parameters

rect	Rect to split.
gap	Gap between the split halves.
out1	Output rect 1.
out2	Output rect 2.
div	The ratio of the total space taken up by the left rect.

```
6.13.2.31 SplitHorizontal() [2/2] static void Infohazard.Core.MathUtility.SplitHorizontal (
    Rect rect,
    float gap,
    out Rect out1,
    out Rect out2,
    out Rect out3,
    float div1 = 1.0f / 3.0f,
    float div2 = 2.0f / 3.0f ) [static]
```

Split a rect into three thirds horizontally, with given gap between the thirds.

Parameters

rect	Rect to split.
gap	Gap between the split halves.
out1	Output rect 1.
out2	Output rect 2.
out3	Output rect 3.
div1	The ratio of the total space taken up by the left rect.
div2	The ratio of the total space taken up by the left and center rect.

```
6.13.2.32 ToV4() static Vector4 Infohazard.Core.MathUtility.ToV4 ( this Vector3 vector) [static]
```

Get a Vector4 with the components (x, y, z, 0).

```
6.13.2.33 ToV4Pos() static Vector4 Infohazard.Core.MathUtility.ToV4Pos (
              this Vector3 vector ) [static]
Get a Vector4 with the components (x, y, z, 1).
6.13.2.34 ToXY() static Vector2 Infohazard.Core.MathUtility.ToXY (
              this Vector3 v ) [static]
Get a Vector2 with the components (x, y).
6.13.2.35 ToXZ() static Vector2 Infohazard.Core.MathUtility.ToXZ (
              this Vector3 v ) [static]
Get a Vector2 with the components (x, z).
\textbf{6.13.2.36} \quad \textbf{ToYX()} \quad \texttt{static Vector2 Infohazard.Core.MathUtility.ToYX} \ (
              this Vector3 v ) [static]
Get a Vector2 with the components (y, x).
\textbf{6.13.2.37} \quad \textbf{ToYZ()} \quad \texttt{static Vector2 Infohazard.Core.MathUtility.ToYZ} \ (
              this Vector3 v ) [static]
Get a Vector2 with the components (y, z).
6.13.2.38 ToZX() static Vector2 Infohazard.Core.MathUtility.ToZX (
              this Vector3 v ) [static]
Get a Vector2 with the components (z, x).
6.13.2.39 ToZY() static Vector2 Infohazard.Core.MathUtility.ToZY (
              this Vector3 v ) [static]
```

Get a Vector2 with the components (z, y).

```
6.13.2.40 WithX() [1/2] static Vector2 Infohazard.Core.MathUtility.WithX ( this Vector2 v, float x) [static]
```

Replace the X component of a vector.

```
6.13.2.41 WithX() [2/2] static Vector3 Infohazard.Core.MathUtility.WithX ( this Vector3 v, float x) [static]
```

Replace the X component of a vector.

```
6.13.2.42 WithY() [1/2] static Vector2 Infohazard.Core.MathUtility.WithY ( this Vector2 v, float y) [static]
```

Replace the Y component of a vector.

```
6.13.2.43 WithY() [2/2] static Vector3 Infohazard.Core.MathUtility.WithY ( this Vector3 v, float y) [static]
```

Replace the Y component of a vector.

```
6.13.2.44 WithZ() [1/2] static Vector3 Infohazard.Core.MathUtility.WithZ ( this Vector2 v, float z) [static]
```

Convert a Vector2 to a Vector3 with the given Z.

```
6.13.2.45 WithZ() [2/2] static Vector3 Infohazard.Core.MathUtility.WithZ ( this Vector3 v, float z) [static]
```

Replace the Z component of a vector.

Projects a point in the world onto a canvas in camera or overlay space.

Similar to Camera. World To Screen Point, but scaled to the size of the canvas and its viewport. Logs an error if the canvas is in world space, as that is not supported.

Parameters

camera	The camera to use for reference.
canvas	The canvas to use for reference.
point	The world point to find on the canvas.

Returns

The point on the canvas, usable as an anchoredPosition.

```
6.13.2.47 XYRotation() static Quaternion Infohazard.Core.MathUtility.XYRotation (

Vector3 right,

Vector3 upHint) [static]
```

Get a quaternion based on a right vector and approximate up vector.

```
6.13.2.48 XZRotation() static Quaternion Infohazard.Core.MathUtility.XZRotation ( Vector3 right, Vector3 forwardHint ) [static]
```

Get a quaternion based on a right vector and approximate forward vector.

```
6.13.2.49 YXRotation() static Quaternion Infohazard.Core.MathUtility.YXRotation (

Vector3 up,

Vector3 rightHint ) [static]
```

Get a quaternion based on a up vector and approximate right vector.

```
6.13.2.50 YZRotation() static Quaternion Infohazard.Core.MathUtility.YZRotation ( Vector3 up, Vector3 forwardHint ) [static]
```

Get a quaternion based on a up vector and approximate forward vector.

```
6.13.2.51 ZXRotation() static Quaternion Infohazard.Core.MathUtility.ZXRotation ( Vector3 forward,  Vector3 rightHint ) [static]
```

Get a quaternion based on a forward vector and approximate right vector.

```
6.13.2.52 ZYRotation() static Quaternion Infohazard.Core.MathUtility.ZYRotation (

Vector3 forward,

Vector3 upHint) [static]
```

Get a quaternion based on a forward vector and approximate up vector.

6.13.3 Member Data Documentation

```
6.13.3.1 BoundsCornerArray readonly Vector3 [] Infohazard.Core.MathUtility.BoundsCornerArray = new Vector3[8] [static]
```

A static array that can be used to store the output of GetCorners, as long as the values are copied from the array right away.

6.13.3.2 Complex static Infohazard.Core.MathUtility.Complex [static]

Evaluate all cubic roots of this Complex.

Parameters

et the cube roots of.	complex	
-----------------------	---------	--

Returns

All three complex cube roots.

6.13.3.3 r1 static Complex Infohazard.Core.MathUtility.r1 [static]

Solve a quadratic equation (find x such that the result is zero) in the form $ax^2 + bx + c = 0$.

Solve a quartic equation (find x such that the result is zero) of the form $ax^4 + bx^3 + cx^2 + dx + e = 0$.

Solve a cubic equation (find x such that the result is zero) in the form $ax^3 + bx^2 + cx + d = 0$.

а	The coefficient for the x^2 term.
b	The coefficient for the x term.
С	The constant term.

The two roots of the quadratic equation, which may be complex.

Parameters

а	The coefficient for the x^3 term.
b	The coefficient for the x^2 term.
С	The coefficient for the x term.
d	The constant term.

Returns

The three roots of the cubic, which may be complex.

Parameters

а	The coefficient for the x^4 term.
b	The coefficient for the x^3 term.
С	The coefficient for the x^2 term.
d	The coefficient for the x term.
е	The constant term.

Returns

The four roots of the quartic, which may be complex.

The documentation for this class was generated from the following file:

• Runtime/Utility/MathUtility.cs

6.14 Infohazard.Core.PassiveTimer Struct Reference

A lightweight timer that does not need to be updated each frame.

Public Types

• enum TimeMode

The various modes available for timers.

Public Member Functions

• PassiveTimer (float interval, TimeMode mode=TimeMode.Scaled, bool initialize=true)

Construct a PassiveTimer with the given interval, which will be both the initial and repeat interval.

- $\bullet \ \ \, \textbf{PassiveTimer} \ (\textbf{float initialInterval, float interval, } \textbf{TimeMode mode=TimeMode.Scaled, bool initialize=true}) \\$
 - Construct a PassiveTimer with the given interval.
- void Initialize ()

Initialize the timer.

• bool TryConsume ()

If the current interval has ended, reset the interval and return true, else return false without reset.

• void StartInterval ()

Restart the interval, so that the timer starts counting down from its repeat interval.

• void EndInterval ()

End the interval, so the timer is in the expired state.

Properties

• float InitialInterval [get, set]

Initial interval to set the timer for in seconds.

• float Interval [get, set]

(Serialized) The repeat interval for the in seconds.

• TimeMode Mode [get, set]

What value for time that the timer uses (scaled, unscaled, or realtime).

bool IsIntervalEnded [get]

Whether the timer is in the expired state, meaning the current interval has elapsed.

• float IntervalStartTime [get, set]

The start time for the current interval.

• float IntervalEndTime [get]

The time at which the current interval will end (or has ended).

• bool |s|nitialized [get, private set]

Whether the timer is initialized.

• bool HasIntervalStarted [get, private set]

Whether an interval has started yet.

float TimeUntilIntervalEnd [get]

The time in seconds until the current interval ends.

• float RatioUntilIntervalEnd [get]

A ratio going from one at interval start to zero at interval end.

• float TimeSinceIntervalStart [get]

The time in seconds since the current interval started.

• float RatioSinceIntervalStart [get]

A ratio going from zero at interval start to one at interval end.

bool DidIntervalEndThisFrame [get]

Whether the current interval ended during the current frame.

• float CurrentTimeWithoutPause [get]

The current time read from Unity, based on the Mode.

float CurrentTime [get]

The current time read from Unity, taking into account time that the PassiveTimer has spent paused.

• float DeltaTime [get]

The delta time read from Unity, based on the Mode.

• float PausedTime [get, private set]

The time that the PassiveTimer has spent in a paused state.

• bool IsPaused [get, set]

Get or set whether the PassiveTimer is paused.

Private Attributes

float initialInterval

(Serialized) Initial interval to set the timer for in seconds.

· float interval

(Serialized) The repeat interval for the timer in seconds.

TimeMode _mode

(Serialized) What value for time that the timer uses (scaled, unscaled, or realtime).

6.14.1 Detailed Description

A lightweight timer that does not need to be updated each frame.

Can be serialized directly in the inspector or created in code. If it is assigned in the inspector, you must call Initialize in Start/Awake/OnEnable/OnSpawned.

A PassiveTimer can be in one of four states:

- It has not yet been initialized (uninitialized state).
- An interval is active and counting down (counting state).
- The timer is paused (paused state).
- An interval has expired (expired state).

6.14.2 Member Enumeration Documentation

```
6.14.2.1 TimeMode enum Infohazard.Core.PassiveTimer.TimeMode
```

The various modes available for timers.

6.14.3 Constructor & Destructor Documentation

Construct a PassiveTimer with the given interval, which will be both the initial and repeat interval.

interval	The initial and repeat interval.
mode	Time mode to use.
initialize	Whether to initialize the timer and start counting immediately.

Construct a PassiveTimer with the given interval.

Parameters

initialInterval	The initial interval.
interval	The repeat interval.
mode	Time mode to use.
initialize	Whether to initialize the timer and start counting immediately.

6.14.4 Member Function Documentation

```
6.14.4.1 EndInterval() void Infohazard.Core.PassiveTimer.EndInterval ( )
```

End the interval, so the timer is in the expired state.

```
6.14.4.2 Initialize() void Infohazard.Core.PassiveTimer.Initialize ( )
```

Initialize the timer.

You must call this when your script initializes if the timer was assigned in the inspector.

```
6.14.4.3 StartInterval() void Infohazard.Core.PassiveTimer.StartInterval ( )
```

Restart the interval, so that the timer starts counting down from its repeat interval.

```
6.14.4.4 TryConsume() bool Infohazard.Core.PassiveTimer.TryConsume ()
```

If the current interval has ended, reset the interval and return true, else return false without reset.

```
This is useful to create ability cooldowns or weapon fire rates. See the following example:
```

```
if (AbilityButtonPressed() && AbilityTimer.TryConsume()) {
   UseAbility();
}
```

Returns

Whether the interval was ended and has been reset.

6.14.5 Member Data Documentation

6.14.5.1 _initialInterval float Infohazard.Core.PassiveTimer._initialInterval [private]

(Serialized) Initial interval to set the timer for in seconds.

6.14.5.2 _interval float Infohazard.Core.PassiveTimer._interval [private]

(Serialized) The repeat interval for the timer in seconds.

6.14.5.3 _mode TimeMode Infohazard.Core.PassiveTimer._mode [private]

(Serialized) What value for time that the timer uses (scaled, unscaled, or realtime).

6.14.6 Property Documentation

6.14.6.1 CurrentTime float Infohazard.Core.PassiveTimer.CurrentTime [get]

The current time read from Unity, taking into account time that the PassiveTimer has spent paused.

6.14.6.2 CurrentTimeWithoutPause float Infohazard.Core.PassiveTimer.CurrentTimeWithoutPause [get]

The current time read from Unity, based on the Mode.

Exceptions

ArgumentOutOfRangeException If Mode is invalid.

6.14.6.3 DeltaTime float Infohazard.Core.PassiveTimer.DeltaTime [get]

The delta time read from Unity, based on the Mode.

Exceptions

ArgumentOutOfRangeException If Mode is invalid or realtime.

6.14.6.4 DidIntervalEndThisFrame bool Infohazard.Core.PassiveTimer.DidIntervalEndThisFrame [get]

Whether the current interval ended during the current frame.

This can be used to create actions that happen only once, the moment a timer expires.

6.14.6.5 HasIntervalStarted bool Infohazard.Core.PassiveTimer.HasIntervalStarted [get], [private set]

Whether an interval has started yet.

6.14.6.6 InitialInterval float Infohazard.Core.PassiveTimer.InitialInterval [get], [set]

Initial interval to set the timer for in seconds.

This interval begins when Initialize is called, or when the timer is created from a non-default constructor.

6.14.6.7 Interval float Infohazard.Core.PassiveTimer.Interval [get], [set]

(Serialized) The repeat interval for the in seconds.

This interval begins when StartInterval or TryConsume is used.

6.14.6.8 IntervalEndTime float Infohazard.Core.PassiveTimer.IntervalEndTime [get]

The time at which the current interval will end (or has ended).

6.14.6.9 IntervalStartTime float Infohazard.Core.PassiveTimer.IntervalStartTime [get], [set]

The start time for the current interval.

6.14.6.10 IsInitialized bool Infohazard.Core.PassiveTimer.IsInitialized [get], [private set]

Whether the timer is initialized.

6.14.6.11 IsIntervalEnded bool Infohazard.Core.PassiveTimer.IsIntervalEnded [get]

Whether the timer is in the expired state, meaning the current interval has elapsed.

6.14.6.12 IsPaused bool Infohazard.Core.PassiveTimer.IsPaused [get], [set]

Get or set whether the PassiveTimer is paused.

It is not necessary to pause timers to account for the game pausing, as long as they are using realtime. This allows an individual timer to be paused separately from the rest of the game.

6.14.6.13 Mode TimeMode Infohazard.Core.PassiveTimer.Mode [get], [set]

What value for time that the timer uses (scaled, unscaled, or realtime).

6.14.6.14 PausedTime float Infohazard.Core.PassiveTimer.PausedTime [get], [private set]

The time that the PassiveTimer has spent in a paused state.

6.14.6.15 RatioSinceIntervalStart float Infohazard.Core.PassiveTimer.RatioSinceIntervalStart [get]

A ratio going from zero at interval start to one at interval end.

6.14.6.16 RatioUntilIntervalEnd float Infohazard.Core.PassiveTimer.RatioUntilIntervalEnd [get]

A ratio going from one at interval start to zero at interval end.

6.14.6.17 TimeSinceIntervalStart float Infohazard.Core.PassiveTimer.TimeSinceIntervalStart [get]

The time in seconds since the current interval started.

6.14.6.18 TimeUntilIntervalEnd float Infohazard.Core.PassiveTimer.TimeUntilIntervalEnd [get]

The time in seconds until the current interval ends.

The documentation for this struct was generated from the following file:

• Runtime/Timing/PassiveTimer.cs

6.15 Infohazard.Core.Pause Class Reference

Manages pausing and unpausing of the game.

Properties

• static bool Paused [get, set]

Controls paused state of the game.

Events

- static Action GamePaused Invoked when the game pauses.
- static Action GameResumed

Invoked when the game un-pauses.

6.15.1 Detailed Description

Manages pausing and unpausing of the game.

Any actions that should only happen when the game is not paused should check Pause.paused. Can be used statically if pause is controlled elsewhere, or placed as a component to pause the game from a UnityEvent. The game will automatically unpause when a new scene is loaded.

6.15.2 Property Documentation

```
6.15.2.1 Paused bool Infohazard.Core.Pause.Paused [static], [get], [set]
```

Controls paused state of the game.

This cannot completely prevent game actions from happening, but it does sets Time.timeScale to 0 so that Physics and animation will stop.

6.15.3 Event Documentation

6.15.3.1 GamePaused Action Infohazard.Core.Pause.GamePaused [static]

Invoked when the game pauses.

6.15.3.2 GameResumed Action Infohazard.Core.Pause.GameResumed [static]

Invoked when the game un-pauses.

The documentation for this class was generated from the following file:

• Runtime/Timing/Pause.cs

6.16 Infohazard.Core.Pool < T > Class Template Reference

Provides a simple pool with an interface similar to the official Unity pool added in 2021.

Public Member Functions

Pool (Func< T > createFunc, Action< T > getAction=null, Action< T > releaseAction=null, Action< T > destroyAction=null, int maxCount=0)

Create a new ObjectPool.

• T Get ()

Retrieve an item from the pool, creating a new one if necessary.

void Release (T item)

Return an object to the pool, destroying it if over max count.

• void Clear ()

Destroy all objects in the pool.

• void Dispose ()

Destroy all objects in the pool.

Properties

• Func< T > CreateFunc [get, set]

Function invoked to create an instance, which must not be null.

Action < T > GetAction [get, set]

Callback invoked when an object is retrieved from the pool.

• Action< T > ReleaseAction [get, set]

Callback invoked when an object is returned to the pool.

Action< T > DestroyAction [get, set]

Callback invoked when an object is destroyed in the pool.

• int MaxCount = 0 [get, set]

Max objects in pool, or 0 for no limit.

6.16.1 Detailed Description

Provides a simple pool with an interface similar to the official Unity pool added in 2021.

Template Parameters

T Type of pooled object.

6.16.2 Constructor & Destructor Documentation

```
Action< T > getAction = null,
Action< T > releaseAction = null,
Action< T > destroyAction = null,
int maxCount = 0)
```

Create a new ObjectPool.

Parameters

createFunc	Function invoked to create an instance, which must not be null.	
getAction	getAction Callback invoked when an object is retrieved from the pool.	
releaseAction	Callback invoked when an object is returned to the pool.	
destroyAction	Callback invoked when an object is destroyed in the pool.	
maxCount	Max objects in pool, or 0 for no limit.	

6.16.3 Member Function Documentation

```
6.16.3.1 Clear() void Infohazard.Core.Pool< T >.Clear ()
```

Destroy all objects in the pool.

```
\textbf{6.16.3.2} \quad \textbf{Dispose()} \quad \texttt{void Infohazard.Core.Pool} < \; \texttt{T} \; > \texttt{.Dispose ()} \\
```

Destroy all objects in the pool.

```
6.16.3.3 Get() T Infohazard.Core.Pool< T >.Get ( )
```

Retrieve an item from the pool, creating a new one if necessary.

Returns

The retrieved object.

```
6.16.3.4 Release() void Infohazard.Core.Pool< T >.Release ( T item )
```

Return an object to the pool, destroying it if over max count.

_					
D٥	ro	m	ച	0	PC

item

6.16.4 Property Documentation

```
\textbf{6.16.4.1} \quad \textbf{CreateFunc} \quad \texttt{Func} < \texttt{T} > \texttt{Infohazard.Core.Pool} < \texttt{T} > .\texttt{CreateFunc} \quad \texttt{[get], [set]}
```

Function invoked to create an instance, which must not be null.

```
6.16.4.2 DestroyAction Action<T> Infohazard.Core.Pool< T >.DestroyAction [get], [set]
```

Callback invoked when an object is destroyed in the pool.

```
\textbf{6.16.4.3} \quad \textbf{GetAction} \quad \texttt{Action} < \texttt{T} > \texttt{Infohazard.Core.Pool} < \texttt{T} > \textbf{.GetAction} \quad \texttt{[get], [set]}
```

Callback invoked when an object is retrieved from the pool.

```
6.16.4.4 MaxCount int Infohazard.Core.Pool< T >.MaxCount = 0 [get], [set]
```

Max objects in pool, or 0 for no limit.

```
6.16.4.5 ReleaseAction Action<T> Infohazard.Core.Pool< T >.ReleaseAction [get], [set]
```

Callback invoked when an object is returned to the pool.

The documentation for this class was generated from the following file:

• Runtime/Pooling/Pool.cs

6.17 Infohazard.Core.PooledParticleEffect Class Reference

A component that can be attached to ParticleSystem GameObjects to make them work correctly with pooling.

Private Attributes

bool despawnOnDone = true

(Serialized) Whether to despawn the Spawnable when the ParticleSystem finishes.

6.17.1 Detailed Description

A component that can be attached to ParticleSystem GameObjects to make them work correctly with pooling.

This script enables ParticleSystems to reset and play when they are spawned using the pooling system, and to optionally despawn themselves when they complete. This script must be placed on a GameObject with a Particle System component, and there must be a Spawnable component in this object or a parent. In order for despawning to work, the ParticleSystem must have its Stop Action set to Callback. If there are multiple ParticleSystems in a prefab, only the root one should have _despawnOnDone set to true.

6.17.2 Member Data Documentation

6.17.2.1 _despawnOnDone bool Infohazard.Core.PooledParticleEffect._despawnOnDone = true [private]

(Serialized) Whether to despawn the Spawnable when the ParticleSystem finishes.

To work, the ParticleSystem must have its Stop Action set to Callback.

The documentation for this class was generated from the following file:

• Runtime/Pooling/PooledParticleEffect.cs

6.18 Infohazard.Core.PooledTrail Class Reference

A component that can be attached to TrailRenderer GameObjects to make them work correctly with pooling.

6.18.1 Detailed Description

A component that can be attached to TrailRenderer GameObjects to make them work correctly with pooling.

This script enables TrailRenderers to reset when they are spawned using the pooling system. This script must be placed on a GameObject with a TrailRenderer component.

The documentation for this class was generated from the following file:

· Runtime/Pooling/PooledTrail.cs

6.19 Infohazard.Core.PoolManager Class Reference

The singleton manager class that handles object pooling.

Public Member Functions

void ClearInactiveObjects ()

Remove and destroy any inactive pooled objects.

Properties

• static PoolManager Instance [get]

The singleton PoolManager instance.

6.19.1 Detailed Description

The singleton manager class that handles object pooling.

There should only ever be on PoolManager at a time, but this can be created either manually or automatically when needed. You can have one PoolManager per scene, or have a shared one across all scenes. The only time you'll typically need to interact with the PoolManager is to call ClearInactiveObjects when loading a new level, if the previously pooled objects are no longer necessary. All normal spawning and despawning of instances should be done through the Spawnable class.

6.19.2 Member Function Documentation

6.19.2.1 ClearInactiveObjects() void Infohazard.Core.PoolManager.ClearInactiveObjects ()

Remove and destroy any inactive pooled objects.

6.19.3 Property Documentation

```
6.19.3.1 Instance PoolManager Infohazard.Core.PoolManager.Instance [static], [get]
```

The singleton PoolManager instance.

If this property is accessed when there is no active instance, one will be created automatically.

The documentation for this class was generated from the following file:

• Runtime/Pooling/PoolManager.cs

6.20 Infohazard.Core.ProgressBar Class Reference

Used to create health bars and other types of progress bars without using a Slider.

Properties

• float FillAmount [get, set]

By what value to fill the bar.

Private Attributes

• Image _fillImage

(Serialized) Image that will be used as the bar fill.

• float _fillAmount = 0.5f

(Serialized) By what value to fill the bar.

TMP_Text _percentText

(Serialized) An optional text label to show the progress percentage on.

6.20.1 Detailed Description

Used to create health bars and other types of progress bars without using a Slider.

It supports images that fill the bar using either the "filled" image type or by manipulating the RectTransform anchors.

6.20.2 Member Data Documentation

```
6.20.2.1 _fillAmount float Infohazard.Core.ProgressBar._fillAmount = 0.5f [private]
```

(Serialized) By what value to fill the bar.

A value of zero means empty, one means full.

```
6.20.2.2 _fillImage Image Infohazard.Core.ProgressBar._fillImage [private]
```

(Serialized) Image that will be used as the bar fill.

If the image mode is set to fill, the fill amount will be controlled. Otherwise, the RectTransform anchors will be controlled.

```
6.20.2.3 _percentText TMP_Text Infohazard.Core.ProgressBar._percentText [private]
```

(Serialized) An optional text label to show the progress percentage on.

The text will be formatted as {XYZ}%, with no decimal places.

6.20.3 Property Documentation

```
6.20.3.1 FillAmount float Infohazard.Core.ProgressBar.FillAmount [get], [set]
```

By what value to fill the bar.

A value of zero means empty, one means full.

The documentation for this class was generated from the following file:

• Runtime/Misc/ProgressBar.cs

6.21 Infohazard.Core.RandomUtility Class Reference

Contains extensions to builtin randomization functionality.

Static Public Member Functions

- static long NextLong (this System.Random random, long min, long max)

 Generate a random long between min and max.
- static ulong NextUlong (this System.Random random)

 Generate a random ulong.

6.21.1 Detailed Description

Contains extensions to builtin randomization functionality.

6.21.2 Member Function Documentation

```
6.21.2.1 NextLong() static long Infohazard.Core.RandomUtility.NextLong ( this System.Random random, long min, long max ) [static]
```

Generate a random long between min and max.

```
6.21.2.2 NextUlong() static ulong Infohazard.Core.RandomUtility.NextUlong ( this System.Random random ) [static]
```

Generate a random ulong.

The documentation for this class was generated from the following file:

• Runtime/Utility/RandomUtility.cs

6.22 Infohazard.Core.SceneControl Class Reference

Provides some methods to navigate to scenes.

Public Member Functions

• void QuitButton ()

Non-static equivalent of Quit.

• void ReloadScene ()

Reload the current scene.

void LoadScene (string sceneName)

Load a scene with a given name.

Static Public Member Functions

· static void Quit ()

If in the editor, exit play mode. Otherwise, close the application.

6.22.1 Detailed Description

Provides some methods to navigate to scenes.

Also provides a static method to quit the game that works in a standalone build as well as in the editor. This script is useful if you're building a super quick main menu (such as in the last half hour of a game jam) and need to hook up your buttons as fast as possible.

6.22.2 Member Function Documentation

```
6.22.2.1 LoadScene() void Infohazard.Core.SceneControl.LoadScene ( string sceneName )
```

Load a scene with a given name.

Scene will be loaded as a single (not additively).

Parameters

sceneName | The scene name to load.

```
6.22.2.2 Quit() static void Infohazard.Core.SceneControl.Quit ( ) [static]
```

If in the editor, exit play mode. Otherwise, close the application.

6.22.2.3 QuitButton() void Infohazard.Core.SceneControl.QuitButton ()

Non-static equivalent of Quit.

6.22.2.4 ReloadScene() void Infohazard.Core.SceneControl.ReloadScene ()

Reload the current scene.

Current scene is determined by SceneManager.GetActiveScene(), and is loaded as a single scene. This method is not very helpful if your game has multiple scenes open at a time.

The documentation for this class was generated from the following file:

· Runtime/Misc/SceneControl.cs

6.23 Infohazard.Core.Singleton< T > Class Template Reference

Base class that makes it easier to write scripts that always have exactly one instance.

Properties

• static T Instance [get]

Get the singleton instance of the script.

6.23.1 Detailed Description

Base class that makes it easier to write scripts that always have exactly one instance.

You can inherit from this script in managers or other scripts. You must still place the script on a GameObject in the scene. A static Instance accessor is automatically provided, which will do a lazy search for the correct instance the first time it is used, or if the previous instance was destroyed. After that it will just return a cached instance.

Template Parameters

T Pass the name of the inheriting class here to set the type of Instance.

Type Constraints

T: SingletonBase

6.23.2 Property Documentation

```
6.23.2.1 Instance T Infohazard.Core.Singleton< T >.Instance [static], [get]
```

Get the singleton instance of the script.

If it hasn't been found yet (or the old instance was destroyed), will do a search using Object.Find{T}. Otherwise it returns the cached instance. However, it will not create a new instance for you.

The documentation for this class was generated from the following file:

• Runtime/Misc/Singleton.cs

6.24 Infohazard.Core.SingletonAsset< T > Class Template Reference

Base class that makes it easier to write ScriptableObjects that always have exactly one instance in your project.

Properties

• static T Instance [get]

Get the singleton instance of the script.

6.24.1 Detailed Description

Base class that makes it easier to write ScriptableObjects that always have exactly one instance in your project.

Similar to Singleton, but for ScriptableObjects. You specify a path in your subclass where the instance should live (this must be under a Resources folder) and the editor will automatically handle loading and even creating this asset for you when needed.

Template Parameters

T Pass the name of the inheriting class here to set the type of Instance.

Type Constraints

T: SingletonAssetBase

6.24.2 Property Documentation

```
6.24.2.1 Instance T Infohazard.Core.SingletonAsset< T >.Instance [static], [get]
```

Get the singleton instance of the script.

If it hasn't been loaded yet, will try to load from SingletonAssetBase.ResourcePath. If in the editor and the asset doesn't exist, it will be created at SingletonAssetBase.ResourceFolderPath/SingletonAssetBase.ResourcePath. Otherwise, the cached instance (or null) will be returned.

The documentation for this class was generated from the following file:

• Runtime/Misc/SingletonAsset.cs

6.25 Infohazard.Core.SingletonAssetBase Class Reference

Base class of SingletonAsset<T>. For internal use only.

Properties

abstract string ResourceFolderPath [get]

Return the path at which the Resources folder containing this asset lives.

• abstract string ResourcePath [get]

Returns the path of this asset relative to its Resources folder.

6.25.1 Detailed Description

Base class of SingletonAsset<T>. For internal use only.

6.25.2 Property Documentation

6.25.2.1 ResourceFolderPath abstract string Infohazard.Core.SingletonAssetBase.Resource← FolderPath [get]

Return the path at which the Resources folder containing this asset lives.

public override string ResourceFolderPath => "Infohazard.Core.Data/Resources";

6.25.2.2 ResourcePath abstract string Infohazard.Core.SingletonAssetBase.ResourcePath [get]

Returns the path of this asset relative to its Resources folder.

The documentation for this class was generated from the following file:

• Runtime/Misc/SingletonAsset.cs

6.26 Infohazard.Core.Spawnable Class Reference

Attach this component to a prefab to enable it to use the pooling system.

Public Member Functions

• void DespawnSelf ()

Despawn this instance and return it to the PoolManager.

Static Public Member Functions

• static Spawnable Spawn (Spawnable prefab, Vector3? position=null, Quaternion? rotation=null, Transform parent=null, bool inWorldSpace=false, ulong persistedInstanceID=0, Scene? scene=null)

Spawn a new pooled instance with the given properties.

static void Despawn (Spawnable instance, float inSeconds=0.0f)

Despawn a pooled instance, optionally after some time has passed.

• static GameObject Spawn (GameObject prefab, Vector3? position=null, Quaternion? rotation=null, Transform parent=null, bool inWorldSpace=false, ulong persistedInstanceID=0, Scene? scene=null)

Spawn a new instance with the given properties, using the pooling system if the prefab has a Spawnable script.

• static void Despawn (GameObject instance, float inSeconds=0.0f)

Despawn an instance, optionally after some time has passed, using the pooling system if the prefab has a Spawnable script.

• static T Spawn< T > (T prefab, Vector3? position=null, Quaternion? rotation=null, Transform parent=null, bool inWorldSpace=false, ulong persistedInstanceID=0, Scene? scene=null)

Spawn a new instance with the given properties, using the pooling system if the prefab has a Spawnable script.

Properties

• bool lsSpawned [get, private set]

Whether or not this object is an active, spawned instance.

• Spawnable Prefab [get]

A reference to the prefab that this object was spawned from.

Events

Action < Spawnable > Spawned

Invoked when the Spawnable is spawned.

Action < Spawnable > Despawned

Invoke when the Spawnable is despawned.

6.26.1 Detailed Description

Attach this component to a prefab to enable it to use the pooling system.

The static methods in this class are also the main way to spawn objects in a way that's compatible with the pooling system. When a Spawnable object is spawned, it will broadcast the OnSpawned message to its children. When it is despawned, it will broadcast the OnDespawned method.

6.26.2 Member Function Documentation

Despawn an instance, optionally after some time has passed, using the pooling system if the prefab has a Spawnable script.

Parameters

instance	The instance to despawn.]
inSeconds	The time to wait before despawning. If zero, despawn is synchronous.	

```
6.26.2.2 Despawn() [2/2] static void Infohazard.Core.Spawnable.Despawn ( Spawnable instance, float inSeconds = 0.0f) [static]
```

Despawn a pooled instance, optionally after some time has passed.

Parameters

instance	The instance to despawn.
inSeconds	The time to wait before despawning. If zero, despawn is synchronous.

6.26.2.3 DespawnSelf() void Infohazard.Core.Spawnable.DespawnSelf ()

Despawn this instance and return it to the PoolManager.

Spawn a new instance with the given properties, using the pooling system if the prefab has a Spawnable script.

Parameters

prefab	The prefab to spawn.
position	The position to spawn at.
rotation	The rotation to spawn at.
parent	The parent to spawn under.
inWorldSpace	If true, position/rotation are global, else they are local to parent.
persistedInstanceID	Existing persisted instance ID to assign.
scene	The scene to spawn in.

Returns

The spawned instance.

Spawn a new pooled instance with the given properties.

Parameters

prefab	The prefab to spawn.
position	The position to spawn at.
rotation	The rotation to spawn at.
parent	The parent to spawn under.
inWorldSpace	If true, position/rotation are global, else they are local to parent.
persistedInstanceID	Existing persisted instance ID to assign.
scene	The scene to spawn in.

Returns

The spawned instance.

Spawn a new instance with the given properties, using the pooling system if the prefab has a Spawnable script.

Parameters

prefab	The prefab to spawn.
position	The position to spawn at.
rotation	The rotation to spawn at.
parent	The parent to spawn under.
inWorldSpace	If true, position/rotation are global, else they are local to parent.
persistedInstanceID	Existing persisted instance ID to assign.
scene	The scene to spawn in.

Generated by Doxygen

Returns

The spawned instance.

Type Constraints

T: Component

6.26.3 Property Documentation

6.26.3.1 IsSpawned bool Infohazard.Core.Spawnable.IsSpawned [get], [private set]

Whether or not this object is an active, spawned instance.

6.26.3.2 Prefab Spawnable Infohazard.Core.Spawnable.Prefab [get]

A reference to the prefab that this object was spawned from.

6.26.4 Event Documentation

6.26.4.1 Despawned Action<Spawnable> Infohazard.Core.Spawnable.Despawned

Invoke when the Spawnable is despawned.

6.26.4.2 Spawned Action<Spawnable> Infohazard.Core.Spawnable.Spawned

Invoked when the Spawnable is spawned.

The documentation for this class was generated from the following file:

• Runtime/Pooling/Spawnable.cs

6.27 Infohazard.Core.StringUtility Class Reference

Contains string processing utilities.

Static Public Member Functions

• static string SplitCamelCase (this string str, bool capitalizeFirst=false)

Splits a camel-case string into words separated by spaces.

6.27.1 Detailed Description

Contains string processing utilities.

6.27.2 Member Function Documentation

```
6.27.2.1 SplitCamelCase() static string Infohazard.Core.StringUtility.SplitCamelCase ( this string str, bool capitalizeFirst = false) [static]
```

Splits a camel-case string into words separated by spaces.

Multiple consecutive capitals are considered the same word.

Parameters

str	The string to split.
capitalizeFirst	Whether to capitalize the first letter.

Returns

The split string.

The documentation for this class was generated from the following file:

• Runtime/Utility/StringUtility.cs

6.28 Infohazard.Core.Tag Class Reference

Provides string constants for builtin Unity tags.

Static Public Attributes

```
    const string Untagged = "Untagged"
        The string "Untagged".
    const string Respawn = "Respawn"
        The string "Respawn".
    const string Finish = "Finish"
        The string "Finish".
    const string EditorOnly = "EditorOnly"
        The string "EditorOnly".
    const string MainCamera = "MainCamera"
        The string "MainCamera".
    const string Player = "Player"
        The string "Player".
```

• const string GameController = "GameController"

```
The string "GameController".
```

• static readonly string[] DefaultTags

Array of default tags provided by Unity.

• static string[] GameOverrideTags = null

Set by the generated Game Tag script.

Properties

• static string[] Tags [get]

Array of all default and custom tags in the project.

6.28.1 Detailed Description

Provides string constants for builtin Unity tags.

To extend with custom tags, see <code>GameTag</code>, which you can generate using the command <code>Infohazard</code> > Generate > Update <code>GameTag.cs</code>.

6.28.2 Member Data Documentation

Array of default tags provided by Unity.

```
6.28.2.2 EditorOnly const string Infohazard.Core.Tag.EditorOnly = "EditorOnly" [static]
```

The string "EditorOnly".

```
6.28.2.3 Finish const string Infohazard.Core.Tag.Finish = "Finish" [static]
```

The string "Finish".

```
6.28.2.4 GameController const string Infohazard.Core.Tag.GameController = "GameController" [static]
```

The string "GameController".

6.28.2.5 GameOverrideTags string [] Infohazard.Core.Tag.GameOverrideTags = null [static]

Set by the generated GameTag script.

6.28.2.6 MainCamera const string Infohazard.Core.Tag.MainCamera = "MainCamera" [static]

The string "MainCamera".

6.28.2.7 Player const string Infohazard.Core.Tag.Player = "Player" [static]

The string "Player".

6.28.2.8 Respawn const string Infohazard.Core.Tag.Respawn = "Respawn" [static]

The string "Respawn".

6.28.2.9 Untagged const string Infohazard.Core.Tag.Untagged = "Untagged" [static]

The string "Untagged".

6.28.3 Property Documentation

6.28.3.1 Tags string [] Infohazard.Core.Tag.Tags [static], [get]

Array of all default and custom tags in the project.

The documentation for this class was generated from the following file:

· Runtime/Misc/Tag.cs

6.29 Infohazard.Core.TagMask Struct Reference

Used to select tags in the inspector, including the ability to select multiple tags.

Public Member Functions

TagMask (long value)

Initialize a new TagMask with the given value.

- override string ToString ()
- bool Equals (TagMask other)
- override bool Equals (object obj)
- · override int GetHashCode ()

Static Public Member Functions

static implicit operator long (TagMask mask)

Convert a TagMask to a long.

• static implicit operator TagMask (long mask)

Convert a long to a TagMask.

static TagMask operator& (in TagMask lhs, in TagMask rhs)

Apply bitwise AND operator to two TagMasks.

static TagMask operator& (TagMask lhs, long rhs)

Apply bitwise AND operator to a TagMask and a long.

static long operator& (long lhs, TagMask rhs)

Apply bitwise AND operator to a long and a TagMask.

static TagMask operator (TagMask Ihs, TagMask rhs)

Apply bitwise OR operator to a TagMask and a TagMask.

static TagMask operator (TagMask Ihs, long rhs)

Apply bitwise OR operator to a TagMask and a long.

static long operator (long lhs, TagMask rhs)

Apply bitwise OR operator to a long and a TagMask.

static TagMask operator[^] (TagMask lhs, TagMask rhs)

Apply bitwise XOR operator to a TagMask and a TagMask.

static TagMask operator[∧] (TagMask lhs, long rhs)

Apply bitwise XOR operator to a TagMask and a long.

static long operator[^] (long lhs, TagMask rhs)

Apply bitwise XOR operator to a long and a TagMask.

- static TagMask operator \sim (TagMask mask)

Apply bitwise NOT operator to a TagMask.

static int NameToTag (string name)

Gets the index of a given tag in the Tag. Tags array.

• static string TagToName (int tag)

Gets the tag name at the given index in the Tag. Tags array.

• static long GetMask (params string[] names)

Get a mask value that contains all the given tag names.

• static long GetMask (string name)

Get a mask value that contains the given tag name.

Static Public Attributes

```
    const long UntaggedMask = 1 << 0</li>
```

Mask value for the Untagged tag.

const long RespawnMask = 1 << 1

Mask value for the Respawn tag.

• const long FinishMask = 1 << 2

Mask value for the Finish tag.

const long EditorOnlyMask = 1 << 3

Mask value for the EditorOnly tag.

const long MainCameraMask = 1 << 4

Mask value for the MainCamera tag.

• const long PlayerMask = 1 << 5

Mask value for the Player tag.

const long GameControllerMask = 1 << 6

Mask value for the GameController tag.

Properties

```
• long Value [get, set]
```

The value of the mask as a 64-bit integer.

6.29.1 Detailed Description

Used to select tags in the inspector, including the ability to select multiple tags.

Works similar to LayerMask. If you have a custom <code>GameTag</code> script generated, your custom tags will be available here too. You can find code constants for those tags in <code>GameTagMask</code>. Like LayerMask, <code>TagMask</code> is implicitly convertable to and from an integer value (long in this case).

6.29.2 Constructor & Destructor Documentation

```
6.29.2.1 TagMask() Infohazard.Core.TagMask.TagMask ( long value )
```

Initialize a new TagMask with the given value.

Parameters

value	The value to initialize with, representing which tags are "on".

6.29.3 Member Function Documentation

```
6.29.3.1 Equals() [1/2] override bool Infohazard.Core.TagMask.Equals ( object obj )
```

```
6.29.3.2 Equals() [2/2] bool Infohazard.Core.TagMask.Equals ( TagMask other )
```

 $\textbf{6.29.3.3} \quad \textbf{GetHashCode()} \quad \text{override int Infohazard.Core.TagMask.GetHashCode ()}$

```
6.29.3.4 GetMask() [1/2] static long Infohazard.Core.TagMask.GetMask ( params string[] names ) [static]
```

Get a mask value that contains all the given tag names.

Parameters

names	Names of tags to include in the mask.
-------	---------------------------------------

Returns

The created mask.

```
6.29.3.5 GetMask() [2/2] static long Infohazard.Core.TagMask.GetMask ( string name ) [static]
```

Get a mask value that contains the given tag name.

Parameters

name Name of tag to include in the mask.

Returns

The created mask.

```
6.29.3.6 NameToTag() static int Infohazard.Core.TagMask.NameToTag ( string name ) [static]
```

Gets the index of a given tag in the Tag. Tags array.

Parameters

name	Tag name.
------	-----------

Returns

The index of the tag or -1 if it doesn't exist.

```
6.29.3.7 operator long() static implicit Infohazard.Core.TagMask.operator long ( TagMask mask ) [static]
```

Convert a TagMask to a long.

Parameters

Returns

The mask's value.

```
6.29.3.8 operator TagMask() static implicit Infohazard.Core.TagMask.operator TagMask ( long mask ) [static]
```

Convert a long to a TagMask.

Parameters

```
mask The mask value.
```

Returns

The created TagMask.

Apply bitwise AND operator to two TagMasks.

Apply bitwise AND operator to a long and a TagMask.

Apply bitwise AND operator to a TagMask and a long.

Apply bitwise XOR operator to a long and a TagMask.

```
6.29.3.13 operator^{\wedge}() [2/3] static TagMask Infohazard.Core.TagMask.operator^{\wedge} ( TagMask lhs, long rhs ) [static]
```

Apply bitwise XOR operator to a TagMask and a long.

```
6.29.3.14 operator^{\wedge}() [3/3] static TagMask Infohazard.Core.TagMask.operator^{\wedge} ( TagMask lhs, TagMask rhs) [static]
```

Apply bitwise XOR operator to a TagMask and a TagMask.

Apply bitwise OR operator to a long and a TagMask.

```
6.29.3.16 operator" | () [2/3]  static TagMask Infohazard.Core.TagMask.operator| ( TagMask lhs, long rhs) [static]
```

Apply bitwise OR operator to a TagMask and a long.

```
6.29.3.17 operator" | () [3/3] static TagMask Infohazard.Core.TagMask.operator | (

TagMask lhs,

TagMask rhs ) [static]
```

Apply bitwise OR operator to a TagMask and a TagMask.

```
6.29.3.18 operator∼() static TagMask Infohazard.Core.TagMask.operator∼ (

TagMask mask) [static]
```

Apply bitwise NOT operator to a TagMask.

```
6.29.3.19 TagToName() static string Infohazard.Core.TagMask.TagToName ( int tag) [static]
```

Gets the tag name at the given index in the Tag. Tags array.

Parameters

```
tag Tag index. Must be in range [0, TAG COUNT - 1].
```

Returns

The tag's name.

```
6.29.3.20 ToString() override string Infohazard.Core.TagMask.ToString ()
```

6.29.4 Member Data Documentation

6.29.4.1 EditorOnlyMask const long Infohazard.Core.TagMask.EditorOnlyMask = 1 << 3 [static]

Mask value for the EditorOnly tag.

6.29.4.2 FinishMask const long Infohazard.Core.TagMask.FinishMask = 1 << 2 [static]

Mask value for the Finish tag.

6.29.4.3 GameControllerMask const long Infohazard.Core.TagMask.GameControllerMask = 1 << 6 [static]

Mask value for the GameController tag.

6.29.4.4 MainCameraMask const long Infohazard.Core.TagMask.MainCameraMask = 1 << 4 [static]

Mask value for the MainCamera tag.

6.29.4.5 PlayerMask const long Infohazard.Core.TagMask.PlayerMask = 1 << 5 [static]

Mask value for the Player tag.

6.29.4.6 RespawnMask const long Infohazard.Core.TagMask.RespawnMask = 1 << 1 [static]

Mask value for the Respawn tag.

6.29.4.7 UntaggedMask const long Infohazard.Core.TagMask.UntaggedMask = 1 << 0 [static]

Mask value for the Untagged tag.

6.29.5 Property Documentation

6.29.5.1 Value long Infohazard.Core.TagMask.Value [get], [set]

The value of the mask as a 64-bit integer.

The documentation for this struct was generated from the following file:

Runtime/Misc/Tag.cs

6.30 Infohazard.Core.TagMaskUtility Class Reference

Static operations on Tag enum values.

Static Public Member Functions

• static bool CompareTagMask (this GameObject obj, long tag)

Return true if GameObject's tag matches given any tag in given value.

• static bool CompareTagMask (this Component obj, long tag)

Return true if Component's tag matches given any tag in given value.

• static void SetTagIndex (this GameObject obj, int tagIndex)

Set the tag index of a GameObject.

static int GetTagIndex (this GameObject obj)

Get the tag index of a GameObject.

static int GetTagIndex (this Component obj)

Get the tag index of a Component.

static long GetTagMask (this GameObject obj)

Get the tag mask of a GameObject.

static long GetTagMask (this Component obj)

Get the tag mask of a Component.

6.30.1 Detailed Description

Static operations on Tag enum values.

6.30.2 Member Function Documentation

```
6.30.2.1 CompareTagMask() [1/2] static bool Infohazard.Core.TagMaskUtility.CompareTagMask ( this Component obj, long tag ) [static]
```

Return true if Component's tag matches given any tag in given value.

Parameters

Г	obj	The Component to check.
\vdash		The tag to compare, which may be multiple tags.

Returns

Whether Component matches given tag.

```
6.30.2.2 CompareTagMask() [2/2] static bool Infohazard.Core.TagMaskUtility.CompareTagMask ( this GameObject obj, long tag ) [static]
```

Return true if GameObject's tag matches given any tag in given value.

Parameters

obj	The GameObject to check.
tag	The tag to compare, which may be multiple tags.

Returns

Whether GameObject matches given tag.

```
6.30.2.3 GetTagIndex() [1/2] static int Infohazard.Core.TagMaskUtility.GetTagIndex ( this Component obj) [static]
```

Get the tag index of a Component.

Parameters

obj	Object to read.
-----	-----------------

Returns

The Component's tag index.

```
6.30.2.4 GetTagIndex() [2/2] static int Infohazard.Core.TagMaskUtility.GetTagIndex ( this GameObject obj ) [static]
```

Get the tag index of a GameObject.

Parameters

obj	Object to read.

Returns

The GameObject's tag index.

6.30.2.5 GetTagMask() [1/2] static long Infohazard.Core.TagMaskUtility.GetTagMask (this Component obj) [static]

Get the tag mask of a Component.

Parameters

obj	Object to read.
-----	-----------------

Returns

The Component's tag as a mask.

```
6.30.2.6 GetTagMask() [2/2] static long Infohazard.Core.TagMaskUtility.GetTagMask ( this GameObject obj) [static]
```

Get the tag mask of a GameObject.

Parameters

```
obj Object to read.
```

Returns

The GameObject's tag as a mask.

```
6.30.2.7 SetTagIndex() static void Infohazard.Core.TagMaskUtility.SetTagIndex ( this GameObject obj, int tagIndex) [static]
```

Set the tag index of a GameObject.

Parameters

obj	Object to modify.	
tagIndex	Tag to set.	

The documentation for this class was generated from the following file:

· Runtime/Misc/Tag.cs

6.31 Infohazard.Core.Editor.TagsGenerator Class Reference

Class used to generate the GameTag.cs file to use your custom tags in code.

Static Public Member Functions

static void Generate ()

Generate the GameTag file.

• static void Remove ()

Remove the GameTag file.

6.31.1 Detailed Description

Class used to generate the GameTag.cs file to use your custom tags in code.

To generate this file, use the menu item Infohazard > Generate > Update GameTag.cs.

6.31.2 Member Function Documentation

```
6.31.2.1 Generate() static void Infohazard.Core.Editor.TagsGenerator.Generate ( ) [static] Generate the GameTag file.
```

```
6.31.2.2 Remove() static void Infohazard.Core.Editor.TagsGenerator.Remove ( ) [static]
```

Remove the GameTag file.

The documentation for this class was generated from the following file:

· Editor/Misc/TagsGenerator.cs

6.32 Infohazard.Core.TimeToLive Class Reference

Despawns a GameObject after a set amount of time.

Properties

• float TimeRemaining [get, set]

How much time remains before the GameObject is destroyed.

Private Attributes

• float _timeToLive = 5

(Serialized) How much time remains before the GameObject is destroyed.

• float _linger = 0

(Serialized) How long the object will remain after its time to live has passed.

GameObject _spawnOnDeath

(Serialized) Optional object that will be spawned when the time to live has passed (but before the linger).

6.32.1 Detailed Description

Despawns a GameObject after a set amount of time.

Compatible with the pooling system.

6.32.2 Member Data Documentation

```
6.32.2.1 _linger float Infohazard.Core.TimeToLive._linger = 0 [private]
```

(Serialized) How long the object will remain after its time to live has passed.

6.32.2.2 _spawnOnDeath GameObject Infohazard.Core.TimeToLive._spawnOnDeath [private]

(Serialized) Optional object that will be spawned when the time to live has passed (but before the linger).

6.32.2.3 _timeToLive float Infohazard.Core.TimeToLive._timeToLive = 5 [private]

(Serialized) How much time remains before the GameObject is destroyed.

6.32.3 Property Documentation

6.32.3.1 TimeRemaining float Infohazard.Core.TimeToLive.TimeRemaining [get], [set]

How much time remains before the GameObject is destroyed.

The documentation for this class was generated from the following file:

• Runtime/Timing/TimeToLive.cs

6.33 Infohazard.Core.TriggerVolume.TriggerEvents Class Reference

Class that stores the UnityEvents used by a TriggerVolume.

Properties

- UnityEvent OnTriggerEnter [get]
 - Invoked when an object matching the tag filter enters the trigger.
- UnityEvent OnTriggerExit [get]
 - Invoked when an object matching the tag filter exits the trigger.
- UnityEvent OnAllExit [get]
 - Invoked when the last object matching the tag filter exits the trigger.

Private Attributes

- UnityEvent _onTriggerEnter
 - (Serialized) Invoked when an object matching the tag filter enters the trigger.
- UnityEvent _onTriggerExit
 - (Serialized) Invoked when an object matching the tag filter exits the trigger.
- UnityEvent _onAllExit
 - (Serialized) Invoked when the last object matching the tag filter exits the trigger.

6.33.1 Detailed Description

Class that stores the UnityEvents used by a TriggerVolume.

6.33.2 Member Data Documentation

6.33.2.1 _onAllExit UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents._onAllExit [private]

(Serialized) Invoked when the last object matching the tag filter exits the trigger.

6.33.2.2 _onTriggerEnter UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents._onTriggerEnter [private]

(Serialized) Invoked when an object matching the tag filter enters the trigger.

6.33.2.3 _onTriggerExit UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents._onTriggerExit [private]

(Serialized) Invoked when an object matching the tag filter exits the trigger.

6.33.3 Property Documentation

6.33.3.1 OnAllExit UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents.OnAllExit [get]

Invoked when the last object matching the tag filter exits the trigger.

6.33.3.2 OnTriggerEnter UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents.OnTriggerEnter [get]

Invoked when an object matching the tag filter enters the trigger.

6.33.3.3 OnTriggerExit UnityEvent Infohazard.Core.TriggerVolume.TriggerEvents.OnTriggerExit [get]

Invoked when an object matching the tag filter exits the trigger.

The documentation for this class was generated from the following file:

• Runtime/Misc/TriggerVolume.cs

6.34 Infohazard.Core.TriggerVolume Class Reference

A script that makes it easy to add events to a trigger collider.

Classes

class TriggerEvents

Class that stores the UnityEvents used by a TriggerVolume.

Properties

• TriggerEvents Events [get]

UnityEvents that enable you to assign functionality in the editor.

Events

Action < GameObject > TriggerEntered
 Invoked when an object matching the tag filter enters the trigger.

Action < GameObject > TriggerExited
 Invoked when an object matching the tag filter exits the trigger.

Action < GameObject > AllExited

Invoked when the last object matching the tag filter exits the trigger.

Private Attributes

• TagMask _tagFilter = TagMask.PlayerMask

(Serialized) Mask of tags that can activate the trigger.

• TriggerEvents _events = default

(Serialized) UnityEvents that enable you to assign functionality in the editor.

6.34.1 Detailed Description

A script that makes it easy to add events to a trigger collider.

Provides both UnityEvents (assignable in the inspector) and normal C# events for when an object enters or leaves the trigger, and when all objects have left the trigger. Also provides a tag filter, allowing you to control which types of object can activate it.

6.34.2 Member Data Documentation

```
6.34.2.1 _events TriggerEvents Infohazard.Core.TriggerVolume._events = default [private]
```

(Serialized) UnityEvents that enable you to assign functionality in the editor.

```
6.34.2.2 _tagFilter TagMask Infohazard.Core.TriggerVolume._tagFilter = TagMask.PlayerMask [private]
```

(Serialized) Mask of tags that can activate the trigger.

6.34.3 Property Documentation

```
6.34.3.1 Events TriggerEvents Infohazard.Core.TriggerVolume.Events [get]
```

UnityEvents that enable you to assign functionality in the editor.

6.34.4 Event Documentation

6.34.4.1 AllExited Action<GameObject> Infohazard.Core.TriggerVolume.AllExited

Invoked when the last object matching the tag filter exits the trigger.

6.34.4.2 TriggerEntered Action<GameObject> Infohazard.Core.TriggerVolume.TriggerEntered

Invoked when an object matching the tag filter enters the trigger.

6.34.4.3 TriggerExited Action<GameObject> Infohazard.Core.TriggerVolume.TriggerExited

Invoked when an object matching the tag filter exits the trigger.

The documentation for this class was generated from the following file:

• Runtime/Misc/TriggerVolume.cs

6.35 Infohazard.Core.TypeSelectAttribute Class Reference

Attribute that draws string fields as a dropdown where a Type can be selected.

Public Member Functions

• TypeSelectAttribute (Type baseClass, bool allowAbstract=false, bool allowGeneric=false, bool search=false)

Construct a new TypeSelectAttribute.

Properties

```
• Type BaseClass [get]
```

If set, dropdown will only show types assignable to this type.

• bool AllowAbstract [get]

Whether to show abstract classes.

• bool AllowGeneric [get]

Whether to show generic types.

• bool Search [get]

Whether to show a search bar.

6.35.1 Detailed Description

Attribute that draws string fields as a dropdown where a Type can be selected.

6.35.2 Constructor & Destructor Documentation

Construct a new TypeSelectAttribute.

Parameters

baseClass If set, dropdown will only show types assignable to this ty			
allowAbstract	Whether to show abstract classes.		
allowGeneric	Whether to show generic types.		
search	Whether to show a search bar./		

6.35.3 Property Documentation

6.35.3.1 AllowAbstract bool Infohazard.Core.TypeSelectAttribute.AllowAbstract [get]

Whether to show abstract classes.

6.35.3.2 AllowGeneric bool Infohazard.Core.TypeSelectAttribute.AllowGeneric [get]

Whether to show generic types.

6.35.3.3 BaseClass Type Infohazard.Core.TypeSelectAttribute.BaseClass [get]

If set, dropdown will only show types assignable to this type.

6.35.3.4 Search bool Infohazard.Core.TypeSelectAttribute.Search [get]

Whether to show a search bar.

The documentation for this class was generated from the following file:

• Runtime/Attributes/TypeSelectAttribute.cs

6.36 Infohazard.Core.TypeUtility Class Reference

Contains utilities for working with C# reflection types and getting a type by its name.

Static Public Member Functions

static Type GetType (string fullName)

Get a type given its full name (including namespace).

Properties

```
• static Assembly[] AllAssemblies [get]
```

Returns an array of all loaded assemblies.

static IEnumerable < Type > AllTypes [get]

Returns an enumeration of all loaded types.

6.36.1 Detailed Description

Contains utilities for working with C# reflection types and getting a type by its name.

6.36.2 Member Function Documentation

```
6.36.2.1 GetType() static Type Infohazard.Core.TypeUtility.GetType ( string fullName ) [static]
```

Get a type given its full name (including namespace).

Parameters

	fullName	Name of the type including namespace.
--	----------	---------------------------------------

Returns

The found type, or null.

6.36.3 Property Documentation

```
6.36.3.1 AllAssemblies Assembly [] Infohazard.Core.TypeUtility.AllAssemblies [static], [get]
```

Returns an array of all loaded assemblies.

```
6.36.3.2 AllTypes IEnumerable<Type> Infohazard.Core.TypeUtility.AllTypes [static], [get]
```

Returns an enumeration of all loaded types.

The documentation for this class was generated from the following file:

• Runtime/Utility/TypeUtility.cs

6.37 Infohazard.Core.UniqueNamedObject Class Reference

This script is used to assign a unique name to an object, which can then be used to find that object.

Static Public Member Functions

· static bool TryGetObject (string name, out GameObject result)

Try to get a GameObject with the given unique name, and return whether it was found.

• static bool TryGetObject (UniqueNameListEntry entry, out GameObject result)

Try to get a GameObject with the given unique name asset, and return whether it was found.

Properties

```
• string UniqueName [get, private set]

Unique name asset for the object.
```

• static IReadOnlyDictionary< string, UniqueNamedObject > Objects [get]

Dictionary of all active UniqueNamedObjects keyed by their unique names.

Private Attributes

UniqueNameListEntry _uniqueName

(Serialized) Unique name asset for the object.

6.37.1 Detailed Description

This script is used to assign a unique name to an object, which can then be used to find that object.

Unique names can be created under a UniqueNameList. The static methods in this class can be used to quickly find objects by their unique names. Since the unique names are asset references, there is no chance of making typos, and they can even be renamed without breaking references. There is nothing that prevents two objects from sharing the same name, but you will get a log error if they are active at the same time.

6.37.2 Member Function Documentation

```
6.37.2.1 TryGetObject() [1/2] static bool Infohazard.Core.UniqueNamedObject.TryGetObject ( string name, out GameObject result ) [static]
```

Try to get a GameObject with the given unique name, and return whether it was found.

Parameters

name	The name to search for.
result	The object with that name, or null if not found.

Returns

Whether the object was found.

Try to get a GameObject with the given unique name asset, and return whether it was found.

Parameters

entry	The name asset to search for.		
result	The object with that name, or null if not found.		

Returns

Whether the object was found.

6.37.3 Member Data Documentation

6.37.3.1 _uniqueName UniqueNameListEntry Infohazard.Core.UniqueNamedObject._uniqueName [private] (Serialized) Unique name asset for the object.

6.37.4 Property Documentation

```
6.37.4.1 Objects IReadOnlyDictionary<string, UniqueNamedObject> Infohazard.Core.UniqueNamed↔ Object.Objects [static], [get]
```

Dictionary of all active UniqueNamedObjects keyed by their unique names.

6.37.4.2 UniqueName string Infohazard.Core.UniqueNamedObject.UniqueName [get], [private set]

Unique name asset for the object.

The documentation for this class was generated from the following file:

• Runtime/UniqueName/UniqueNamedObject.cs

6.38 Infohazard.Core.UniqueNameList Class Reference

A list used to organize unique names used by objects.

Properties

IReadOnlyList < UniqueNameListEntry > Entries [get]
 All unique name assets in this list.

Private Attributes

UniqueNameListEntry[] _entries
 (Serialized) All unique name assets in this list.

6.38.1 Detailed Description

A list used to organize unique names used by objects.

You can have one or many UniqueNameLists in your project, it is totally up to you. When selecting a unique name for an object, you will have the option to create a new one in any UniqueNameList.

6.38.2 Member Data Documentation

6.38.2.1 _entries UniqueNameListEntry [] Infohazard.Core.UniqueNameList._entries [private] (Serialized) All unique name assets in this list.

6.38.3 Property Documentation

6.38.3.1 Entries IReadOnlyList<UniqueNameListEntry> Infohazard.Core.UniqueNameList.Entries [get]

All unique name assets in this list.

The documentation for this class was generated from the following file:

• Runtime/UniqueName/UniqueNameList.cs

6.39 Infohazard.Core.UniqueNameListEntry Class Reference

A unique name asset, usable by a UniqueNamedObject.

6.39.1 Detailed Description

A unique name asset, usable by a UniqueNamedObject.

The asset's name is the unique name that will be referenced. UniqueNameListEntries should be created via a UniqueNameList.

The documentation for this class was generated from the following file:

Runtime/UniqueName/UniqueNameListEntry.cs