Chapter 9: Virtual Memory

Chapter 9: Virtual Memory

- □ Background
- Demand Paging
- □ Copy-on-Write
- □ Page Replacement
- □ Allocation of Frames
- □ Thrashing
- □ Memory-Mapped Files
- □ Allocating Kernel Memory
- Other Considerations
- □ Operating-System Examples

Objectives To describe the benefits of a virtual memory system To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames To discuss the principle of the working-set model To examine the relationship between shared memory and memory-mapped files To explore how kernel memory is managed

Background


- ☐ Code needs to be in memory to execute, but entire program rarely used
 - ☐ Error code, unusual routines, large data structures
- ☐ Entire program code not needed at same time
- □ Consider ability to execute partially-loaded program
 - ☐ Program no longer constrained by limits of physical memory
 - □ Each program takes less memory while running -> more programs run at the same time
 - ▶ Increased CPU utilization and throughput with no increase in response time or turnaround time
 - □ Less I/O needed to load or swap programs into memory -> each user program runs faster

Background (Cont.)

- ☐ **Virtual memory** separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - □ Less I/O needed to load or swap processes

Background (Cont.)


- ☐ Virtual address space logical view of how process is stored in memory
 - □ Usually start at address 0, contiguous addresses until end of space
 - ☐ Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation





Virtual-address Space

Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up" Maximizes address space between the two is hole.

- - No physical memory needed until heap or stack grows to a given new page
- ☐ Enables **sparse** address spaces with holes left for growth, dynamically linked libraries, etc.
- □ System libraries shared via mapping into virtual address space
- □ Shared memory by mapping pages read-write into virtual address space
- ☐ Pages can be shared during fork(), speeding process creation








Basic Concepts


- □ With swapping, pager guesses which pages will be used before swapping out again
- ☐ Instead, pager brings in only those pages into memory
- □ How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- ☐ If pages needed are already **memory resident**
 - □ No difference from non demand-paging
- ☐ If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code

Valid-Invalid Bit

- □ With each table entry valid-invalid bit is associated page $(\mathbf{v} \Rightarrow \text{in-memory} - \text{memory} \text{ resident}, \mathbf{i} \Rightarrow \text{not-in-memory})$
- ☐ Initially valid—invalid bit is set to i on all entries
- ☐ Example of a page table snapshot:



 \square During MMU address translation, if valid-invalid bit in page table entry is $\mathbf{i} \Rightarrow$ page fault




Page Fault

☐ If there is a reference to a page, first reference to that page will trap to operating system:

page fault

- 1. Operating system looks at another table to decide:
 - □ Invalid reference ⇒ abort
 - Just not in memory
- 2. Find free frame
- 3. Swap page into frame via scheduled disk operation
- 4. Reset tables to indicate page now in memory Set validation bit = \mathbf{v}
- 5. Restart the instruction that caused the page fault




Aspects of Demand Paging

- ☐ Extreme case start process with *no* pages in memory
 - OS sets instruction pointer to first instruction of process, non-memory-resident page fault
 - And for every other process pages on first access
 - Pure demand paging
- ☐ Actually, a given instruction could access multiple pages -> multiple page faults
 - □ Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - □ Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - □ Page table with valid / invalid bit
 - ☐ Secondary memory (swap device with **swap space**)
 - Instruction restart

Instruction Restart

- □ Consider an instruction that could access several different locations
 - □ block move



- □ auto increment/decrement location
- ☐ Restart the whole operation?
 - What if source and destination overlap?

Performance of Demand Paging

- ☐ Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - 2. Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12.Restore the user registers, process state, and new page table, and then resume the interrupted instruction

Performance of Demand Paging (Cont.)

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - □ Read the page lots of time
 - ☐ Restart the process again just a small amount of time
- □ Page Fault Rate $0 \le p \le 1$
 - \Box if p = 0 no page faults
 - \Box if p = 1, every reference is a fault
- ☐ Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in )
```

Demand Paging Example

- ☐ Memory access time = 200 nanoseconds
- ☐ Average page-fault service time = 8 milliseconds
- □ EAT = $(1 p) \times 200 + p$ (8 milliseconds) = $(1 - p \times 200 + p \times 8,000,000$ = $200 + p \times 7,999,800$
- $\hfill \square$ If one access out of 1,000 causes a page fault, then

EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!


- ☐ If want performance degradation < 10 percent
 - □ 220 > 200 + 7,999,800 x p 20 > 7,999,800 x p
 - □ p < .0000025
 - □ < one page fault in every 400,000 memory accesses


Demand Paging Optimizations

- ☐ Swap space I/O faster than file system I/O even if on the same device
 - ☐ Swap allocated in larger chunks, less management needed than file system
- ☐ Copy entire process image to swap space at process load time
 - ☐ Then page in and out of swap space
 - □ Used in older BSD Unix
- □ Demand page in from program binary on disk, but discard rather than paging out when freeing frame
 - Used in Solaris and current BSD
 - ☐ Still need to write to swap space
 - Pages not associated with a file (like stack and heap) anonymous memory
 - ▶ Pages modified in memory but not yet written back to the file system
- □ Mobile systems
 - ☐ Typically don't support swapping
 - □ Instead, demand page from file system and reclaim read-only pages (such as code)

Copy-on-Write

- □ **Copy-on-Write** (COW) allows both parent and child processes to initially **share** the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- □ COW allows more efficient process creation as only modified pages are copied
- ☐ In general, free pages are allocated from a **pool** of **zero-fill-on-demand** pages
 - Pool should always have free frames for fast demand page execution
 - ▶ Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- U vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
 - ☐ Designed to have child call exec()
 - Very efficient






What Happens if There is no Free Frame? □ Used up by process pages □ Also in demand from the kernel, I/O buffers, etc □ How much to allocate to each? □ Page replacement – find some page in memory, but not really in use, page it out □ Algorithm – terminate? swap out? replace the page? □ Performance – want an algorithm which will result in minimum number of page faults □ Same page may be brought into memory several times

Page Replacement


- ☐ Prevent **over-allocation** of memory by modifying page-fault service routine to include page replacement
- ☐ Use **modify** (**dirty**) **bit** to reduce overhead of page transfers only modified pages are written to disk
- □ Page replacement completes separation between logical memory and physical memory large virtual memory can be provided on a smaller physical memory



Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a **victim** frame
 - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap


Note now potentially 2 page transfers for page fault – increasing EAT





Page and Frame Replacement Algorithms


- ☐ Frame-allocation algorithm determines
 - □ How many frames to give each process
 - □ Which frames to replace
- □ Page-replacement algorithm
 - □ Want lowest page-fault rate on both first access and re-access
- □ Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- ☐ In all our examples, the **reference string** of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1










Least Recently Used (LRU) Algorithm

- □ Use past knowledge rather than future
- ☐ Replace page that has not been used in the most amount of time
- ☐ Associate time of last use with each page

reference string




page frames

- ☐ 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- □ But how to implement?


LRU Algorithm (Cont.)

- □ Counter implementation
 - □ Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - □ When a page needs to be changed, look at the counters to find smallest value
 - Search through table needed
- Stack implementation
 - ☐ Keep a stack of page numbers in a double link form:
 - □ Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement
- ☐ LRU and OPT are cases of **stack algorithms** that don't have Belady's Anomaly




LRU Approximation Algorithms

- ☐ LRU needs special hardware and still slow
- □ Reference bit
 - □ With each page associate a bit, initially = 0
 - □ When page is referenced bit set to 1
 - □ Replace any with reference bit = 0 (if one exists)
 - ▶ We do not know the order, however
- □ Second-chance algorithm
 - ☐ Generally FIFO, plus hardware-provided reference bit
 - □ Clock replacement
 - ☐ If page to be replaced has
 - Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules



Enhanced Second-Chance Algorithm

- ☐ Improve algorithm by using reference bit and modify bit (if available) in concert
- ☐ Take ordered pair (reference, modify)
- 1. (0, 0) neither recently used not modified best page to replace
- 2. (0, 1) not recently used but modified not quite as good, must write out before replacement
- 3. (1, 0) recently used but clean probably will be used again soon
- 4. (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- ☐ When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
 - ☐ Might need to search circular queue several times



Page-Buffering Algorithms

- ☐ Keep a pool of free frames, always
 - ☐ Then frame available when needed, not found at fault time
 - ☐ Read page into free frame and select victim to evict and add to free pool
 - □ When convenient, evict victim
- ☐ Possibly, keep list of modified pages
 - □ When backing store otherwise idle, write pages there and set to non-dirty
- □ Possibly, keep free frame contents intact and note what is in them
 - ☐ If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected

Applications and Page Replacement All of these algorithms have OS guessing about future page access Some applications have better knowledge – i.e. databases Memory intensive applications can cause double buffering OS keeps copy of page in memory as I/O buffer Application keeps page in memory for its own work Operating system can given direct access to the disk, getting out of the way of the applications Raw disk mode Bypasses buffering, locking, etc

Allocation of Frames | Each process needs minimum number of frames | Example: IBM 370 – 6 pages to handle SS MOVE instruction: | instruction is 6 bytes, might span 2 pages | 2 pages to handle from | 2 pages to handle to | Maximum of course is total frames in the system | Two major allocation schemes | fixed allocation | priority allocation

Fixed Allocation

- □ Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - ☐ Keep some as free frame buffer pool
- □ Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$-s_i = \text{size}$$
 of process p_i $m = 64$

$$-S = \sum_{i} S_{i}$$

$$-m = \text{total}$$
 number of frames $s_2 = 127$

-
$$a_i$$
 = allocation for $p_i = \frac{s_i}{S} \times m$ $a_1 = \frac{10}{137} \times 62 \approx 4$ $a_2 = \frac{127}{137} \times 62 \approx 57$

Priority Allocation

- □ Use a proportional allocation scheme using priorities rather than size
- \square If process P_i generates a page fault,
 - □ select for replacement one of its frames
 - □ select for replacement a frame from a process with lower priority number

Global vs. Local Allocation


- ☐ **Global replacement** process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common
- □ **Local replacement** each process selects from only its own set of allocated frames
 - □ More consistent per-process performance
 - But possibly underutilized memory

Non-Uniform Memory Access

- □ So far all memory accessed equally
- ☐ Many systems are **NUMA** speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- □ Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled
 - And modifying the scheduler to schedule the thread on the same system board when possible
 - Solved by Solaris by creating Igroups
 - Structure to track CPU / Memory low latency groups
 - Used my schedule and pager
 - ▶ When possible schedule all threads of a process and allocate all memory for that process within the Igroup


Thrashing

- ☐ If a process does not have "enough" pages, the page-fault rate is very high
 - □ Page fault to get page
 - □ Replace existing frame
 - ☐ But quickly need replaced frame back
 - ☐ This leads to:
 - ▶ Low CPU utilization
 - ▶ Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
- \square Thrashing = a process is busy swapping pages in and out



Demand Paging and Thrashing

- □ Why does demand paging work?
 - **Locality model**
 - Process migrates from one locality to another
 - Localities may overlap
- □ Why does thrashing occur?
 - Σ size of locality > total memory size
 - □ Limit effects by using local or priority page replacement



Working-Set Model

- $\square \ \Delta \equiv \text{working-set window} \equiv \text{a fixed number of page references}$
 - Example: 10,000 instructions
- \square WSS_i (working set of Process P_i) =
 - total number of pages referenced in the most recent Δ (varies in time)
 - $\hfill\Box$ if Δ too small will not encompass entire locality
 - $\hfill\Box$ if Δ too large will encompass several localities
 - \Box if $\Delta = \infty \Rightarrow$ will encompass entire program
- \Box $D = \Sigma WSS_i \equiv \text{total demand frames}$
 - □ Approximation of locality
- □ if $D > m \Rightarrow$ Thrashing
- □ Policy if *D* > m, then suspend or swap out one of the processes page reference table


... 2 6 1 5 7 7 7 7 5 1 6 2 3 4 1 2 3 4 4 4 3 4 3 4 4 4 1 3 2 3 4 4 4 3 4 4 4 . . . $\Delta \qquad \qquad \Delta \qquad$

Keeping Track of the Working Set

- ☐ Approximate with interval timer + a reference bit
- □ Example: Δ = 10,000
 - □ Timer interrupts after every 5000 time units
 - □ Keep in memory 2 bits for each page
 - □ Whenever a timer interrupts copy and sets the values of all reference bits to 0
 - $\hfill\Box$ If one of the bits in memory = 1 \Rightarrow page in working set
- □ Why is this not completely accurate?
- ☐ Improvement = 10 bits and interrupt every 1000 time units


Page-Fault Frequency

- □ More direct approach than WSS
- □ Establish "acceptable" **page-fault frequency** (**PFF**) rate and use local replacement policy
 - □ If actual rate too low, process loses frame
 - □ If actual rate too high, process gains frame



Working Sets and Page Fault Rates

- n Direct relationship between working set of a process and its page-fault rate
- n Working set changes over time
- n Peaks and valleys over time





Memory-Mapped Files

- ☐ Memory-mapped file I/O allows file I/O to be treated as routine memory access by **mapping** a disk block to a page in memory
- □ A file is initially read using demand paging
 - ☐ A page-sized portion of the file is read from the file system into a physical page
 - Subsequent reads/writes to/from the file are treated as ordinary memory accesses
- ☐ Simplifies and speeds file access by driving file I/O through memory rather than read() and write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared
- ☐ But when does written data make it to disk?
 - ☐ Periodically and / or at file close() time
 - ☐ For example, when the pager scans for dirty pages

Memory-Mapped File Technique for all I/O

- □ Some OSes uses memory mapped files for standard I/O
- ☐ Process can explicitly request memory mapping a file via mmap() system call
 - □ Now file mapped into process address space
- ☐ For standard I/O (open(), read(), write(), close()), mmap anyway
 - ☐ But map file into kernel address space
 - ☐ Process still does read() and write()
 - Copies data to and from kernel space and user space
 - ☐ Uses efficient memory management subsystem
 - Avoids needing separate subsystem
- ☐ COW can be used for read/write non-shared pages
- Memory mapped files can be used for shared memory (although again via separate system calls)





Shared Memory in Windows API


- ☐ First create a **file mapping** for file to be mapped
 - ☐ Then establish a view of the mapped file in process's virtual address space
- □ Consider producer / consumer
 - □ Producer create shared-memory object using memory mapping features
 - □ Open file via CreateFile(), returning a HANDLE
 - ☐ Create mapping via CreateFileMapping() creating a named shared-memory object
 - ☐ Create view via MapViewOfFile()
- □ Sample code in Textbook

Allocating Kernel Memory

- □ Treated differently from user memory
- □ Often allocated from a free-memory pool
 - ☐ Kernel requests memory for structures of varying sizes
 - □ Some kernel memory needs to be contiguous
 - ▶ I.e. for device I/O


Buddy System

- ☐ Allocates memory from fixed-size segment consisting of physically-contiguous pages
- ☐ Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - □ Request rounded up to next highest power of 2
 - □ When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- ☐ For example, assume 256KB chunk available, kernel requests 21KB
 - □ Split into A_{L and} A_R of 128KB each
 - → One further divided into B_L and B_R of 64KB
 - One further into C₁ and C_R of 32KB each one used to satisfy request
- ☐ Advantage quickly **coalesce** unused chunks into larger chunk
- □ Disadvantage fragmentation



Slab Allocator

- □ Alternate strategy
- ☐ **Slab** is one or more physically contiguous pages
- ☐ Cache consists of one or more slabs
- ☐ Single cache for each unique kernel data structure
 - □ Each cache filled with **objects** instantiations of the data structure
- □ When cache created, filled with objects marked as free
- ☐ When structures stored, objects marked as used
- ☐ If slab is full of used objects, next object allocated from empty slab
 - □ If no empty slabs, new slab allocated
- ☐ Benefits include no fragmentation, fast memory request satisfaction



Slab Allocator in Linux

- ☐ For example process descriptor is of type struct task struct
- □ Approx 1.7KB of memory
- ☐ New task -> allocate new struct from cache
 - □ Will use existing free struct task struct
- ☐ Slab can be in three possible states
 - 1. Full all used
 - 2. Empty all free
 - 3. Partial mix of free and used
- □ Upon request, slab allocator
 - 1. Uses free struct in partial slab
 - 2. If none, takes one from empty slab
 - 3. If no empty slab, create new empty

Slab Allocator in Linux (Cont.)

- □ Slab started in Solaris, now wide-spread for both kernel mode and user memory in various OSes
- ☐ Linux 2.2 had SLAB, now has both SLOB and SLUB allocators
 - □ SLOB for systems with limited memory
 - ▶ Simple List of Blocks maintains 3 list objects for small, medium, large objects
 - □ SLUB is performance-optimized SLAB removes per-CPU queues, metadata stored in page structure

Other Considerations -- Prepaging

- Pre-paging
 - ☐ To reduce the large number of page faults that occurs at process startup
 - Pre-page all or some of the pages a process will need, before they are referenced
 - ☐ But if pre-paged pages are unused, I/O and memory was wasted
 - \square Assume s pages are pre-paged and α of the pages is used
 - Is cost of $s * \alpha$ save pages faults > or < than the cost of pre-paging $s * (1-\alpha)$ unnecessary pages?
 - → α near zero ⇒ pre-paging loses

Other Issues - Page Size

- □ Sometimes OS designers have a choice
 - Especially if running on custom-built CPU
- ☐ Page size selection must take into consideration:
 - Fragmentation
 - □ Page table size
 - Resolution
 - □ I/O overhead
 - Number of page faults
 - Locality
 - ☐ TLB size and effectiveness
- \square Always power of 2, usually in the range 2^{12} (4,096 bytes) to 2^{22} (4,194,304 bytes)
- □ On average, growing over time

Other Issues - TLB Reach

- □ TLB Reach The amount of memory accessible from the TLB
- ☐ TLB Reach = (TLB Size) X (Page Size)
- ☐ Ideally, the working set of each process is stored in the TLB
 - □ Otherwise there is a high degree of page faults
- □ Increase the Page Size
 - ☐ This may lead to an increase in fragmentation as not all applications require a large page size
- □ Provide Multiple Page Sizes
 - ☐ This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

Other Issues – Program Structure

- □ Program structure
 - ☐ int[128,128] data;
 - ☐ Each row is stored in one page
 - □ Program 1

for
$$(j = 0; j < 128; j++)$$

for $(i = 0; i < 128; i++)$
data $[i,j] = 0;$


 $128 \times 128 = 16,384$ page faults

□ Program 2

128 page faults


Other Issues - I/O interlock

- □ **I/O Interlock** Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm
- □ **Pinning** of pages to lock into memory



Operating System Examples

- □ Windows
- □ Solaris



Solaris
□ Maintains a list of free pages to assign faulting processes
□ Lotsfree – threshold parameter (amount of free memory) to begin paging
□ Desfree – threshold parameter to increasing paging
☐ Minfree – threshold parameter to being swapping
□ Paging is performed by pageout process
□ Pageout scans pages using modified clock algorithm
☐ Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
Pageout is called more frequently depending upon the amount of free memory available
□ Priority paging gives priority to process code pages

