# tarfile — Read and write tar archive files

Source code: Lib/tarfile.py

The tarfile module makes it possible to read and write tar archives, including those using gzip, bz2 and lzma compression. Use the zipfile module to read or write .zip files, or the higher-level functions in shutil.

### Some facts and figures:

- reads and writes gzip, bz2 and lzma compressed archives if the respective modules are available.
- read/write support for the POSIX.1-1988 (ustar) format.
- read/write support for the GNU tar format including longname and longlink extensions, read-only support for all variants of the sparse extension including restoration of sparse files.
- read/write support for the POSIX.1-2001 (pax) format.
- handles directories, regular files, hardlinks, symbolic links, fifos, character devices and block devices and is able to acquire and restore file information like timestamp, access permissions and owner.

Changed in version 3.3: Added support for 1zma compression.

tarfile. open(name=None, mode='r', fileobj=None, bufsize=10240, \*\*kwargs)

Return a TarFile object for the pathname *name*. For detailed information on TarFile objects and the keyword arguments that are allowed, see TarFile Objects.

*mode* has to be a string of the form 'filemode[:compression]', it defaults to 'r'. Here is a full list of mode combinations:

mode	action
'r' or 'r:*'	Open for reading with transparent compression (recommended).
'r:'	Open for reading exclusively without compression.
'r:gz'	Open for reading with gzip compression.
'r:bz2'	Open for reading with bzip2 compression.
'r:xz'	Open for reading with Izma compression.
'x' or 'x:'	Create a tarfile exclusively without compression. Raise an FileExistsError exception if it already exists.

mode	action
'x:gz'	Create a tarfile with gzip compression. Raise an FileExistsError exception if it already exists.
'x:bz2'	Create a tarfile with bzip2 compression. Raise an FileExistsError exception if it already exists.
'x:xz'	Create a tarfile with Izma compression. Raise an FileExistsError exception if it already exists.
'a' or 'a:'	Open for appending with no compression. The file is created if it does not exist.
'w' or 'w:'	Open for uncompressed writing.
'w:gz'	Open for gzip compressed writing.
'w:bz2'	Open for bzip2 compressed writing.
'w:xz'	Open for Izma compressed writing.

Note that 'a:gz', 'a:bz2' or 'a:xz' is not possible. If *mode* is not suitable to open a certain (compressed) file for reading, ReadError is raised. Use *mode* 'r' to avoid this. If a compression method is not supported, CompressionError is raised.

If *fileobj* is specified, it is used as an alternative to a file object opened in binary mode for *name*. It is supposed to be at position 0.

For modes 'w:gz', 'r:gz', 'w:bz2', 'r:bz2', 'x:gz', 'x:bz2', tarfile.open() accepts the keyword argument *compresslevel* (default 9) to specify the compression level of the file.

For special purposes, there is a second format for *mode*: 'filemode|[compression]'. tarfile.open() will return a TarFile object that processes its data as a stream of blocks. No random seeking will be done on the file. If given, *fileobj* may be any object that has a read() or write() method (depending on the *mode*). *bufsize* specifies the blocksize and defaults to 20 \* 512 bytes. Use this variant in combination with e.g. sys.stdin, a socket file object or a tape device. However, such a TarFile object is limited in that it does not allow random access, see Examples. The currently possible modes:

Mode	Action
'r *'	Open a <i>stream</i> of tar blocks for reading with transparent compression.
'r '	Open a <i>stream</i> of uncompressed tar blocks for reading.
'r gz'	Open a gzip compressed <i>stream</i> for reading.
'r bz2'	Open a bzip2 compressed <i>stream</i> for reading.
'r xz'	Open an Izma compressed <i>stream</i> for reading.

Mode	Action
'w '	Open an uncompressed <i>stream</i> for writing.
'w gz'	Open a gzip compressed <i>stream</i> for writing.
'w bz2'	Open a bzip2 compressed <i>stream</i> for writing.
'w xz'	Open an Izma compressed <i>stream</i> for writing.

Changed in version 3.5: The 'x' (exclusive creation) mode was added.

Changed in version 3.6: The name parameter accepts a path-like object.

### class tarfile. TarFile

Class for reading and writing tar archives. Do not use this class directly: use tarfile.open() instead. See TarFile Objects.

## tarfile.is\_tarfile(name)

Return True if *name* is a tar archive file, that the tarfile module can read.

The tarfile module defines the following exceptions:

### exception tarfile. TarError

Base class for all tarfile exceptions.

### exception tarfile. ReadError

Is raised when a tar archive is opened, that either cannot be handled by the tarfile module or is somehow invalid.

# exception tarfile. CompressionError

Is raised when a compression method is not supported or when the data cannot be decoded properly.

### exception tarfile. StreamError

Is raised for the limitations that are typical for stream-like TarFile objects.

### exception tarfile. ExtractError

Is raised for *non-fatal* errors when using TarFile.extract(), but only if TarFile.errorlevel == 2.

# exception tarfile.HeaderError

Is raised by TarInfo.frombuf() if the buffer it gets is invalid.

The following constants are available at the module level:

### tarfile. **ENCODING**

The default character encoding: 'utf-8' on Windows, the value returned by sys.getfilesystemencoding() otherwise.

Each of the following constants defines a tar archive format that the tarfile module is able to create. See section Supported tar formats for details.

### tarfile. USTAR FORMAT

POSIX.1-1988 (ustar) format.

### tarfile. GNU FORMAT

GNU tar format.

### tarfile. PAX\_FORMAT

POSIX.1-2001 (pax) format.

### tarfile. **DEFAULT FORMAT**

The default format for creating archives. This is currently PAX\_FORMAT.

Changed in version 3.8: The default format for new archives was changed to PAX\_FORMAT from GNU FORMAT.

### See also:

### Module zipfile

Documentation of the zipfile standard module.

### **Archiving operations**

Documentation of the higher-level archiving facilities provided by the standard shutil module.

### **GNU tar manual, Basic Tar Format**

Documentation for tar archive files, including GNU tar extensions.

# TarFile Objects

The TarFile object provides an interface to a tar archive. A tar archive is a sequence of blocks. An archive member (a stored file) is made up of a header block followed by data blocks. It is possible to store a file in a tar archive several times. Each archive member is represented by a TarInfo object, see TarInfo Objects for details.

A TarFile object can be used as a context manager in a with statement. It will automatically be closed when the block is completed. Please note that in the event of an exception an archive opened for writing will not be finalized; only the internally used file object will be closed. See the Examples section for a use case.

New in version 3.2: Added support for the context management protocol.

class tarfile. TarFile(name=None, mode='r', fileobj=None, format=DEFAULT\_FORMAT, tarinfo=TarInfo, dereference=False, ignore\_zeros=False, encoding=ENCODING, errors='surrogateescape', pax\_headers=None, debug=0, errorlevel=0)

All following arguments are optional and can be accessed as instance attributes as well.

name is the pathname of the archive. name may be a path-like object. It can be omitted if fileobj is given. In this case, the file object's name attribute is used if it exists.

mode is either 'r' to read from an existing archive, 'a' to append data to an existing file, 'w' to create a new file overwriting an existing one, or 'x' to create a new file only if it does not already exist.

If *fileobj* is given, it is used for reading or writing data. If it can be determined, *mode* is overridden by *fileobj*'s mode. *fileobj* will be used from position 0.

**Note:** *fileobj* is not closed, when TarFile is closed.

format controls the archive format for writing. It must be one of the constants USTAR\_FORMAT, GNU\_FORMAT or PAX\_FORMAT that are defined at module level. When reading, format will be automatically detected, even if different formats are present in a single archive.

The tarinfo argument can be used to replace the default TarInfo class with a different one.

If *dereference* is False, add symbolic and hard links to the archive. If it is True, add the content of the target files to the archive. This has no effect on systems that do not support symbolic links.

If *ignore\_zeros* is False, treat an empty block as the end of the archive. If it is True, skip empty (and invalid) blocks and try to get as many members as possible. This is only useful for reading concatenated or damaged archives.

debug can be set from 0 (no debug messages) up to 3 (all debug messages). The messages are written to sys.stderr.

If errorlevel is 0, all errors are ignored when using TarFile.extract(). Nevertheless, they appear as error messages in the debug output, when debugging is enabled. If 1, all fatal errors are raised as OSError exceptions. If 2, all non-fatal errors are raised as TarError exceptions as well.

The *encoding* and *errors* arguments define the character encoding to be used for reading or writing the archive and how conversion errors are going to be handled. The default settings will work for most users. See section Unicode issues for in-depth information.

The *pax\_headers* argument is an optional dictionary of strings which will be added as a pax global header if *format* is PAX\_FORMAT.

Changed in version 3.2: Use 'surrogateescape' as the default for the errors argument.

Changed in version 3.5: The 'x' (exclusive creation) mode was added.

Changed in version 3.6: The name parameter accepts a path-like object.

# classmethod TarFile.open(...)

Alternative constructor. The tarfile.open() function is actually a shortcut to this classmethod.

## TarFile.getmember(name)

Return a TarInfo object for member *name*. If *name* can not be found in the archive, KeyError is raised.

**Note:** If a member occurs more than once in the archive, its last occurrence is assumed to be the most up-to-date version.

# TarFile.getmembers()

Return the members of the archive as a list of TarInfo objects. The list has the same order as the members in the archive.

# TarFile.getnames()

Return the members as a list of their names. It has the same order as the list returned by getmembers().

# TarFile.list(verbose=True, \*, members=None)

Print a table of contents to sys.stdout. If *verbose* is False, only the names of the members are printed. If it is True, output similar to that of **Is -I** is produced. If optional *members* is given, it must be a subset of the list returned by getmembers().

Changed in version 3.5: Added the members parameter.

# TarFile.next()

Return the next member of the archive as a TarInfo object, when TarFile is opened for reading. Return None if there is no more available.

# TarFile. extractall(path=".", members=None, \*, numeric\_owner=False)

Extract all members from the archive to the current working directory or directory *path*. If optional *members* is given, it must be a subset of the list returned by <code>getmembers()</code>. Directory information like owner, modification time and permissions are set after all members have been extracted. This is done to work around two problems: A directory's modification time is reset each time a file is created in it. And, if a directory's permissions do not allow writing, extracting files to it will fail.

If *numeric\_owner* is True, the uid and gid numbers from the tarfile are used to set the owner/group for the extracted files. Otherwise, the named values from the tarfile are used.

**Warning:** Never extract archives from untrusted sources without prior inspection. It is possible that files are created outside of *path*, e.g. members that have absolute filenames starting with "/" or filenames with two dots "..".

Changed in version 3.5: Added the numeric\_owner parameter.

Changed in version 3.6: The path parameter accepts a path-like object.

### TarFile. extract(member, path="", set\_attrs=True, \*, numeric\_owner=False)

Extract a member from the archive to the current working directory, using its full name. Its file information is extracted as accurately as possible. *member* may be a filename or a TarInfo object. You can specify a different directory using *path*. *path* may be a path-like object. File attributes (owner, mtime, mode) are set unless *set\_attrs* is false.

If *numeric\_owner* is True, the uid and gid numbers from the tarfile are used to set the owner/group for the extracted files. Otherwise, the named values from the tarfile are used.

**Note:** The extract() method does not take care of several extraction issues. In most cases you should consider using the extractall() method.

**Warning:** See the warning for extractall().

Changed in version 3.2: Added the set attrs parameter.

Changed in version 3.5: Added the numeric owner parameter.

Changed in version 3.6: The path parameter accepts a path-like object.

### TarFile. extractfile(member)

Extract a member from the archive as a file object. *member* may be a filename or a TarInfo object. If *member* is a regular file or a link, an io.BufferedReader object is returned. Otherwise, None is returned.

Changed in version 3.3: Return an io.BufferedReader object.

# TarFile. add(name, arcname=None, recursive=True, \*, filter=None)

Add the file *name* to the archive. *name* may be any type of file (directory, fifo, symbolic link, etc.). If given, *arcname* specifies an alternative name for the file in the archive. Directories are added recursively by default. This can be avoided by setting *recursive* to False. Recursion adds entries in sorted order. If *filter* is given, it should be a function that takes a TarInfo object argument and returns the changed TarInfo object. If it instead returns None the TarInfo object will be excluded from the archive. See Examples for an example.

Changed in version 3.2: Added the filter parameter.

Changed in version 3.7: Recursion adds entries in sorted order.

```
TarFile. addfile(tarinfo, fileobj=None)
```

Add the TarInfo object *tarinfo* to the archive. If *fileobj* is given, it should be a binary file, and tarinfo.size bytes are read from it and added to the archive. You can create TarInfo objects directly, or by using gettarinfo().

```
TarFile. gettarinfo(name=None, arcname=None, fileobj=None)
```

Create a TarInfo object from the result of os.stat() or equivalent on an existing file. The file is either named by *name*, or specified as a file object *fileobj* with a file descriptor. *name* may be a path-like object. If given, *arcname* specifies an alternative name for the file in the archive, otherwise, the name is taken from *fileobj*'s name attribute, or the *name* argument. The name should be a text string.

You can modify some of the TarInfo's attributes before you add it using addfile(). If the file object is not an ordinary file object positioned at the beginning of the file, attributes such as size may need modifying. This is the case for objects such as GzipFile. The name may also be modified, in which case arcname could be a dummy string.

Changed in version 3.6: The name parameter accepts a path-like object.

```
TarFile.close()
```

Close the TarFile. In write mode, two finishing zero blocks are appended to the archive.

# TarFile. pax\_headers

A dictionary containing key-value pairs of pax global headers.

# TarInfo Objects

A TarInfo object represents one member in a TarFile. Aside from storing all required attributes of a file (like file type, size, time, permissions, owner etc.), it provides some useful methods to determine its type. It does *not* contain the file's data itself.

TarInfo objects are returned by TarFile's methods getmember(), getmembers() and gettarinfo().

```
class tarfile. TarInfo(name="")
```

Create a TarInfo object.

classmethod TarInfo.frombuf(buf, encoding, errors)

Create and return a TarInfo object from string buffer buf.

Raises HeaderError if the buffer is invalid.

classmethod TarInfo. fromtarfile(tarfile)

Read the next member from the TarFile object tarfile and return it as a TarInfo object.

# TarInfo. **tobuf**(format=DEFAULT\_FORMAT, encoding=ENCODING, errors='surrogateescape')

Create a string buffer from a TarInfo object. For information on the arguments see the constructor of the TarFile class.

Changed in version 3.2: Use 'surrogateescape' as the default for the errors argument.

A TarInfo object has the following public data attributes:

#### TarInfo. name

Name of the archive member.

### TarInfo. **Size**

Size in bytes.

### TarInfo. mtime

Time of last modification.

#### TarInfo. mode

Permission bits.

### TarInfo. type

File type. *type* is usually one of these constants: REGTYPE, AREGTYPE, LNKTYPE, SYMTYPE, DIRTYPE, FIFOTYPE, CONTTYPE, CHRTYPE, BLKTYPE, GNUTYPE\_SPARSE. To determine the type of a TarInfo object more conveniently, use the is\*() methods below.

### TarInfo. linkname

Name of the target file name, which is only present in TarInfo objects of type LNKTYPE and SYMTYPE.

### TarInfo. uid

User ID of the user who originally stored this member.

### TarInfo.gid

Group ID of the user who originally stored this member.

### TarInfo. uname

User name.

### TarInfo.gname

Group name.

# TarInfo.pax\_headers

A dictionary containing key-value pairs of an associated pax extended header.

A TarInfo object also provides some convenient query methods:

```
TarInfo.isfile()
```

Return True if the Tarinfo object is a regular file.

# TarInfo.isreg()

Same as isfile().

# TarInfo.isdir()

Return True if it is a directory.

# TarInfo.issym()

Return True if it is a symbolic link.

## TarInfo.islnk()

Return True if it is a hard link.

# TarInfo.ischr()

Return True if it is a character device.

## TarInfo.isblk()

Return True if it is a block device.

# TarInfo. isfifo()

Return True if it is a FIFO.

# TarInfo.isdev()

Return True if it is one of character device, block device or FIFO.

# Command-Line Interface

New in version 3.4.

The tarfile module provides a simple command-line interface to interact with tar archives.

If you want to create a new tar archive, specify its name after the -c option and then list the filename(s) that should be included:

```
$ python -m tarfile -c monty.tar spam.txt eggs.txt
```

Passing a directory is also acceptable:

```
$ python -m tarfile -c monty.tar life-of-brian_1979/
```

If you want to extract a tar archive into the current directory, use the -e option:

```
$ python -m tarfile -e monty.tar
```

You can also extract a tar archive into a different directory by passing the directory's name:

```
$ python -m tarfile -e monty.tar other-dir/
```

For a list of the files in a tar archive, use the -1 option:

```
$ python -m tarfile -l monty.tar
```

# Command-line options

```
-l <tarfile>
-list <tarfile>
List files in a tarfile.

-c <tarfile> <source1> ... <sourceN>
--create <tarfile> <source1> ... <sourceN>
Create tarfile from source files.

-e <tarfile> [<output_dir>]
--extract <tarfile> [<output_dir>]
Extract tarfile into the current directory if output_dir is not specified.

-t <tarfile>
--test <tarfile>
--test <tarfile>
Test whether the tarfile is valid or not.

-v, --verbose
```

# **Examples**

Verbose output.

How to extract an entire tar archive to the current working directory:

```
import tarfile
tar = tarfile.open("sample.tar.gz")
tar.extractall()
tar.close()
```

How to extract a subset of a tar archive with TarFile.extractall() using a generator function instead of a list:

```
import os
import tarfile

def py_files(members):
    for tarinfo in members:
        if os.path.splitext(tarinfo.name)[1] == ".py":
            yield tarinfo

tar = tarfile.open("sample.tar.gz")
tar.extractall(members=py_files(tar))
tar.close()
```

How to create an uncompressed tar archive from a list of filenames:

```
import tarfile
tar = tarfile.open("sample.tar", "w")
for name in ["foo", "bar", "quux"]:
    tar.add(name)
tar.close()
```

The same example using the with statement:

```
import tarfile
with tarfile.open("sample.tar", "w") as tar:
   for name in ["foo", "bar", "quux"]:
        tar.add(name)
```

How to read a gzip compressed tar archive and display some member information:

```
import tarfile
tar = tarfile.open("sample.tar.gz", "r:gz")
for tarinfo in tar:
    print(tarinfo.name, "is", tarinfo.size, "bytes in size and is", end="")
    if tarinfo.isreg():
        print("a regular file.")
    elif tarinfo.isdir():
        print("a directory.")
    else:
        print("something else.")
tar.close()
```

How to create an archive and reset the user information using the *filter* parameter in TarFile.add():

```
import tarfile
def reset(tarinfo):
    tarinfo.uid = tarinfo.gid = 0
    tarinfo.uname = tarinfo.gname = "root"
    return tarinfo
tar = tarfile.open("sample.tar.gz", "w:gz")
```

```
tar.add("foo", filter=reset)
tar.close()
```

# Supported tar formats

There are three tar formats that can be created with the tarfile module:

- The POSIX.1-1988 ustar format (USTAR\_FORMAT). It supports filenames up to a length of at best 256 characters and linknames up to 100 characters. The maximum file size is 8 GiB. This is an old and limited but widely supported format.
- The GNU tar format (GNU\_FORMAT). It supports long filenames and linknames, files bigger than 8 GiB and sparse files. It is the de facto standard on GNU/Linux systems. tarfile fully supports the GNU tar extensions for long names, sparse file support is read-only.
- The POSIX.1-2001 pax format (PAX\_FORMAT). It is the most flexible format with virtually no limits. It supports long filenames and linknames, large files and stores pathnames in a portable way. Modern tar implementations, including GNU tar, bsdtar/libarchive and star, fully support extended pax features; some old or unmaintained libraries may not, but should treat pax archives as if they were in the universally-supported ustar format. It is the current default format for new archives.

It extends the existing *ustar* format with extra headers for information that cannot be stored otherwise. There are two flavours of pax headers: Extended headers only affect the subsequent file header, global headers are valid for the complete archive and affect all following files. All the data in a pax header is encoded in *UTF-8* for portability reasons.

There are some more variants of the tar format which can be read, but not created:

- The ancient V7 format. This is the first tar format from Unix Seventh Edition, storing only regular files and directories. Names must not be longer than 100 characters, there is no user/group name information. Some archives have miscalculated header checksums in case of fields with non-ASCII characters.
- The SunOS tar extended format. This format is a variant of the POSIX.1-2001 pax format, but is not compatible.

# Unicode issues

The tar format was originally conceived to make backups on tape drives with the main focus on preserving file system information. Nowadays tar archives are commonly used for file distribution and exchanging archives over networks. One problem of the original format (which is the basis of all other formats) is that there is no concept of supporting different character encodings. For example, an ordinary tar archive created on a *UTF-8* system cannot be read correctly on a *Latin-1* system if it contains non-*ASCII* characters. Textual metadata (like filenames, linknames, user/group names) will appear damaged. Unfortunately, there is no way to autodetect the

encoding of an archive. The pax format was designed to solve this problem. It stores non-ASCII metadata using the universal character encoding *UTF-8*.

The details of character conversion in tarfile are controlled by the *encoding* and *errors* keyword arguments of the TarFile class.

encoding defines the character encoding to use for the metadata in the archive. The default value is sys.getfilesystemencoding() or 'ascii' as a fallback. Depending on whether the archive is read or written, the metadata must be either decoded or encoded. If encoding is not set appropriately, this conversion may fail.

The *errors* argument defines how characters are treated that cannot be converted. Possible values are listed in section Error Handlers. The default scheme is 'surrogateescape' which Python also uses for its file system calls, see File Names, Command Line Arguments, and Environment Variables.

For PAX\_FORMAT archives (the default), *encoding* is generally not needed because all the metadata is stored using *UTF-8*. *encoding* is only used in the rare cases when binary pax headers are decoded or when strings with surrogate characters are stored.