Geographic Information Systems 2022-2023

Exercise 6 - Coordinate Reference System - ArcGIS

Introduction

GOALS OF THE EXERCISE

- Learn how to identify and define the CRS of a map.
- Understand how ArcGIS Pro manages different CRS in the same map
- · Project one gds from one CRS to another CRS
- Define a new CRS for a gds and solve projection issues

Source data

Download from Fenix the file Ex06_CRS.zip, which contains the following datasets:

- CntrCaptETRS89.shp point dataset with World Country Capital cities
- etrs89lcc.shp polygon dataset with World countries boundaries
- GlobalAdmCountriesWGS84.shp polygon dataset with World countries boundaries

1. Identify and define the CRS of a map.

- 1. Create a new ArcGIS Pro project
 - 1.1 . Add the folder with the extracted files to the newly created project with a folder connection. This can be done on the Catalog pane, or with tool "Add Folder" in the Insert tab.
- 2. Identify the current CRS of your map
 - 2.1. On the Contents pane, right-click on Map and select Properties. The entry "Coordinate Systems" shows your current CRS. Take note of the CRS, which is default for newly created maps.
 - 2.2. Still on Map properties, verify that you can create a list of favorite CRS.
 - 2.3. Add a new map to your project. Verify that the default CRS is WGS 1984 (EPSG: 3857)
- 3. Add the CntrCaptETRS89 gds to map
 - 3.1. On the Catalog pane, use the context menu of the gds to add it.
 - 3.2. What is the CRS of the added gds?
 - use the context menu of the layer to see its metainforation
 - 3.3. Check again the map's CRS. Did it change? Take note of its name.
- 4. Remark: the map's CRS always changes to the first added gds CRS!
- 5. Add the GlobalAdmCountriesWGS84 gds to the map

- 5.1. Take note of the CRS of this layer
- 5.2. Check the CRS of the map. Did it change?
- 5.3. **Remark**: ArcGIS Pro executed an "On the Fly" transformation ("on the fly" coordinate transformations OFT) to the project CRS; therefore, presently, visualization is done using EPSG 4258. However, the layers' CRS didn't change
- 6. Save your project.

2. Understand how ArcGIS Pro manages different CRS in the same map

- 1. Change the map's CRS
 - 1.1. Use the context menu of the map to change the map's CRS to WGS84 (EPSG: 4326)
 - 1.2. **Remark**: The ETRS89 and WGS84 are both geographic CRS (both use not projected coordinate systems lat/long in degrees).
 - 1.3. Would it be appropriate to change this map's CRS to a projected CRS?
- 2. Save your project.

3. Project one gds from one CRS to another CRS

- 1. Perform a gds coordinates transformation
 - 1.1. Export the layer CntrCaptETRS89 as a new gds named CntrCaptWGS84 (in a new geopackage dataOut file format under a DataOut folder) referenced to the WGS84 CRS (EPSG: 4326)
 - Use the Tab Environments in the export panel to select the CRS
 - 1.2. **Remark**: WGS84 and ETRS89 presently are datums coincident to within 1 meter.
- 2. Repeat the operation to create a new layer CntrCaptwGS84_v2 (in the same geopackage location), but using the tool Project (Data Management Tools)
- 3. It is not important to save the project now. Why?

4. Define a new CRS for a gds and solve projection issues

- 1. Add labels to the CntrCaptwGS84 layer to visualize the NAME_ASCI attribute values (use the green color).
- 2. Add labels to the GlobalAdmCountriesWGS84 layer to visualize the FIRST_NAME attribute values (use the black color).
- 3. Zoom in to your country region. Is the capital wrongly located?
- 4. Add the etrs89lcc gds to the project.
- 5. Zoom to the etrs89lcc layer.
 - 5.1. Hint: use the layer context menu.

- 6. Is the result satisfactory? Why? What is the problem?
- 7. Save the project
- 8. By default ArcGIS assigns the default project CRS to gds without CRS
 - 8.1. Check the current CRS of the layer etrs89lcc
- 9. Actually the etrs89lcc gds coordinates are referenced to the ETRS89 + Lambert Conic Conformal projection CRS ETRS89 / LCC Europe (EPSG: 3034)
- 10. To fix this problem, define the projection of the layer etrs89lcc
 - 10.1. Open the tool **Define Projection** (Data Management Tools)
 - 10.2. Select the layer and define the CRS (note: check the correct CRS through its EPSG ID)
- 11. Refresh and check is the layer is correctly projected
- 12. Save the project

5. Calculate point feature coordinates in different CRS

- 1. Create a new gds from the CntrCaptWGS84, containing only the following capitals: Lisbon, Madrid, Berlin and Amsterdam; this new gds must be referenced to the ETRS89 / LAEA Europe CRS (EPSG: 3035); name this new gds Europe4CaptETR89LAEA
 - 1.1. LEAE = Lambert Azimuthal Equal Area projection.
 - 1.2. The LEAE projection is appropriate to represent the whole EU and units are meters.
 - 1.3. It is possible to convert the GlobalAdmCountriesWGS84 gds to the EPSG 3035 but the result is not satisfactory try it later on ...
- Use the Add Geometry Attributes on the Attribute table of the layer to calculate new attributes named "latitude" and "longitude", and containing point-y and point-x values for the 4 capitals mentioned above referenced to the EPSG 3035
 - 2.1. Analyze the result, comparing to the LAT and LONG original values
- 3. Save the project

6. Calculate distances

- 1. Turn off all project layers but the Europe4CaptETRS89LAEA layer
- 2. Zoom to this layer extent
- 3. In order to calculate the distances between the 4 capitals, use the tool **Generate Origin Destination Links**
 - 3.1. As origin layer choose Europe4CaptETRS89LAEA.
 - 3.2. As destination layer select the same laye

- 3.3. Give the name CaptDistMatr to the output class
- 3.4. Do not select group fields
- 4. Open the attribute table of the newly created output class and take note of the distances between capitals
- 5. Analyze the result
- 6. Save the project
- 7. From the original, CntrCaptETRS89, export a new layer named EuropeanCaptETRS89, with only Lisbon, Madrid, Berlin and Amsterdam selected.
- 8. Use the tool **Generate Origin Destination Links** to calculate distances in this layer, over the ellipsoid GRS 1980 (the ETRS89 ellipsoid):
 - 8.1. Lisbon-Madrid: 504,327.702m
 - 8.2. Lisbon-Berlin: 2,309,476.737m
- 9. Euclidean distances (on the map), from Europe4CaptETRS89LAEA:
 - 9.1. Lisbon-Madrid: 501,691.748m
 - 9.2. Lisbon-Berlin: 2,300,384.469m
- 10. Differences:
 - 10.1. Lisbon-Madrid: 2,635.955m
 - 10.2. Lisbon-Berlin: 9,092.268m
- 11. Were these differences expected?
- 12. Save the project

7. Ad-hoc measurements using ArcGIS

- 1. Set the CRS project to WGS 84 (not projected)
 - 1.1. ...the reason being that the gds in this project are global
- 2. Open the Measure tool available from the Map tab
 - 2.1. On the layer EuropeanCaptETRS89, measure distance between capitals
 - 2.2. Note that:
 - planar measurements are not available
 - the distance link shows a curve shape
- 3. Why will the measurements be referenced to the WGS84 ellipsoid?

- 4. Zoom in to your country region and measure the distance between some pairs of capitals (units may be changed ...).
- 5. Explore the Measure tool. Click on the starting and ending points of the segment to be measured
 - 5.1. Double-click to end a measurement
 - 5.2. Do composed measurements based on several segments, for example, over a main road of the background image
- 6. The Measure Line / Area / Angle tool results often are imprecise ...
 - 6.1. It is suitable only to obtain ad-hoc measurements
- 7. Insert a new map (in tab Insert)
- 8. Copy the layer EuropeanCaptETRS89 to this new map and zoom to the layer
- 9. Confirm that the map CRS is ETRS 1989 (EPSG: 4258)
- 10. Insert a new map, add EuropeanCaptETRS89, zoom to the layer extent and change the project CRS to ETRS89 / LAEA Europe (EPSG: 3035) and analyze the result.
- 11. Repeat with CRS ETRS89 / LCC Europe (EPSG: 3034) and analyze the result.
- 12. Repeat with CRS WGS 84 (EPSG: 4326) and save the project!
- 13. Save the project