Profiling and benchmarking

Roman Khatko



Optimization Problem

Define Optimization Criteria

- Elapsed time
- Throughput
- Requests / sec
- Latency
- Frames per second
- Power
- •

Define Stop Criteria

- Optimization Criteria value when we're done
- May depend on the tuning potential

Workload

- System → Workload
- Simple case app itself
- In complex system focus on something:
 - Specific data
 - Specific execution scenario
 - •


Workload must be:

- Representative Workload improvement leads to system improvement.
- Measurable It is possible to calculate Optimization Criteria after each run.
- Reproducible Optimization Criteria value persists if the workload does not change.

Start with a solid baseline

- Use optimal compiler flags
 - Compile in Release mode
 - Compile with optimization flags (at least -O2)
- Use optimized libraries and runtimes
 - Intel® oneAPI libraries
 - Intel® Distribution for Python
- Measure on the system without unrelated activity
- Run multiple times to calculate deviations
- Check the correctness
- Invest in the measurement automation!

Optimization Process



- Start with the baseline
- Iterate
- Finish, when stopping condition is met
- For efficiency, this process should be guided by the Profiler

Software optimization directions

Compiler options

- Release build with debug information for profiling
- Optimization levels: -00, -02, -03, -0fast
 - Enabled optimizations depend on the compiler
 - Example to allow auto-vectorization:
 - Intel Compiler: -O2
 - GCC: -O2 -ftree-vectorize
- Allowed Instructions
 - ICC: <u>-xHost</u>, <u>-xCASCADELAKE</u> will run only on current machine; only on CascadeLake servers
 - GCC: -march=native, -march=cascadelake
 - Portable binaries with multiple code paths
 - ICC: -axCASCADELAKE,COMMON-AVX512,CORE-AVX2,SSE4.2
 - GCC: target_clones + flatten function attributes
- Fast Math
 - Ofast: -O3 + fast math optimizations
 - ICC: <u>-fp-model fast</u>
 - GCC: -ffp-contract=fast

Example:

- X*X*X*X*X*X*X -> 7 MUL
- A=X*X, B=A*A, C=B*B -> 3 MUL


Check if options allow the compiler to optimize!

Ways to optimize performance and their impact

- Performance increase is unknown and might be huge
- Algorithmic optimization
- Design optimization

- Limited performance increase
- Parallelization
- Vectorization
- Memory Access
- Other microarchitecture optimizations
- Offload


Optimization level – potential impact



Evaluate the directions – data driven approach

VTune Profiler – Performance Snapshot

- Algorithmic and design optimizations
- Parallelization
- Vectorization
- Offload
- Memory Access
- Other microarchitecture optimizations



Algorithmic optimization

VTune Profiler - Hotspots

- Focus on CPU Time
- Identify Hotspots most timeconsuming functions, loops
- Focus on Hotspots
- Choose better algorithms (complexity, constant)
- Use libraries optimized for target HW

Top Hotspots

This section lists the most active functions in your application. Optimizing these hotspot functions typically results in improving overall application performance.

Function	Module	CPU Time®
multiply1	matrix	146.389s
init_arr	matrix	0.020s

^{*}N/A is applied to non-summable metrics.

Software design optimization

VTune Profiler - Hotspots


- Algorithm optimization "calculate fast"
- Design optimization "avoid calculations"
- Rework application architecture to reduce the calculations
 - Cache frequent requests
 - Avoid unnecessary copies

Parallel optimizations

VTune Profiler - Threading

Perspectives:


- CPUs
 - CPU Utilization
 - Logical cores, Physical cores
- Threads
 - Effective CPU time, Spin and Overhead Time
 - Inactive time, Sync Wait time, Preemption time
- Sync objects



Vectorization


Intel® Advisor

SIMD instructions:



Vectorization boundaries

AVX-512 zmm register size




Vectorization


Intel® VTune Profiler – HPC Performance Characterization

- New CPU's support x86 ISA extensions: AVX, AVX2, AVX-512
- Optimized libraries
 - Update the library to benefit from the new ISA extension
- Pragmas hints to the compiler
 - Recompile to benefit from the new ISA extension
 - Align, prefer SOA vs AOS
- Intrinsics & asm
 - Rewrite to benefit from the new ISA extension
 - Try to avoid with pragmas and compiler options
 - Limit to small "kernels"
 - Keep the reference code

uArch optimizations

- µArch performance gain is limited by ideal CPI (Clocks Per Instruction)
- CPI does not depend on CPU clockticks: frequency which may change
- Why instructions might not retire:
 - Front-end bound
 - Back-end bound
 - Bad Speculation
- Top-Down methodology






Microarchitecture optimization – Top down

Elapsed Time[®]: 22.583s

	•		
	Clockticks:	647,479,000,000	
	Instructions Retired:	69,560,600,000	
	CPI Rate [®] :	9.308	
	MUX Reliability®:	0.998	
\odot	Retiring [®] :	5.5%	of Pipeline Slots
\odot	Front-End Bound®:	3.7%	of Pipeline Slots
\odot	Bad Speculation [®] :	0.2%	of Pipeline Slots
\odot	Back-End Bound ®:	90.7%	of Pipeline Slots
		85.6%	of Pipeline Slots
	O L1 Bound ::	0.0%	of Clockticks
	L2 Bound *:	0.0%	of Clockticks
	L3 Bound [®] :	0.8%	of Clockticks
	O DRAM Bound ::	89.4%	of Clockticks
	Store Bound [®] :	0.0%	of Clockticks
	O Core Bound ::	5.1%	of Pipeline Slots
	Average CPU Frequency [®] :	3.7 GHz	
	Total Thread Count:	9	
	Paused Time®:	Os	



This diagram represents inefficiencies in CPU usage. Treat it as a pipe with an output flow equal to the "pipe efficiency" ratio: (Actual Instructions Retired)/(Maximum Possible Instruction Retired). If there are pipeline stalls decreasing the pipe efficiency, the pipe shape gets more narrow.

Top-down metrics can be applied to the specific hotspot

Memory Access optimizations

VTune Profiler – Memory Access

- Start with Top-Down methodology to locate the problem
- Make your app NUMA-aware
- Reduce <u>frequent DRAM accesses</u>
- Fix <u>false sharing</u> issues
- Add hints for prefetchers

Summary

- Use optimized libraries
- Use optimal compiler flags
- Get a solid baseline
- Define optimization criteria for your workload
- Profile your code, measure
- Optimize your code design and algorithms first
- Parallelize
- Vectorize, help the compiler rather than play with assembly code
- Optimize memory access
- Optimize for microarchitecture efficiency
- Offload to the accelerators

Links

- Intel® VTune™ Profiler
- Intel® VTune™ Profiler Performance Analysis Cookbook
- Intel® oneAPI Toolkits
- Intel® Advisor



VTune Profiler Demo

#