Steps to convert moored CTD and RCM ODF files to NetCDF files

Jaimie Harbin

2023-03-01

Introduction

This vignette discusses the steps to convert a moored conductivity-temperature-depth (CTD) or a rotary current meter (RCM) ODF file to a NetCDF file. To convert a list of CTD or RCM ODF files follow the work flow provided below. To date, the odfToNetCDF package can convert MCAT files from ODF or from matlab and can convert RCMs from ODFs. The data used in this example is from the Davis Strait with an ODF origin.

1: Get necessary CF data

To get the necessary data, use the getCFData() function. This function gets the available standard names, units, codes,names, and type of data for the required information for the specified instrument type.

2: Creating oce objects

read.oce()

To read an oceanographic data file of origin ODF, use read.oce() from the oce package. This function "reads an oceanographic data file, auto-discovering the file type from the first line of the file. This function tries to infer the file type from the first line, using oceMagic(). If it can be discovered, then an instrument-specific file reading function is called, with the file and with any additional arguments being supplied." (Kelley and Richards, 2022).

matlabToOce()

If the origin of the file is a matlab file for a MCTD, the user must instead use the matlabToOce() function. This function removes NaN values in moored CTD Matlab files. It starts by reading a matlab file readMat(), then cycling through the multiple profiles of multiple stations to determine which data values are finite. The finite data values are then used to create an oce ctd object using as.ctd().

3 Rename variables in climate forecast (CF) standard

To rename variables in CF standard, use the nameReplacement() function. This function replaces DFO codes with CF standards. For ctd types, if conductivity ratio (CRAT) exists, the values are converted to sea_water_electrical_conductivity values to abide by CF standards, and the unit is changed to the specified unit.

Remove derived data/metadata

To remove derived data and metadata, use the removeDerived() function. This function removes data and metadata that is derived. For a CTD type, the only data and metadata kept is time, conductivity, salinity, tem-




Figure 1: Figure 1: Work flow of the odfToNetCDF package for CTD and RCM data types with descriptions on the left and relevant functions on the right

perature, and pressure. For an RCM type, the only data and metadata kept is horizontal_current_direction, barotropic_sea_water_x_velocity, sea_water_pressure, sea_water_practical_salinity, time, and sea water temperature.

Fix the metadata

To fix the metadata, use the fixMetadata() function. This function ensures the proper units are associated with each variable and adds place holders for flags if they do not already exist.

Convert ODF to NetCDF

To finally convert an ODF file to a NetCDF file, use the convertNetCDF() function. This function converts and odf object to a netCDF files for CTD and RCM types.

The convertNetCDF() function does the following:

Step 1: Remove the time Step 2: Determine units and standard_name for each code (using divideDataFrame.R) Step 3: Populate the variable, var, units, max,min, standard_name, and flags Step 4: About to check number of variables Step 5: Check dimensions of time, station, lon, lat, and dimnchar Step 6: Define netCDF variables using ncvar_def. Step 7: Create new netCDF file on disk using nc_create. Step 8: Insert data to an existing netCDF using ncvar_put Step 9: Insert attributes (metadata) into a netCDF file

Workflow

A typical workflow for an ODF derived file is as follows:

```
library(odfToNetCDF)
library(oce)
data <- getCFData(type="ctd")
f <- system.file("extdata", "mctd.ODF", package="odfToNetCDF")
odf1 <- read.odf(f)
odf2 <- nameReplacement(odf1, data=data, unit="S/m")
odf3 <- removeDerived(odf2)
odf4 <- fixMetadata(odf3, data=data)
convertNetCDF(odf4, data=data)</pre>
```

Check odf metadata

In addition to the suggested work flow, the user also has the ability to use the odfMetadataCheck() function, which was provided by Emily O'Grady. This function checks that the ODF file has all of the required metadata needed to build a NetCDF file. This metadata includes: longitude, latitude, type, model, samplingInterval, countryInstituteCode, cruiseNumber, station, serialNumber, cruise, sounding, scientist, waterDepth, depthMin, depthMax, institute, and it ensures the names of the parameters conform to General Formatting (GF3) standards.

Caution

It's important to note for RCM files, code HCDT (Horizontal current direction (true)) and HCSP do not have a CF standard. The standard name has been added as horizontal_current_direction and horizontal_current_speed respectively. Additionally, unlike mCTD files, no data ranges are being checked. It's recommended that the user investigates the data themselves.

Acknowlegments

We'd like to acknowledge the background information and starter functions created by Patrick Upson as well as testing and modifications made by Roger Pettipas.

References

Kelley, D., and Richards, C. (2020). oce: Analysis of Oceanographic Data. Available online at: https://CRAN.R-project.org/package=oce (accessed August 23, 2022).