Multilayer

Mehdi JAFARI ZADEH

Date: January 30, 2025

Contents

1	Tut	orial: Inter-VLAN Routing with ROAS and Multilayer Switches	5
	1.1	Introduction	5
	1.2	Router-on-a-Stick (ROAS)	5
		1.2.1 Overview	5
		1.2.2 How It Works	5
		1.2.3 Configuration Steps	5
		1.2.4 Advantages and Disadvantages	6
	1.3	Inter-VLAN Routing with a Multilayer Switch (MLS)	6
		1.3.1 Overview	6
		1.3.2 How It Works	6
		1.3.3 Configuration Steps	6
		1.3.4 Advantages and Disadvantages	7
	1.4	Choosing Between ROAS and MLS	7
	1.5	Conclusion	7
Ι	Ex	tercises and Hands-On Practice	9
2	Roi	ıter-on-a-Stick (ROAS)	11
_		31 d 20101 (20012)	
3	$\mathbf{M}\mathbf{u}$	ltilayer Switch (MLS)	13
ΙΙ	A	nswer Key and Explanations	15
4	Rot	iter-on-a-Stick (ROAS) - Answers	17
	4.1	PC Configuration	19
5	$\mathbf{M}\mathbf{u}$	ltilayer Switch (MLS) - Answers	21
6	Ans	swers to ROAS Exercises	23
	6.1	VLAN & Trunking Configuration Answers	23
	6.2	Router Subinterface Configuration Answers	23
	6.3	Troubleshooting ROAS Answers	23
	6.4	ACL and DHCP Configuration Answers	23
7	Ans	swers to Multilayer Switch Exercises	25
	7.1	VLAN and SVI Configuration Answers	25
	7.2	IP Routing and EtherChannel Answers	25
	7.3	Routing Protocol Configuration Answers	25
A	Cis	co IOS Command Reference	27

В	Troubleshooting Common VLAN and Inter-VLAN Issues	29
\mathbf{C}	Additional Study Resources and Certification Guide	31

4

CONTENTS

Tutorial: Inter-VLAN Routing with ROAS and Multilayer Switches

1.1 Introduction

Virtual Local Area Networks (VLANs) are used in network environments to segment traffic and improve performance and security. However, devices in separate VLANs cannot communicate with each other by default. Inter-VLAN routing allows devices from different VLANs to communicate, and this can be achieved through two main methods: Router-on-a-Stick (ROAS) and Multilayer Switch (MLS) Inter-VLAN Routing.

1.2 Router-on-a-Stick (ROAS)

1.2.1 Overview

Router-on-a-Stick (ROAS) is a method of inter-VLAN routing that uses a single router with a trunk link to a switch. The router performs all routing functions between VLANs.

1.2.2 How It Works

- 1. A trunk link is established between the router and the switch.
- 2. Subinterfaces are created on the router for each VLAN.
- 3. Each subinterface is assigned an IP address that acts as the default gateway for its respective VLAN.
- 4. The switch forwards VLAN-tagged traffic to the router, which then routes it to the appropriate VLAN.

1.2.3 Configuration Steps

On the Switch

```
configure terminal
interface GigabitEthernet0/1
switchport mode trunk
switchport trunk allowed vlan 10,20
exit
```

On the Router

```
configure terminal
interface GigabitEthernet0/1
no shutdown
interface GigabitEthernet0/1.10
encapsulation dot1Q 10
ip address 192.168.10.1 255.255.255.0
exit
interface GigabitEthernet0/1.20
encapsulation dot1Q 20
ip address 192.168.20.1 255.255.255.0
exit
```

1.2.4 Advantages and Disadvantages

Advantages:

- Cost-effective for small networks.
- Simple to implement.

Disadvantages:

- Limited scalability due to reliance on a single router interface.
- Potential bottleneck due to the router processing all inter-VLAN traffic.

1.3 Inter-VLAN Routing with a Multilayer Switch (MLS)

1.3.1 Overview

A multilayer switch (MLS) can perform routing functions at Layer 3, eliminating the need for an external router.

1.3.2 How It Works

- 1. The MLS is configured with Switched Virtual Interfaces (SVIs) for each VLAN.
- 2. Each SVI is assigned an IP address that acts as the default gateway for its VLAN.
- 3. The MLS handles inter-VLAN routing internally, reducing latency.

1.3.3 Configuration Steps

Enable Routing on the Switch

```
configure terminal ip routing
```

Create and Configure SVIs

```
interface vlan 10
ip address 192.168.10.1 255.255.255.0
no shutdown
exit
interface vlan 20
ip address 192.168.20.1 255.255.255.0
no shutdown
exit
```

1.3.4 Advantages and Disadvantages

Advantages:

- Higher performance as traffic remains within the switch.
- Scalability for larger networks.
- Reduced latency due to elimination of external routing hops.

Disadvantages:

- Higher cost compared to ROAS.
- Requires a switch with Layer 3 capabilities.

1.4 Choosing Between ROAS and MLS

Feature	Router-on-a-Stick (ROAS)	Multilayer Switch (MLS)
Cost	Lower	Higher
Performance	Slower (bottlenecks)	Faster
Scalability	$\operatorname{Limited}$	$\mathbf{Scalable}$
Complexity	Simple	$\operatorname{Moderate}$
Hardware Needed	Router & L2 Switch	L3 Switch

Table 1.1: Comparison of ROAS and MLS

For small networks with limited VLANs, ROAS is a cost-effective solution. For larger enterprise networks requiring higher performance, MLS is the preferred method.

1.5 Conclusion

Inter-VLAN routing is essential for modern networks to ensure seamless communication between VLANs. While ROAS is a simple and cost-effective solution, MLS offers improved performance and scalability. Choosing the right method depends on network size, traffic load, and budget considerations. Implementing the correct inter-VLAN routing solution ensures an efficient, high-performing, and well-segmented network infrastructure.

8CHAPTER 1. TUTORIAL: INTER-VLAN ROUTING WITH ROAS AND MULTILAYER SWITCHES

Part I Exercises and Hands-On Practice

Router-on-a-Stick (ROAS)

- 1. Configure the ${\tt GigabitEthernet0/0}$ interface as a trunk.
- 2. Assign subinterface 0/0.10 for VLAN 10 with IP 192.168.10.1/24.
- 3. Assign subinterface 0/0.20 for VLAN 20 with IP 192.168.20.1/24.
- 4. Assign subinterface 0/0.30 for VLAN 30 with IP 192.168.30.1/24.
- 5. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.10.
- 6. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.20.
- 7. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.30.
- 8. Enable IP routing on the router.
- 9. Verify VLANs on the switch.
- 10. Configure FastEthernet0/1 as a trunk on Switch1.
- 11. Configure FastEthernet0/1 as a trunk on Switch2.
- 12. Configure FastEthernet0/1 as a trunk on Switch3.
- 13. Assign FastEthernet0/2 on Switch1 to VLAN 10.
- 14. Assign FastEthernet0/2 on Switch2 to VLAN 20.
- 15. Assign FastEthernet0/2 on Switch3 to VLAN 30.
- 16. Set PC1's gateway to 192.168.10.1.
- 17. Set PC2's gateway to 192.168.20.1.
- 18. Set PC3's gateway to 192.168.30.1.
- 19. Verify trunking status on switches.
- 20. Show the current VLAN configuration.
- 21. Display the routing table to check inter-VLAN routing.
- 22. Show all subinterfaces configured on the router.
- 23. Check encapsulation settings for all subinterfaces.
- 24. Verify if PC1 can ping PC2.

- 25. Verify if PC3 can ping PC1.
- $26. \ \, \text{Save the running configuration}.$
- 27. Debug IP routing issues.
- 28. Remove subinterface 0/0.30.
- 29. Disable the trunk link on Switch1.
- 30. Reset the router configuration.

Multilayer Switch (MLS)

- 1. Enable IP routing on the multilayer switch.
- 2. Create VLAN 10 on the switch.
- 3. Create VLAN 20 on the switch.
- 4. Create VLAN 30 on the switch.
- 5. Assign interface VLAN 10 an IP address 192.168.10.1/24.
- 6. Assign interface VLAN 20 an IP address 192.168.20.1/24.
- 7. Assign interface VLAN 30 an IP address 192.168.30.1/24.
- 8. Assign interface FastEthernet0/1 to VLAN 10.
- 9. Assign interface FastEthernet0/2 to VLAN 20.
- 10. Assign interface FastEthernet0/3 to VLAN 30.
- 11. Configure trunking on FastEthernet0/24.
- 12. Allow VLAN 10, 20, and 30 on trunk FastEthernet0/24.
- 13. Set FastEthernet0/24 as a dynamic desirable trunk.
- 14. Assign PC1's default gateway to 192.168.10.1.
- 15. Assign PC2's default gateway to 192.168.20.1.
- 16. Assign PC3's default gateway to 192.168.30.1.
- 17. Verify VLAN assignments on the switch.
- $18. \ \ Display \ trunk \ ports \ status.$
- 19. Show the switch routing table.
- 20. Enable HSRP (Hot Standby Router Protocol) for VLAN 10.
- 21. Enable HSRP for VLAN 20.
- 22. Enable HSRP for VLAN 30.
- 23. Configure SVI (Switched Virtual Interface) for VLAN 10.
- 24. Configure SVI for VLAN 20.

- $25.\,$ Configure SVI for VLAN 30.
- 26. Show all SVI interfaces.
- 27. Verify if PC1 can ping PC2.
- 28. Verify if PC3 can ping PC1.
- $29. \;\; \text{Debug SVI connectivity issues.}$
- 30. Reset the multilayer switch configuration.

Part II Answer Key and Explanations

Router-on-a-Stick (ROAS) - Answers

1. Configure the GigabitEthernetO/O interface as a trunk

```
Router(config)# interface GigabitEthernetO/O
Router(config-if)# no shutdown
Router(config-if)# exit
```

2. Assign subinterface 0/0.10 for VLAN 10 with IP 192.168.10.1/24

```
Router(config)# interface GigabitEthernet0/0.10
Router(config-subif)# encapsulation dot1Q 10
Router(config-subif)# ip address 192.168.10.1 255.255.255.0
Router(config-subif)# exit
```

3. Assign subinterface 0/0.20 for VLAN 20 with IP 192.168.20.1/24

```
Router(config)# interface GigabitEthernet0/0.20
Router(config-subif)# encapsulation dot1Q 20
Router(config-subif)# ip address 192.168.20.1 255.255.255.0
Router(config-subif)# exit
```

4. Assign subinterface 0/0.30 for VLAN 30 with IP 192.168.30.1/24

```
Router(config)# interface GigabitEthernet0/0.30
Router(config-subif)# encapsulation dot1Q 30
Router(config-subif)# ip address 192.168.30.1 255.255.255.0
Router(config-subif)# exit
```

5. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.10

```
Router(config)# interface GigabitEthernet0/0.10
Router(config-subif)# encapsulation dot1Q 10
Router(config-subif)# exit
```

6. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.20

```
Router(config)# interface GigabitEthernet0/0.20
Router(config-subif)# encapsulation dot1Q 20
Router(config-subif)# exit
```

7. Enable 802.1Q encapsulation on subinterface GigabitEthernet0/0.30

```
Router(config)# interface GigabitEthernet0/0.30
Router(config-subif)# encapsulation dot1Q 30
Router(config-subif)# exit
```

8. Enable IP routing on the router

```
Router(config)# ip routing
```

9. Verify VLANs on the switch

```
Switch# show vlan brief
```

10. Configure FastEthernet0/1 as a trunk on Switch1.

```
Switch1(config)# interface FastEthernet0/1
Switch1(config-if)# switchport mode trunk
Switch1(config-if)# exit
```

11. Configure FastEthernet0/1 as a trunk on Switch2.

```
Switch2(config)# interface FastEthernet0/1
Switch2(config-if)# switchport mode trunk
Switch2(config-if)# exit
```

12. Configure FastEthernet0/1 as a trunk on Switch3.

```
Switch3(config)# interface FastEthernet0/1
Switch3(config-if)# switchport mode trunk
Switch3(config-if)# exit
```

13. Assign FastEthernet0/2 on Switch1 to VLAN 10

```
Switch1(config)# interface FastEthernet0/2
Switch1(config-if)# switchport mode access
Switch1(config-if)# switchport access vlan 10
Switch1(config-if)# exit
```

14. Assign FastEthernet0/2 on Switch2 to VLAN 20

```
Switch2(config)# interface FastEthernet0/2
Switch2(config-if)# switchport mode access
Switch2(config-if)# switchport access vlan 20
Switch2(config-if)# exit
```

15. Assign FastEthernet0/2 on Switch3 to VLAN 30

```
Switch3(config)# interface FastEthernet0/2
Switch3(config-if)# switchport mode access
Switch3(config-if)# switchport access vlan 30
Switch3(config-if)# exit
```

4.1 PC Configuration

- 16. Set PC1's gateway to 192.168.10.1
- 17. Set PC2's gateway to 192.168.20.1
- 18. Set PC3's gateway to 192.168.30.1

```
PC1> ip default-gateway 192.168.10.1
PC2> ip default-gateway 192.168.20.1
PC3> ip default-gateway 192.168.30.1
```

19. Verify trunking status on switches.

```
Switch# show interfaces trunk
```

20. Show current VLAN configuration

```
Switch# show vlan brief
```

21. Display the routing table

```
Router# show ip route
```

22. Show all subinterfaces

```
Router# show ip interface brief
```

23. Check encapsulation settings

```
Router# show interfaces GigabitEthernet0/0.10
Router# show interfaces GigabitEthernet0/0.20
Router# show interfaces GigabitEthernet0/0.30
```

- 24. Verify if PC1 can ping PC2.
- 25. Verify if PC3 can ping PC1.

```
PC1> ping 192.168.20.1
PC3> ping 192.168.10.1
```

26. Save the running configuration

```
Router# write memory
Switch# write memory
```

27. Debug IP routing issues

```
Router# debug ip routing
```

28. Remove subinterface 0/0.30

```
Router(config)# no interface GigabitEthernet0/0.30
```

29. Disable trunk link on Switch1

Switch1(config)# interface FastEthernet0/1
Switch1(config-if)# switchport mode access
Switch1(config-if)# exit

30. Reset the router configuration

Router# write erase Router# reload

Multilayer Switch (MLS) - Answers

1. Enable IP routing on the multilayer switch.

```
ip routing
```

2. Create VLAN 10 on the switch.

```
vlan 10
```

3. Assign interface VLAN 10 an IP address 192.168.10.1/24.

```
interface vlan 10
ip address 192.168.10.1 255.255.255.0
no shutdown
```

4. Assign FastEthernet0/1 to VLAN 10.

```
interface FastEthernet0/1
switchport mode access
switchport access vlan 10
```

5. Configure trunking on FastEthernet0/24.

```
interface FastEthernet0/24
switchport mode trunk
switchport trunk allowed vlan 10,20,30
```

6. Set PC1's default gateway.

```
ip default-gateway 192.168.10.1
```

7. Show VLAN assignments.

```
show vlan brief
```

8. Show the switch routing table.

```
show ip route
```

9. Enable HSRP for VLAN 10.

```
interface vlan 10
standby 1 ip 192.168.10.254
```

10. Configure Switched Virtual Interface (SVI) for VLAN 20.

```
interface vlan 20
ip address 192.168.20.1 255.255.255.0
no shutdown
```

11. Show all SVI interfaces.

```
show ip interface brief
```

12. Verify connectivity between VLANs using ping.

```
ping 192.168.20.1
```

13. Debug SVI connectivity issues.

```
debug ip routing
```

14. Reset the multilayer switch configuration.

```
erase startup-config reload
```

Answers to ROAS Exercises

- 6.1 VLAN & Trunking Configuration Answers
- 6.2 Router Subinterface Configuration Answers
- 6.3 Troubleshooting ROAS Answers
- 6.4 ACL and DHCP Configuration Answers

Answers to Multilayer Switch Exercises

- 7.1 VLAN and SVI Configuration Answers
- 7.2 IP Routing and EtherChannel Answers
- 7.3 Routing Protocol Configuration Answers

Appendix A

Cisco IOS Command Reference

Appendix B

Troubleshooting Common VLAN and Inter-VLAN Issues

Appendix C

Additional Study Resources and Certification Guide