MIT Proto Developers Guide

Jacob Beal

Date: January 3, 2010, SVN Version: 10

This is a guide to developing for the MIT Proto project. It outlines the various components of the project, how they fit together, and how to develop for them safely.

Contents

1	Credits for Proto	1
2	Overview	2
3	Installed File Locations	3
4	Compiler	3
5	Libraries	4
6	ProtoKernel	4
7	Simulator 7.1 Distributions	5 6
8	Adding Simulator Functionality 8.1 Extensions via customizations.cpp 8.2 Current Plug-in System 8.3 Future Plug-in System	7 7 7 8
9	Regression Testing	9

1 Credits for Proto

The Proto language was created in partnership by Jonathan Bachrach and Jacob Beal. As they created the language, Jonathan created the first implementation of MIT Proto, including the first compiler, kernel, simulator, and embedded device implementations. Since that time, Jake and other contributors have built on the work begun by Jonathan.

MIT Proto also includes contributions from (alphabetically):

Anna Derbakova, Takeshi Fujiwara, Tony Grue, Tom Hsu, Joshua Horowitz, Kanak Kshetri, Dustin Mitchell, Omar Mysore, Maciej Pacula, Hayes Raffle, Dany Qumsiyeh, Omari Stephens, Mark Tobenkin, Dan Vickery




Figure 1: Relationship of MIT Proto components (blue) and extensions (red)

The Protobo platform code in platforms/protobo/ also includes Topobo-related code from (alphabetically):

Mike Fleder, Limor Fried, Josh Lifton, Laura Yip

2 Overview

Proto is a language designed for implementing distributed systems on spatially-structured networks of static or mobile devices. The programmer describes a desired behavior for the continuous space occupied by the network, which can be translated into a program by which individual devices cooperate to produce an approximation of the desired behavior. Such programs can then be rendered into an executable than can run equivalently on different hardware platforms.

Components MIT Proto is an implementation of Proto which supplies four main components:

- A compiler which turns Proto code into executable code for individual devices
- A library of Proto code implementing commonly used functions
- An implementation of the ProtoKernel virtual machine, one means of executing programs on individual devices.
- An event-based simulator, based on ProtoKernel, for debugging and visualization of Proto programs executing on a network

MIT Proto is typically invoked through one of two executables, p2b and proto. The name p2b stands for "Proto to bytecode" and is a standalone invocation of the compiler. The proto executable, on the other hand, first compiles and then executes in the simulator.

Extensions MIT Proto has interfaces allowing this system to be extended in three ways:

- The compiler can emit code customized to different platforms
- ProtoKernel can incorporate a set of platform-specific opcodes
- The simulator supports plug-in:
 - Distributions for laying out the devices of a network (e.g. random, grid, torus).
 - Models for the evolution of time on individual devices (e.g. synchronous, drifting clocks)
 - Physics "layers" for simulating the interaction of sensors and actuators with aspects of a dynamic external environment (e.g. wireless communication, chemical diffusion, Newtonian kinetics, LEDs and beeps)

MIT Proto's is copylefted such that any modification of its components is copylefted as well, but extensions need not be.

3 Installed File Locations

MIT Proto uses autotools to build and install on a machine. By default, the installation directory prefix is /usr/local/ (or the OS-appropriate equivalent). From this base, the following default locations are used (reconfigurable via ./configure when the project is being built):

- Executables are placed in PREFIX/bin/
- The library files in the build directories lib/ and /lib/core/ are both placed into PREFIX/share/proto/lib. This directory is part of the default search path for executions of the compiler.
- Platform definition files for platform PLATFORM are expected to be found in PREFIX/share/proto/platforms/PLATFORM
- The header files needed for building extensions for MIT Proto should be installed in PREFIX/include/proto/, but currently are not. NEEDS DEVELOPER ATTENTION
- Under the future plug-in system, the simulator should search for plug-ins in PREFIX/share/proto/platforms/sim/

4 Compiler

This document describes only the compiler's interactions with other pieces of the installation and its major known bugs. The internal structure of the compiler will not be documented in detail at this time, because it is both highly complex and obsolete.

Compiling for a Platform The compiler loads platform-specific operations during its initialization. When given a --platform *PLATFORM* argument, it reads the platform definition file platform_ops.h from the platform directory for *PLATFORM* (see above). This file is expected to contain C comments and a single enum of the form:

```
typedef enum {
  opcode-name = CORE_CMD_OPS,
  opcode-name,
  ...
MAX_CMD_OPS
} PLATFORM_OPCODES;
```

This file gives the compiler names and numbers for the opcodes to be defined.

The compiler then reads the platform definition file platform_ops.proto from the same directory. This is a Proto file and is expected to contain a set of defop expressions of the form:

```
(defop opcode-name function-name type ...)
```

where opcode-name should match some entry in the platform_ops.h file (though they can be in a different order), and function-name is the Proto function that will invoke the opcode. The first type expression specifies the return type, and any others that follow specify argument types for the operator. The type expressions are currently allowed only to be one of scalar, boolean, and (vector 3).

Compilation and Files Compilation always starts with a Proto expression on the command line. Except for the smallest of programs, this expression is not self-contained. Whenever the compiler encounters a function *name* that it does not know, it searches for a file called *name*.proto in the directories listed in its path. By default, the path consists of the current directory and the installed library location. These two command line arguments:

```
--path PATH
--basepath PATH
```

add to the default path and override the default path, respectively.

Known Bugs Important known bugs in the current compiler are:

- Variables in a letfed that are not used within the body of the letfed are not updated correctly.
- Variables in let statements that are used only within a conditional further on in the code are inlined
 inside that conditional, which makes side effects of the computation in the let happen only in the
 domain of that branch of the conditional.

Neocompiler A complete rebuild of the compiler is in progress, but not currently checked into the repository. When complete, it will implement an enhanced version of Proto, fix a number of known compiler bugs, change how platform-specific opcodes are handled, and allow compilation for execution on systems other than ProtoKernel. **NEEDS DEVELOPER ATTENTION**

5 Libraries

MIT Proto includes two libraries: the functions in lib/are moderately complex programs that make useful building blocks, while the functions in lib/core/ are language primitives implemented in Proto. They are mixed together in installation, but kept separate in the build so that maintenance of the "library" collection is not cluttered up by the large numbers of simple core functions like log10 and logn. The core library exists because it helps minimize the number of opcodes needed without hardwiring definitions into the compiler.

6 ProtoKernel

SECTION IN PROGRESS

Built purely in C (no C++) for minimum size and maximum portability across embedded platforms.

7 Simulator

SECTION IN PROGRESS

Event-driven simulation

```
class EventConsumer {
public:
    virtual BOOL handle_key(KeyEvent* key) {return FALSE;} // return if consumed
    virtual BOOL handle_mouse(MouseEvent* mouse) {return FALSE;} // same return
    virtual void visualize() {} // draw, assuming a prepared OpenGL context
    // evolve moves state forward in time to 'limit' (an absolute)
    virtual BOOL evolve(SECONDS limit) {} // return whether state changed
};
```

Time real time vs. simulation time vs. device time

Visualization

7.1 Distributions

```
class Distribution {
  public:
    int n; Rect *volume;
    METERS width, height, depth; // bounding box of volume occupied
    Distribution(int n, Rect *volume) { // subclasses often take an Args* too
        this->n=n; this->volume=volume;
        width = volume->r-volume->l; height = volume->t-volume->b; depth=0;
        if(volume->dimensions()==3) depth=((Rect3*)volume)->c-((Rect3*)volume)->f;
    }
    // puts location in *loc and returns whether a device should be made
    virtual BOOL next_location(METERS *loc) { return FALSE; } // loc is a 3-vec
};
```

7.2 Time Models

```
// a bit of state attached to a device to say how its time advances
class DeviceTimer {
  public: // both of these report delay from the current compute time
    virtual void next_transmit(SECONDS* d_true, SECONDS* d_internal)=0;
    virtual void next_compute(SECONDS* d_true, SECONDS* d_internal)=0;
    virtual DeviceTimer* clone_device()=0; // split the timer for a clone dev
};

// factory class for producing DeviceTimers
class TimeModel {
    public:
        virtual DeviceTimer* next_timer(SECONDS* start_lag)=0;
        virtual SECONDS cycle_time()=0;
};
```

7.3 Layers

```
class Layer : public EventConsumer {
 public:
                   // what number layer this is, for lookup during callbacks
  int id;
                   // -ND[layer] is expected to turn off dumping for a layer
 BOOL can_dump;
  SpatialComputer* parent;
 Layer(SpatialComputer* p);
 virtual ~Layer() {} // make sure that destruction is passed to subclasses
 virtual BOOL handle_key(KeyEvent* key) {return FALSE;}
 virtual void visualize() {}
 virtual BOOL evolve(SECONDS dt) { return FALSE; }
 virtual void add_device(Device* d)=0;
                                         // may add a DeviceLayer to Device
 virtual void device_moved(Device* d) {} // adjust for device motion
 // removal, updates handled through DeviceLayer
 virtual void dump_header(FILE* out) {} // field names in ""s for a data file
 virtual layer_type get_type() { return LAYER_OTHER; }
};
// this is the device-specific instantiation of a layer
class DeviceLayer : public EventConsumer {
 public:
 Device* container;
 DeviceLayer(Device* container) { this->container=container; }
 virtual "DeviceLayer() {}; // make sure destruction cascades correctly
 virtual void preupdate() {} // to called before computation
 virtual void update() {} // to called after a computation
 virtual void visualize() {} // to be called at visualization
 virtual BOOL handle_key(KeyEvent* event) { return FALSE; }
 virtual void copy_state(DeviceLayer* src)=0; // to be called during cloning
 virtual void dump_state(FILE* out, int verbosity) {}; // print state to file
};
// The Body/BodyDynamics is a layer that is stored and managed
// specially because it tracks the position of the device in space.
class Body : public DeviceLayer {
 public:
 BOOL moved;
 Body(Device* container) : DeviceLayer(container) {}
 virtual ~Body() {}; // make sure destruction cascades correctly
  // on delete, a body should remove itself from the BodyDynamics
 virtual const flo* position()=0; // returns a 3-space coordinate
 virtual const flo* velocity()=0; // returns a 3-space vector
 virtual const flo* orientation()=0; // returns a quaternion
 virtual const flo* ang_velocity()=0; // returns a 3-space vector
 virtual void set_position(flo x, flo y, flo z)=0;
 virtual void set_velocity(flo dx, flo dy, flo dz)=0;
 virtual void set_orientation(const flo *q)=0;
 virtual void set_ang_velocity(flo dx, flo dy, flo dz)=0;
 virtual flo display_radius()=0; // bigger bodies get bigger displays
 virtual void render_selection()=0; // render for selection
  void copy_state(DeviceLayer* src) {} // required virtual is moot
};
```

```
// BodyDynamics is a special type of layer, implementing the base physics
class BodyDynamics : public Layer {
  public:
   BodyDynamics(SpatialComputer* p) : Layer(p) {}
   virtual ~BodyDynamics() {} // make sure destruction is passed to subclasses
   virtual Body* new_body(Device* d, flo x, flo y, flo z)=0;
   void add_device(Device* d) {} // required virtual, replaced by new_body
};
```

7.4 Adding Simulated Hardware

8 Adding Simulator Functionality

As previously noted, the simulator can be extended with new distributions for laying out device positions, models for the evolution of time on individual devices, and physics "layers" for simulating interaction with an external environment.

Extensions were originally added via the file src/sim/customizations.cpp. This is being phased out because it forces extensions into the core MIT Proto distribution, defeating their purpose. There is now a simple plug-in system built in and a design for a better plug-in system. This document describes all three.

8.1 Extensions via customizations.cpp

During the initialization of the spatial computer model in the simulator, three "choose" functions are called to select layers, distributions, and time models. The choose_layers function is called first, and it calls choose_distribution and choose_time_model internally.

These functions should examine the command line arguments and set the appropriate spatial computer model state variables. The choose_layers may add any number of layers using the function

```
int SpatialComputer::addLayer(Layer* layer);
```

The exception is the BodyDynamics layer managing the motion of devices in the spatial computer: there must be precisely one BodyDynamics, and it is placed in the model state variable physics.

Likewise, the effect of the choose_distribution and choose_time_model functions is to set the model state variables distribution and time_model, respectively.

Adding new functionality generally just entails adding one or more new test clauses: the code for choose_distribution is a good model to work from.

8.2 Current Plug-in System

The current simple plug-in system provides sharply limited functionality. Plug-ins are created as dynamic libraries with the name proto-name.dylib or proto-name.so, and stored in a location where the operating system's dynamic library loader can find them, e.g. /usr/local/lib/.

The set of plugins to load is specified with a command-line argument

```
-plugins name, name, \dots
```

where each name maps to a library proto-name.dylib or proto-name.so.

Each library supplies one layer, which the choose_layers function obtains by calling the function

```
Layer* get_layer(Args *args, SpatialComputer *cpu, int n);
```

on the library, where args is the current command line arguments, cpu is the model under construction, and n is the number of devices to be created. If the layer is a BodyDynamics, it should identify itself as such by implementing a member function

```
layer_type get_type()
```

that returns the enum value LAYER_PHYSICS. As always, there must be precisely one BodyDynamics, no more and no less.

Plugins for time models and distributions are not currently supported (though there is partial code toward that effect). The plug-in system also attempts to provide special-case handling for layers that simulate radio communication; this does not work correctly and should never have existed.

8.3 Future Plug-in System

The plug-in system to be implemented will replace the current system entirely. Before creating the spatial computer model, the simulator will scan the the simulator's platform directory and find all dynamic library files (those ending in .dylib, .so, or .dll. Each one will be loaded, and if the library contains a symbol named get_proto_plugins, that symbol will be invoked as the C function:

```
ProtoPluginLibrary* get_proto_plugins()
```

This function returns an object subclassed from the type ProtoPluginLibrary, which is defined:

Each of the three functions in this interface is used to poll whether a desired layer, time model, or distribution can be obtained from this plugin. The function should return the requested object if it can supply it, and NULL if not. For each function, name is a C string naming the desired object, args is the current command line arguments, cpu is the model under construction, and n is the number of devices to be created. The function may consume command-line arguments, but must not modify the model directly.

The spatial computer model also will expose functions that can be used by "meta-plugins" to combine together the functions of other objects:

```
virtual Layer* SpatialComputer::find_layer(char* name, Args* args, int n);
virtual Layer* SpatialComputer::find_time_model(char* name, Args* args, int n);
virtual Layer* SpatialComputer::find_distribution(char* name, Args* args, int n);
```

For example, a multi-radio communication model could use the find_layer function to fetch a layer to model each radio on the device.

Layers, time models, and distributions are invoked by the command line arguments

```
-L layer-TM time-model-DD distribution
```

During the construction of the spatial computer model, these command line arguments are used to find what object is desired. The constructor then first polls each plug-in in turn, followed by the built-in choose functions, taking the first object returned or throwing an error when none can supply the desired object.

In case of problematic conflicts between plugins, the command-line argument

```
-NP name
```

can be used to not load a particular plugin and

```
-OP name, name, \dots
```

can be used to load only the specified set of plugins, in the order specified.

Further Extension: Per-Layer Opcodes In addition to the plugins described above, the simulator ought to be able to load particular sets of platform-specific opcodes along with each layer, and make those available to the compiler as well. This is not yet implemented, and the interface is not yet well specified. NEEDS DEVELOPER ATTENTION

9 Regression Testing

MIT Proto comes with a built in regression test suite, located in src/tests/. The file prototest.py is a Python script for executing tests, and files ending in .test are particular test suites.

A test suite is invoked by running:

```
./prototest.py suite.test
```

Multiple test suites can be given; for example,

```
./prototest.py *.test
```

will execute every test in the directory.

The regression tester works by executing either proto or p2b, capturing its output as a file (by default stored in src/tests/dumps/), then comparing the contents of this file against values specified for the test.

The command to be executed for a test is specified as:

```
test: $(app) arguments
```

where *app* is either PROTO or P2B. The arguments -D and -dump-stem are supplied automatically if the test does not supply them explicitly, and -headless is added for tests invoking the simulator.

Following the executable specification is a series of lines specifying comparisons to perform on the output of the execution. Each line is formatted:

```
test line column expected-value [additional-args]
```

The *line* and *column* values specify which output token is to be compared, counting from zero, and splitting each line into "columns" on whitespace. The *column* can also have the special value _, meaning that the comparison should be performed against the entire line (trimming leading and following whitespace, but leaving the interior intact).

The test specifies how the expected-value is to be compared to the actual value found at line and column:

- =, >, <, >=, <=, and != treat the value as a scalar number and perform the appropriate numerical comparison. Note that comparison with infinity can be done by giving an expected value of Inf or -Inf.
- ~= treats the value as a number and tests for approximate equality, using an additional argument tolerance for how different the value can be from expected-value.

- is_nan checks whether the value is equal to the special floating point "not a number" value (needed because, by IEEE standards, NaN is not equal to itself). An *expected-value* must be supplied, but is ignored.
- is treats the value as a string and performs a case-insensitive comparison with *expected-value* (e.g. "OUTPUT", "Output", and "output" all match).

A test succeeds if the executable terminates normally (exit code 0) and if all comparisons return true. For each file suite.test, a summary of test results is printed on standard out and full detail is output into a file suite.test.RESULTS.

Other notes:

- Lines beginning with // are treated as comments.
- Default paths and other options in prototest.py can be changed using various command line arguments. These options can be listed by running ./prototest.py -h