Fluid Mechanics

Analytical solutions for simple fluid flows

Lecturer: Jakob Hærvig

Slides by Jakob Hærvig (AAU Energy) and Jacob Andersen (AAU Build)

Complexities involved in Navier-Stokes equations

No universal analytical solution due to non-linearities $(u\partial u/\partial x)$

- Solution *approximated* using *numerical methods* (e.g. CFD)
- Solution found by *experiments*

Analytical solutions for *only a few problems*

- Simple geometries: Flow between two plates or in a tube
- Simple flows: Steady, laminar and fully-developed flows

x-direction:

$$ho \left(rac{\partial u}{\partial t} + urac{\partial u}{\partial x} + vrac{\partial u}{\partial y} + wrac{\partial u}{\partial z}
ight) = -rac{\partial p}{\partial x} + \mu \left(rac{\partial^2 u}{\partial x^2} + rac{\partial^2 u}{\partial y^2} + rac{\partial^2 u}{\partial z^2}
ight) +
ho g_x$$

y-direction:

$$ho \left(rac{\partial v}{\partial t} + u rac{\partial v}{\partial x} + v rac{\partial v}{\partial y} + w rac{\partial v}{\partial z}
ight) = -rac{\partial p}{\partial y} + \mu \left(rac{\partial^2 v}{\partial x^2} + rac{\partial^2 v}{\partial y^2} + rac{\partial^2 v}{\partial z^2}
ight) +
ho g_y$$

z-direction:

$$ho \left(rac{\partial w}{\partial t} + u rac{\partial w}{\partial x} + v rac{\partial w}{\partial y} + w rac{\partial w}{\partial z}
ight) = -rac{\partial p}{\partial z} + \mu \left(rac{\partial^2 w}{\partial x^2} + rac{\partial^2 w}{\partial y^2} + rac{\partial^2 w}{\partial z^2}
ight) +
ho g_z$$

Why look at these *simplified* problems?

For which applications is the flow between two plates important?

Flow between two plates—whether *pressure-driven* (plane Poiseuille flow) or *shear-driven* (Couette flow)—is a **canonical model** that underpins both engineering practice and natural phenomena. It's important in many applications, including:

Engineering & Technology

- Lubrication: Thin films of oil in bearings, pistons, gears, or seals are modeled as flow between parallel
 plates.
- Microfluidics: Lab-on-a-chip devices use narrow rectangular channels, which are essentially parallel
 plate flows.
- Heat exchangers: Plate-type exchangers rely on fluid moving between closely spaced plates for efficient heat transfer.
- · Coating & printing: Flow of paint, varnish, or ink in thin layers is approximated by plate flows.
- Polymer processing: Sheet extrusion and film casting involve molten polymer flow between plates.

Everyday Phenomena

- Sticking of wet surfaces: Two glass slides or a credit card and plastic sleeve resist separation due to viscous flow in the thin liquid film.
- · Windshield wipers: The thin water film between blade and glass behaves like a parallel-plate channel.
- Food preparation: Spreading butter, cream, or sauces between slices involves thin-film flow.

Biology & Medicine

- Synovial joints: Cartilage surfaces slide with synovial fluid in between, modeled as shear-driven thin-film flow.
- **Blood in microvessels**: Capillaries and arterioles often approximate parallel-plate geometries at small scales.
- Dialysis and filtration: Fluids move between thin membranes in channels resembling plate flows.

Fundamental & Educational Value

- Provides one of the few exact solutions of Navier–Stokes—great for teaching velocity profiles, shear stress, and pressure gradients.
- Serves as a building block for more complex flows (e.g., lubrication theory, Reynolds equation).
- Helps illustrate the importance of viscosity, low Reynolds number flows, and scaling laws.

Current research uses *Poiseuille flow* for verification of CFD

CO₂ diffuses into the fiber and is captured

- Really (!) long fibres (l/D pprox 12000)
- Steady, laminar, fully-developed flow is a *very good* assumption
- Prescribed boundary condition

Results: Code verification results






Figure: Hollow fibre membrane





Bazhenov, S. D., Bildyukevich, A. V., & Volkov, A. V. (2018). Gas-Liquid Hollow Fiber Membrane Contactors for Different Applications. Fibers, 6(4), 76. https://doi.org/10.3390/fib6040076

Code: Inlet boundary condition in OpenFOAM

Flow between plates

Incompressible, *steady*, *fully developed*, *laminar flow* between two *infinite plates*

• Velocity only in *x*-direction:

$$\circ$$
 then, $u=u(y)$, $v=w=0$

• Steady flow:


$$\circ$$
 then, $\partial u/\partial t=\partial v/\partial t=\partial w/\partial t=0$

- By continuity equation: $\partial u/\partial x + \partial v/\partial y + \partial w/\partial z = 0$
 - \circ then, $\partial u/\partial x=0$
- No gravity in x and z directions:

$$\circ$$
 then, $q_x = q_z = 0$

Navier-Stokes equations *reduce* to:

$$oldsymbol{x}:0=-rac{\partial p}{\partial x}+\murac{\partial^2 u}{\partial y^2},\;\;oldsymbol{y}:0=-rac{\partial p}{\partial y}+
ho g_y,\;\;oldsymbol{z}:0=-rac{\partial p}{\partial z}$$



x-direction:

$$\rho\left(\frac{\partial u}{\partial t} + u\frac{\partial u}{\partial x} + v\frac{\partial u}{\partial y} + w\frac{\partial u}{\partial z}\right) = -\frac{\partial p}{\partial x} + \mu\left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 u}{\partial z^2}\right) + \rho g_x$$

y-direction:

$$\rho\left(\frac{\partial v}{\partial t} + u\frac{\partial v}{\partial x} + v\frac{\partial v}{\partial y} + w\frac{\partial v}{\partial z}\right) = -\frac{\partial p}{\partial y} + \mu\left(\frac{\partial^2 v}{\partial x^2} + \frac{\partial^2 v}{\partial y^2} + \frac{\partial^2 v}{\partial z^2}\right) + \rho g_y$$

z-direction:

$$\rho\left(\frac{\partial w}{\partial t} + u\frac{\partial w}{\partial x} + v\frac{\partial w}{\partial y} + w\frac{\partial w}{\partial z}\right) = -\frac{\partial p}{\partial z} + \mu\left(\frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} + \frac{\partial^2 w}{\partial z^2}\right) + \rho g_z$$

Flow between two stationary plates

Integrating twice to get u(y):

$$egin{align} rac{\partial^2 u}{\partial y^2} &= rac{1}{\mu} rac{\partial p}{\partial x} \ &rac{\partial u}{\partial y} &= rac{1}{\mu} rac{\partial p}{\partial x} y + C_1 \ &u &= rac{1}{2\mu} rac{\partial p}{\partial x} y^2 + C_1 y + C_2 \ \end{pmatrix}$$


Using *boundary conditions*:


At $y = \pm h$ we have u = 0

$$C_1=0, C_2=-rac{1}{2\mu}rac{\partial p}{\partial x}h^2$$

Velocity profile (by inserting C_1 and C_2):

$$u(y)=rac{1}{2\mu}rac{\partial p}{\partial x}(y^2-h^2)$$





Volume flow rate (integrating velocity profile):

$$q=\int_{-h}^{h}u(y)=-rac{2h^{3}}{3\mu}\left(rac{\partial p}{\partial x}
ight)$$

Average velocity:

$$V=rac{q}{2h}=-rac{h^2}{3\mu}\left(rac{\partial p}{\partial x}
ight)$$

Maximum velocity (centre of channel, y = 0):

$$u_{max}=u(y=0)=-rac{h^2}{2\mu}\left(rac{\partial p}{\partial x}
ight)=rac{3}{2}V$$

Flow between one stationary and one moving plate (aka Couette flow)

Integrating twice to get u(y):

$$egin{aligned} rac{\partial^2 u}{\partial y^2} &= rac{1}{\mu} rac{\partial p}{\partial x} \ &rac{\partial u}{\partial y} &= rac{1}{\mu} rac{\partial p}{\partial x} y + C_1 \ &u &= rac{1}{2\mu} rac{\partial p}{\partial x} y^2 + C_1 y + C_2 \end{aligned}$$


Using *boundary conditions*:


At y = 0 we have u = 0

At y = b we have u = U

Finding C_1 and C_2 and inserting:

$$u(y) = Urac{y}{b} + rac{1}{2\mu}rac{\partial p}{\partial x}(y^2 - by)$$





$$P=-rac{b^2}{2\mu U}\left(rac{\partial p}{\partial x}
ight)$$

Flow in a circular pipe (aka Poiseuille flow)

Incompressible, steady, fully developed, laminar flow in a circular pipe

• Velocity only in *z*-direction:

$$\circ$$
 then, $v_z=v_z(r), v_ heta=v_r=0$

• Steady flow:

$$\circ$$
 then, $\partial u/\partial t = \partial v/\partial t = \partial w/\partial t = 0$

- ullet By continuity equation: $rac{1}{r}rac{\partial(rv_r)}{\partial r}+rac{1}{r}rac{\partial v_ heta}{\partial heta}+rac{\partial v_z}{\partial z}=0$
 - \circ then, $\partial v_z/\partial z=0$
- No gravity in *z* direction:
 - \circ *then,* $g_z = 0$


Navier-Stokes equations *reduce* to:


$$oldsymbol{z}:0=-rac{\partial p}{\partial z}+\murac{1}{r}rac{\partial}{\partial r}\left(rrac{\partial v_z}{\partial r}
ight), \;\; oldsymbol{r}:0=
ho g_r-rac{\partial p}{\partial r}, \;\; oldsymbol{ heta}:0=
ho g_ heta-rac{1}{r}rac{\partial p}{\partial heta}$$

Integration, applying boundary conditions and find C_1 and C_2 :

$$v_z(r) = rac{1}{4\mu} - \left(rac{\partial p}{\partial z}
ight) \left(r^2 - R^2
ight)$$

• Velocity is a function of viscosity μ , pressure gradient $\partial p/\partial z$ and pipe radius R.





z-direction:

$$\rho\left(\frac{\partial v_z}{\partial t} + v_r \frac{\partial v_z}{\partial r} + \frac{v_\theta}{r} \frac{\partial v_z}{\partial \theta} + v_z \frac{\partial v_z}{\partial z}\right) = -\frac{\partial p}{\partial z} + \mu\left(\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial v_z}{\partial r}\right) + \frac{1}{r^2} \frac{\partial^2 v_z}{\partial \theta^2} + \frac{\partial^2 v_z}{\partial z^2}\right) + \rho g_z$$

r-direction:

$$\rho\left(\frac{\partial v_r}{\partial t} + v_r \frac{\partial v_r}{\partial r} + \frac{v_\theta}{r} \frac{\partial v_r}{\partial \theta} - \frac{v_\theta^2}{r} + v_z \frac{\partial v_r}{\partial z}\right) = -\frac{\partial p}{\partial r} + \mu\left(\frac{1}{r} \frac{\partial}{\partial r} \left(r \frac{\partial v_r}{\partial r}\right) - \frac{v_r}{r^2} + \frac{1}{r^2} \frac{\partial^2 v_r}{\partial \theta^2} - \frac{2}{r^2} \frac{\partial v_r}{\partial \theta} + \frac{\partial^2 v_r}{\partial z^2}\right) + \rho g_r$$

θ -direction:

$$\rho\left(\frac{\partial v_{\theta}}{\partial t} + v_{r}\frac{\partial v_{\theta}}{\partial r} + \frac{v_{\theta}}{r}\frac{\partial v_{\theta}}{\partial \theta} - \frac{v_{r}v_{\theta}}{r} + v_{z}\frac{\partial v_{\theta}}{\partial z}\right) = -\frac{1}{r}\frac{\partial p}{\partial \theta} + \mu\left(\frac{1}{r}\frac{\partial}{\partial r}\left(r\frac{\partial v_{\theta}}{\partial r}\right) - \frac{v_{\theta}}{r^{2}} + \frac{1}{r^{2}}\frac{\partial^{2}v_{\theta}}{\partial \theta^{2}} + \frac{2}{r^{2}}\frac{\partial v_{r}}{\partial \theta} + \frac{\partial^{2}v_{\theta}}{\partial z^{2}}\right) + \rho g_{\theta}$$

Details on flow in *circular pipes* (aka Poiseuille flow)

• Volume flow rate (integrate velocity):

$$Q=2\pi\int_{0}^{R}v_{z}(r)rdr=-rac{\pi R^{4}}{8\mu}\left(rac{\partial p}{\partial z}
ight)=rac{\pi R^{4}\Delta p}{8\mu l}$$

- Flow rate is a function of *viscosity* μ , *pressure gradient* $\partial p/\partial z$ and *pipe radius* R.
- Average velocity (divide by area):

$$V=rac{Q}{A}=rac{-rac{\pi R^4}{8\mu}\left(rac{\partial p}{\partial z}
ight)}{\pi R^2}=-rac{R^2}{8\mu}\left(rac{\partial p}{\partial z}
ight)=rac{R^2\Delta p}{8\mu l}$$

- Mean velocity is a function of *viscosity* μ , *pressure gradient* $\partial p/\partial z$ and *pipe radius* R.
- Maximum velocity (r=0):

$$v_z(r=0) = rac{1}{4\mu} - \left(rac{\partial p}{\partial z}
ight)(0^2 - R^2) = -rac{R^2}{4\mu}\left(rac{\partial p}{\partial z}
ight) = rac{R^2\Delta p}{4\mu l}$$

• Mean velocity is a function of *viscosity* μ , *pressure gradient* $\partial p/\partial z$ and *pipe radius* R.


• Ratio of centerline to mean velocity ($v_z(r=0)/V$):

$$rac{v_z(r=0)}{V} = rac{rac{R^2\Delta p}{4\mu l}}{rac{R^2\Delta p}{8\mu l}} = 2$$

• Centerline velocity is exactly *twice* the mean velocity.

Exercise: Upward moving fluid film

A wide moving belt passes through a container of a viscous liquid. The belt moves vertically upward with a constant velocity, V_0 , as illustrated in the figure. Because of viscous forces the belt picks up a film of fluid of thickness h. Gravity tends to make the fluid drain down the belt. Assume that the flow is laminar, steady, and fully developed.



$$\rho\left(\frac{\partial u}{\partial t} + u\frac{\partial u}{\partial x} + v\frac{\partial u}{\partial y} + w\frac{\partial u}{\partial z}\right) = -\frac{\partial p}{\partial x} + \mu\left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 u}{\partial z^2}\right) + \rho g_x$$

$$\rho\left(\frac{\partial v}{\partial t} + u\frac{\partial v}{\partial x} + v\frac{\partial v}{\partial y} + w\frac{\partial v}{\partial z}\right) = -\frac{\partial p}{\partial y} + \mu\left(\frac{\partial^2 v}{\partial x^2} + \frac{\partial^2 v}{\partial y^2} + \frac{\partial^2 v}{\partial z^2}\right) + \rho g_y$$

$$\rho\left(\frac{\partial w}{\partial t} + u\frac{\partial w}{\partial x} + v\frac{\partial w}{\partial y} + w\frac{\partial w}{\partial z}\right) = -\frac{\partial p}{\partial z} + \mu\left(\frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} + \frac{\partial^2 w}{\partial z^2}\right) + \rho g_z$$