SLEIGH

A Language for Rapid Processor Specification Last updated September 5, 2019 Originally published December 16, 2005

Table of Contents

1. Introduction to P-Code	. 2
1.1. Address Spaces	3
1.2. Varnodes	. 3
1.3. Operations	. 4
2. Basic Specification Layout	5
2.1. Comments	. 5
2.2. Identifiers	. 5
2.3. Strings	. 5
2.4. Integers	. 5
2.5. White Space	
3. Preprocessing	6
3.1. Including Files	
3.2. Preprocessor Macros	6
3.3. Conditional Compilation	
4. Basic Definitions	
4.1. Endianess Definition	
4.2. Alignment Definition	
4.3. Space Definitions	
4.4. Naming Registers	
4.5. Bit Range Registers	
4.6. User-Defined Operations	
5. Introduction to Symbols	
5.1. Notes on Namespaces	
5.2. Predefined Symbols	
6. Tokens and Fields	
6.1. Defining Tokens and Fields	
6.2. Fields as Family Symbols	
6.3. Attaching Alternate Meanings to Fields	
6.4. Context Variables	
7. Constructors	
7.1. The Five Sections of a Constructor	
7.2. The Table Header	
7.3. The Display Section	
7.4. The Bit Pattern Section	
7.5. Disassembly Actions Section	
7.6. The With Block	
7.7. The Semantic Section	
7.8. Tables	
7.9. P-code Macros	
7.10. Build Directives	
7.11. Delay Slot Directives	
8. Using Context	
8.1. Basic Use of Context Variables	

	8.2. Local Context Change	41
	8.3. Global Context Change	42
9	P-code Tables	4:

History

This document describes the syntax for the SLEIGH processor specification language, which was developed for the GHIDRA project. The language that is now called SLEIGH has undergone several redesign iterations, but it can still trace its heritage from the language SLED, from whom its name is derived. SLED, the "Specification Language for Encoding and Decoding", was defined by Norman Ramsey and Mary F. Fernandez as a concise way to define the translation, in both directions, between machine instructions and their corresponding assembly statements. This facilitated the development of architecture independent disassemblers and assemblers, such as the New Jersey Machine-code Toolkit.

The direct predecessor of SLEIGH was an implementation of SLED for GHIDRA, which concentrated on its reverse-engineering capabilities. The main addition of SLEIGH is the ability to provide semantic descriptions of instructions for data-flow and decompilation analysis. This piece of SLEIGH was originally a separate language, the Semantic Syntax Language (SSL), very loosely based on concepts and a language of the same name developed by Cristina Cifuentes, Mike Van Emmerik and Norman Ramsey, for the University of Queensland Binary Translator (UQBT) project.

Overview

SLEIGH is a language for describing the instruction sets of general purpose microprocessors, in order to facilitate the reverse engineering of software written for them. SLEIGH was designed for the GHI-DRA reverse engineering platform and is used to describe microprocessors with enough detail to facilitate two major components of GHIDRA, the disassembly and decompilation engines. For disassembly, SLEIGH allows a concise description of the translation from the bit encoding of machine instructions to human-readable assembly language statements. Moreover, it does this with enough detail to allow the disassembly engine to break apart the statement into the mnemonic, operands, sub-operands, and associated syntax. For decompilation, SLEIGH describes the translation from machine instructions into *p-code*. P-code is a Register Transfer Language (RTL), distinct from SLEIGH, designed to specify the *semantics* of machine instructions. By *semantics*, we mean the detailed description of how an instruction actually manipulates data, in registers and in RAM. This provides the foundation for the data-flow analysis performed by the decompiler.

A SLEIGH specification typically describes a single microprocessor and is contained in a single file. The term *processor* will always refer to this target of the specification.

Italics are used when defining terms and for named entities. Bold is used for SLEIGH keywords.

1. Introduction to P-Code

Although p-code is a distinct language from SLEIGH, because a major purpose of SLEIGH is to specify the translation from machine code to p-code, this document serves as a primer for p-code. The key concepts and terminology are presented in this section, and more detail is given in Section 7.7, "The Semantic Section". There is also a complete set of tables which list syntax and descriptions for p-code operations in the Appendix.

The design criteria for p-code was to have a language that looks much like modern assembly instruction sets but capable of modeling any general purpose processor. Code for different processors can be translated in a straightforward manner into p-code, and then a single suite of analysis software can be used to do data-flow analysis and decompilation. In this way, the analysis software becomes *retargetable*, and it

isn't necessary to redesign it for each new processor being analyzed. It is only necessary to specify the translation of the processor's instruction set into p-code.

So the key properties of p-code are

- The language is machine independent.
- The language is designed to model general purpose processors.
- Instructions operate on user defined registers and address spaces.
- All data is manipulated explicitly. Instructions have no indirect effects.
- Individual p-code operations mirror typical processor tasks and concepts.

SLEIGH is the language which specifies the translation from a machine instruction to p-code. It specifies both this translation and how to display the instruction as an assembly statement.

A model for a particular processor is built out of three concepts: the *address space*, the *varnode*, and the *operation*. These are generalizations of the computing concepts of RAM, registers, and machine instructions respectively.

1.1. Address Spaces

An *address* space for p-code is a generalization of the indexed memory (RAM) that a typical processor has access to, and it is defined simply as an indexed sequence of memory *words* that can be read and written by p-code. In almost all cases, a *word* of the space is a *byte* (8 bits), and we will usually use the term *byte* instead of *word*. However, see the discussion of the **wordsize** attribute of address spaces below.

The defining characteristics of a space are its name and its size. The size of a space indicates the number of distinct indices into the space and is usually given as the number of bytes required to encode an arbitrary index into the space. A space of size 4 requires a 32 bit integer to specify all indices and contains 2³² bytes. The index of a byte is usually referred to as the *offset*, and the offset together with the name of the space is called the *address* of the byte.

Any manipulation of data that p-code operations perform happens in some address space. This includes the modeling of data stored in RAM but also includes the modeling of processor registers. Registers must be modeled as contiguous sequences of bytes at a specific offset (see the definition of varnodes below), typically in their own distinct address space. In order to facilitate the modeling of many different processors, a SLEIGH specification provides complete control over what address spaces are defined and where registers are located within them.

Typically, a processor can be modeled with only two spaces, a *ram* address space that represents the main memory accessible to the processor via its data-bus, and a *register* address space that is used to implement the processor's registers. However, the specification designer can define as many address spaces as needed.

There is one address space that is automatically defined for a SLEIGH specification. This space is used to allocate temporary storage when the SLEIGH compiler breaks down the expressions describing processor semantics into individual p-code operations. It is called the *unique* space. There is also a special address space, called the *const* space, used as a placeholder for constant operands of p-code instructions. For the most part, a SLEIGH specification doesn't need to be aware of this space, but it can be used in certain situations to force values to be interpreted as constants.

1.2. Varnodes

A *varnode* is the unit of data manipulated by p-code. It is simply a contiguous sequence of bytes in some address space. The two defining characteristics of a varnode are

- The address of the first byte.
- The number of bytes (size).

With the possible exception of constants treated as varnodes, there is never any distinction made between one varnode and another. They can have any size, they can overlap, and any number of them can be defined.

Varnodes by themselves are typeless. An individual p-code operation forces an interpretation on each varnode that it uses, as either an integer, a floating-point number, or a boolean value. In the case of an integer, the varnode is interpreted as having a big endian or little endian encoding, depending on the specification (see Section 4.1, "Endianess Definition"). Certain instructions also distinguish between signed and unsigned interpretations. For a signed integer, the varnode is considered to have a standard twos complement encoding. For a boolean interpretation, the varnode must be a single byte in size. In this special case, the zero encoding of the byte is considered a *false* value and an encoding of 1 is a *true* value.

These interpretations only apply to the varnode for a particular operation. A different operation can interpret the same varnode in a different way. Any consistent meaning assigned to a particular varnode must be provided and enforced by the specification designer.

1.3. Operations

P-code is intended to emulate a target processor by substituting a sequence of p-code operations for each machine instruction. Thus every p-code operation is naturally associated with the address of a specific machine instruction, but there is usually more than one p-code operation associated with a single machine instruction. Except in the case of branching, p-code operations have fall-through control flow, both within and across machine instructions. For a single machine instruction, the associated p-code operations execute from first to last. And if there is no branching, execution picks up with the first operation corresponding to the next machine instruction.

Every p-code operation can take one or more varnodes as input and can optionally have one varnode as output. The operation can only make a change to this *output varnode*, which is always indicated explicitly. Because of this rule, all manipulation of data is explicit. The operations have no indirect effects. In general, there is absolutely no restriction on what varnodes can be used as inputs and outputs to p-code operations. The only exceptions to this are that constants cannot be used as output varnodes and certain operations impose restrictions on the *size* of their varnode operands.

The actual operations should be familiar to anyone who has studied general purpose processor instruction sets. They break up into groups.

Table 1. P-code Operations

Operation Category	List of Operations
Data Moving	COPY, LOAD, STORE
Arithmetic	INT_ADD, INT_SUB, INT_CARRY, INT_SCARRY, INT_SBORROW, IN-T_2COMP, INT_MULT, INT_DIV, INT_SDIV, INT_REM, INT_SREM
Logical	<pre>INT_NEGATE, INT_XOR, IN- T_AND, INT_OR, INT_LEFT, IN- T_RIGHT, INT_SRIGHT, POP- COUNT</pre>

Operation Category	List of Operations
Integer Comparison	INT_EQUAL, INT_NOTEQUAL, IN- T_SLESS, INT_SLESSEQUAL, IN- T_LESS, INT_LESSEQUAL
Boolean	BOOL_NEGATE, BOOL_XOR, BOOL_AND, BOOL_OR
Floating Point	FLOAT_ADD, FLOAT_SUB, FLOAT_MULT, FLOAT_DIV, FLOAT_NEG, FLOAT_ABS, FLOAT_SQRT, FLOAT_NAN
Floating Point Compare	FLOAT_EQUAL, FLOAT_NOTEQUAL, FLOAT_LESS, FLOAT_LESSEQUAL
Floating Point Conversion	INT2FLOAT, FLOAT2FLOAT, TRUNC, CEIL, FLOOR, ROUND
Branching	BRANCH, CBRANCH, BRANCHIND, CALL, CALLIND, RETURN
Extension/Truncation	INT_ZEXT, INT_SEXT, PIECE, SUBPIECE
Managed Code	CPOOLREF, NEW

We postpone a full discussion of the individual operations until Section 7.7, "The Semantic Section".

2. Basic Specification Layout

A SLEIGH specification is typically contained in a single file, although see Section 3.1, "Including Files". The file must follow a specific format as parsed by the SLEIGH compiler. In this section, we list the basic formatting rules for this file as enforced by the compiler.

2.1. Comments

Comments start with the '#' character and continue to the end of the line. Comments can appear anywhere except the *display section* of a constructor (see Section 7.3, "The Display Section") where the '#' character will be interpreted as something that should be printed in disassembly.

2.2. Identifiers

Identifiers are made up of letters a-z, capitals A-Z, digits 0-9 and the characters '.' and '_'. An identifier can use these characters in any order and for any length, but it must not start with a digit.

2.3. Strings

String literals can be used, when specifying names and when specifying how disassembly should be printed, so that special characters are treated as literals. Strings are surrounded by the double quote character "" and all characters in between lose their special meaning.

2.4. Integers

Integers are specified either in a decimal format or in a standard *C-style* hexadecimal format by prepending the number with "0x". Alternately, a binary representation of an integer can be given by prepending the string of '0' and '1' characters with "0b".

```
1006789
0xf5CC5
0xf5cc5
0b11110101110011000101
```

Numbers are treated as unsigned except when used in patterns where they are treated as signed (see Section 7.4, "The Bit Pattern Section"). The number of bytes used to encode the integer when specifying the semantics of an instruction is inferred from other parts of the syntax (see Section 7.3, "The Display Section"). Otherwise, integers should be thought of as having arbitrary precision. Currently, SLEIGH stores integers internally with 64 bits of precision.

2.5. White Space

White space characters include space, tab, line-feed, vertical line-feed, and carriage-return ('', '\t', '\r', '\v', '\n'). Variations in spacing have no effect on the parsing of the file except in string literals.

3. Preprocessing

SLEIGH provides support for simple file inclusion, macros, and other basic preprocessing functions. These are all invoked with directives that start with the '@' character, which must be the first character in the line.

3.1. Including Files

In general a single SLEIGH specification is contained in a single file, and the compiler is invoked on one file at a time. Multiple files can be put together for one specification by using the @include directive. This must appear at the beginning of the line and is followed by the path name of the file to be included, enclosed in double quotes.

```
@include "example.slaspec"
```

Parsing proceeds as if the entire line is replaced with the contents of the indicated file. Multiple inclusions are possible, and the included files can have their own @include directives.

3.2. Preprocessor Macros

SLEIGH allows simple (unparameterized) macro definitions and expansions. A macro definition occurs on one line and starts with the @define directive. This is followed by an identifier for the macro and then a string to which the macro should expand. The string must either be a proper identifier itself or surrounded with double quotes. The macro can then be expanded with typical "\$(identifier)" syntax at any other point in the specification following the definition.

```
@define ENDIAN "big"
    ...
define endian=$(ENDIAN);
```

This example defines a macro identified as *ENDIAN* with the string "big", and then expands the macro in a later SLEIGH statement. Macro definitions can also be made from the command line and in the

".spec" file, allowing multiple specification variations to be derived from one file. SLEIGH also has an @undef directive which removes the definition of a macro from that point on in the file.

```
@undef ENDIAN
```

3.3. Conditional Compilation

SLEIGH supports several directives that allow conditional inclusion of parts of a specification, based on the existence of a macro, or its value. The lines of the specification to be conditionally included are bounded by one of the @if... directives described below and at the bottom by the @endif directive. If the condition described by the @if... directive is true, the bounded lines are evaluated as part of the specification, otherwise they are skipped. Nesting of these directives is allowed: a second @if... @endif pair can occur inside an initial @if and @endif.

3.3.1. @ifdef and @ifndef

The **@ifdef** directive is followed by a macro identifier and evaluates to true if the macro is defined. The **@ifndef** directive is similar except it evaluates to true if the macro identifier is *not* defined.

```
@ifdef ENDIAN
define endian=$(ENDIAN);
@else
define endian=little;
@endif
```

This directive can only take a single identifier as an argument, any other form is flagged as an error. For logically combining a test of whether a macro is defined with other tests, use the **defined** operator in an @if or @elif directive (See below).

3.3.2. @if

The @if directive is followed by a boolean expression with macros as the variables and strings as the constants. Comparisons between macros and strings are currently limited to string equality or inequality. But individual comparisons can be combined arbitrarily using parentheses and the boolean operators '&&', '||', and '^^'. These represent a *logical and*, a *logical or*, and a *logical exclusive-or* operation respectively. It is possible to test whether a particular macro is defined within the boolean expression for an @if directive, by using the defined operator. This exists as a keyword and a functional operator only within a preprocessor boolean expression. The defined keyword takes as argument a macro identifier, and it evaluates to true if the macro is defined.

```
@if defined(X_EXTENSION) || (VERSION == "5")
...
@endif
```

3.3.3. @else and @elif

An @else directive splits the lines bounded by an @if directive and an @endif directive into two parts. The first part is included in the processing if the initial @if directive evaluates to true, otherwise the second part is included.

The @elif directive splits the bounded lines up as with @else, but the second part is included only if the previous @if was false and the condition specified in the @elif itself is true. Between one @if and @en-

dif pair, there can be multiple @elif directives, but only one @else, which must occur after all the @elif directives.

```
@if PROCESSOR == "mips"
@ define ENDIAN "big"
@elif ((PROCESSOR=="x86")&&(OS!="win"))
@ define ENDIAN "little"
@else
@ define ENDIAN "unknown"
@endif
```

4. Basic Definitions

SLEIGH files must start with all the definitions needed by the rest of the specification. All definition statements start with the keyword **define** and end with a semicolon ';'.

4.1. Endianess Definition

The first definition in any SLEIGH specification must be for endianess. Either

This defines how the processor interprets contiguous sequences of bytes as integers. It effects how integer fields within an instruction are interpreted (see Section 6.1, "Defining Tokens and Fields"), and it also effects the details of how the processor is supposed to implement atomic operations like integer addition and integer compare. The specification designer should only need to worry about these details when labeling instruction fields, otherwise the specification language will hide endianess issues.

4.2. Alignment Definition

An alignment definition looks like

```
define alignment=integer;
```

This specifies the byte alignment of instructions within their address space. It defaults to 1 or no alignment. When disassembling an instruction at a particular, the disassembler checks the alignment of the address against this value and can opt to flag an unaligned instruction as an error.

4.3. Space Definitions

The definition of an address space looks like

```
define space spacename attributes ;
```

The *spacename* is the name of the new space, and *attributes* looks like zero or more of the following lines:

```
type=(ram_space|rom_space|register_space)
size=integer
default
wordsize=integer
```

The only required attribute is **size** which specifies the number of bytes needed to address any byte within the space, for example a 32-bit address space has size 4.

A space of type **ram_space** is defined as follows:

- · It is read/write.
- It is part of the standard memory map of the processor.
- It is addressable in the sense that the processor may load and store from dynamic pointers into the space.

A space of type **register_space** is intended to model the processor's general-purpose registers. In terms of accessing and manipulating data within the space, SLEIGH and p-code make no distinction between the type **ram_space** or the type **register_space**. But there are still some distinguishing properties of a space labeled with **register_space**.

- It is read/write.
- It is *not* part of the standard memory map of the processor.
- In terms of GHIDRA, there will not be separate windows for the space and references into the space will not be stored.
- Named symbols within the space will have Register objects associated with them in GHIDRA.
- It is *not* addressable. Data-flow analysis will assume that data within the space cannot be manipulated indirectly via pointer, so there is no pointer aliasing. Make sure this is true!

A space of type **rom_space** has seen little use so far but is intended to be the same as a **ram_space** that is not writable.

At least one space needs to be labeled with the **default** attribute. This should be the space that the processor accesses with its main address bus. In terms of the rest of the specification file, this sets the default space referred to by the '*' operator (see Section 7.7.1.2, "The '*' Operator"). It also has meaning to GHIDRA.

The average 32-bit processor requires only the following two space definitions.

```
define space ram type=ram_space size=4 default;
define space register type=register_space size=4;
```

The **wordsize** attribute can be used to specify the size of the memory location referred to with a single address. If a space has **wordsize** two, then each address of the space refers to 16 bits of data, rather than 8 bits. If the space has **size** two, then there are still 2^{16} different addresses, but since each address accesses two bytes, there are twice as many bytes, 2^{17} , in the space. If the **wordsize** attribute is not specified, the size of a memory location defaults to one byte (8 bits).

4.4. Naming Registers

The general purpose registers of the processors can be named with the following define syntax:

```
define spacename offset=integer size=integer stringlist ;
```

A *stringlist* is either a single string or a white space separated list of strings in square brackets '[' and ']'. A string of just "_" indicates a skip in the sequence for that definition. The offset corresponding to that position in the list of names will not have a varnode defined at it.

This defines specific varnodes within the indicated address space. Each name in the list is assigned to a varnode in turn starting at the indicated offset within the space. Each varnode occupies the indicated number of bytes in size. There is no restriction on size, and by reusing the same offset in different **define** statements, overlapping varnodes are allowed. This is most often used to give registers their standard names but could be used to label any semantic variable that might need to be accessed globally by the processor. Overlapping register sequences like the x86 EAX/AX/AL can be easily modeled with overlapping varnode definitions.

Here is a typical example of register definition:

```
define register offset=0 size=4
    [EAX ECX EDX EBX ESP EBP ESI EDI ];
define register offset=0 size=2
    [AX _ CX _ DX _ BX _ SP _ BP _ SI _ DI];
define register offset=0 size=1
    [AL AH _ _ CL CH _ _ DL DH _ _ BL BH ];
```

4.5. Bit Range Registers

Many processors define registers that either consist of a single bit or otherwise don't use an integral number of bytes. A recurring example in many processors is the status register which is further subdivided into the overflow and result flags for the arithmetic instructions. These flags are typically have labels like ZF for the zero flag or CF for the carry flag and can be considered logical registers contained within the status register. SLEIGH allows registers to be defined like this using the **define bitrange** statement, but there are some important caveats with its use. A bit register like this is problematic for the underlying p-code instructions that SLEIGH models because the smallest object they can manipulate directly is a byte. In order to manipulate single bits, p-code must use a combination of bitwise logical, extension, and truncation operations. So a register defined as a bit range is not really a varnode as described in Section 1.2, "Varnodes", but is really just a signal to the SLEIGH compiler to fill in the proper operators to simulate the bit manipulation. Using this feature may greatly increase the complexity of the compiled specification with little indication within the specification file itself.

A bit range register must be defined on top of another normal register. In this example, *statusreg* is defined first as a 4 byte register, and the bit registers themselves are built by the following **define bitrange** statement. A single bit register definition consists of an identifier for the register, followed by '=', then the name of the register containing the bits, and finally a pair of numbers in square brackets. The first number indicates the lowest significant bit in the containing register of the bit range, where bit 0 is the least significant bit. The second number indicates the number of bits in the new register. Multiple definitions can be included in a single **define bitrange** statement, and the command is finally terminated with a semicolon. In the example, three new registers are defined on top of *statusreg*, each made up of 1 bit. The new registers *zf*, *cf*, and *sf* represent the tenth, eleventh, and twelfth bit of *statusreg* respectively.

The syntax for defining a new bit register is consistent with the pseudo bit range operator, described in Section 7.7.1.5, "Bit Range Operator", and the resulting symbol is really just a placeholder for this operator. Whenever SLEIGH sees this symbol it generates p-code precisely as if the designer had used the bit range operator instead. Section 7.7.1.5, "Bit Range Operator", provides some additional details about how p-code is generated, which apply to the use of bit range registers.

If a defined bit range happens to fall on byte boundaries, the new symbol will in fact be a normal varnode, so the **define bitrange** statement can be used as an alternate syntax for defining overlapping registers.

4.6. User-Defined Operations

The specification designer can define new p-code operations using a **define pcodeop** statement. This statement automatically reserves an internal form for the new p-code operation and associates an identifier with it. This identifier can then be used in semantic expressions (see Section 7.7.1.8, "User-Defined Operations"). The following example defines a new p-code operation *arctan*.

define pcodeop arctan;

This construction should be used sparingly. The definition does not specify how the new operation is supposed to actually manipulate data, and any analysis routines cannot know what the specification designer intended. The operation will be treated as a black box. It will hold its place in syntax trees, and the routines will understand how data flows into and out of it. But, no other analysis will be possible.

New operations should be defined only after considering the above points and the general philosophy of p-code. The designer should have a detailed description of the new operation in mind, even though this cannot be put in the specification. If it all possible, the operation should be atomic, with specific inputs and outputs, and with no side-effects. The most common use of a new operation is to encapsulate actions that are too esoteric or too complicated to implement.

5. Introduction to Symbols

After the definition section, we are prepared to start writing the body of the specification. This part of the specification shows how the bits in an instruction break down into opcodes, operands, immediate values, and the other pieces of an instruction. Then once this is figured out, the specification must also describe exactly how the processor would manipulate the data and operands if this particular instruction were executed. All of SLEIGH revolves around these two major tasks of disassembling and following semantics. It should come as no surprise then that the primary symbols defined and manipulated in the specification all have two key properties.

- 1. How does the symbol get displayed as part of the disassembly?
- 2. What semantic variable is associated with the symbol, and how is it constructed?

Formally a Specific Symbol is defined as an identifier associated with

- 1. A string displayed in disassembly.
- 2. varnode used in semantic actions, and any p-code used to construct that varnode.

The named registers that we defined earlier are the simplest examples of specific symbols (see Section 4.4, "Naming Registers"). The symbol identifier itself is the string that will get printed in disassembly and the varnode associated with the symbol is the one constructed by the define statement.

The other crucial part of the specification is how to map from the bits of a particular instruction to the specific symbols that apply. To this end we have the *Family Symbol*, which is defined as an identifier associated with a map from machine instructions to specific symbols.

Family Symbol: Instruction Encodings => Specific Symbols

The set of instruction encodings that map to a single specific symbol is called an *instruction pattern* and is described more fully in Section 7.4, "The Bit Pattern Section". In most cases, this can be thought of as a mask on the bits of the instruction and a value that the remaining unmasked bits must match. At any rate, the family symbol identifier, when taken out of context, represents the entire collection of specific symbols involved in this map. But in the context of a specific instruction, the identifier represents the one specific symbol associated with the encoding of that instruction by the family symbol map.

Given these maps, the idea of the specification is to build up more and more complicated family symbols until we have a single root symbol. This gives us a single map from the bits of an instruction to the full disassembly of it and to the sequence of p-code instructions that simulate the instruction.

The symbol responsible for combining smaller family symbols is called a *table*, which is fully described in Section 7.8, "Tables". Any *table* symbol can be used in the definition of other *table* symbols until the root symbol is fully described. The root symbol has the predefined identifier *instruction*.

5.1. Notes on Namespaces

Almost all identifiers live in the same global "scope". The global scope includes

- Names of address spaces
- · Names of tokens
- · Names of fields
- Names of user-defined p-code ops
- · Names of registers
- Names of macros (see Section 7.9, "P-code Macros")
- Names of tables (see Section 7.8, "Tables")

All of the names in this scope must be unique. Each individual *constructor* (defined in Section 7, "Constructors") defines a local scope for operand names. As with most languages, a local symbol with the same name as a global symbol *hides* the global symbol while that scope is in affect.

5.2. Predefined Symbols

We list all of the symbols that are predefined by SLEIGH.

Table 2. Predefined Symbols

Identifier	Meaning	
instruction	The root instruction table.	
const	Special address space for building constant varnodes.	
unique	Address space for allocating temporary registers.	
inst_start	Offset of the address of the current instruction.	
inst_next Offset of the address of the next instruction.		

Identifier	Meaning	
epsilon	A special identifier indicating an empty bit pattern.	

The most important of these to be aware of are <code>inst_start</code> and <code>inst_next</code>. These are family symbols which map in the context of particular instruction to the integer offset of either the address of the instruction or the address of the next instruction respectively. These are used in any relative branching situation. The other symbols are rarely used. The <code>const</code> and <code>unique</code> identifiers are address spaces. The <code>epsilon</code> identifier is inherited from SLED and is a specific symbol equivalent to the constant zero. The <code>instruction</code> identifier is the root instruction table.

6. Tokens and Fields

6.1. Defining Tokens and Fields

A *token* is one of the byte-sized pieces that make up the machine code instructions being modeled. Instruction *fields* must be defined on top of them. A *field* is a logical range of bits within an instruction that can specify an opcode, or an operand etc. Together tokens and fields determine the basic interpretation of bits and how many bytes the instruction takes up. To define a token and the fields associated with it, we use the **define token** statement.

```
define token tokenname ( integer )
  fieldname=(integer,integer) attributelist
   ...
;
```

The first part of the definition defines the name of a token and the number of bits it uses (this must be a multiple of 8). Following this there are one or more field declarations specifying the name of the field and the range of bits within the token making up the field. The size of a field does *not* need to be a multiple of 8. The range is inclusive where the least significant bit in the token is labeled 0. The endianess of the processor will effect this labeling when defining tokens that are bigger than 1 byte. After each field declaration, there can be zero or more of the following attribute keywords:

```
signed
hex
dec
```

These attributes are defined in the next section. There can be any manner of repeats and overlaps in the fields so long as they all have different names.

6.2. Fields as Family Symbols

Fields are the most basic form of family symbol; they define a natural map from instruction bits to a specific symbol as follows. We take the set of bits within the instruction as given by the field's defining range and treat them as an integer encoding. The resulting integer is both the display portion and the semantic meaning of the specific symbol. The display string is obtained by converting the integer into either a decimal or hexadecimal representation (see below), and the integer is treated as a constant varnode in any semantic action.

The attributes of the field affect the resulting specific symbol in obvious ways. The **signed** attribute determines whether the integer encoding should be treated as just an unsigned encoding or if a twos-com-

plement encoding should be used to obtain a signed integer. The **hex** or **dec** attributes describe whether the integer should be displayed with a hexadecimal or decimal representation. The default is hexadecimal. [Currently the **dec** attribute is not supported]

6.3. Attaching Alternate Meanings to Fields

The default interpretation of a field is probably the most natural but of course processors interpret fields within an instruction in a wide variety of ways. The **attach** keyword is used to alter either the display or semantic meaning of fields into the most common (and basic) interpretations. More complex interpretations must be built up out of tables.

6.3.1. Attaching Registers

Probably *the* most common processor interpretation of a field is as an encoding of a particular register. In SLEIGH this can be done with the **attach variables** statement:

attach variables fieldlist registerlist;

A *fieldlist* can be a single field identifier or a space separated list of field identifiers surrounded by square brackets. A *registerlist* must be a square bracket surrounded and space separated list of register identifiers as created with **define** statements (see Section Section 4.4, "Naming Registers"). For each field in the *fieldlist*, instead of having the display and semantic meaning of an integer, the field becomes a look-up table for the given list of registers. The original integer interpretation is used as the index into the list starting at zero, so a specific instruction that has all the bits in the field equal to zero yields the first register (a specific varnode) from the list as the meaning of the field in the context of that instruction. Note that both the display and semantic meaning of the field are now taken from the new register.

A particular integer can remain unspecified by putting a '_' character in the appropriate position of the register list or also if the length of the register list is less than the integer. A specific integer encoding of the field that is unspecified like this does *not* revert to the original semantic and display meaning. Instead this encoding is flagged as an invalid form of the instruction.

6.3.2. Attaching Other Integers

Sometimes a processor interprets a field as an integer but not the integer given by the default interpretation. A different integer interpretation of the field can be specified with an **attach values** statement.

attach values fieldlist integerlist;

The *integerlist* is surrounded by square brackets and is a space separated list of integers. In the same way that a new register interpretation is assigned to fields with an **attach variables** statement, the integers in the list are assigned to each field specified in the *fieldlist*. [Currently SLEIGH does not support unspecified positions in the list using a '_']

6.3.3. Attaching Names

It is possible to just modify the display characteristics of a field without changing the semantic meaning. The need for this is rare, but it is possible to treat a field as having influence on the display of the disassembly but having no influence on the semantics. Even if the bits of the field do have some semantic meaning, sometimes it is appropriate to define overlapping fields, one of which is defined to have no semantic meaning. The most convenient way to break down the required disassembly may not be the most

convenient way to break down the semantics. It is also possible to have symbols with semantic meaning but no display meaning (see Section 7.4.5, "Invisible Operands").

At any rate we can list the display interpretation of a field directly with an attach names statement.

```
attach names fieldlist stringlist;
```

The *stringlist* is assigned to each of the fields in the same manner as the **attach variables** and **attach values** statements. A specific encoding of the field now displays as the string in the list at that integer position. Field values greater than the size of the list are interpreted as invalid encodings.

6.4. Context Variables

SLEIGH supports the concept of *context variables*. For the most part processor instructions can be unambiguously decoded by examining only the bits of the instruction encoding. But in some cases, decoding may depend on the state of processor. Typically, the processor will have some set of status flags that indicate what mode is being used to process instructions. In terms of SLEIGH, a context variable is a *field* which is defined on top of a register rather than the instruction encoding (token).

```
define context contextreg
  fieldname=(integer,integer) attributelist
   ...
:
```

Context variables are defined with a **define context** statement. The keywords must be followed by the name of a defined register. The remaining part of the definition is nearly identical to the normal definition of fields. Each context variable defined on this register is listed in turn, specifying the name, the bit range, and any attributes. All the normal field attributes, **signed**, **dec**, and **hex**, can also be used for context variables.

Context variables introduce a new, dedicated, attribute: **noflow**. By default, globally setting a context variable affects instruction decoding from the point of the change, forward, following the flow of the instructions, but if the variable is labeled as **noflow**, any change is limited to a single instruction. (See Section 8.3.1, "Context Flow")

Once the context variable is defined, in terms of the specification syntax, it can be treated as if it were just another field. See Section 8, "Using Context", for a complete discussion of how to use context variables.

7. Constructors

Fields are the basic building block for family symbols. The mechanisms for building up from fields to the root *instruction* symbol are the *constructor* and *table*.

A *constructor* is the unit of syntax for building new symbols. In essence a constructor describes how to build a new family symbol, by describing, in turn, how to build a new display meaning, how to build a new semantic meaning, and how encodings map to these new meanings. A *table* is a set of one or more constructors and is the final step in creating a new family symbol identifier associated with the pieces defined by constructors. The name of the table is this new identifier, and it is this identifier which can be used in the syntax for subsequent constructors.

The difference between a constructor and table is slightly confusing at first. In short, the syntactical elements described in this chapter, for combining existing symbols into new symbols, are all used to de-

scribe a single constructor. Specifications for multiple constructors are combined to describe a single table. Since many tables are built with only one constructor, it is natural and correct to think of a constructor as a kind of table in and of itself. But it is only the table that has an actual family symbol identifier associated with it. Most of this chapter is devoted to describing how to define a single constructor. The issues involved in combining multiple constructors into a single table are addressed in Section 7.8, "Tables".

7.1. The Five Sections of a Constructor

A single complex statement in the specification file describes a constructor. This statement is always made up of five distinct sections that are listed below in the order in which the must occur.

- 1. Table Header
- 2. Display Section
- 3. Bit Pattern Sections
- 4. Disassembly Actions Section
- 5. Semantics Actions Section

The full set of rules for correctly writing each section is long and involved, but for any given constructor in a real specification file, the syntax typically fits on a single line. We describe each section in turn.

7.2. The Table Header

Every constructor must be part of a table, which is the element with an actual family symbol identifier associated with it. So each constructor starts with the identifier of the table it belongs to followed by a colon ':'.

model: ...

The above line starts the definition of a constructor that is part of the table identified as *mode1*. If the identifier has not appeared before, a new table is created. If other constructors have used the identifier, the new constructor becomes an additional part of that same table. A constructor in the root *instruction* table is defined by omitting the identifier.

: ...

The identifier *instruction* is actually reserved for the root table, but should not be used in the table header as the SLEIGH parser uses the blank identifier to help distinguish assembly mnemonics from operands (see Section 7.3.1, "Mnemonic").

7.3. The Display Section

The *display section* consists of all characters after the table header ':' up to the SLEIGH keyword **is**. The section's primary purpose is to assign disassembly display meaning to the constructor. The section's secondary purpose is to define local identifiers for the pieces out of which the constructor is being built. Characters in the display section are treated as literals with the following exceptions.

- · Legal identifiers are not treated literally unless
 - a. The identifier is surrounded by double quotes.
 - b. The identifier is considered a mnemonic (see below).
- The character '^' has special meaning.

- White space is trimmed from the beginning and end of the section.
- Other sequences of white space characters are condensed into a single space.

In particular, all punctuation except '^' loses its special meaning. Those identifiers that are not treated as literals are considered to be new, initially undefined, family symbols. We refer to these new symbols as the *operands* of the constructor. And for root constructors, these operands frequently correspond to the natural assembly operands. Thinking of it as a family symbol, the constructor's display meaning becomes the string of literals itself, with each identifier replaced with the display meaning of the symbol corresponding to that identifier.

```
model: (op1),op2 is ...
```

In the above example, a constructor for table mode1 is being built out of two pieces, symbol op1 and symbol op2. The characters '(', ')', and ',' become literal parts of the disassembly display for symbol mode1. After the display strings for op1 and op2 are found, they are inserted into the string of literals, forming the constructor's display string. The white space characters surrounding the op1 identifier are preserved as part of this string.

The identifiers op1 and op2 are local to the constructor and can mask global symbols with the same names. The symbols will (must) be defined in the following sections, but only their identifiers are established in the display section.

7.3.1. Mnemonic

If the constructor is part of the root instruction table, the first string of characters in the display section that does not contain white space is treated as the *literal mnemonic* of the instruction and is not considered a local symbol identifier even if it is legal.

```
:and (var1) is ...
```

In the above example, the string "var1" is treated as a symbol identifier, but the string "and" is considered to be the mnemonic of the instruction.

There is nothing that special about the mnemonic. As far as the display meaning of the constructor is concerned, it is just a sequence of literal characters. Although the current parser does not concern itself with this, the mnemonic of any assembly language instruction in general is used to guarantee the uniqueness of the assembly representation. It is conceivable that a forward engineering engine built on SLEIGH would place additional requirements on the mnemonic to assure uniqueness, but for reverse engineering applications there is no such requirement.

7.3.2. The '^' character

The '^' character in the display section is used to separate identifiers from other characters where there shouldn't be white space in the disassembly display. This can be used in any manner but is usually used to attach display characters from a local symbol to the literal characters of the mnemonic.

```
:bra^cc op1,op2 is ...
```

In the above example, "bra" is treated as literal characters in the resulting display string followed immediately, with no intervening spaces, by the display string of the local symbol cc. Thus the whole constructor actually has three operands, denoted by the three identifiers cc, op1, and op2.

If the '^' is used as the first (non-whitespace) character in the display section of a base constructor, this inhibits the first identifier in the display from being considered the mnemonic, as described in Section 7.3.1, "Mnemonic". This allows specification of less common situations, where the first part of the mnemonic, rather than perhaps a later part, needs to be considered as an operand. An initial '^' character can also facilitate certain recursive constructions.

7.4. The Bit Pattern Section

Syntactically, this section comes between the keyword **is** and the delimiter for the following section, either an '{' or an '['. The *bit pattern section* describes a constructor's *pattern*, the subset of possible instruction encodings that the designer wants to *match* the constructor being defined.

7.4.1. Constraints

The patterns required for processor specifications can almost always be described as a mask and value pair. Given a specific instruction encoding, we can decide if the encoding matches our pattern by looking at just the bits specified by the *mask* and seeing if they match a specific *value*. The fields, as defined in Section 6.1, "Defining Tokens and Fields", typically give us our masks. So to construct a pattern, we can simply require that the field take on a specific value, as in the example below.

```
:halt is opcode=0x15 { ...
```

Assuming the symbol *opcode* was defined as a field, this says that a root constructor with mnemonic "halt" matches any instruction where the bits defining this field have the value 0x15. The equation "opcode=0x15" is called a *constraint*.

The standard bit encoding of the integer is used when restricting the value of a field. This encoding is used even if an **attach** statement has assigned a different meaning to the field. The alternate meaning does not apply within the pattern. This can be slightly confusing, particularly in the case of an **attach values** statement, which provides an alternate integer interpretation of the field.

7.4.2. The '&' and '|' Operators

More complicated patterns are built out of logical operators. The meaning of these are fairly straightforward. We can force two or more constraints to be true at the same time, a *logical and* '&', or we can require that either one constraint or another must be true, a *logical or* '|'. By using these with constraints and parentheses for grouping, arbitrarily complicated patterns can be constructed.

```
:nop is (opcode=0 & mode=0) | (opcode=15) { ...
```

Of the two operators, the *logical and* is much more common. The SLEIGH compiler typically can group together several constraints that are combined with this operator into a single efficient mask/value check, so this operator is to be preferred if at all possible. The *logical or* operator usually requires two or more mask/value style checks to correctly implement.

7.4.3. Defining Operands and Invoking Subtables

The principle way of defining a constructor operand, left undefined from the display section, is done in the bit pattern section. If an operand's identifier is used by itself, not as part of a constraint, then the operand takes on both the display and semantic definition of the global symbol with the same identifier. The syntax is slightly confusing at first. The identifier must appear in the pattern as if it were a term in a sequence of constraints but without the operator and right-hand side of the constraint.

```
define token instr(32)
    opcode = (0,5)
    r1 = (6,10)
    r2 = (11,15);
attach variables [ r1 r2 ] [ reg0 reg1 reg2 reg3 ];
:add r1,r2 is opcode=7 & r1 & r2 { ...
```

This is a typical example. The *add* instruction must have the bits in the *opcode* field set specifically. But it also uses two fields in the instruction which specify registers. The r1 and r2 identifiers are defined to be local because they appear in the display section, but their use in the pattern section of the definition links the local symbols with the global register symbols defined as fields with attached registers. The constructor is essentially saying that it is building the full *add* instruction encoding out of the register fields r1 and r2 but is not specifying their value.

The syntax makes a little more sense keeping in mind this principle:

• The pattern must somehow specify all the bits and symbols being used by the constructor, even if the bits are not restricted to specific values.

The linkage from local symbol to global symbol will happen for any global identifier which represents a family symbol, including table symbols. This is in fact the principle mechanism for recursively building new symbols from old symbols. For those familiar with grammar parsers, a SLEIGH specification is in part a grammar specification. The terminal symbols, or tokens, are the bits of an instruction, and the constructors and tables are the non-terminating symbols. These all build up to the root instruction table, the grammar's start symbol. So this link from local to global is simply a statement of the grouping of old symbols into the new constructor.

7.4.4. Variable Length Instructions

There are some additional complexities to designing a specification for a processor with variable length instructions. Some initial portion of an instruction must always be parsed. But depending on the fields in this first portion, additional portions of varying lengths may need to be read. The key to incorporating this behavior into a SLEIGH specification is the token. Recall that all fields are built on top of a token which is defined to be a specific number of bytes. If a processor has fixed length instructions, the specification needs to define only a single token representing the entire instruction, and all fields are built on top of this one token. For processors with variable length instructions however, more than one token needs to be defined. Each token has different fields defined upon it, and the SLEIGH compiler can distinguish which tokens are involved in a particular constructor by examining the fields it uses. The tokens that are actually used by any matching constructors determine the final length of the instruction. SLEIGH has two operators that are specific to variable length instruction sets and that give the designer control over how tokens fit together.

7.4.4.1. The ';' Operator

The most important operator for patterns defining variable length instructions is the concatenation operator ';'. When building a constructor with fields from two or more tokens, the pattern must explicitly define the order of the tokens. In terms of the logic of the pattern expressions themselves, the ';' operator has the same meaning as the '&' operator. The combined expression matches only if both subexpressions are true. However, it also requires that the subexpressions involve multiple tokens and explicitly indicates an order for them.

```
define token base(8)
```

In the above example, we see the definitions of two different tokens, *base* and *immtoken*. For the first instruction, *inc*, the constructor uses fields *op* and *reg*, both defined on *base*. Thus, the pattern applies constraints to just a single byte, the size of base, in the corresponding encoding. The second instruction, *add*, uses fields *op* and *reg*, but it also uses field *imm16* contained in *immtoken*. The ';' operator indicates that token *base* (via its fields) comes first in the encoding, followed by *immtoken*. The constraints on *base* will therefore correspond to constraints on the first byte of the encoding, and the constraints on *immtoken* will apply to the second and third bytes. The length of the final encoding for *add* will be 3 bytes, the sum of the lengths of the two tokens.

If two pattern expressions are combined with the '&' or '|' operator, where the concatenation operator ';' is also being used, the designer must make sure that the tokens underlying each expression are the same and come in the same order. In the example *add* instruction for instance, the '&' operator combines the "op=3" and "reg" expressions. Both of these expressions involve only the token *base*, so the matching requirement is satisfied. The '&' and '|' operators can combine expressions built out of more than one token, but the tokens must come in the same order. Also these operators have higher precedence than the ';' operator, so parentheses may be necessary to get the intended meaning.

7.4.4.2. The '...' Operator

The ellipsis operator '...' is used to satisfy the token matching requirements of the '&' and '|' operators (described in the previous section), when the operands are of different lengths. The ellipsis is a unary operator applied to a pattern expression that extends its token length before it is combined with another expression. Depending on what side of the expression the ellipsis is applied, the expression's tokens are either right or left justified within the extension.

```
addrmode: reg is reg & mode=0 { ...
addrmode: #imm16 is mode=1; imm16 { ...

:xor "A",addrmode is op=4 ... & addrmode { ...
```

Extending the example from the previous section, we add a subtable *addrmode*, representing an operand that can be encoded either as a register, if *mode* is set to zero, or as an immediate value, if the *mode* bit is one. If the immediate value mode is selected, the operand is built by reading an additional two bytes directly from the instruction encoding. So the *addrmode* table can represent a 1 byte or a 3 byte encoding depending on the mode. In the following *xor* instruction, *addrmode* is used as an operand. The particular instruction is selected by encoding a 4 in the *op* field, so it requires a constraint on that field in the pattern expression. Since the instruction uses the *addrmode* operand, it must combine the constraint on *op* with the pattern for *addrmode*. But *op* involves only the token *base*, while *addrmode* may also involve *immtoken*. The ellipsis operator resolves the conflict by extending the *op* constraint to be whatever the length of *addrmode* turns out to be.

Since the *op* constraint occurs to the left of the ellipsis, it is considered left justified, and the matching requirement for '&' will insist that *base* is the first token in all forms of *addrmode*. This allows the *xor* instruction's constraint on *op* and the *addrmode* constraint on *mode* to be combined into constraints on a single byte in the final encoding.

7.4.5. Invisible Operands

It is not necessary for a global symbol, which is needed by a constructor, to appear in the display section of the definition. If the global identifier is used in the pattern section as it would be for a normal operand definition but the identifier was not used in the display section, then the constructor defines an *invisible operand*. Such an operand behaves and is parsed exactly like any other operand but there is absolutely no visible indication of the operand in the final display of the assembly instruction. The one common type of instruction that uses this is the relative branch (see Section 7.5.1, "Relative Branches") but it is otherwise needed only in more esoteric instructions. It is useful in situations where you need to break up the parsing of an instruction along lines that don't quite match the assembly.

7.4.6. Empty Patterns

Occasionally there is a need for an empty pattern when building tables. An empty pattern matches everything. There is a predefined symbol *epsilon* which has been traditionally used to indicate an empty pattern.

7.4.7. Advanced Constraints

A constraint does not have to be of the form "field = constant", although this is almost always what is needed. In certain situations, it may be more convenient to use a different kind of constraint. Special care should be taken when designing these constraints because they can substantially deviate from the mask/value model used to implement most constraints. These more general constraints are implemented by splitting it up into smaller states which can be modeled as a mask/value pair. This is all done automatically, and the designer may inadvertently create huge numbers of parsing states for a single constraint.

A constraint can actually be built out of arbitrary expressions. These *pattern expressions* are more commonly used in disassembly actions and are defined in Section 7.5.2, "General Actions and Pattern Expressions", but they can also be used in constraints. So in general, a constraint is any equation where the left-hand side is a single family symbol, the right-hand side is an arbitrary pattern expression, and the constraint operator is one of the following:

Table 3. Constraint Operators

Operator Name	Syntax
Integer equality	=
Integer inequality	!=
Integer less-than	<
Integer greater-than	>

For a particular instruction encoding, each variable evaluates to a specific integer depending on the encoding. A constraint is *satisfied* if, when all the variables are evaluated, the equation is true.

```
:xor r1,r2 is opcode=0xcd & r1 & r2 { r1 = r1 ^ r2; }
:clr r1 is opcode=0xcd & r1 & r2=r1 { r1 = 0; }
```

The above example illustrates a situation that does come up occasionally. A processor uses an exclusive-or instruction to clear a register by setting both operands of the instruction to the same register. The first line in the example illustrates such an instruction. However, processor documentation stipulates, and analysts prefer, that, in this case, the disassembler should print a pseudo-instruction *clr*. The distinguishing feature of *clr* from *xor* is that the two fields, specifying the two register inputs to *xor*, are equal.

The easiest way to specify this special case is with the general constraint, "r2 = r1", as in the second line of the example. The SLEIGH compiler will implement this by enumerating all the cases where r2 equals r1, creating as many states as there are registers. But the specification itself, at least, remains compact.

7.5. Disassembly Actions Section

After the bit pattern section, there can optionally be a section for doing dynamic calculations, which must be between square brackets. For certain kinds of instructions, there is a need to calculate values that depend on the specific bits of the instruction, but which cannot be obtained as an integer interpretation of a field or by building with an **attach values** statement. So SLEIGH provides a mechanism to build values of arbitrary complexity. This section is not intended to emulate the execution of the processor (this is the job of the semantic section) but is intended to produce only those values that are needed at disassembly time, usually for part of the disassembly display.

7.5.1. Relative Branches

The canonical example of an action at disassembly time is a branch relocation. A jump instruction encodes the address of where it jumps to as a relative offset to the instruction's address, for instance. But when we display the assembly, we want to show the absolute address of the jump destination. The correct way to specify this is to reserve an identifier in the display section which represents the absolute address, but then, instead of defining it in the pattern section, we define it in the disassembly action section as a function of the current address and the relative offset.

```
jmpdest: reloc is simm8 [ reloc=inst_next + simm8*4; ] { ...
```

The identifier *reloc* is reserved in the display section for this constructor, but the identifier is not defined in the pattern section. Instead, an invisible operand *simm8* is defined which is attached to a global field definition. The *reloc* identifier is defined in the action section as the integer obtained by adding a multiple of *simm8* to *inst_next*, a symbol predefined to be equal to the address of the following instruction (see Section 5.2, "Predefined Symbols"). Now *reloc* is a specific symbol with both semantic and display meaning equal to the desired absolute address. This address is calculated separately, at disassembly time, for every instruction that this constructor matches.

7.5.2. General Actions and Pattern Expressions

In general, the disassembly actions are encoded as a sequence of assignments separated by semicolons. The left-hand side of each statement must be a single operand identifier, and the right-hand side must be a *pattern expression*. A *pattern expression* is made up of both integer constants and family symbols that have retained their semantic meaning as integers, and it is built up out of the following typical operators:

Operator Name	Syntax
Integer addition	+
Integer subtraction	-
Integer multiplication	*
Integer division	/
Left-shift	<<
Arithmetic right-shift	>>
Bitwise and	\$and

Operator Name	Syntax
	& (within square brackets)
Bitwise or	\$or (within square brack- ets)
Bitwise xor	\$xor ^
Bitwise negation	~

For the sake of these expressions, integers are considered signed values of arbitrary precision. Expressions can also make use of parentheses. A family symbol can be used in an expression, only if it can be resolved to a particular specific symbol. This generally means that a global family symbol, such as a field, must be attached to a local identifier before it can be used.

The left-hand side of an assignment statement can be a context variable (see Section 6.4, "Context Variables"). An assignment to such a variable changes the context in which the current instruction is being disassembled and can potentially have a drastic effect on how the rest of the instruction is disassembled. An assignment of this form is considered local to the instruction and will not effect how other instructions are parsed. The context variable is reset to its original value before parsing other instructions. The disassembly action may also contain one or more **globalset** directives, which cause changes to context variables to become more permanent. This directive is distinct from the operators in a pattern expression and must be invoked as a separate statement. See Section 8, "Using Context", for a discussion of how to effectively use context variables and Section 8.3, "Global Context Change", for details of the **globalset** directive.

Note that there are two syntax forms for the logical operators in a pattern expression. When an expression is used as part of a constraint, the "\$and" and "\$or" forms of the operators must be used in order to distinguish the bitwise operators from the special pattern combining operators, '&' and ']' (as described in Section 7.4.2, "The '&' and ']' Operators"). However inside the square braces of the disassembly action section, '&' and ']' are interpreted as the usual logical operators.

7.6. The With Block

To avoid tedious repetition and to ease the maintenance of specifications already having many, many constructors and tables, the *with block* is provided. It is a syntactic construct that allows a designer to apply a table header, bit pattern constraints, and/or disassembly actions to a group of constructors. The block starts at the **with** directive and ends with a closing brace. All constructors within the block are affected:

In the example, both constructors are added to the table identified by *op1*. Both require the context field *mode* to be equal to 1. The listed constraints take the form described in Section 7.4, "The Bit Pattern Section", and they are joined to those given in the constructor statement as if prepended using '&'. Similarly, the actions take the form described in Section 7.5, "Disassembly Actions Section" and are prepended to the actions given in the constructor statement. Prepending the actions allows the statement

to override actions in the with block. Both technically occur, but only the last one has a noticeable effect. The above example could have been equivalently specified:

```
op1:reg is mode=1 & reg & ind=0 [ mode=2; mode=1; ] { ... }
op1:[ref] is mode=1 & reg & ind=1 [ mode=2; ] { ... }
```

The three parts (table header, bit pattern section, and disassembly actions section) of the with block are all optional. Any of them may be omitted, though omitting all of them is rather pointless. With blocks may also be nested. The innermost with block having a table header specifies the default header of the constructors it contains. The constraints and actions are combined outermost to innermost, left to right. Note that when a with block has a table header specifying a table that does not yet exist, the table is created immediately. Inside a with block that has a table header, a nested with block may specify the *instruction* table by name, as in "with instruction: {...}". Inside such a block, the rule regarding mnemonic literals is restored (see Section 7.3.1, "Mnemonic").

7.7. The Semantic Section

The final section of a constructor definition is the *semantic section*. This is a description of how the processor would manipulate data if it actually executed an instruction that matched the constructor. From the perspective of a single constructor, the basic idea is that all the operands for the constructor have been defined in the bit pattern or disassembly action sections as either specific or family symbols. In context, all the family symbols map to specific symbols, and the semantic section uses these and possibly other global specific symbols in statements that describe the action of the constructor. All specific symbols have a varnode associated with them, so within the semantic section, symbols are manipulated as if they were varnodes.

The semantic section for one constructor is surrounded by curly braces '{' and '}' and consists of zero or more statements separated by semicolons ';'. Most statements are built up out of C-like syntax, where the variables are the symbols visible to the constructor. There is a direct correspondence between each type of operator used in the statements and a p-code operation. The SLEIGH compiler generates p-code operations and varnodes corresponding to the SLEIGH operators and symbols by collapsing the syntax trees represented by the statements and creating temporary storage within the *unique* space when it needs to.

```
:add r1,r2 is opcode=0x26 \& r1 \& r2 \{ r1 = r1 + r2; \}
```

The above example generates exactly one integer addition operation, INT_ADD , where the input varnodes are r1 and r2 and the output varnode is r1.

7.7.1. Expressions

Expressions are built out of symbols and the binary and unary operators listed in Table 5, "Semantic Expression Operators and Syntax" in the Appendix. All expressions evaluate to an integer, floating point, or boolean value, depending on the final operation of the expression. The value is then used depending on the kind of statement. Most of the operators require that their input and output varnodes all be the same size (see Section 7.7.3, "Varnode Sizes"). The operators all have a precedence, which is used by the SLEIGH compiler to determine the ordering of the final p-code operations. Parentheses can be used within expressions to affect this order.

7.7.1.1. Arithmetic, Logical and Boolean Operators

For the most part these operators should be familiar to software developers. The only real differences arise from the fact that varnodes are typeless. So for instance, there has to be separate operators to distin-

guish between dividing unsigned numbers '/', dividing signed numbers 's/', and dividing floating point numbers 'f/'.

Carry, borrow, and overflow calculations are implemented with separate operations, rather than having indirect effects with the arithmetic operations. Thus the *INT_CARRY*, *INT_SCARRY*, and *INT_SBOR-ROW* operations may be unfamiliar to some people in this form (see the descriptions in the Appendix).

7.7.1.2. The '*' Operator

The dereference operator, which generates *LOAD* operations (and *STORE* operations), has slightly unfamiliar syntax. The '*' operator, as is usual in many programming languages, indicates that the affected variable is a pointer and that the expression is *dereferencing* the data being pointed to. Unlike most languages, in SLEIGH, it is not immediately clear what address space the variable is pointing into because there may be multiple address spaces defined. In the absence of any other information, SLEIGH assumes that the variable points into the *default* space, as labeled in the definition of one of the address spaces with the **default** attribute. If that is not the space desired, the default can be overridden by putting the identifier for the space in square brackets immediately after the '*'.

It is also frequently not clear what the size of the dereferenced data is because the pointer variable is typeless. The SLEIGH compiler can frequently deduce what the size must be by looking at the operation in the context of the entire statement (see Section 7.7.3, "Varnode Sizes"). But in some situations, this may not be possible, so there is a way to specify the size explicitly. The operator can be followed by a colon ':' and an integer indicating the number of bytes being dereferenced. This can be used with or without the address space override. We give an example of each kind of override in the example below.

```
:load r1,[r2] is opcode=0x99 & r1 & r2 { r1 = * r2; }
:load2 r1,[r2] is opcode=0x9a & r1 & r2 { r1 = *[other] r2; }
:load3 r1,[r2] is opcode=0x9b & r1 & r2 { r1 = *:2 r2; }
:load4 r1,[r2] is opcode=0x9c & r1 & r2 { r1 = *[other]:2 r2; }
```

Keep in mind that the address represented by the pointer is not a byte address if the **wordsize** attribute is set to something other than one.

7.7.1.3. Extension

Most processors have instructions that extend small values into big values, and many instructions do these minor data manipulations implicitly. In keeping with the p-code philosophy, these operations must be specified explicitly with the *INT_ZEXT* and *INT_SEXT* operators in the semantic section. The *IN-T_ZEXT*, does a so-called *zero extension*. The low-order bits are copied from the input, and any remaining high-order bits in the result are set to zero. The *INT_SEXT*, does a *signed extension*. The low-order bits are copied from the input, but any remaining high-order bits in the result are set to the value of the high-order bit of the input. The *INT_ZEXT* operation is invoked with the **zext** operator, and the *IN-T_SEXT* operation is invoked with the **sext** operator.

7.7.1.4. Truncation

There are two forms of syntax indicating a truncation of the input varnode. In one the varnode is followed by a colon ':' and an integer indicating the number of bytes to copy into the output, starting with the least significant byte. In the second form, the varnode is followed by an integer, surrounded by parentheses, indicating the number of least significant bytes to truncate from the input. This second form doesn't directly specify the size of the output, which must be inferred from context.

```
:split r1,lo,hi is opcode=0x81 & r1 & lo & hi {
```

```
lo = r1:4;
hi = r1(4);
}
```

This is an example using both forms of truncation to split a large value r1 into two smaller pieces, lo and hi. Assuming r1 is an 8 byte value, lo receives the least significant half and hi receives the most significant half.

7.7.1.5. Bit Range Operator

A specific subrange of bits within a varnode can be explicitly referenced. Depending on the range, this may amount to just a variation on the truncation syntax described earlier. But for this operator, the size and boundaries of the range do not have to be restricted to byte alignment.

```
:bit3 r1,r2 is op=0x7e & r1 & r2 { r1 = zext(r2[3,1]); }
```

A varnode, r2 in this example, is immediately followed by square brackets '[' and ']' indicating a bit range, and within the brackets, there are two parameters separated by a comma. The first parameter is an integer indicating the least significant bit of the resulting bit range. The bits of the varnode are labeled in order of significance, with the least significant bit of the varnode being 0. The second parameter is an integer indicating the number of bits in the range. In the example, a single bit is extracted from r2, and its value is extended to fill r1. Thus r1 takes either the value 0 or 1, depending on bit 3 of r2.

There are some caveats associated with using this operator. Bit range extraction is really a pseudo operator, as real p-code can only work with memory down to byte resolution. The bit range operator will generate some combination of *INT_RIGHT*, *INT_AND*, and *SUBPIECE* to simulate the extraction of smaller or unaligned pieces. The "r2[3,1]" from the example generates the following p-code, for instance.

```
u1 = INT_RIGHT r2,#3
u2 = SUBPIECE u1,0
u3 = INT AND u2,#0x1
```

The result of any bit range operator still has a size in bytes. This size is always the minimum number of bytes needed to contain the resulting bit range, and if there are any extra bits in the result these are automatically set to zero.

This operator can also be used on the left-hand side of assignments with similar behavior and caveats (see Section 7.7.2.7, "Bit Range Assignments").

7.7.1.6. Address-of Operator

There is an *address-of* operator for generating the address offset of a selected varnode as an integer value for use in expressions. Use of this operator is a little subtle because it does *not* generate a p-code operation that calculates the desired value. The address is only calculated at disassembly time and not during execution. The operator can only be used if the symbol referenced has a static address.

Warning

The current SLEIGH compiler cannot distinguish when the symbol has an address that can always be resolved during disassembly. So improper use may not be flagged as an error, and the specification may produce unexpected results.

There '&' operator in front of a symbol invokes this function. The ampersand can also be followed by a colon ':' and an integer explicitly indicating the size of the resulting constant as a varnode.

```
:copyr r1 is op=0x3b & r1 { tmp:4 = &r1 + 4; r1 = *[reqister]tmp;}
```

The above is a contrived example of using the address-of operator to copy from a register that is not explicitly indicated by the instruction. This example constructs the address of the register following rI within the register space, and then loads rI with data from that address. The net effect of all this is that the register following rI is copied into rI, even though it is not mentioned directly in the instruction. Notice that the address-of operator only produces the offset portion of the address, and to copy the desired value, the '*' operator must have a register space override.

7.7.1.7. Managed Code Operations

SLEIGH provides basic support for instructions where encoding and context don't provide a complete description of the semantics. This is the case typically for *managed code* instruction sets where generation of the semantic details of an instruction may be deferred until run-time. Support for these operators is architecture dependent, otherwise they just act as black-box functions.

The constant pool operator, **cpool**, returns sizes, offsets, addresses, and other structural constants. It behaves like a *query* to the architecture about these constants. The first parameter is generally an *object reference*, and additional parameters are constants describing the particular query. The operator returns the requested value. In the following example, an object reference *regParamC* and the encoded constant *METHOD_INDEX* are sent as part of a query to obtain the final destination address of an object method.

If object memory allocation is an atomic feature of the instruction set, the specification designer can use the **newobject** functional operator to implement it in SLEIGH. It takes one or two parameters. The first parameter is a *class reference* or other value describing the object to be allocated, and the second parameter is an optional count of the number of objects to allocate. It returns a pointer to the allocated object.

7.7.1.8. User-Defined Operations

Any identifier that has been defined as a new p-code operation, using the **define pcodeop** statement, can be invoked as an operator using functional syntax. The SLEIGH compiler assumes that the operator can take an arbitrary number of inputs, and if used in an expression, the compiler assumes the operation returns an output. Using this syntax of course generates the particular p-code operation reserved for the identifier.

```
define pcodeop arctan;
...
:atan r1,r2 is opcode=0xa3 & r1 & r2 { r1 = arctan(r2); }
```

7.7.2. Statements

We describe the types of semantic statements that are allowed in SLEIGH.

7.7.2.1. Assignment Statements and Temporary Variables

Of course SLEIGH allows assignment statements with the '=' operator, where the right-hand side is an arbitrary expression and the left-hand side is the varnode being assigned. The assigned varnode can be any specific symbol in the scope of the constructor, either a global symbol or a local operand.

In SLEIGH, the keyword **local** is used to allocate temporary variables. If an assignment statement is prepended with **local**, and the identifier on the left-hand side of an assignment does not match any symbol in the scope of the constructor, a named temporary varnode is created in the *unique* address space to hold the result of the expression. The new symbol becomes part of the local scope of the constructor, and can be referred to in the following semantic statements. The size of the new varnode is calculated by examining the statement in context (see Section 7.7.3, "Varnode Sizes"). It is also possible to explicitly indicate the size by using the colon ':' operator followed by an integer size in bytes. The following examples demonstrate the temporary variable *tmp* being defined using both forms.

```
:swap r1,r2 is opcode=0x41 & r1 & r2 {
    local tmp = r1;
    r1 = r2;
    r2 = tmp;
}
:store r1,imm is opcode=0x42 & r1 & imm {
    local tmp:4 = imm+0x20;
    *r1 = tmp;
}
```

The **local** keyword can also be used to declare a named temporary varnode, without an assignment statement. This is useful for temporaries that are immediately passed into a macro.

```
:pushflags r1 is opcode=0x43 & r1 {
    local tmp:4;
    packflags(tmp);
    * r1 = tmp;
    r1 = r1 - 4;
}
```

Warning

Currently, the SLEIGH compiler does not need the **local** keyword to create a temporary variable. For any assignment statement, if the left-hand side has a new identifier, a new temporary symbol will be created using this identifier. Unfortunately, this can cause SLEIGH to blindly accept assignment statements where the left-hand side identifier is a misspelling of an existing symbol. Use of the **local** keyword is preferred and may be enforced in future compiler versions.

7.7.2.2. Storage Statements

SLEIGH supports fairly standard *storage statement* syntax to complement the load operator. The left-hand side of an assignment statement uses the '*' operator to indicate a dynamic storage location, followed by an arbitrary expression to calculate the location. This syntax of course generates the p-code *STORE* operator as the final step of the statement.

```
:sta [r1],r2 is opcode=0x20 & r1 & r2 { *r1 = r2; }
:stx [r1],r2 is opcode=0x21 & r1 & r2 { *[other] r1 = r2; }
```

```
:sti [r1],imm is opcode=0x22 & r1 & imm { *:4 r1 = imm; }
```

The same size and address space considerations that apply to the '*' operator when it is used as a load operator also apply when it is used as a store operator, see Section 7.7.1.2, "The '*' Operator". Unless explicit modifiers are given, the default address space is assumed as the storage destination, and the size of the data being stored is calculated from context. Keep in mind that the address represented by the pointer is not a byte address if the **wordsize** attribute is set to something other than one.

7.7.2.3. Exports

The semantic section doesn't just specify how to generate p-code for a constructor. Except for those constructors in the root table, this section also associates a semantic meaning to the table symbol the constructor is part of, allowing the table to be used as an operand in other tables. The mechanism for making this association is the *export* statement. This must be the last statement in the section and consists of the **export** keyword followed by the specific symbol to be associated with the constructor. In general, the constructor will have a sequence of assignment statements building a final value, and then the varnode containing the value will be exported. However, anything can be exported.

```
mode: reg++ is addrmode=0x2 & reg { tmp=reg; reg=reg+1; export tmp; }
```

This is an example of a post-increment addressing mode that would be used to build more complicated instructions. The constructor increments a register *reg* but stores a copy of its original value in *tmp*. The varnode *tmp* is then exported, associating it with the table symbol *mode*. When this constructor is matched, as part of a more complicated instruction, the symbol *mode* will represent the original semantic value of *reg* but with the standard post-increment side effect.

The table symbol associated with the constructor becomes a *reference* to the varnode being exported, not a copy of the value. If the table symbol is written to, as the left-hand side of an assignment statement, in some other constructor, the exported varnode is affected. A constant can be exported if its size as a varnode is given explicitly with the ':' operator.

It is not legal to put a full expression in an **export** statement, any expression must appear in an earlier statement. However, a single '&' operator is allowed as part of the statement and it behaves as it would in a normal expression (see Section 7.7.1.6, "Address-of Operator"). It causes the address of the varnode being modified to be exported as an integer constant.

7.7.2.4. Dynamic References

The only other operator allowed as part of an **export** statement, is the '*' operator. The semantic meaning of this operator is the same as if it were used in an expression (see Section 7.7.1.2, "The '*' Operator"), but it is worth examining the effects of this form of export in detail. Bearing in mind that an **export** statement exports a *reference*, using the '*' operator in the statement exports a *dynamic reference*. The varnode being modified by the '*' is interpreted as a pointer to another varnode. It is this varnode being pointed to which is exported, even though the address may be dynamic and cannot be determined at disassembly time. This is not the same as dereferencing the pointer into a temporary variable that is then exported. The dynamic reference can be both read and *written*. Internally, the SLEIGH compiler keeps track of the pointer and inserts a *LOAD* or *STORE* operation when the symbol associated with the dynamic reference is referred to in other constructors.

```
mode: reg[off] is addr=1 & reg & off {
    ea = reg + off;
    export *:4 ea;
}
dest: reloc is abs [ reloc = abs * 4; ] {
```

```
export *[ram]:4 reloc;
}
```

In the first example, the effective address of an operand is calculated from a register *reg* and a field of the instruction *off*. The constructor does not export the resulting pointer *ea*, it exports the location being pointed to by *ea*. Notice the size of this location (4) is given explicitly with the ':' modifier. The '*' operator can also be used on constant pointers. In the second example, the constant operand *reloc* is used as the offset portion of an address into the *ram* address space. The constant *reloc* is calculated at disassembly time from the instruction field *abs*. This is a very common construction for jump destinations (see Section 7.5.1, "Relative Branches") but can be used in general. This particular combination of a disassembly time action and a dynamic export is a very general way to construct a family of varnodes.

Dynamic references are a key construction for effectively separating addressing mode implementations from instruction semantics at higher levels.

7.7.2.5. Branching Statements

This section discusses statements that generate p-code branching operations. These are listed in Table 7, "Branching Statements", in the Appendix.

There are six forms covering the gamut of typical assembly language branches, but in terms of actual semantics there are really only three. With p-code,

- CALL is semantically equivalent to BRANCH,
- CALLIND is semantically equivalent to BRANCHIND, and
- RETURN is semantically equivalent to BRANCHIND.

The reason for this is that calls and returns imply the presence of some sort of a stack. Typically an assembly language call instruction does several separate actions, manipulating a stack pointer, storing a return value, and so on. When translating the call instruction into p-code, these actions must be implemented with explicit operations. The final step of the instruction, the actual jump to the destination of the call is now just a branch, stripped of its implied meaning. The *CALL*, *CALLIND*, and *RETURN* operations, are kept as distinct from their *BRANCH* counterparts in order to provide analysis software a hint as to the higher level meaning of the branch.

There are actually two fundamentally different ways of indicating a destination for these branch operations. By far the most common way to specify a destination is to give the *address* of a machine instruction. It bears repeating here that there is typically more than one p-code operation per machine instruction. So specifying a *destination address* really means that the destination is the first p-code operation for the (translated) machine instruction at that address. For most cases, this is the only kind of branching needed. The rarer case of *p-code relative* branching is discussed in the following section (Section 7.7.2.6, "P-code Relative Branching"), but for the remainder of this section, we assume the destination is ultimately given as an address.

There are two ways to specify a branching operation's destination address; directly and indirectly. Where a direct address is needed, as for the *BRANCH*, *CBRANCH*, and *CALL* instructions, The specification can give the integer offset of the jump destination within the address space of the current instruction. Optionally, the offset can be followed by the name of another address space in square brackets, if the destination is in another address space.

```
:reset is opcode=0x0 { goto 0x1000; }
:modeshift is opcode=0x1 { goto 0x0[codespace]; }
```

Of course, most branching instructions encode the destination of the jump within the instruction somehow. So the jump destination is almost always represented by an operand symbol and its associated

varnode. For a direct branch, the destination is given by the address space and the offset defining the varnode. In this case, the varnode itself is really just an annotation of the jump destination and not used as a variable. The best way to define varnodes which annotate jump destinations in this way is with a dynamic export.

```
dest: rel is simm8 [ rel = inst_next + simm8*4; ] {
    export *[ram]:4 rel;
}
```

In this example, the operand *rel* is defined with a disassembly action in terms of the address of the following instruction, *inst_next*, and a field specifying a relative relocation, *simm8*. The resulting exported varnode has *rel* as its offset and *ram* as its address space, by virtue of the dynamic form of the export. The symbol associated with this varnode, *dest*, can now be used in branch operations.

```
:jmp dest is opcode=3 & dest {
    goto dest;
}
:call dest is opcode=4 & dest {
    *:4 sp = inst_next;
    sp=sp-4;
    call dest;
}
```

The above examples illustrate the direct forms of the **goto** and **call** operators, which generate the p-code *BRANCH* and *CALL* operations respectively. Both these operations take a single annotation varnode as input, indicating the destination address of the jump. Notice the explicit manipulation of a stack pointer *sp*, for the call instruction. The *CBRANCH* operation takes two inputs, a boolean value indicating whether or not the branch should be taken, and a destination annotation.

```
:bcc dest is opcode=5 & dest { if (carryflag==0) goto dest; }
```

As in the above example, the *CBRANCH* operation takes two inputs, a boolean value indicating whether or operation is invoked with the **if goto** operation takes two inputs, a boolean value indicating whether or syntax. The condition of the **if** operation takes two inputs, a boolean value indicating whether or can be any semantic expression that results in a boolean value. The destination must be an annotation varnode.

The operators *BRANCHIND*, *CALLIND*, and *RETURN* all have the same semantic meaning and all use the same syntax to specify an indirect address.

```
:b [reg] is opcode=6 & reg {
    goto [reg];
}
:call (reg) is opcode=7 & reg {
    *:4 sp = inst_next;
    sp=sp-4;
    call [reg];
}
:ret is opcode=8 {
    sp=sp+4;
    tmp:4 = * sp;
```

```
return [tmp];
}
```

Square brackets surround the varnode containing the address. Currently, any indirect address must be in the address space containing the branch instruction. The offset of the destination address is taken dynamically from the varnode. The size of the varnode must match the size of the destination space.

7.7.2.6. P-code Relative Branching

In some cases, the semantics of an instruction may require branching within the semantics of a single instruction, so specifying a destination address is too course. In this case, SLEIGH is capable of p-code relative branching. Individual p-code operations can be identified by a label, and this label can be used as the destination specifier, after the **goto** keyword. A label, within the semantic section, is any identifier surrounded by the '<' and '>' characters. If this construction occurs at the beginning of a statement, we say the label is defined, and that identifier is now associated with the first p-code operation corresponding to the following statement. Any label must be defined exactly once in this way. When the construction is used as a destination, immediately after a **goto** or **call**, this is referred to as a label reference. Of course the p-code destination meant by a label reference is the operation at the point where the label was defined. Multiple references to the same label are allowed.

```
:sum r1,r2,r3 is opcode=7 & r1 & r2 & r3 {
    tmp:4 = 0;
    r1 = 0;
    <loopstart>
    r1 = r1 + *r2;
    r2 = r2 + 4;
    tmp = tmp + 1;
    if (tmp < r3) goto <loopstart>;
}
```

In the example above, the string "loopstart" is the label identifier which appears twice; once at the point where the label is defined at the top of the loop, after the initialization, and once as a reference where the conditional branch is made for the loop.

References to labels can refer to p-code that occurs either before or after the branching statement. But label references can only be used in a branching statement, they cannot be used as a varnode in other expressions. The label identifiers are local symbols and can only be referred to within the semantic section of the constructor that defines them. Branching into the middle of some completely different instruction is not possible.

Internally, branches to labels are encoded as a relative index. Each p-code operation is assigned an index corresponding to the operation's position within the entire translation of the instruction. Then the branch can be expressed as a relative offset between the branch operation's index and the destination operation's index. The SLEIGH compiler encodes this offset as a constant varnode that is used as input to the *BRANCH*, *CBRANCH*, or *CALL* operation.

7.7.2.7. Bit Range Assignments

The bit range operator can appear on the left-hand side of an assignment. But as with the '*' operator, its meaning is slightly different when used on this side. The bit range is specified in square brackets, as before, by giving the integer specifying the least significant bit of the range, followed by the number of bits in the range. In contrast with its use on the right however (see Section 7.7.1.5, "Bit Range Operator"), the indicated bit range is filled rather than extracted. Bits obtained from evaluating the expression on the right are extracted and spliced into the result at the indicated bit offset.

```
:bitset3 r1 is op=0x7d & r1 { r1[3,1] = 1; }
```

In this example, bit 3 of varnode r1 is set to 1, leaving all other bits unaffected.

As in the right-hand case, the desired insertion is achieved by piecing together some combination of the p-code operations *INT_LEFT*, *INT_ZEXT*, *INT_AND*, and *INT_OR*.

In terms of the rest of the assignment expression, the bit range operator is again assumed to have a size equal to the minimum number of bytes needed to hold the bit range. In particular, in order to satisfy size restrictions (see Section 7.7.3, "Varnode Sizes"), the right-hand side must match this size. Furthermore, it is assumed that any extra bits in the right-hand side expression are already set to zero.

7.7.3. Varnode Sizes

All statements within the semantic section must be specified up to the point where the sizes of all varnodes are unambiguously determined. Most specific symbols, like registers, must have their size defined by definition, but there are two sources of size ambiguity.

- Constants
- Temporary Variables

The SLEIGH compiler does not make assumptions about the size of a constant variable based on the constant value itself. This is true of values occurring explicitly in the specification and of values that are calculated dynamically in a disassembly action. As described in Section 7.7.2.1, "Assignment Statements and Temporary Variables", temporary variables do not need to have their size given explicitly.

The SLEIGH compiler can usually fill in the required size by examining these situations in the context of the entire semantic section. Most p-code operations have size restrictions on their inputs and outputs, which when put together can uniquely determine the unspecified sizes. Referring to Table 5, "Semantic Expression Operators and Syntax" in the Appendix, all arithmetic and logical operations, both integer and floating point, must have inputs and outputs all of the same size. The only exceptions are as follows. The overflow operators, INT_CARRY, INT_SCARRY, INT_SBORROW, and FLOAT_NAN have a boolean output. The shift operators, INT_LEFT, INT_RIGHT, and INT_SRIGHT, currently place no restrictions on the shift amount operand. All the comparison operators, both integer and floating point, insist that their inputs are all the same size, and the output must be a boolean variable, with a size of 1 byte.

The operators without a size constraint are the load and store operators, the extension and truncation operators, and the conversion operators. As discussed in Section 7.7.1.2, "The '*' Operator", the '*' operator cannot get size information for the dynamic (pointed-to) object from the pointer itself. The other operators by definition involve a change of size from input to output.

If the SLEIGH compiler cannot discover the sizes of constants and temporaries, it will report an error stating that it could not resolve variable sizes for that constructor. This can usually be fixed rapidly by appending the size ':' modifier to either the '*' operator, the temporary variable definition, or to an explicit integer. Here are three examples of statements that generate a size resolution error, each followed by a variation which corrects the error.

```
:sta [r1],imm is opcode=0x3a & r1 & imm {
         *r1 = imm; #Error
}
:sta [r1],imm is opcode=0x3a & r1 & imm {
         *:4 r1 = imm; #Correct
}
```

```
{
:inc [r1]
              is opcode=0x3b & r1
    tmp = *r1 + 1; *r1 = tmp;
                                                       # Error
:inc [r1]
               is opcode=0x3b & r1
    tmp:4 = *r1 + 1; *r1 = tmp;
                                                       # Correct
:clr [r1]
              is opcode=0x3c & r1
                                          {
    * r1 = 0;
                                                       # Error
              is opcode=0x3c & r1
:clr [r1]
    * r1 = 0:4;
                                                       # Correct
```

7.7.4. Unimplemented Semantics

The semantic section must be present for every constructor in the specification. But the designer can leave the semantics explicitly unimplemented if the keyword **unimpl** is put in the constructor definition in place of the curly braces. This serves as a placeholder if a specification is still in development or if the designer does not intend to model data flow for portions of the instruction set. Any instruction involving a constructor that is unimplemented in this way will still be disassembled properly, but the basic data flow routines will report an error when analyzing the instruction. Analysis routines then can choose whether or not to intentionally ignore the error, effectively treating the unimplemented portion of the instruction as if it does nothing.

```
:cache r1 is opcode=0x45 & r1 unimpl
:nop is opcode=0x0 { }
```

7.8. Tables

A single constructor does not form a new specific symbol. The *table* that the constructor is associated with via its table header is the actual symbol that can be reused to build up more complicated elements. With all the basic building blocks now in place, we outline the final elements for building symbols that represent larger and larger portions of the disassembly and p-code translation process.

The best analogy here is with grammar specifications and Regular Language parsers. Those who have used *yacc*, *bison*, or otherwise looked at BNF grammars should find the concepts here familiar.

With SLEIGH, there are in some sense two separate grammars being parsed at the same time. A display grammar and a semantic grammar. To the extent that the two grammars breakdown in the same way, SLEIGH can exploit the similarity to produce an extremely concise description.

7.8.1. Matching

If a table contains exactly one constructor, the meaning of the table as a specific symbol is straightforward. The display meaning of the symbol comes from the *display section* of the constructor, and the symbol's semantic meaning comes from the constructor's *semantic section*.

```
mode1: (r1) is addrmode=1 & r1 { export r1; }
```

The table symbol in this example is mode1. Assuming this is the only constructor, the display meaning of the symbol are the literal characters '(', and ')' concatenated with the display meaning of r1, presumably a register name that has been attached. The semantic meaning of mode1, because of the export statement, becomes whatever register is matched by the r1.

```
model: (r1) is addrmode=1 & r1 { export r1; }
model: [r2] is addrmode=2 & r2 { export r2; }
```

If there are two or more constructors defined for the same table, the *bit pattern section* is used to select between the constructors in context. In the above example, the *mode1* table is now defined with two constructors and the distinguishing feature of their bit patterns is that in one the *addrmode* field must be 1 and in the other it must be 2. In the context of a particular instruction, the matching constructor can be determined uniquely based on this field, and the *mode1* symbol takes on the display and semantic characteristics of the matching constructor.

The bit patterns for constructors under a single table must be built so that a constructor can be uniquely determined in context. The above example shows the easiest way to accomplish this. The two sets of instruction encodings, which match one or the other of the two *addrmode* constraints, are disjoint. In general, if each constructor has a set of instruction encodings associated with it, and if the sets for any two constructors are disjoint, then no two constructors can match at the same time.

It is possible for two sets to intersect, if one of the two sets properly contains the other. In this situation, the constructor corresponding to the smaller (contained) set is considered a *special case* of the other constructor. If an instruction encoding matches the special case, that constructor is used to define the symbol, even though the other constructor will also match. If the special case does not match but the other more general constructor does, then the general constructor is used to define the symbol.

```
zA: r1 is addrmode=3 & r1 { export r1; }
zA: "0" is addrmode=3 & r1=0 { export 0:4; } # Special case
```

In this example, the symbol zA takes on the same display and semantic meaning as rI, except in the special case when the field rI equals 0. In this case, zA takes on the display and semantic meaning of the constant zero. Notice that the first constructor has only the one constraint on addrmode, which is also a constraint for the second constructor. So any instruction that matches the second must also match the first

The same exact rules apply when there are more than two constructors. Any two sets defined by the bit patterns must be either disjoint or one contained in the other. It is entirely possible to have one general case with many special cases, or a special case of a special case, and so on.

If the patterns for two constructors intersect, but one pattern does not properly contain the other, this is generally an error in the specification. Depending on the flags given to the SLEIGH compiler, it may be more or less lenient with this kind of situation however. In the case where an intersection is not flagged as an error, the *first* constructor that matches, in the order that the constructors appear in the specification, is used.

If two constructors intersect, but there is a third constructor whose pattern is exactly equal to the intersection, then the third pattern is said to *resolve* the conflict produced by the first two constructors. An instruction in the intersection will match the third constructor, as a specialization, and the remaining pieces in the patterns of the first two constructors are disjoint. A resolved conflict like this is not flagged as an error even with the strictest checking. Other types of intersections, in combination with lenient checking, can be used for various tricks in the specification but should generally be avoided.

7.8.2. Specific Symbol Trees

When the SLEIGH parser analyzes an instruction, it starts with the root symbol *instruction*, and decides which of the constructors defined under it match. This particular constructor is likely to be defined in terms of one or more other family symbols. The parsing process recurses at this point. Each of the unresolved family symbols is analyzed in the same way to find the matching specific symbol. The matching

is accomplished either with a table lookup, as with a field with attached registers, or with the matching algorithm described in Section 7.8.1, "Matching". By the end of the parsing process, we have a tree of specific symbols representing the parsed instruction. We present a small but complete SLEIGH specification to illustrate this hierarchy.

```
define endian=big;
define space ram type=ram_space size=4 default;
define space register type=register_space size=4;
define register offset=0 size=4 [ r0 r1 r2 r3 r4 r5 r6 r7 ];
define token instr(16)
  op=(10,15) \mod (6,9) \mod (0,2)
attach variables [ reg1 reg2 ] [ r0 r1 r2 r3 r4 r5 r6 r7 ];
op2: reg2 is mode=0 & reg2
                             { export reg2; }
op2: imm is mode=1 & imm
                             {
                              export *[const]:4 imm; }
op2: [reg2] is mode=2 & reg2 { tmp = *:4 reg2; export tmp;}
:and reg1,op2 is op=0x10 \& reg1 \& op2 \{ reg1 = reg1 \& op2;
:xor reg1,op2 is op=0x11 & reg1 & op2 { reg1 = reg1 ^ op2;
    reg1,op2 is op=0x12 & reg1 & op2 { reg1 = reg1 | op2; }
```

This processor has 16 bit instructions. The high order 6 bits are the main *opcode* field, selecting between logical operations, *and*, *or*, and *xor*. The logical operations each take two operands, reg1 and op2. The operand reg1 selects between the 8 registers of the processor, r0 through r7. The operand op2 is a table built out of more complicated addressing modes, determined by the field mode. The addressing mode can either be direct, in which op2 is really just the register selected by reg2, it can be immediate, in which case the same bits are interpreted as a constant value imm, or it can be an indirect mode, where the register reg2 is interpreted as a pointer to the actual operand. In any case, the two operands are combined by the logical operation and the result is stored back in reg1.

The parsing proceeds from the root symbol down. Once a particular matching constructor is found, any disassembly action associated with that constructor is executed. After that, each operand of the constructor is resolved in turn.




Figure 1. Two Encodings and the Resulting Specific Symbol Trees

In Figure 1, "Two Encodings and the Resulting Specific Symbol Trees", we can see the break down of two typical instructions in the example instruction set. For each instruction, we see the how the encodings split into the relevant fields and the resulting tree of specific symbols. Each node in the trees are labeled with the base family symbol, the portion of the bit pattern that matches, and then the resulting specific symbol or constructor. Notice that the use of the overlapping fields, reg2 and imm, is determined by the matching constructor for the op2 table. SLEIGH generates the disassembly and p-code for these encodings by walking the trees.

7.8.2.1. Disassembly Trees

If the nodes of each tree are replaced with the display information of the corresponding specific symbol, we see how the disassembly statement is built.




Figure 2. Two Disassembly Trees

Figure 2, "Two Disassembly Trees", shows the resulting disassembly trees corresponding to the specific symbol trees in Figure 1, "Two Encodings and the Resulting Specific Symbol Trees". The display information comes from constructor display sections, the names of attached registers, or the integer interpretation of fields. The identifiers in a constructor display section serves as placeholders for the subtrees below them. By walking the tree, SLEIGH obtains the final illustrated assembly statements corresponding to the original instruction encodings.

7.8.2.2. P-code Trees

A similar procedure produces the resulting p-code translation of the instruction. If each node in the specific symbol tree is replaced with the corresponding p-code, we see how the final translation is built.




Figure 3. Two P-code Trees

Figure 3, "Two P-code Trees" lists the final p-code translation for our example instructions and shows the trees from which the translation is derived. Symbol names within the p-code for a particular node, as with the disassembly tree, are placeholders for the subtree below them. The final translation is put

together by concatenating the p-code from each node, traversing the nodes in a depth-first order. Thus the p-code of a child tends to come before the p-code of the parent node (but see Section 7.9, "P-code Macros"). Placeholders are filled in with the appropriate varnode, as determined by the export statement of the root of the corresponding subtree.

7.9. P-code Macros

SLEIGH supports a macro facility for encapsulating semantic actions. The syntax, in effect, allows the designer to define p-code subroutines which can be invoked as part of a constructor's semantic action. The subroutine is expanded automatically at compile time.

A macro definition is started with the **macro** keyword, which can occur anywhere in the file before its first use. This is followed by the global identifier for the new macro and a parameter list, comma separated and in parentheses. The body of the definition comes next, surrounded by curly braces. The body is a sequence of semantic statements with the same syntax as a constructor's semantic section. The identifiers in the macro's parameter list are local in scope. The macro can refer to these and any global specific symbol.

```
macro resultflags(op) {
  zeroflag = (op == 0);
  signflag = (op1 s< 0);
}
:add r1,r2 is opcode=0xba & r1 & r2 { r1 = r1 + r2; resultflags(r1); }</pre>
```

The macro is invoked in the semantic section of a constructor by using the identifier with a functional syntax, listing the varnodes which are to be passed into the macro. In the example above, the macro *resultflags* calculates the value of two global flags by comparing its parameter to zero. The *add* constructor invokes the macro so that the *r1* is used in the comparisons. Parameters are passed by *reference*, so the value of varnodes passed into the macro can be changed. Currently, there is no syntax for returning a value from the macro, except by writing to a parameter or global symbol.

Almost any statement that can be used in a constructor can also be used in a macro. This includes assignment statements, branching statements, **delayslot** directives, and calls to other macros. A **build** directive however should not be used in a macro.

7.10. Build Directives

Because the nodes of a specific symbol tree are traversed in a depth-first order, the p-code for a child node in general comes before the p-code of the parent. Furthermore, without special intervention, the specification designer has no control over the order in which the children of a particular node are traversed. The **build** directive is used to affect these issues in the rare cases where it is necessary. The **build** directive occurs as another form of statement in the semantic section of a constructor. The keyword **build** is followed by one of the constructor's operand identifiers. Then, instead of filling in the operand's associated p-code based on an arbitrary traversal of the symbol tree, the directive specifies that the operand's p-code must occur at that point in the p-code for the parent constructor.

This directive is useful in situations where an instruction supports prefixes or addressing modes with side-effects that must occur in a particular order. Suppose for example that many instructions support a condition bit in their encoding. If the bit is set, then the instruction is executed only if a status flag is set. Otherwise, the instruction always executes. This situation can be implemented by treating the instruction variations as distinct constructors. However, if many instructions support the same variation, it is probably more efficient to treat the condition bit which distinguishes the variants as a special operand.

```
cc: "c" is condition=1 { if (flag==1) goto inst_next; }
cc: is condition=0 { }

:and^cc r1,r2 is opcode=0x67 & cc & r1 & r2 {
   build cc;
   r1 = r1 & r2;
}
```

In this example, the conditional variant is distinguished by a 'c' appended to the assembly mnemonic. The cc operand performs the conditional side-effect, checking a flag in one case, or doing nothing in the other. The two forms of the instruction can now be implemented with a single constructor. To make sure that the flag is checked first, before the action of the instruction, the cc operand is forced to evaluate first with a **build** directive, followed by the normal action of the instruction.

7.11. Delay Slot Directives

For processors with a pipe-lined architecture, multiple instructions are typically executing simultaneously. This can lead to processor conventions where certain pairs of instructions do not seem to execute sequentially. The standard examples are branching instructions that execute the instruction in the *delay slot*. Despite the fact that execution of the branch instruction does not fall through, the following instruction is executed anyway. Such semantics can be implemented in SLEIGH with the **delayslot** directive.

This directive appears as a standalone statement in the semantic section of a constructor. When p-code is generated for a matching instruction, at the point where the directive occurs, p-code for the following instruction(s) will be generated and inserted. The directive takes a single integer argument, indicating the minimum number of bytes in the delay slot. Additional machine instructions will be parsed and p-code generated, until at least that many bytes have been disassembled. Typically the value of 1 is used to indicate that there is exactly one more instruction in the delay slot.

This is an example of a conditional branching instruction with a delay slot. The p-code for the following instruction is inserted before the final *CBRANCH*. Notice that the **delayslot** directive can appear anywhere in the semantic section. In this example, the condition governing the branch is evaluated before the directive because the following instruction could conceivably affect the registers checked by the condition.

Because the **delayslot** directive combines two or more instructions into one, the meaning of the symbol *inst_next* becomes ambiguous. It is not clear anymore what exactly the "next instruction" is. SLEIGH uses the following conventions for interpreting an *inst_next* symbol. If it is used in the semantic section, the symbol refers to the address of the instruction after any instructions in the delay slot. However, if it is used in a disassembly action, the *inst_next* symbol refers to the address of the instruction immediately after the first instruction, even if there is a delay slot.

8. Using Context

For most practical specifications, the disassembly and semantic meaning of an instruction can be determined by looking only at the bits in the encoding of that instruction. SLEIGH syntax reflects this fact as every constructor or attached register is ultimately decided by examining *fields*, the syntactic representation of these instruction bits. In some cases however, the instruction encoding itself may not be enough.

Additional information, which we refer to as *context*, may be necessary to fully resolve the meaning of the instruction.

In truth, almost every modern processor has multiple modes of operation, where the exact interpretation of instructions may depend on that mode. Typical examples include distinguishing between a 16-bit mode and a 32-bit mode, or between a big endian mode or a little endian mode. But for the specification designer, these are of little consequence because most software for such a processor will run in only one mode without ever changing it. The designer need only pick the most popular or most important mode for his projects and design to that. If there is in fact software that runs under a different mode, the other mode can be described in a separate specification.

However, for certain processors or software, the need to distinguish between different interpretations of the same instruction encoding, based on context, may be a crucial part of the disassembly and analysis process. There are two typical situations where this becomes necessary.

- The processor supports two (or more) separate instruction sets. The set to use is usually determined by special bits in a status register, and a single piece of software frequently switches between these modes.
- The processor supports instructions that temporarily affect the execution of the immediately following instruction(s). For example, many processors support hardware *loop* instructions that automatically cause the following instructions to repeat without an explicit instruction causing the branching and loop counting.

SLEIGH solves these problems by introducing *context variables*. The syntax for defining these symbols was described in Section 6.4, "Context Variables". As mentioned there, the easiest and most common way to use a context variable is as just another field to use in our bit patterns. It gives us the extra information we need to distinguish between different instructions whose encodings are otherwise the same.

8.1. Basic Use of Context Variables

Suppose a processor supports the use of two different sets of registers in its main addressing mode, based on the setting of a status bit which can be changed dynamically. If an instruction is executed with this bit cleared, then one set of registers is used, and if the bit is set, the other registers are used. The instructions otherwise behave identically.

```
define endian=big;
define space ram type=ram_space size=4 default;
define space register type=register_space size=4;
define register offset=0 size=4 [ r0 r1 r2 r3 r4 r5 r6 r7 ];
define register offset=0x100 size=4 [ s0 s1 s2 s3 s4 s5 s6 s7 ];

define token instr(16)
   op=(10,15) rreg1=(7,9) sreg1=(7,9) imm=(0,6);
define context statusreg
   mode=(3,3);
attach variables [ rreg1 ] [ r0 r1 r2 r3 r4 r5 r6 r7 ];
attach variables [ sreg1 ] [ s0 s1 s2 s3 s4 s5 s6 s7 ];

Reg1: rreg1 is mode=0 & rreg1 { export rreg1; }
Reg1: sreg1 is mode=1 & sreg1 { export sreg1; }

:addi Reg1,#imm is op=1 & Reg1 & imm { Reg1 = Reg1 + imm; }
```

In this example the symbol Reg1 uses the 3 bits (7,9) to select one of eight registers. If the context variable mode is set to 0, it selects an r register, through the rreg1 field. If mode is set to 1 on the other hand, an s register is selected instead via sreg1. The addi instruction (encoded as 0x0590 for example) can disassemble in one of two ways.

```
addi r3,#0x10 OR addi s3,#0x10
```

This is the same behavior as if *mode* were defined as a field instead of a context variable, except that there is nothing in the instruction encoding itself which indicates which of the two forms will be chosen. An engine doing the disassembly will have global state associated with the *mode* variable that will make the final decision about which form to generate. The setting of this state is (at least partially) out of the control of SLEIGH, although see the following sections.

8.2. Local Context Change

SLEIGH can make direct modifications to context variables through statements in the disassembly action section of a constructor. The left-hand side of an assignment statement in this section can be a context variable, see Section 7.5.2, "General Actions and Pattern Expressions". Because the result of this assignment is calculated in the middle of the instruction disassembly, the change in value of the context variable can potentially affect any remaining parsing for that instruction. A modal variable is being added to what was otherwise a stateless grammar, a common technique in many practical parsing engines.

Any assignment statement changing a context variable is immediately executed upon the successful match of the constructor containing the statement and can be used to guide the parsing of the constructor's operands. We introduce two more instructions to the example specification from the previous section.

```
:raddi Reg1,#imm is op=2 & Reg1 & imm [ mode=0; ] {
    Reg1 = Reg1 + imm;
}
:saddi Reg1,#imm is op=3 & Reg1 & imm [ mode=1; ] {
    Reg1 = Reg1 + imm;
}
```

Notice that both new constructors modify the context variable *mode*. The raddi instruction sets mode to 0 and effectively guarantees that an *r* register will be produced by the disassembly. Similarly, the *saddi* instruction can force an *s* register. Both are in contrast to the *addi* instruction, which depends on a global state. The changes to *mode* made by these instructions only persist for parsing of that single instruction. For any following instructions, if the matching constructors use *mode*, its value will have reverted to its original global state. The same holds for any context variable modified with this syntax. If an instruction needs to permanently modify the state of a context variable, the designer must use constructions described in Section 8.3, "Global Context Change".

Clearly, the behavior of the above example could be easily replicated without using context variables at all and having the selection of a register set simply depend directly on the *op* field. But, with more complicated addressing modes, local modification of context variables can drastically reduce the complexity and size of a specification.

At the point where a modification is made to a context variable, the specification designer has the guarantee that none of the operands of the constructor have been evaluated yet, so if their matching depends on this context variable, they will be affected by the change. In contrast, the matching of any ancestor

constructor cannot be affected. Other constructors, which are not direct ancestors or descendants, may or may not be affected by the change, depending on the order of evaluation. It is usually best not to depend on this ordering when designing the specification, with the possible exception of orderings which are guaranteed by **build** directives.

8.3. Global Context Change

It is possible for an instruction to attempt a permanent change to a context variable, which would then affect the parsing of other instructions, by using the **globalset** directive in a disassembly action. As mentioned in the previous section, context variables have an associated global state, which can be used during constructor matching. A complete model for this state is, unfortunately, outside the scope of SLEIGH. The disassembly engine has to make too many decisions about what is getting disassembled and what assumptions are being made to give complete control of the context to SLEIGH. Because of this caveat, SLEIGH syntax for making permanent context changes should be viewed as a suggestion to the disassembly engine.

For processors that support multiple modes, there are typically specific instructions that switch between these modes. Extending the example from the previous sections, we add two instructions to the specification for permanently switching which register set is being used.

The register set is, as before, controlled by the *mode* variable, and as with a local change to context, the variable is assigned to inside the square brackets. The *rmode* instruction sets *mode* to 0, in order to select *r* registers via *rreg1*, and *smode* sets *mode* to 1 in order to select *s* registers. As is described in Section 8.2, "Local Context Change", these assignments by themselves cause only a local context change. However, the subsequent **globalset** directives make the change persist outside of the the instructions themselves. The **globalset** directive takes two parameters, the second being the particular context variable being changed. The first parameter indicates the first address where the new context takes effect. In the example, the expectation is that a mode change affects any subsequent instructions. So the first parameter to **globalset** here is *inst_next*, indicating that the new value of *mode* begins at the next address.

8.3.1. Context Flow

A global change to context that affects instruction decoding is typically open-ended. I.e. once the mode switching instruction is executed, a permanent change is made to the run-time processor state, and all future instruction decoding is affected, until another mode switch is encountered. In terms of SLEIGH by default, the effect of a **globalset** directive follows *flow*. Starting from the address specified in the directive, the change in context follows the control-flow of the instructions, through branches and calls, until an execution path terminates or another context change is encountered.

Flow following behavior can be overridden by adding the **noflow** attribute to the definition of the context field. (See Section 6.4, "Context Variables") In this case, a **globalset** directive only affects the context of a single instruction at the specified address. Subsequent instructions retain their original context. This can be useful in a variety of situations but is typically used to let one instruction alter the behavior, not necessarily the decoding, of the following instruction. In the example below, an indirect branch instruction jumps through a link register lr. If the previous instruction moves the program counter in to lr, it communicates this to the branch instruction through the LRset context variable so that the branch can be interpreted as a return, rather than a generic indirect branch.

An alternative to the **noflow** attribute is to simply issue multiple directives within a single constructor, so an explicit end to a context change can be given. The value of the variable exported to the global state is the one in affect at the point where the directive is issued. Thus, after one **globalset**, the same context variable can be assigned a different value, followed by another **globalset** for a different address.

Because context in SLEIGH is controlled by a disassembly process, there are some basic caveats to the use of the **globalset** directive. With *flowing* context changes, there is no guarantee of what global state will be in affect at a particular address. During disassembly, at any given point, the process may not have uncovered all the relevant directives, and the known directives may not necessarily be consistent. In general, for most processors, the disassembly at a particular address is intended to be absolute. So given enough information, it should be possible to make a definitive determination of what the context is at a certain address, but there is no guarantee. It is up to the disassembly process to fully determine where context changes begin and end and what to do if there are conflicts.

9. P-code Tables

We list all the p-code operations by name along with the syntax for invoking them within the semantic section of a constructor definition (see Section 7.7, "The Semantic Section"), and with a description of the operator. The terms v0 and v1 represent identifiers of individual input varnodes to the operation. In terms of syntax, v0 and v1 can be replaced with any semantic expression, in which case the final output varnode of the expression becomes the input to the operator. The term spc represents the identifier of an address space, which is a special input to the LOAD and STORE operations. The identifier of any address space can be used.

This table lists all the operators for building semantic expressions. The operators are listed in order of precedence, highest to lowest.

P-code Name	SLEIGH Syntax	Description
SUBPIECE	least significant n bytes	The least significant n bytes of v0. Truncate least significant n bytes of v0. Most significant
	(= /	bytes may be truncated depending on result size.
POPCOUNT	popcount(v0)	Count the number of 1 bits in v0.
(simulated)	v0[6,1]	Extract a range of bits from v0, putting result in a minimum number of bytes. The bracketed numbers give respectively, the least significant bit and the number of bits in the range.
LOAD	* v1 *[spc]v1	Dereference v1 as pointer into default space. Optionally specify space to load from and size of data in bytes.

P-code Name	SLEIGH Syntax	Description
	*:2 v1	
	*[spc]:2 v1	
BOOL_NEGATE	!v0	Negation of boolean value v0.
INT_NEGATE	~v0	Bitwise negation of v0.
INT_2COMP	-v0	Twos complement of v0.
FLOAT_NEG	f- v0	Additive inverse of v0 as a floating-point number.
INT_MULT	v0 * v1	Integer multiplication of v0 and v1.
INT_DIV	v0 / v1	Unsigned division of v0 by v1.
INT_SDIV	v0 s/ v1	Signed division of v0 by v1.
INT_REM	v0 % v1	Unsigned remainder of v0 modulo v1.
INT_SREM	v0 s% v1	Signed remainder of v0 modulo v1.
FLOAT_DIV	v0 f/ v1	Division of v0 by v1 as floating-point numbers.
FLOAT_MULT	v0 f* v1	Multiplication of v0 and v1 as floating-point numbers.
INT_ADD	v0 + v1	Addition of v0 and v1 as integers.
INT_SUB	v0 - v1	Subtraction of v1 from v0 as integers.
FLOAT_ADD	v0 f+ v1	Addition of v0 and v1 as floating-point numbers.
FLOAT_SUB	v0 f- v1	Subtraction of v1 from v0 as floating-point numbers.
INT_LEFT	v0 << v1	Left shift of v0 by v1 bits.
INT_RIGHT	v0 >> v1	Unsigned (logical) right shift of v0 by v1 bits.
INT_SRIGHT	v0 s>> v1	Signed (arithmetic) right shift of v0 by b1 bits.
INT_SLESS	v0 s< v1 v1 s> v0	True if v0 is less than v1 as a signed integer.
INT_SLESSEQUAL	v0 s<= v1 v1 s>= v0	True if v0 is less than or equal to v1 as a signed integer.
INT_LESS	v0 < v1 v1 > v0	True if v0 is less than v1 as an unsigned integer.
INT_LESSEQUAL	v0 <= v1 v1 >= v0	True if v0 is less than or equal to v1 as an unsigned integer.
FLOAT_LESS	v0 f< v1 v1 f> v0	True if v0 is less than v1 viewed as floating-point numbers.
FLOAT_LESSEQUAL	v0 f<= v1 v1 f>= v0	True if v0 is less than or equal to v1 as floating-point.
INT_EQUAL	v0 == v1	True if v0 equals v1.
INT_NOTEQUAL	v0 != v1	True if v0 does not equal v1.

P-code Name	SLEIGH Syntax	Description
FLOAT_EQUAL	v0 f== v1	True if v0 equals v1 viewed as floating-point numbers.
FLOAT_NOTEQUAL	v0 f!= v1	True if v0 does not equal v1 viewed as floating-point numbers.
INT_AND	v0 & v1	Bitwise Logical And of v0 with v1.
INT_XOR	v0 ^ v1	Bitwise Exclusive Or of v0 with v1.
INT_OR	v0 v1	Bitwise Logical Or of v0 with v1.
BOOL_XOR	v0 ^^ v1	Exclusive-Or of booleans v0 and v1.
BOOL_AND	v0 && v1	Logical-And of booleans v0 and v1.
BOOL_OR	v0 v1	Logical-Or of booleans v0 and v1.
INT_ZEXT	zext(v0)	Zero extension of v0.
INT_SEXT	sext(v0)	Sign extension of v0.
INT_CARRY	carry(v0,v1)	True if adding v0 and v1 would produce an unsigned carry.
INT_SCARRY	scarry(v0,v1)	True if adding v0 and v1 would produce a signed carry.
INT_SBORROW	sborrow(v0,v1)	True if subtracting v1 from v0 would produce a signed borrow.
FLOAT_NAN	nan(v0)	True if v0 is not a valid floating-point number (NaN).
FLOAT_ABS	abs(v0)	Absolute value of v0 as floating point number.
FLOAT_SQRT	sqrt(v0)	Square root of v0 as floating-point number.
INT2FLOAT	int2float(v0)	Floating-point representation of v0 viewed as an integer.
FLOAT2FLOAT	float2float(v0)	Copy of floating-point number v0 with more or less precision.
TRUNC	trunc(v0)	Signed integer obtained by truncating v0.
FLOAT_CEIL	ceil(v0)	Nearest integer greater than v0.
FLOAT_FLOOR	floor(v0)	Nearest integer less than v0.
FLOAT_ROUND	round(v0)	Nearest integer to v0.
CPOOLREF	cpool(v0,)	Access value from the constant pool.
NEW	newobject(v0)	Allocate object of type described by v0.
USER_DEFINED	ident(v0,)	User defined operator <i>ident</i> , with functional syntax.

The following table lists the basic forms of a semantic statement.

Table 6. Basic Statements and Associated Operators

P-code Name	SLEIGH Syntax	Description
COPY, other	v0 = v1;	Assignment of v1 to v0.

P-code Name	SLEIGH Syntax	Description
STORE	*v0 = v1 *[spc]v0 = v1; *:4 v0 = v1; *[spc]:4 v0 = v1;	Store v1 in default space using v0 As pointer. Optionally specify space to store in and size of data in bytes.
USER_DEFINED	ident(v0,);	Invoke user-defined operation ident as a standalone statement, with no output.
	v0[8,1] = v1;	Fill a bit range within v0 using v1, leaving the rest of v0 unchanged.
	ident(v0,);	Invoke the macro named ident.
	build <i>ident</i> ;	Execute the p-code to build operand <i>ident</i> .
	delayslot(1);	Execute the p-code for the following instruction.

The following table lists the branching operations and the statements which invoke them.

Table 7. Branching Statements

P-code Name	SLEIGH Syntax	Description
BRANCH	goto v0;	Branch execution to address of v0.
CBRANCH	if (v0) goto v1;	Branch execution to address of v1 if v0 equals 1 (true).
BRANCHIND	goto [v0];	Branch execution to v0 viewed as an offset in current space.
CALL	call v0;	Branch execution to address of v0. Hint that branch is subroutine call.
CALLIND	call [v0];	Branch execution to v0 viewed as an offset in current space. Hint that branch is subroutine call.
RETURN	return [v0];	Branch execution to v0 viewed as an offset in current space. Hint that branch is a subroutine return.