PDEs and numerical methods

Lecture notes

ENSIMAG 2A MMIS and Master 1 MSIAM

Eric Blayo, Fall 2019

Warning: the objective of this document is only to summarize some key notions and gather some lecture notes. It is thus far from being exhaustive nor self-sufficient.

Contents

1	Some basic notions about PDEs 1										
	1.1	ODEs and PDEs	1								
	1.2	Usual partial differential operators	1								
	1.3	Green formulas	2								
	1.4	Some definitions related to PDEs	3								
	1.5	Classification of PDEs	4								
	1.6	Fourier analysis of PDEs	5								
2	Introduction to finite differences 7										
	2.1	1-D Taylor formulas	8								
	2.2	Finite difference schemes	9								
		2.2.1 Approximation schemes	9								
		2.2.2 A general method for deriving a finite difference scheme	9								
		2.2.3 Usual schemes for the first- and second-order derivatives	11								
		2.2.4 Fourier analysis of finite difference schemes	11								
	2.3	The finite difference method: a simple example	13								
	2.4										
		2.4.1 Consistence, stability and convergence	15								
		2.4.2 Equivalent equation	15								
		2.4.3 Other properties	16								
	2.5	2.5 Considering boundary conditions									
		2.5.1 Validity of finite difference schemes near boundaries	17								
		2.5.2 Dirichlet conditions	17								
		2.5.3 Neumann conditions	18								
	2.6	The n-D case	18								
3	Laplace and Poisson problems 21										
	3.1	Some vocabulary	21								
	3.2	Some general remarks on harmonic functions	21								
		3.2.1 Harmonic functions in \mathbb{R}^2	21								
		3.2.2 Harmonic functions in bounded domains in \mathbb{R}^2	22								
		3.2.3 Some properties of harmonic functions	22								
	3.3	Poisson equation in \mathbb{R}^2 and \mathbb{R}^3	23								
	3.4										
	3.5	Finite difference schemes	24								

CONTENTS

4		ling with the time variable	25					
	4.1	Discretization of $\frac{\partial u}{\partial t}$	25					
	4.2	Time discretization of $F(u)$	25					
	4.3	Stability	26					
		4.3.1 Numerical stability	26					
		4.3.2 Investigating the stability: the Fourier method	27					
		4.3.3 Other methods for investigating stability issues	28					
	4.4	Some time discretization schemes	29					
		4.4.1 One step methods	29					
		4.4.2 Multi-step methods	30					
		4.4.3 Predictor-corrector schemes	30					
5	The	transport equation	31					
	5.1	Some generalities	31					
		5.1.1 Physical interpretation	31					
		5.1.2 Boundary conditions	31					
	5.2	Resolution: the method of characteristics	32					
		5.2.1 Eulerian vs Lagrangian representations	32					
		5.2.2 Method of characteristics: general principle	32					
		5.2.3 Case of a pure transport equation	33					
		5.2.4 Case of a bounded domain	33					
	5.3	Numerical schemes for the 1D transport equation	34					
	5.5	5.3.1 Euler one-sided explicit schemes	34					
			36					
			36					
		5.3.3 Other schemes	96					
6	The wave equation 3							
	6.1	Some properties	37					
		6.1.1 Conservation of energy	37					
		6.1.2 Initial conditions	37					
	6.2	Analytical solutions	37					
		6.2.1 1-D solution: change of variables	38					
		6.2.2 1-D d'Alembert solution	39					
		6.2.3 Analytical solutions through Fourier transform	39					
		6.2.4 Case of a bounded domain: separation of variables	40					
	6.3	Discretization schemes	41					
	0.5	6.3.1 Second-order standard explicit scheme	41					
		6.3.2 Lax-Wendroff scheme	42					
7	The	diffusion equation	43					
•	7.1	Physical interpretation	43					
	7.2	Analytical solutions in n -D	43					
		7.2.1 Diffusion in a bounded domain $\Omega \subset \mathbb{R}^n$	44					
		7.2.2 Diffusion in \mathbb{R}^n	44					
	7.3	Analytical solutions in 1-D	45					

CONTENTS

		7.3.1	1-D diffusion in a bounded interval	45							
		7.3.2	1-D diffusion in $\mathbb R$	45							
		7.3.3	Some properties of the 1-D solution in $\mathbb R$	46							
		7.3.4	Adding a source term	46							
		7.3.5	Energy of the solution	47							
	7.4		rical schemes for the diffusion equation	47							
		7.4.1	Usual Euler explicit scheme	47							
		742	Other schemes	48							
		1.1.2	Cutor Schemes	10							
Α	Rem	ninder o	on Fourier series and Fourier transforms	49							
	A.1	Fourier	r series expansion	49							
			r transform								
В	The	Laplac	cian operator and its spectrum	51							
	B.1	Genera	al results	51							
			-D case	52							
C	Some generic calculations related to finite difference schemes										
	C.1	C.1 Fourier analysis: computation of transfer functions and stability studies									
	C.2	Small	o and big O	55							
			utation of equivalent PDEs	55							
		-	retation of the effect of the dominant error term	57							

Chapter 1

Some basic notions about PDEs

1.1 ODEs and PDEs

Definition 1.1. A differential equation is a relationship involving a function u and (some of) its derivatives. It is called an **ordinary differential equation (ODE)** if u depends on one single variable, or a **partial differential equation (PDE)** if u depends on several variables.

Examples

- $-u''(x) + x^2 u'(x) x u(x) = \sin x$ is an ODE.
- $\qquad \qquad \frac{\partial^2 u}{\partial x^2}(x,y,z) + \frac{\partial u}{\partial y}(x,y,z) \frac{\partial u}{\partial z}(x,y,z) = 0 \ \ \text{is a PDE}.$

1.2 Usual partial differential operators

Definition 1.2. Let $u: \Omega \subset \mathbb{R}^n \to \mathbb{R}$. The **directional (or Gâteaux) derivative** of u at point $\mathbf{x} \in \Omega$ in direction $\mathbf{d} \in \mathbb{R}^n$ is

$$\frac{\partial u}{\partial \mathbf{d}}(\mathbf{x}) = \lim_{\alpha \to 0} \frac{u(\mathbf{x} + \alpha \mathbf{d}) - u(\mathbf{x})}{\alpha}$$

Examples

- ▶ A partial derivative is a directional derivative in a direction belonging to the canonical basis.
- Let $u(x,y) = x^2 2xy + y$ and $\mathbf{d} = (1,2)$. The directional derivative of u in direction \mathbf{d} is

$$\frac{\partial u}{\partial \mathbf{d}}(\mathbf{x}) = -2x - 2y + 2$$

Definition 1.3. Let $u: \Omega \subset \mathbb{R}^n \to \mathbb{R}$. The gradient of u at point x is

$$\operatorname{grad} u(\mathbf{x}) = \nabla u(\mathbf{x}) = \begin{pmatrix} \frac{\partial u}{\partial x_1}(\mathbf{x}) \\ \vdots \\ \frac{\partial u}{\partial x_n}(\mathbf{x}) \end{pmatrix}$$

Theorem 1.1. An important relation: $\frac{\partial u}{\partial \mathbf{d}}(\mathbf{x}) = \nabla u(\mathbf{x}). \mathbf{d}$

Definition 1.4. Let
$$\mathbf{u}:\Omega\subset\mathbb{R}^n\to\mathbb{R}^n$$
 denoted by $\mathbf{u}(\mathbf{x})=\begin{pmatrix}u_1(x_1,\ldots,x_n)\\ \vdots\\ u_n(x_1,\ldots,x_n)\end{pmatrix}$. The **divergence** of \mathbf{u} is: $\operatorname{div}\mathbf{u}=\sum_{i=1}^n\frac{\partial u_i}{\partial x_i}$. It can also be denoted formally by $\nabla.\mathbf{u}$

Definition 1.5. Let $\mathbf{u}: \Omega \subset \mathbb{R}^3 \to \mathbb{R}^3$. The **curl** of \mathbf{u} is defined by:

$$\operatorname{curl} \mathbf{u} = \begin{pmatrix} \frac{\partial u_3}{\partial x_2} - \frac{\partial u_2}{\partial x_3} \\ \frac{\partial u_1}{\partial x_3} - \frac{\partial u_3}{\partial x_1} \\ \frac{\partial u_2}{\partial x_1} - \frac{\partial u_1}{\partial x_2} \end{pmatrix}$$

It can also be denoted formally by $\nabla \wedge \mathbf{u}$.

Definition 1.6. Let $u: \Omega \subset \mathbb{R}^n \to \mathbb{R}$. The **Laplacian** of u is defined by $\Delta u = \sum_{i=1}^n \frac{\partial^2 u}{\partial x_i^2}$

It can also be defined for
$$\mathbf{u}:\Omega\subset\mathbb{R}^n\to\mathbb{R}^n$$
 by $\Delta\mathbf{u}=\left(\begin{array}{c}\Delta u_1\\ \vdots\\ \Delta u_n\end{array}\right)$

 Δu is sometimes denoted by $\nabla^2 u$.

1.3 Green formulas

Let Ω an open bounded subset of \mathbb{R}^n , with a piecewise smooth boundary $\partial\Omega$. The external normal vector to $\partial\Omega$ is denoted by n. So called **Green formulas**¹ are actually particular cases

¹e.g. Gauss (or Ostrogradsky, or divergence) theorem, Stokes theorem, Green-Riemann theorem...

of integration by parts.

The basic Green formula reads:

$$\int_{\Omega} \frac{\partial u}{\partial x_k} v \, d\mathbf{x} = -\int_{\Omega} u \, \frac{\partial v}{\partial x_k} \, d\mathbf{x} + \int_{\partial \Omega} u \, v \, (\mathbf{e}_k \cdot \mathbf{n}) \, d\mathbf{s}$$

where e_k is the unit vector in direction x_k , and where u and v are continuously differentiable functions on $\overline{\Omega}$.

All other formulas derive from it, like for instance:

$$\int_{\Omega} \Delta u \ v \ d\mathbf{x} = -\int_{\Omega} \nabla u . \nabla v \ d\mathbf{x} + \int_{\partial \Omega} \frac{\partial u}{\partial \mathbf{n}} \, v \ d\mathbf{s}$$

$$\int_{\Omega} u \operatorname{div} \mathbf{E} \ d\mathbf{x} = -\int_{\Omega} \nabla u . \mathbf{E} \ d\mathbf{x} + \int_{\partial \Omega} u \ (\mathbf{E}.\mathbf{n}) \ d\mathbf{s}$$

1.4 Some definitions related to PDEs

Definition 1.7. Like for ODEs, the **order** of a PDE is the highest degree of derivation that appears in the PDE.

Definition 1.8. Like for ODEs, a PDE is **linear** iff the relation is linear w.r.t. u and its partial derivatives. The PDE is said to be **non linear** otherwise.

Definition 1.9. Like for ODEs, a PDE is **quasi linear** if each nonlinear term is actually a n^{th} derivative multiplied by a coefficient which depends only on \mathbf{x} , u and its derivatives up to order n-1.

Examples

- The inviscid Burgers equation $\frac{\partial u}{\partial t} + u \frac{\partial u}{\partial x} = f$ is a non linear first order PDE. It is actually a quasi linear PDE.
- ▶ The transport-diffusion equation $\frac{\partial u}{\partial t} + \mathbf{c} \cdot \nabla u \nu \, \Delta u = f$ is a linear second order PDE.

Definition 1.10. A PDE that involves the time variable is a **time-dependent** (or evolution) equation. Otherwise it is a **steady-state** (or time-independent, or stationary) equation.

Definition 1.11. PDEs are generally complemented with **boundary conditions (BCs)**, prescribed on the limits of the domain, and with an **initial condition** (generally the value of the solution at the initial time) if the PDE is time-dependent.

Some usual boundary conditions are:

$$\begin{array}{ll} \textbf{Dirichlet} & u=g \quad \text{ on } \partial\Omega \\ \\ \textbf{Neumann} & \frac{\partial u}{\partial \mathbf{n}}=g \quad \text{ on } \partial\Omega \\ \\ \textbf{Robin (or Fourier)} & \frac{\partial u}{\partial \mathbf{n}}+r\,u=g \quad \text{ on } \partial\Omega \end{array}$$

Definition 1.12. A steady-state PDE with boundary conditions is also called a **boundary value problem**.

A time-dependent PDE with initial conditions is also called an **initial value problem**, or a **Cauchy problem**.

Definition 1.13. A problem (PDE + initial and/or boundary conditions) is **well-posed** (in the sense of Hadamard) iff it has a unique solution, that continuously depends on the "parameters" of the problem (shape of the domain, coefficients in the equation, initial and/or boundary conditions...). Otherwise the problem is said to be **ill-posed**.

This continuous dependence is a crucial property for numerical simulation, since numerical solutions result from perturbations of the original problem. It is thus a necessary condition for numerical solutions to hopefully be correct approximations of the true solution.

1.5 Classification of PDEs

Many PDEs can roughly be classified into three main categories, which can generally be loosely described as follows:

- elliptic: time-independent, describing smooth equilibrium states
- **parabolic**: time-dependent and diffusive
- hyperbolic: time-dependent and wave-like, with finite speed of propagation

This classification can be made mathematically precise in particular for second order linear PDEs. Let consider such a PDE on $\Omega \subset \mathbb{R}^n$:

$$\sum_{i=1}^{n} \sum_{j=1}^{n} a_{ij}(\mathbf{x}) \frac{\partial^{2} u}{\partial x_{i} \partial x_{j}} + \sum_{i=1}^{n} b_{i}(\mathbf{x}) \frac{\partial u}{\partial x_{i}} + c(\mathbf{x})u = f \qquad (E)$$

The quadratic form corresponding to its second order part is

$$Q_{\mathbf{x}}(X_1,\ldots,X_n) = \sum_{i=1}^n \sum_{j=1}^n a_{ij}(\mathbf{x}) X_i X_j$$

(E) is said to be:

elliptic at point \mathbf{x} iff $Q_{\mathbf{x}}$ is definite (positive or negative)

parabolic at point \mathbf{x} iff $Q_{\mathbf{x}}$ is positive or negative, but not definite

hyperbolic at point \mathbf{x} iff $Q_{\mathbf{x}}$ is neither definite, nor positive or negative

Examples

- ▶ The wave equation $\frac{\partial^2 u}{\partial t^2} c^2 \Delta u = 0$ is a hyperbolic equation.
- ▶ The Laplace equation $\Delta u = 0$ is an elliptic equation.
- ▶ The diffusion equation $\frac{\partial u}{\partial t} \nu \Delta u = 0$ is a parabolic equation.
- ▶ The equation $x \frac{\partial^2 u}{\partial x^2} + y \frac{\partial^2 u}{\partial y^2} = 0$ is elliptic for xy > 0, parabolic for xy = 0, and hyperbolic for xy < 0.
- ► The Schrödinger equation $\frac{\partial u}{\partial t} i\nu\Delta u = 0$ does not fall in the preceding classes, due to its non real coefficient.

We will study typical equations of each of these three categories in the following chapters.

1.6 Fourier analysis of PDEs

As will be seen in the following chapters, Fourier analysis is a powerful tool for studying PDEs and their approximations (see Appendix A for some reminders on Fourier series and Fourier transforms).

The basic idea is that a linear homogeneous (i.e. with a null right-hand side) PDE with constant coefficients has **plane-wave solutions** of the form $u(\mathbf{x},t)=e^{i(\mathbf{k}.\mathbf{x}+\omega t)}, \ \mathbf{k}\in\mathbb{R}^n, \omega\in\mathbb{C}$ (or $u(\mathbf{x})=e^{i\mathbf{k}.\mathbf{x}}$ if it is a steady-state equation). Another point of view, for time-dependent PDEs, consists in observing that if an initial data $u_0(\mathbf{x})=e^{i\mathbf{k}.\mathbf{x}}$ is supplied to such an equation, then it has a solution $u(\mathbf{x},t)=e^{i\omega t}u_0(\mathbf{x})$ (where ω depends on \mathbf{k}), i.e. the initial condition multiplied by an oscillatory factor. Characterizing \mathbf{k} and ω provides information on the equation.

CHAPTER 1. SOME BASIC NOTIONS ABOUT PDES

Moreover, comparing this characterization with similar ones corresponding to approximate equations obtained by numerical methods (such as the finite difference method that is described in these notes) is a way to assess the quality of the approximations. Fourier analysis will also lead to the notions of dissipation and dispersion errors, and numerical stability, that will be introduced later.

Definition 1.14. The relationship between ω and k is called the **dispersion relation**.

Examples Making $u(\mathbf{x},t)=e^{i(\mathbf{k}.\mathbf{x}+\omega t)}$ in the equations introduced in the previous section leads to the following dispersion relations:

- wave equation: $\omega^2 = c^2 \|\mathbf{k}\|^2$
- diffusion equation: $\omega = i\nu \, \|\mathbf{k}\|^2$
- Schrödinger equation: $\omega = -\nu \, \|\mathbf{k}\|^2$

Chapter 2

Introduction to finite differences

The **finite difference method** provides a numerical approximation of the solutions of ODEs and PDEs. It consists in

- be defining a **mesh**, also called a **grid**, approximating the physical domain Ω where the equation is defined. For the finite difference method, contrary to the finite element method, this grid is almost always structured. This means that the **grid points** (or **nodes**) are regularly spaced (i.e. the **space step** is constant), or can be transformed into such a form by a simple function (see Figure 2.1). If one deals with a time-dependent PDE, then a mesh of the time interval is also defined (the time interval is divided into **time steps**, see Figure 2.2)
- looking for an approximation u_i^n of the exact solution at each node i and at each time step n (or more simply for an approximation u_i of the exact solution at each node i if the problem does not depend on time). This is achieved by replacing the exact equation at each node i and at each time step n by an approximate equation involving only the u_j^k , $j=\ldots,i-1,i,i+1,\ldots$, $k=\ldots,n-1,n,n+1,\ldots$ The basic tool for building this approximation is the Taylor formula.




Figure 2.1: some examples of finite difference grids




Figure 2.2: Regular space-time discretization

2.1 1-D Taylor formulas

Taylor formulas provide local polynomial approximations of regular functions. Let us recall for instance the Taylor-Lagrange formula for a function of one variable.

Theorem 2.1. Let u with \mathcal{C}^n regularity on [a,b], and with a $(n+1)^{\text{th}}$ derivative on (a,b). Then there exists $\zeta \in (a,b)$ such that

$$u(b) = u(a) + (b-a)u'(a) + \dots + \frac{(b-a)^n}{n!} u^{(n)}(a) + \frac{(b-a)^{n+1}}{(n+1)!} u^{(n+1)}(\zeta)$$
 (2.1)

This can be rewritten in the following way:

Theorem 2.2. Let u with C^n regularity in a neighborhood of x, and with a $(n+1)^{\text{th}}$ derivative in this neighborhood. Then, for h sufficiently small:

$$u(x+h) = u(x) + h u'(x) + \dots + \frac{h^n}{n!} u^{(n)}(x) + \mathcal{O}(h^{n+1})$$

This leads to the well-known **Taylor polynomials** approximating common functions. The exact meaning of the notation \mathcal{O} is given in Appendix C.2.

This 1-D formula is sufficient in most cases to derive finite difference schemes, even for multidimensional problems. However, for some specific schemes, multidimensional Taylor expansion might be necessary. An example in the 2-D case is given in $\S 2.6$.

2.2 Finite difference schemes

In this section, we will explain how finite difference schemes are built, and introduce usual schemes for the approximation of first and second order derivatives. Then we will introduce a way to analyze finite difference schemes.

We will only deal with 1-D functions, and will consider that functions are regular enough, so that their high order derivatives exist and Taylor expansions make sense.

2.2.1 Approximation schemes

Let x_0, x_1, \ldots, x_q distinct points and $p \in \mathbb{N}$. If we find real coefficients α_j $(j = 0, \ldots, q)$ such that

$$u^{(p)}(x_0) \simeq \sum_{j=0}^{q} \alpha_j \ u(x_j)$$

then this linear combination is called an **approximation scheme**, or a **finite difference scheme**, for $u^{(p)}(x_0)$.

This scheme is said to be **consistent** iff $u^{(p)}(x_0) - \sum_{j=0}^q \alpha_j u(x_j) \longrightarrow 0$ as $h \longrightarrow 0$.

The scheme is said to be k^{th} -order accurate iff $u^{(p)}(x_0) = \sum_{j=0}^q \alpha_j \ u(x_j) + \mathcal{O}(h^k)$. k is the order of accuracy of the scheme.

The grid points involved in a finite difference scheme form its so-called associated stencil.

2.2.2 A general method for deriving a finite difference scheme

Let x_0, x_1, \ldots, x_q distinct points, and $h_j = x_j - x_0$ $(j = 1, \ldots, q)$. We intend to build a consistent approximation scheme for $u^{(p)}(x_0)$, for $p \leq q$.

The Taylor-Lagrange formula applied to u at point x_i (j = 1, ..., q) at order q reads

$$u(x_j) = u(x_0) + h_j u'(x_0) + \dots + \frac{h_j^q}{q!} u^{(q)}(x_0) + \mathcal{O}(h_j^{q+1})$$

Let build an arbitrary linear combination of these expansions:

$$\sum_{j=1}^{q} \alpha_{j} u(x_{j}) = \left(\sum_{j=1}^{q} \alpha_{j}\right) u(x_{0}) + \left(\sum_{j=1}^{q} \alpha_{j} h_{j}\right) u'(x_{0}) + \dots + \frac{1}{q!} \left(\sum_{j=1}^{q} \alpha_{j} h_{j}^{q}\right) u^{(q)}(x_{0}) + \left(\sum_{j=1}^{q} \alpha_{j} \mathcal{O}(h_{j}^{q+1})\right) (2.2)$$

CHAPTER 2. INTRODUCTION TO FINITE DIFFERENCES

This combination is an approximation scheme for $u^{(p)}(x_0)$ as soon as the coefficients of $u^{(k)}(x_0)$ vanish for $k = 1, \ldots, q, \ k \neq p$:

$$\begin{cases} \sum_{j=1}^{q} \alpha_{j} h_{j} & = & 0 \\ \vdots & & \vdots \\ \sum_{j=1}^{q} \alpha_{j} h_{j}^{p-1} & = & 0 \\ \sum_{j=1}^{q} \alpha_{j} h_{j}^{p} & = & p! & \text{i.e.} \end{cases} \begin{pmatrix} h_{1} & h_{2} & \cdots & h_{q} \\ \vdots & & & \vdots \\ h_{1}^{p-1} & h_{2}^{p-1} & \cdots & h_{q}^{p-1} \\ h_{1}^{p} & h_{2}^{p} & \cdots & h_{q}^{p} \\ h_{1}^{p+1} & h_{2}^{p+1} & \cdots & h_{q}^{p+1} \\ \vdots & & & \vdots \\ h_{1}^{q} & h_{2}^{q} & \cdots & h_{q}^{q} \end{pmatrix} \begin{pmatrix} \alpha_{1} \\ \vdots \\ \alpha_{p-1} \\ \alpha_{p} \\ \alpha_{p+1} \\ \vdots \\ \alpha_{q} \end{pmatrix} = \begin{pmatrix} 0 \\ \vdots \\ 0 \\ p! \\ 0 \\ \vdots \\ 0 \end{pmatrix} (2.3)$$

$$\vdots$$

$$\sum_{j=1}^{q} \alpha_{j} h_{j}^{q} = 0$$

This is a $q \times q$ linear system of Vandermonde type. Thus it has a unique solution $\alpha_1, \ldots, \alpha_q$ iff the h_j s are q distinct values, which is obviously the case since the x_j s are distinct points. Moreover the only non homogeneous equation in this system implies that $\alpha_j = \mathcal{O}(h^{-p}), \ j=1,\ldots,q$, where h is a common order of magnitude for the h_j s (for instance h can be taken as the minimum, mean, or maximum value of the h_j s).

The linear system (2.3) being satisfied, (2.2) becomes

$$\sum_{j=1}^{q} \alpha_j u(x_j) = \left(\sum_{j=1}^{q} \alpha_j\right) u(x_0) + u^{(p)}(x_0) + \mathcal{O}(h^{q+1-p})$$

i.e.

$$u^{(p)}(x_0) = \sum_{j=1}^{q} \alpha_j u(x_j) - \left(\sum_{j=1}^{q} \alpha_j\right) u(x_0) + \mathcal{O}(h^{q+1-p})$$
(2.4)

Theorem 2.3. Using q additional grid points x_1, \ldots, x_q , one can build an approximation of $u^{(p)}(x_0)$ at order q+1-p. ¹

Theorem 2.4. A direct consequence of the preceding result is that a k^{th} -order scheme is exact for any polynomial function u which degree is lower than or equal to k.

This is simply due to the fact that, following (2.1), the error term $\mathcal{O}(h^{q+1-p})$ in (2.4) is a combination of $(q+1)^{\text{th}}$ -order derivatives of u. If the scheme is k^{th} -order accurate, then q+1-p=k, i.e. q+1=k+p>k. Given the fact that, for a polynomial of degree k, the derivatives of order greater than k are zero, the error term is thus also zero.

 $^{^{1}}$ We will actually see later that, if p is even and if the scheme is symmetric, the order of the approximation becomes q+2-p.

2.2.3 Usual schemes for the first- and second-order derivatives

Using the Taylor-Lagrange formula at points x + h and x - h with a positive increment h leads to the following usual schemes for the first-order derivative:

$$\mathbf{v}'(x) = \frac{u(x+h) - u(x)}{h} + \mathcal{O}(h)$$
: first-order **right-sided** (or **downstream**) scheme

$$lacksquare u'(x) = rac{u(x) - u(x-h)}{h} + \mathcal{O}(h)$$
 : first-order **left-sided** (or **upwind**) scheme

$$lacksquare u'(x) = rac{u(x+h) - u(x-h)}{2h} + \mathcal{O}(h^2)$$
 : second-order **centered** scheme

The two first-order schemes are said to be **one-sided**, since they involve grid points only on one side of the current grid point of interest x, while the second-order scheme is said to be **two-sided**.

Similarly, the most usual scheme for the second derivative is the second-order centered scheme:

$$u''(x) = \frac{u(x-h) - 2u(x) + u(x+h)}{h^2} + \mathcal{O}(h^2)$$
(2.5)

We can see that the orders of accuracy of these schemes follow the rule described by Theorem 2.3. The order is indeed equal to q+1-p for the schemes approximating u' (p=1, q=1 for the one-sided schemes and q=2 for the two-sided scheme), and q+2-p for the second-order centered scheme for u'' (p=q=2).

2.2.4 Fourier analysis of finite difference schemes

Spectral (or Fourier) analysis is a powerful tool to study the properties and the quality of approximation schemes. It consists in looking at the effect of a numerical scheme in the frequency space.

Since any regular function can be written as an integral or a series of complex exponential functions (see Appendix A), we only need to consider the effect of a finite difference scheme on a generic exponential function $u_{\omega}(x)=e^{i\omega x},\,\omega\in\mathbb{R}$. Let then define the **transfer function** T of an operator S as $S(u_{\omega})=T(\omega)\,u_{\omega}$. The transfer function of a finite difference scheme is then obtained taking h=1 (for normalization purpose) and $\omega\in[0,\pi]$ (to fulfill the Nyquist-Shannon criterion²).

Example Let consider the derivation operator:

$$S: u \longrightarrow u'$$

We have obviously $S(u_{\omega})(x)=(e^{i\omega x})'=i\omega\,e^{i\omega x}$, i.e. $S(u_{\omega})=i\omega\,u_{\omega}$. The transfer function corresponding to the first order derivation is thus $T(\omega)=i\omega$. Moreover, since $i\omega\,e^{i\omega x}=\omega\,e^{i(\omega x+\pi/2)}$,

 $^{^2}$ The Nyquist-Shannon criterion states that a sufficient condition for a sample to capture all the information from a continuous signal is that the sample rate is larger than, or equal to, twice the maximum frequency contained in the continuous signal. On a regular grid of step h, the sampling rate is equal to 1/h, i.e. 1 if we take h=1 for the sake of normalization. The continuous signal $e^{i\omega x}$ is made of one single frequency $\omega/(2\pi)$. Then the Nyquist-Shannon criterion reads: $1 \geq 2\omega/(2\pi)$, i.e. $\omega \leq \pi$.

the derivation changes the amplitude of u_{ω} (by a factor of ω) and its phase (by adding a $\pi/2$ delay).

Let now consider the two following finite difference schemes approximating the first derivative:

$$S_h^{(1)}: u \longrightarrow \frac{u(.+h)-u(.)}{h} \quad \text{ and } \quad S_h^{(2)}: u \longrightarrow \frac{u(.+h)-u(.-h)}{2h}$$

 $S_1^{(1)}(u_\omega)=e^{i\omega(x+1)}-e^{i\omega x} \text{ and } S_1^{(2)}(u_\omega)=\frac{1}{2}\left(e^{i\omega(x+1)}-e^{i\omega(x-1)}\right) \text{, which implies that their transfer functions are respectively } T^{(1)}(\omega)=e^{i\omega}-1 \text{ and } T^{(2)}(\omega)=i\sin\omega. \text{ They are compared with the transfer function } T(\omega)=i\omega \text{ of the exact continuous derivation in Figure 2.3.}$




Figure 2.3: Real (left panel) and imaginary (right panel) parts of the transfer function for the exact derivation operator (blue curves), and the $S_h^{(1)}$ (red curves) and $S_h^{(2)}$ (yellow curves) finite difference schemes

An important aspect contributing to the quality of a finite difference scheme is its ability to modify as few as possible the exact transfer function, nor its phase neither its amplitude. In the present example, some simple algebra leads to

$$T^{(1)}(\omega) = \mathrm{sinc}\left(\frac{\omega}{2}\right)\,e^{i\omega/2}\,T(\omega) \qquad \text{and} \qquad T^{(2)}(\omega) = \mathrm{sinc}\left(\omega\right)\,T(\omega)$$

where $\mathrm{sinc}(\omega) = \frac{\sin \omega}{\omega}$ is the cardinal sine function (see Figure A.1 in Appendix A). Under this form, it is clear that $S^{(1)}$ modifies both the amplitude and the phase w.r.t. S, while $S^{(2)}$ modifies the amplitude but not the phase.

Definition 2.1. A scheme S_h that modifies the amplitude of Fourier components w.r.t. to the exact operator S is said to be **diffusive** or **dissipative**. The modification of this amplitude is called the **diffusion error** or **dissipation error** of the scheme.

Definition 2.2. A scheme S_h that modifies the phase of Fourier components w.r.t. to the exact operator S is said to be **dispersive**. The modification of this phase is called the **dispersion error** of the scheme.

Both errors appear clearly by looking at the ratio T_1/T : there is a dissipation error³ as soon as the amplitude of this ratio is not equal to 1, and a dispersion error as soon as its phase is non zero (i.e. the ratio is not a real number).

As can be seen in the above example, these errors are not constant, but generally depend on the wavenumber ω . For most schemes, the errors are small for small wavenumbers, and increase for larger ones.

Some generic calculations facilitating the computation of transfer functions are given in Appendix C.1.

2.3 The finite difference method: a simple example

Let now illustrate the principle of the finite difference method on the very simple example of the ODE: -u''(x) = f(x) for $x \in (a,b)$, with boundary conditions u(a) = 0 and u(b) = 0.

The finite difference method consists in:

- building a mesh of the domain [a,b]. Let take here for instance the regular mesh defined by $x_i = a + ih$ (i = 0, ..., N+1) with h = (b-a)/(N+1).
- \triangleright considering the ODE on grid points only. The original ODE on (a,b) is replaced by

$$\begin{cases} -u''(x_i) = f(x_i) & i = 1, \dots, N \\ u(x_0) = u(x_{N+1}) = 0 \end{cases}$$

replacing the differential operator by a finite difference scheme. Here, we can use the second order scheme (2.5) seen previously, and the ODE at point x_i reads

$$\begin{cases} -\frac{1}{h^2} \left(u(x_{i-1}) - 2u(x_i) + u(x_{i+1}) \right) + \varepsilon_i = f(x_i) &, i = 1, \dots, N \quad \text{with } \varepsilon_i = \mathcal{O}(h^2) \\ u(x_0) = u(x_{N+1}) = 0 \end{cases}$$

$$(2.6)$$

▶ neglecting the error terms ε_i , and then actually solving the remaining system. In the present case, it is thus the simple linear system:

$$\begin{cases} -u_{i-1} + 2u_i - u_{i+1} = h^2 f(x_i) &, i = 1, \dots, N \\ u_0 = u_{N+1} = 0 \end{cases}$$
 (2.7)

where u_i is the approximation of $u(x_i)$.

The preceding problem can of course be written in matrix form. Let

$$A_{h} = \frac{1}{h^{2}} \begin{pmatrix} 2 & -1 & & & 0 \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & -1 & 2 & -1 \\ 0 & & & -1 & 2 \end{pmatrix}, \quad F = \begin{pmatrix} f(x_{1}) \\ \vdots \\ f(x_{N}) \end{pmatrix}, \quad E = \begin{pmatrix} \varepsilon_{1} \\ \vdots \\ \varepsilon_{N} \end{pmatrix}$$

³Note that one speaks about "dissipation error" even if the amplitude of T_h/T is greater than 1.

CHAPTER 2. INTRODUCTION TO FINITE DIFFERENCES

$$U = \left(\begin{array}{c} u(x_1) \\ \vdots \\ u(x_N) \end{array} \right), \quad \text{and} \quad U_h = \left(\begin{array}{c} u_1 \\ \vdots \\ u_N \end{array} \right)$$

Then (2.6) reads: $A_h U + E = F$, while (2.7) reads:

$$A_h U_h = F (2.8)$$

Before addressing the issues of the existence and uniqueness of U_h and of its convergence towards U, let present some numerical results, for the particular case where the exact solution is $u(x) = e^{-x/8} \sin x$ for $x \in [0, 6\pi]$ (the right-hand side is then $f(x) = \frac{-1}{64}e^{-x/8}$ $(63\sin x + 16\cos x)$). Figure 2.4 compares this exact solution u with the numerical approximation u_h for several values of h. It clearly illustrates the convergence of the finite difference solution towards the true solution as h decreases. The rate of this convergence can be quantified by computing the norm of the error $||U_h - U||$ for the different values of h. This quantity is displayed in Figure 2.5 in log-log scale. As can be seen, the error decreases almost linearly, with a slope which is very close to 2. This means that the error behaves like Ch^2 , which is consistent with the second order discretization of the numerical scheme.




Figure 2.4: u(x) (red curve) and $u_h(x)$ (blue curve) for N=10, N=20 and N=30




Figure 2.5: $||U_h - U||_2$ (blue curve) and $||U_h - U||_{\infty}$ (red curve) compared to the theoretical h^2 slope (yellow line)

2.4 Properties of the scheme and of the numerical solution

2.4.1 Consistence, stability and convergence

As seen before, when applied to an ODE or a PDE, the finite difference method leads (at least for linear equations) to a linear system $A_hU_h=F$, while the exact equations are $A_hU+E_h=F$. At this stage, two questions arise naturally:

- \blacktriangleright Is the problem well posed, i.e. does the system have a unique solution U_h ?
- ▶ If the problem is well posed, does its numerical solution U_h converge to the exact continuous solution U as h tends to 0 ?

Definition 2.3. The scheme is said to be **consistent** iff $E_h \longrightarrow 0$ as $h \longrightarrow 0$.

Definition 2.4. The error of the numerical solution is $||U_h - U|| = ||A_h^{-1}E_h|| \le ||A_h^{-1}|| \, ||E_h||$. The fact that $||A_h^{-1}||$ is bounded independently of h is called **stability**.

Theorem 2.5. Stability and consistency lead obviously to **convergence**: $U_h \longrightarrow U$ as $h \longrightarrow 0$. This is even an equivalence for simple linear problems.

Example In the preceding example, A_h is invertible, since it is a symmetric positive definite matrix. Therefore (2.8) is well posed.

Given its expression, E_h obviously tends to 0 as h tends to 0: the numerical scheme is consistent. To get the convergence of the approximation method, we have thus to show that $\|A_h^{-1}\|$ is bounded independently of h. Note that this is not obvious at all, since A_h is a $N \times N$ matrix, with N tending to infinity as h tends to 0. In the present case, it can be shown for instance that $\|A_h^{-1}\| \leq \max\left(1, \frac{2(b-a)^2}{\pi^2}\right)$ for h sufficiently small.

2.4.2 Equivalent equation

Associated to convergence properties is the notion of **equivalent equation**. As a matter of fact, using Taylor expansion, the numerical scheme can be reformulated as a series (w.r.t. h), the first term of which (i.e. corresponding to h^0) is the original equation (iff the discretization is consistent). This expression is the so-called equivalent equation associated to the numerical scheme. However the most interesting term in the error is the one corresponding to the lowest power of h, also called **dominant error term**, which may give an indication on the way the numerical scheme modifies the true solution. That is why, by extension, the term **equivalent equation** is also frequently employed to indicate the original equation with only the dominant error term in addition.

Example Coming back to the preceding example, we have:

$$\frac{u(x+h) - 2u(x) + u(x-h)}{h^2} = u''(x) + \frac{h^2}{12}u^{(4)}(x) + \frac{h^4}{360}u^{(6)}(x) + \dots$$

Therefore the finite difference method actually solves the equivalent equation

$$-u''(x) - \frac{h^2}{12}u^{(4)}(x) - \frac{h^4}{360}u^{(6)}(x) - \dots = f(x)$$

The dominant error term is: $-\frac{h^2}{12}u^{(4)}(x)$, and the equation with this additional term only

$$-u''(x) - \frac{h^2}{12}u^{(4)}(x) = f(x)$$

is also called the equivalent equation.

Some generic calculations facilitating the computation of equivalent PDEs are given in Appendix C.3 and a general result allowing for the interpretation of its dominant error term is given in Appendix C.4.

2.4.3 Other properties

Additional issues may also be of interest. For instance, it might be important that U_h also satisfies some specific mathematical or physical properties satisfied by U (e.g. conservation laws, symmetry, positivity...). Such properties are called **mimetic properties** of the numerical scheme.

Example Let consider the homogeneous ODE -u''(x) = 0 on (a,b), with Dirichlet boundary conditions $u(a) = \alpha$ and $u(b) = \beta$. The exact solution is obviously $u(x) = \alpha + \frac{x-a}{b-a}(\beta-\alpha)$. This function satisfies a so-called "maximum principle" (we will come back on this notion in the following chapters) in the sense that the extrema of the function are reached only on the boundary of the domain (for x = a and x = b).

Following the discretization used previously, the corresponding finite difference solution satisfies:

$$\begin{cases} -u_{i-1} + 2u_i - u_{i+1} = 0 &, i = 1, \dots, N \\ u_0 = \alpha &, u_{N+1} = \beta \end{cases}$$

Remarking that $u_i = \frac{1}{2}(u_{i-1} + u_{i+1})$, a simple proof by contradiction shows that the approximate solution also reaches its extrema for x = a and x = b. This is a mimetic property of the numerical scheme.

2.5 Considering boundary conditions

Until this point, we did not detail the management of boundary conditions in the finite difference method. This aspect was also hidden in the example of §2.3, due to the fact that we had homogeneous Dirichlet conditions u(a) = u(b) = 0.

The way boundary conditions must be accounted for depends on each particular case. One must check that the finite difference schemes are still valid in the vicinity of the boundary and, if it is not the case, locally use other schemes. Moreover, boundary conditions must be integrated in the system of discretized equations.

2.5.1 Validity of finite difference schemes near boundaries

Numerical schemes often cannot be used in the vicinity of the boundary. As an example, with the same notations as in section 2.3, if one approximates u''(x) by

$$u''(x_i) = \frac{-u_{i-2} + 16 u_{i-1} - 30 u_i + 16 u_{i+1} - u_{i+2}}{12 h^2} + \mathcal{O}(h^4)$$

this scheme cannot be used for grid points x_1 and x_N , since x_{-1} and x_{N+2} do not exist. Other schemes must be considered, for instance the usual centered scheme:

$$u''(x_1) \simeq \frac{u_0 - 2u_1 + u_2}{h^2}$$
 and $u''(x_N) \simeq \frac{u_{N-1} - 2u_N + u_{N+1}}{h^2}$

However, as seen before, this scheme is only second-order accurate. Discretization errors will then be larger at these two points than elsewhere, which may corrupt the overall quality of the numerical solution. To avoid this, another possibility consists in using one-sided fourth-order schemes, the price to pay being a larger stencil.

2.5.2 Dirichlet conditions

Non homogeneous Dirichlet boundary conditions can be easily integrated within numerical schemes. For instance, if one replaces the homogeneous Dirichlet conditions u(a) = u(b) = 0 by nonhomogeneous ones $u(a) = \alpha$ and $u(b) = \beta$ in the example of §2.3, system (2.8) becomes

$$\frac{1}{h^2} \begin{pmatrix}
1 & 0 & & & 0 \\
-1 & 2 & -1 & & \\
& & \ddots & \ddots & \ddots & \\
& & & -1 & 2 & -1 \\
0 & & & 0 & 1
\end{pmatrix}
\begin{pmatrix}
u_0 \\
u_1 \\
\vdots \\
u_N \\
u_{N+1}
\end{pmatrix} = \begin{pmatrix}
\alpha \\
f(x_1) \\
\vdots \\
f(x_N) \\
\beta
\end{pmatrix}$$

or, if directly eliminating u_0 and u_{N+1} :

$$\frac{1}{h^2} \begin{pmatrix} 2 & -1 & & & 0 \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & -1 & 2 & -1 \\ 0 & & & -1 & 2 \end{pmatrix} \begin{pmatrix} u_1 \\ \vdots \\ \vdots \\ u_N \end{pmatrix} = \begin{pmatrix} f(x_1) + \frac{\alpha}{h^2} \\ \vdots \\ \vdots \\ f(x_N) + \frac{\beta}{h^2} \end{pmatrix}$$

2.5.3 Neumann conditions

In case of a Neumann boundary condition, the derivative must of course also be approximated by a finite difference scheme. For instance, if one replaces the Dirichlet condition $u(a) = \alpha$ by the Neumann condition $u'(a) = \alpha$ in the previous example, one can use the first-order approximation:

$$\frac{u_1 - u_0}{h} = \alpha$$

which leads to the system

$$\frac{1}{h^2} \begin{pmatrix} -h & h & & & 0 \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & -1 & 2 & -1 \\ 0 & & & 0 & 1 \end{pmatrix} \begin{pmatrix} u_0 \\ u_1 \\ \vdots \\ u_N \\ u_{N+1} \end{pmatrix} = \begin{pmatrix} \alpha \\ f(x_1) \\ \vdots \\ f(x_N) \\ \beta \end{pmatrix}$$

One could also use the second-order scheme

$$\frac{-3u_0 + 4u_1 - u_2}{2h} = \alpha$$

leading in that case to

$$\frac{1}{h^2} \begin{pmatrix} -3h & 4h & -h & & 0 \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & -1 & 2 & -1 \\ 0 & & & 0 & 1 \end{pmatrix} \begin{pmatrix} u_0 \\ u_1 \\ \vdots \\ u_N \\ u_{N+1} \end{pmatrix} = \begin{pmatrix} 2\alpha \\ f(x_1) \\ \vdots \\ f(x_N) \\ \beta \end{pmatrix}$$

2.6 The n-D case

Most PDEs involve more than one space variable. However, even in n-D with n > 1, the discretization of differential operators very often requires 1-D finite difference schemes only, since it can be done in each direction independently.

Example Let consider the 2-D Laplacian operator $\Delta u(x,y) = \frac{\partial^2 u}{\partial x^2}(x,y) + \frac{\partial^2 u}{\partial y^2}(x,y)$. Using the usual second-order centered approximation (2.5) for the second derivative, one gets immediately:

$$\frac{u(x+h,y) - 2u(x,y) + u(x-h,y)}{h^2} + \frac{u(x,y+k) - 2u(x,y) + u(x,y-k)}{k^2} = \Delta u(x,y) + \mathcal{O}(h^2 + k^2)$$

or, taking h = k:

$$\frac{u(x+h,y) + u(x-h,y) + u(x,y+h) + u(x,y-h) - 4u(x,y)}{h^2} = \Delta u(x,y) + \mathcal{O}(h^2) \quad (2.9)$$

However, if one considers a more complex stencil involving other grid points, it may be necessary to use a multi-dimensional Taylor formula to build the finite difference scheme. For instance, in 2-D:

Theorem 2.6. The Taylor formula in two real variables reads:

$$\begin{split} u(x+h,y+k) &= u(x,y) + h \frac{\partial u}{\partial x}(x,y) + k \frac{\partial u}{\partial y}(x,y) \\ &+ \frac{h^2}{2} \frac{\partial^2 u}{\partial x^2}(x,y) + hk \frac{\partial^2 u}{\partial x \partial y}(x,y) + \frac{k^2}{2} \frac{\partial^2 u}{\partial y^2}(x,y) \\ &\vdots \\ &+ \sum_{p=0}^n \frac{h^p k^{n-p}}{p! \ (n-p)!} \ \frac{\partial^n u}{\partial x^p \partial y^{n-p}}(x,y) \\ &+ \mathcal{O}(h^{n+1} + k^{n+1}) \end{split}$$

Example Coming back to the 2-D Laplacian operator, the preceding Taylor formula can be used to prove that

$$\frac{u(x+h,y+h) + u(x-h,y+h) + u(x+h,y-h) + u(x-h,y-h) - 4u(x,y)}{2h^2} = \Delta u(x,y) + \mathcal{O}(h^2)$$

More precisely:

$$\frac{u(x+h,y+h)+u(x-h,y+h)+u(x+h,y-h)+u(x-h,y-h)-4u(x,y)}{2h^2} = \\ \Delta u(x,y) + \frac{h^2}{12} \left(\frac{\partial^4 u}{\partial x^4}(x,y) + 6 \frac{\partial^4 u}{\partial x^2 \, \partial y^2}(x,y) + \frac{\partial^4 u}{\partial y^4}(x,y) \right) + o(h^2)$$

while the more usual scheme (2.9) satisfies

$$\frac{u(x+h,y)+u(x-h,y)+u(x,y+h)+u(x,y-h)-4u(x,y)}{h^2} = \frac{\Delta u(x,y)+\frac{h^2}{12}\left(\frac{\partial^4 u}{\partial x^4}(x,y)+\frac{\partial^4 u}{\partial y^4}(x,y)\right)+o(h^2)}{h^2}$$

CHAPTER 2. INTRODUCTION TO FINITE DIFFERENCES

Chapter 3

Laplace and Poisson problems

3.1 Some vocabulary

The steady-state solution of a physical phenomenon governed by diffusion satisfies

$$-\mathsf{div}\ (k(\mathbf{x})\,\nabla u(\mathbf{x})) = f$$

where u is the state variable (temperature, chemical concentration...), k is the diffusion coefficient and f the forcing term (source/sink).

If k is actually a constant, the PDE becomes $-k \Delta u = f$, called a **Poisson equation**.

Moreover, if f is equal to zero, the PDE becomes $\Delta u = 0$, called a **Laplace equation**. The solutions of Laplace equation are called **harmonic functions**.

3.2 Some general remarks on harmonic functions

3.2.1 Harmonic functions in \mathbb{R}^2

Examples of harmonic functions in \mathbb{R}^2 are:

$$u(x,y) = a(x^2 - y^2) + bxy + cx + dy + e$$

► In polar coordinates:

$$\begin{cases} u_0(r,\theta) = c_0 \ln r + d_0 \\ u_n(r,\theta) = (a_n \cos n\theta + b_n \sin n\theta) \left(c_n r^n + \frac{d_n}{r^n} \right) & \forall n \in \mathbb{N}^* \end{cases}$$
 for $r \neq 0, \forall a_n, b_n, c_n, d_n \in \mathbb{R}$

Moreover, Δ being a linear operator, any linear combination of harmonic functions is also an harmonic function.

Therefore there are "many" harmonic functions since Span $\{u_{\lambda}^1, u_{\lambda}^2, \lambda \in \mathbb{R}\}$, which is a space of uncountable infinite dimension, is included in the set of harmonic functions in \mathbb{R}^2 .

3.2.2 Harmonic functions in bounded domains in \mathbb{R}^2

PDEs are often defined on bounded domains, rather than on \mathbb{R}^n . Analytical solutions can be found in some cases, in particular for domains with simple geometries, like rectangles or disks in \mathbb{R}^2 . This is the case for the Laplace equation, where preceding elementary harmonic functions can be combined to get solutions on particular domains. For instance:

The solution to the Laplace equation in $\Omega=(0,L_x)\times(0,L_y)$ with Dirichlet boundary conditions $u(0,y)=h(y), u(L_x,y)=u(x,0)=u(x,L_y)=0$ can be obtained by a separation of variables technique. It reads

$$u(x,y) = \sum_{k>1} \alpha_k \left(e^{\lambda_k x} - e^{\lambda_k (2L_x - x)} \right) \sin(\lambda_k y)$$

where
$$\lambda_k = \frac{k\pi}{L_y}$$
 and $\alpha_k = \frac{2}{L_y \left(1 - e^{2\lambda_k L_x}\right)} \int_0^{L_y} h(y) \sin(\lambda_k y) \, dy$.

► The solution to the Laplace equation on the open disk Ω of center (0,0) and radius R with Dirichlet boundary conditions $u=g(\theta)$ is

$$u(r,\theta) = K(r,\theta) * g(\theta) = \frac{1}{2\pi} \int_0^{2\pi} K(r,\theta-\alpha)g(\alpha) \, d\alpha \quad \text{ where } K(r,\theta) = \frac{R^2 - r^2}{R^2 + r^2 - 2rR\cos\theta}$$

3.2.3 Some properties of harmonic functions

The harmonic functions share a number of properties. For an open set $\Omega \subset \mathbb{R}^n$:

- ▶ Global influence of boundary values: u changes everywhere in Ω as soon as the Dirichlet boundary data changes somewhere on $\partial\Omega$.
- ▶ Regularity: If the Dirichlet boundary data $g \in C^0(\partial\Omega)$ then $u \in C^\infty(\Omega)$.
- ▶ Mean value property: Let $B(\mathbf{x},r)$ denote the ball of center \mathbf{x} and radius r. For each closed ball $B(\mathbf{x},r) \subset \Omega$:

$$u(\mathbf{x}) = \frac{1}{|B(\mathbf{x}, r)|} \int_{B(\mathbf{x}, r)} u(\mathbf{y}) d\mathbf{y} = \frac{1}{|\partial B(\mathbf{x}, r)|} \int_{\partial B(\mathbf{x}, r)} u(\boldsymbol{\sigma}) d\boldsymbol{\sigma}$$

This means that the value of an harmonic function at point $\mathbf x$ is the average of its values over every ball and every sphere which center is $\mathbf x$ and which is contained in the domain. One can even prove that, if u is a \mathcal{C}^2 function that satisfies the mean value property, then u is an harmonic function.

▶ Maximum principle: If $u \in C^2(\Omega)$ and $u \in C^0(\overline{\Omega})$, then u has no extreme values in Ω .

3.3 Poisson equation in \mathbb{R}^2 and \mathbb{R}^3

In \mathbb{R}^2 , the Laplacian operator in polar coordinates reads $\Delta u = \frac{\partial^2 u}{\partial r^2} + \frac{1}{r} \frac{\partial u}{\partial r} + \frac{1}{r^2} \frac{\partial^2 u}{\partial \theta^2}$.

The corresponding radial harmonic functions, defined on $\mathbb{R}^2 \setminus \{(0,0)\}$, are

$$u(r,\theta) = u(r) = a \ln r + b \qquad \forall a, b \in \mathbb{R}$$

In \mathbb{R}^3 , the Laplacian operator in spherical coordinates reads

$$\Delta u = \frac{\partial^2 u}{\partial r^2} + \frac{2}{r} \frac{\partial u}{\partial r} + \frac{1}{r^2 \sin \phi} \frac{\partial^2 u}{\partial \theta^2} + \frac{1}{r^2 \sin \phi} \frac{\partial}{\partial \phi} \left(\sin \phi \frac{\partial u}{\partial \phi} \right)$$

The corresponding radial harmonic functions, defined on $\mathbb{R}^3 \setminus \{(0,0,0)\}$, are

$$u(r, \theta, \phi) = u(r) = \frac{a}{r} + b \quad \forall a, b \in \mathbb{R}$$

The function

$$K(r) = \begin{cases} & \frac{1}{2\pi} \ln r & \text{in } \mathbb{R}^2 \smallsetminus \{(0,0)\} \\ & \frac{-1}{4\pi r} & \text{in } \mathbb{R}^3 \smallsetminus \{(0,0,0)\} \end{cases}$$

which corresponds to particular cases of the preceding radial harmonic functions, is called **Poisson kernel** in \mathbb{R}^2 or \mathbb{R}^3 .

Theorem 3.1. Let consider the Poisson problem $\Delta u(\mathbf{x}) = f(\mathbf{x})$ in \mathbb{R}^n (n=2 or 3), with $\|u\| \to 0$ as $\|\mathbf{x}\| \to \infty$. Then u = K * f is a solution to this problem. Moreover, if $f \in \mathcal{C}^2$ and is zero far away from 0, then $u \in \mathcal{C}^2$.

Theorem 3.2. (generalization to a bounded domain)

Let Ω a bounded domain in \mathbb{R}^n (n=2 or 3), and $\mathbf{x} \in \Omega$. Let $K_{\mathbf{x}}$ the solution of

$$\left\{ \begin{array}{ll} \Delta K_{\mathbf{x}} &= 0 & \text{in } \Omega \\ K_{\mathbf{x}} &= K(.-\mathbf{x}) & \text{on } \partial \Omega \end{array} \right.$$

Let $G(\mathbf{x}, \mathbf{y}) = K(\mathbf{y} - \mathbf{x}) - K_{\mathbf{x}}(\mathbf{y})$ (G is called a **Green function** associated to the Laplacian operator and to Ω).

Then
$$u(\mathbf{x}) = \int_{\Omega} f(\mathbf{y}) \, G(\mathbf{x}, \mathbf{y}) \, d\mathbf{y} - \int_{\partial \Omega} g(\mathbf{s}) \, \frac{\partial G}{\partial \mathbf{n}}(\mathbf{s}) \, d\mathbf{s}$$
 is a solution to the Poisson problem
$$\left\{ \begin{array}{rcl} \Delta u &= f & \text{in } \Omega \\ u &= g & \text{on } \partial \Omega \end{array} \right.$$

where f and q are given regular functions.

The proofs of these theorems imply the introduction of the so-called distribution theory.

3.4 Companion equations and operators

Several other operators are close to, or derived from, the Laplacian operator. Some well-known ones are:

- the **Helmholtz operator** $\Delta + \lambda^2 \operatorname{Id}$. $\Delta u + \lambda^2 u = 0$ is the Helmholtz equation. It appears for instance in acoustics, seismology, electromagnetic radiation..., and actually for every problem linked to the diffusion equation or to the wave equation. As a matter of fact, as will be discussed later (see §6.2.4, §7.2.1 and Appendix B), solving the Helmholtz equation corresponds to looking for the eigenvalues and eigenfunctions of the Laplacian operator, which are fundamental components of the solutions of these equations.
- ▶ the **biharmonic operator** Δ^2 : $\Delta^2 u = \Delta(\Delta u)$. It appears for instance in continuum mechanics. A famous example is also the *Chladni figures*, where an experimental device (sand on vibrating plates) highlights the zero isolines of its eigenfunctions.
- ▶ and more generally the iterated Laplacian operators Δ^p ($p \in \mathbb{N}$). They appear in particular in the parameterization of dissipation processes in fluid mechanics.

3.5 Finite difference schemes

As seen in Chapter 2, the usual discretization scheme for the second-order derivative is given by (2.5):

$$u''(x) = \frac{u(x+h) - 2u(x) + u(x-h)}{h^2} + \mathcal{O}(h^2)$$

Hence the usual second-order finite difference scheme for the Laplacian:

$$\Delta u_{i_1,i_2,\dots,i_N} = \frac{u_{i_1-1,i_2,\dots,i_N} - 2u_{i_1,i_2,\dots,i_N} + u_{i_1+1,i_2,\dots,i_N}}{h_1^2} + \dots + \frac{u_{i_1,i_2,\dots,i_N-1} - 2u_{i_1,i_2,\dots,i_N} + u_{i_1,i_2,\dots,i_N+1}}{h_N^2} + \mathcal{O}(h^2)$$

with the convention $h^2 = \sum_{i=1}^N h_i^2$.

In the particular case N=2, it reads:

$$\Delta u_{i,j} = \frac{u_{i-1,j} - 2u_{i,j} + u_{i+1,j}}{h_x^2} + \frac{u_{i,j-1} - 2u_{i,j} + u_{i,j+1}}{h_y^2} + \mathcal{O}(h^2) ,$$

which reduces to the well-known five-point scheme if $h_x = h_y$:

$$\Delta u_{i,j} = \frac{u_{i-1,j} + u_{i+1,j} + u_{i,j-1} + u_{i,j+1} - 4u_{ij}}{h^2} + \mathcal{O}(h^2)$$

The discretization of the Laplace equation with these second-order schemes leads to a numerical solution that obviously satisfies the maximum principle, since $u_{i_1,i_2,...,i_N}$ appears as a weighted average, with positive weights, of neighboring points.

Some properties of this scheme, and of an alternative 9-point scheme, are given in the exercise sheet.

Chapter 4

Dealing with the time variable

This chapter focuses on aspects related to the finite difference discretization of time-dependent PDEs. Let consider the generic equation $\frac{\partial u}{\partial t} = F(u)$ where F is a partial differential operator involving only derivatives with regard to space coordinates. For example, $F(u) = -\mathbf{c}(\mathbf{x},t).\nabla u$ corresponds to a transport equation (see Chapter 5) while $F(u) = \operatorname{div}(k(\mathbf{x},t)\nabla u)$ corresponds to a diffusion equation (see Chapter 7).

4.1 Discretization of $\frac{\partial u}{\partial t}$

The most usual schemes for the time derivative are:

$$\qquad \textbf{Euler forward:} \ \, \frac{\partial u}{\partial t}(x,t) = \frac{u(x,t+\delta t) - u(x,t)}{\delta t} + \mathcal{O}(\delta t)$$

$$\qquad \textbf{Euler backward} \colon \, \frac{\partial u}{\partial t}(x,t) = \frac{u(x,t) - u(x,t-\delta t)}{\delta t} + \mathcal{O}(\delta t)$$

$$\qquad \textbf{Leap-frog:} \ \, \frac{\partial u}{\partial t}(x,t) = \frac{u(x,t+\delta t) - u(x,t-\delta t)}{2\delta t} + \mathcal{O}(\delta t^2)$$

Euler schemes are obviously first-order accurate, while the leap-frog scheme is second-order accurate.

These schemes are widely used, mostly because of their simplicity. However many other time integration schemes are available, some of them being given in §4.4.

4.2 Time discretization of F(u)

When discretizing in time the equation $\frac{\partial u}{\partial t} = F(u)$, several choices can be made for the evaluation of F(u).

▶ If it is evaluated at time t, the scheme is said to be **explicit**, since $u(x, t + \delta t)$ can be explicitly expressed from the values of u at previous time steps.

Example *Euler forward* + *explicit scheme*

$$\frac{u(x,t+\delta t)-u(x,t)}{\delta t}\simeq F(u(x,t)) \quad \longrightarrow \quad u(x,t+\delta t)\simeq u(x,t)+\delta t\, F(u(x,t))$$

▶ On the opposite, if F(u) is evaluated at time $t + \delta t$, the scheme is said to be **implicit**, since it is necessary to solve an equation to deduce $u(x, t + \delta t)$ from the values of u at previous time steps.

Example *Euler forward* + *implicit scheme*

$$\frac{u(x,t+\delta t)-u(x,t)}{\delta t} \simeq F(u(x,t+\delta t)) \quad \longrightarrow \quad u(x,t+\delta t)-\delta t \, F(u(x,t+\delta t)) \simeq u(x,t)$$

▶ A combination of both approaches is also possible:

$$\alpha F(u(x, t + \delta t)) + (1 - \alpha) F(u(x, t)), \quad \text{with } 0 \le \alpha \le 1$$

 $\alpha=0$ corresponds to the explicit scheme and $\alpha=1$ to the implicit one. For $0<\alpha<1$, the scheme is said to be **semi-implicit**.

The particular case $\alpha=0.5$ is called the **Crank-Nicolson** scheme. One of its main interests comes from the fact that an Euler forward scheme associated with a Crank-Nicolson discretization of F(u) corresponds actually to a second-order approximation of $\frac{\partial u}{\partial t}=F(u)$ at point $(x,t+\delta t/2)$ (and not only to an obvious first-order approximation of this equation at point (x,t)).

An explicit scheme is simpler and generally requires less calculations at each time step than an implicit scheme. But an implicit scheme is often more stable (see $\S4.3$) and allows larger time steps than an explicit scheme.

4.3 Stability

4.3.1 Numerical stability

The finite difference method leads to an approximation of the solution of a differential equation, the main error source being the truncation error, related to the approximation of derivatives by numerical schemes¹. This error can be reduced by decreasing the values of the time and space steps, and/or by using higher-order schemes. However, nothing ensures that a small initial error will not grow up into a large error after a number of time steps.

 $^{^{1}}$ The other error source, but to a much lesser extent, is the rounding error, due to the representation of real numbers in a computer

Definition 4.1. A finite difference scheme for a time dependent differential equation is said to be **stable** iff errors remain bounded during the computations. This implies that the numerical solution remains bounded (whenever the exact solution is bounded, of course).

This notion of (in)stability can be illustrated for instance by considering the ODE $\frac{\partial u}{\partial t} = -\lambda u$ ($\lambda > 0$), with the initial condition u(0) = 1. Its exact solution is $u(t) = \exp(-\lambda t)$.

An explicit forward Euler discretization reads: $\frac{u_{n+1}-u_n}{\delta t}=-\lambda\;u_n\;\text{where}\;u_n\;\text{is an approximation}$ of $u(n\delta t)$. This leads to $u_n=(1-\lambda\delta t)\,u_{n-1}=\cdots=(1-\lambda\delta t)^nu_0$. Choosing a time step δt such that $|1-\lambda\delta t|>1$, i.e. $\delta t>2/\lambda$, will thus make u_n tend to infinity. This phenomenon is called a **numerical blow-up**. On the contrary, choosing $\delta t\leq 2/\lambda$ ensures that the u_n 's remain bounded. Hence the **stability condition**: $\delta t\leq \frac{2}{\lambda}$.

Thus the stability of numerical schemes must be investigated when discretizing a time dependent differential equation.

Warning Numerical stability does not imply convergence towards the exact solution, but only ensures that no numerical blow-up will occur (to be convinced, choose for instance $\delta t = 2/\lambda$ in the preceding example).

4.3.2 Investigating the stability: the Fourier method

As mentioned in §1.6, the **Fourier method**, also called **Von Neumann method**, is the most common approach for investigating the stability of a numerical scheme discretizing a **linear** differential equation. It consists in considering the expansion into Fourier series (see Appendix A) of the initial condition u(x,0):

$$u(x,0) = \sum_{k=-\infty}^{+\infty} c_k e^{ik\omega x}$$
(4.1)

The numerical scheme is stable iff it is stable for any individual component $e^{ik\omega x}$. Let $u_n(x)$ the numerical approximation of the exact solution u at time $n\delta t$. For linear schemes, it can easily be proved by recurrence that, if $u_0(x)=e^{ipx}$ ($p\in\mathbb{R}$), then $u_n(x)=\xi^n e^{ipx}$, where ξ is a complex number that depends on p and on the numerical scheme (in particular on the time and space steps). The Fourier stability criterion then consists in imposing that $|\xi|\leq 1$ for any p, which implies constraints on the time and space steps.

Example Let consider the 1D transport equation $\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0$ for $x \in [0, L], t > 0$, with c > 0, and with the initial condition $u(x,0) = u_0(x)$ and some boundary condition at x = 0. Let a regular mesh of [0,L], with δx the mesh step. Let also δt the time step, and u_j^n the approximation of the exact solution at time $n \, \delta t$ at grid point j. Let consider the discretization scheme:

$$\frac{u_j^{n+1} - u_j^n}{\delta t} + c \, \frac{u_j^n - u_{j-1}^n}{\delta x} = 0$$

Replacing u^n_j by $\xi^n e^{ipj\delta x}$ leads to $\frac{\xi-1}{\delta t}+c\,\frac{1-e^{-ip\delta x}}{\delta x}=0$ i.e. $\xi=1-c\,\frac{\delta t}{\delta x}\,\left(1-e^{-ip\delta x}\right)$. The modulus of ξ is thus:

$$|\xi|^2 = 1 + 2\left(1 - \cos(p\delta x)\right)C(C - 1)$$
 with $C = c\frac{\delta t}{\delta x}$

The stability condition $|\xi| \leq 1, \forall p \in \mathbb{R}$, is thus equivalent to $C \leq 1$, i.e. $\frac{\delta x}{\delta t} \geq c$. This condition is called the Courant-Friedrichs-Lewy (or CFL) condition. The dimensionless quantity $c \frac{\delta t}{\delta x}$ is called the Courant (or CFL) number.

Remarks

- Note that stability must be investigated considering the homogeneous equation (i.e. without any right-hand side). As a matter of fact, a source or sink term would continuously inject or consume energy, which could make the solution blow up or remain bounded independently of the intrinsic properties of the numerical scheme.
- ► For this approach and the expansion (4.1) to be rigorous, the PDE and the numerical scheme must be linear, with constant coefficients. However it is actually used for much more general cases (by linearizing the equation and/or freezing the coefficients), and it generally provides a good guess at the possible constraints on the time and space steps.
- In the same way, this approach is usually applied to the PDE on all space with no boundaries $(x \in \mathbb{R})$. It can also be used to study the stability of problems with periodic boundary conditions. But studying the stability of problems with more general boundary conditions can be quite difficult. Von Neumann analysis actually addresses the issue of stability of the PDE discretization alone.
- ▶ This method can be generalized to 2D and 3D cases.

Some generic calculations facilitating the computation of stability criteria are given in Appendix C.1.

4.3.3 Other methods for investigating stability issues

Other methods are available to study the stability properties of finite difference schemes.

▶ The eigenvalue method consists in writing the matrix form of the scheme:

$$U^{n+1} = MU^n \qquad \text{ with } U^n = \left(\begin{array}{c} u_1^n \\ \vdots \\ u_J^n \end{array} \right)$$

We have then obviously $U^n=M^nU^0$. A stability condition is thus that the spectral radius of M (i.e. the maximum of the moduli of its eigenvalues) be less or equal to 1. One has thus to study the eigenvalues of M.

- Stability can be also be directly assessed by the **energy method**. Let define the energy of the discrete solution as $E^n = \sum_{j=1}^J (u^n_j)^2$. The goal is then to prove that this quantity remains bounded independently of n, as n tends to infinity. Note that, thanks to the Parseval's theorem (see Appendix A), this corresponds to the Fourier method, but in the real space.
- These three methods (Fourier, eigenvalue, energy) aim at proving the L^2 stability of the scheme, i.e. the fact that the L^2 norm of the numerical solution remains bounded independently of the time. Other stability criteria may also be used, like for instance the L^∞ stability (i.e. working on the L^∞ norm of the numerical solution).

4.4 Some time discretization schemes

Numerous time integration schemes are available for ODEs and PDEs. Without looking for exhaustiveness, let us mention a few.

Let the differential equation $\frac{\partial u}{\partial t} = F(u,t)$ with the initial condition $u(0) = u_0$. Let δt the time step, $t_n = n \, \delta t$ and u_n the approximation of $u(t_n)$.

4.4.1 One step methods

One step methods are integration schemes determining the value at the next time step using only the value at the current time step. The simplest one is the already mentioned Euler method. Let cite also the **midpoint method** (second order):

$$k_1 = \delta t F(u_n, t_n)$$

 $k_2 = \delta t F(u_n + \frac{k_1}{2}, t_n + \frac{\delta t}{2})$
 $u_{n+1} = u_n + k_2$

and more generally the **Runge-Kutta methods**, the most famous one being probably the fourth-order scheme:

$$k_{1} = \delta t F(u_{n}, t_{n})$$

$$k_{2} = \delta t F(u_{n} + \frac{k_{1}}{2}, t_{n} + \frac{\delta t}{2})$$

$$k_{3} = \delta t F(u_{n} + \frac{k_{2}}{2}, t_{n} + \frac{\delta t}{2})$$

$$k_{4} = \delta t F(u_{n} + k_{3}, t_{n} + \delta t)$$

$$u_{n+1} = u_{n} + \frac{k_{1}}{6} + \frac{k_{2}}{3} + \frac{k_{3}}{3} + \frac{k_{4}}{6}$$

4.4.2 Multi-step methods

Contrary to one-step methods, the value at the next time step is obtained using values at several preceding time steps. Let cite **Adams-Bashforth explicit methods** (k^{th} -order):

$$\begin{array}{ll} k=1 & u_{n+1}=u_n+\delta t \, F(u_n,t_n) & \text{(i.e. explicit Euler scheme)} \\ k=2 & u_{n+2}=u_{n+1}+\frac{\delta t}{2} \left[3F(u_{n+1},t_{n+1})-F(u_n,t_n)\right] \\ k=3 & u_{n+3}=u_{n+2}+\frac{\delta t}{12} \left[23F(u_{n+2},t_{n+2})-16F(u_{n+1},t_{n+1})+5F(u_n,t_n)\right] \\ k=4 & u_{n+4}=u_{n+3}+\frac{\delta t}{24} \left[55F(u_{n+3},t_{n+3})-59F(u_{n+2},t_{n+2})+37F(u_{n+1},t_{n+1})-9F(u_n,t_n)\right] \end{array}$$

and the **Adams-Moulton implicit methods** (k^{th} -order):

$$\begin{array}{ll} k=1 & u_{n+1}=u_n+\delta t \, F(u_{n+1},t_{n+1}) & \text{(i.e. implicit Euler scheme)} \\ k=2 & u_{n+1}=u_n+\frac{\delta t}{2} \left[F(u_{n+1},t_{n+1})+F(u_n,t_n) \right] \\ k=3 & u_{n+2}=u_{n+1}+\frac{\delta t}{12} \left[5F(u_{n+2},t_{n+2})+8F(u_{n+1},t_{n+1})-F(u_n,t_n) \right] \\ k=4 & u_{n+3}=u_{n+2}+\frac{\delta t}{24} \left[9F(u_{n+3},t_{n+3})+19F(u_{n+2},t_{n+2})-5F(u_{n+1},t_{n+1})+F(u_n,t_n) \right] \end{array}$$

4.4.3 Predictor-corrector schemes

The idea underlying this approach is to get performances close to implicit schemes without their major drawback, i.e. without solving a linear system. It is decomposed in two stages:

- **Prediction**: use an explicit scheme to get a first approximation \widetilde{u}_{n+1} .
- **Correction**: use an implicit scheme, but replacing u_{n+1} by its approximation \widetilde{u}_{n+1} in the implicit part of the equation.

Example Prediction with an explicit Euler scheme and correction with an implicit Euler scheme reads:

Prediction:
$$\widetilde{u}_{n+1} = u_n + \delta t F(u_n, t_n)$$
.

Correction:
$$u_{n+1} = u_n + \delta t F(\widetilde{u}_{n+1}, t_{n+1}).$$

Chapter 5

The transport equation

This chapter focuses on the **transport equation** $\frac{\partial u}{\partial t}(\mathbf{x},t) + \mathbf{c}(\mathbf{x},t) \cdot \nabla u(\mathbf{x},t) = 0$, and more generally on linear first-order PDEs: $\frac{\partial u}{\partial t}(\mathbf{x},t) + \mathbf{c}(\mathbf{x},t) \cdot \nabla u(\mathbf{x},t) + r(\mathbf{x},t) \cdot u(\mathbf{x},t) = f(\mathbf{x},t)$.

5.1 Some generalities

5.1.1 Physical interpretation

Let consider a scalar quantity $u(\mathbf{x},t)$ transported by a given velocity field $\mathbf{c}(\mathbf{x},t)$ in a domain $\Omega \subset \mathbb{R}^n$ (e.g. the concentration of some chemical species in a fluid, an oil spill in the ocean...). In case of a pure transport, i.e. without any interaction of the quantity with the surrounding medium, the behavior of u is governed by the equation

$$\frac{\partial u}{\partial t}(\mathbf{x}, t) + \mathbf{c}(\mathbf{x}, t) \cdot \nabla u(\mathbf{x}, t) = 0$$

i.e.
$$\frac{\partial u}{\partial t}(\mathbf{x},t) + \sum_{i=1}^n c_i(\mathbf{x},t) \frac{\partial u}{\partial x_i}(\mathbf{x},t) = 0$$

This can easily be proved by stating that, for an infinitesimal interval of time δt , $u(\mathbf{x}+\mathbf{c}(\mathbf{x},t)\,\delta t,t+\delta t)=u(\mathbf{x},t)$, then developing the first term using a Taylor expansion, and making δt tend to zero.

5.1.2 Boundary conditions

The basic principle regarding boundary conditions is that, for the transport equation to be well-posed, information is required at the boundary where and when the transport field is incoming, but not where and when it is outgoing. Denoting $\mathbf{n}(\mathbf{x})$ the outward normal vector for $\mathbf{x} \in \partial \Omega$, this incoming portion of the boundary is $\partial \Omega^-(t) = \{\mathbf{x} \in \partial \Omega \, / \, \mathbf{c}(\mathbf{x},t).\, \mathbf{n}(\mathbf{x}) < 0\}$.

5.2 Resolution: the method of characteristics

5.2.1 Eulerian vs Lagrangian representations

In the context of continuum mechanics (fluid mechanics, solid mechanics), the system state can be described using either an Eulerian or a Lagrangian point of view. The **Eulerian** point of view consists in quantifying the properties of the medium (mass, velocity, temperature...) at every time t for any given location \mathbf{x} . On the other hand, in the **Lagrangian** point of view, the observer follows a specific material particle all along its motion.

We will use in the following the notation $X(s; \mathbf{x}, t)$ to indicate the location at time s of the material particle that is located at point \mathbf{x} at time t. \mathbf{x} is the Eulerian coordinate, while X is the Lagrangian one.

5.2.2 Method of characteristics: general principle

Let consider the general linear first-order PDE in \mathbb{R}^n :

$$\begin{cases} \frac{\partial u}{\partial t}(\mathbf{x}, t) + \mathbf{c}(\mathbf{x}, t) \cdot \nabla u(\mathbf{x}, t) + r(\mathbf{x}, t) u(\mathbf{x}, t) = f(\mathbf{x}, t) & \mathbf{x} \in \mathbb{R}^n, t > 0 \\ u(\mathbf{x}, 0) = u_0(\mathbf{x}) \end{cases}$$

with: $\mathbf{c}(\mathbf{x},t): \mathbb{R}^n \times \mathbb{R}_+ \to \mathbb{R}^n$ a continuous function, Lipschitz continuous w.r.t. t $r(\mathbf{x},t)$ and $f(\mathbf{x},t): \mathbb{R}^n \times \mathbb{R}_+ \to \mathbb{R}$ continuous functions $u_0(\mathbf{x}): \mathbb{R}^n \to \mathbb{R}$ a continuous function.

The **method of characteristics** to solve this PDE consists in the following steps:

- \blacktriangleright Let (\mathbf{x}, t) fixed.
- \triangleright Solve the differential system (n equations, n unknowns):

$$\left\{ \begin{array}{l} X'(s) = \mathbf{c}(X(s),s) \\ \\ X(t) = \mathbf{x} \end{array} \right.$$

Its solution is denoted X(s), or $X(s; \mathbf{x}, t)$. It is called the **characteristic curve** or **characteristic function** related to (\mathbf{x}, t) . It corresponds to the trajectory that the material particle would follow in the pure transport case (i.e. r = f = 0).

We have then $\frac{d}{ds}u(X(s),s)=f(X(s),s)-r(X(s),s)$ u(X(s),s), which means that Z(s)=u(X(s),s) satisfies Z'(s)=f(X(s),s)-r(X(s),s) Z(s).

Solve the ODE:

$$\begin{cases} Z'(s) + r(X(s), s) \ Z(s) = f(X(s), s) \quad s > 0 \\ Z(0) = u(X(0), 0) = u_0(X(0; \mathbf{x}, t)) \end{cases}$$

► Then: $u(\mathbf{x},t) = u(X(t),t) = Z(t;\mathbf{x},t)$

Example Let consider the PDE

$$\begin{cases} \frac{\partial u}{\partial t} + x \frac{\partial u}{\partial x} + y \frac{\partial u}{\partial y} - 3u = 0 & (x, y) \in \mathbb{R}^2, t > 0 \\ u(x, y, 0) = x + y & \end{cases}$$

With previous notations, $\mathbf{c}(\mathbf{x},t) = (c_1(x,y,t), c_2(x,y,t)) = (x,y)$, $r(\mathbf{x},t) = -3$ and $f(\mathbf{x},t) = 0$. For fixed (x,y,t), the first step consists in solving

$$\begin{cases} X_1'(s) = c_1(X(s), s) = X_1(s) \\ X_1(t) = x \end{cases} \text{ and } \begin{cases} X_2'(s) = c_2(X(s), s) = X_2(s) \\ X_2(t) = y \end{cases}$$

This leads to $X_1(s) = x e^{s-t}$ and $X_2(s) = y e^{s-t}$.

The second step consists then in solving

$$\begin{cases} Z'(s) - 3Z(s) = 0 & s > 0 \\ Z(0) = u(X(0), 0) = u_0(X(0; x, y, t)) = u_0(x e^{-t}, y e^{-t}) = (x + y) e^{-t} \end{cases}$$

which leads to $Z(s)=(x+y)\,e^{3s-t}$. Hence the solution $u(x,y,t)=Z(t;x,y,t)=(x+y)\,e^{2t}$.

5.2.3 Case of a pure transport equation

The particular case where $r(\mathbf{x},t) = f(\mathbf{x},t) = 0$ corresponds to a pure transport equation:

$$\begin{cases} \frac{\partial u}{\partial t}(\mathbf{x}, t) + \mathbf{c}(\mathbf{x}, t) \cdot \nabla u(\mathbf{x}, t) = 0 \\ u(\mathbf{x}, 0) = u_0(\mathbf{x}) \end{cases}$$

The previous methodology leads to the solution $u(\mathbf{x},t) = u_0(X(0;\mathbf{x},t))$, which becomes $u_0(\mathbf{x} - \mathbf{c}t)$ in the particular case of a constant \mathbf{c} .

5.2.4 Case of a bounded domain

If the PDE is defined on a bounded domain $\Omega \subset \mathbb{R}^n$, the computation of $X(0; \mathbf{x}, t)$ may become impossible, since the trajectory $s \longrightarrow X(s; \mathbf{x}, t)$ may be out of Ω for $s < \tau_{in}$, with $\tau_{in} > 0$. Let thus $\tau_{in}(\mathbf{x}, t) = \inf \{ s \in [0, t] / X(s; \mathbf{x}, t) \in \Omega \}$ (τ_{in} exists since the set is not empty and has 0 as a lower bound).

▶ If $\tau_{in}(\mathbf{x},t) > 0$, then $X(\tau_{in}(\mathbf{x},t);\mathbf{x},t)$ is located on $\partial\Omega$ and one has thus to modify the initial condition in the ODE for Z, which becomes

$$\left\{ \begin{array}{l} Z'(s) + r(X(s),s) \ Z(s) = f(X(s),s) \quad s > \tau_{in}(\mathbf{x},t) \\ \\ Z(\tau_{in}(\mathbf{x},t)) = u(X(\tau_{in}(\mathbf{x},t)),\tau_{in}(\mathbf{x},t)) = \text{a value given by the boundary condition} \end{array} \right.$$

▶ If $\tau_{in}(\mathbf{x},t) = 0$, then $X(\tau_{in}(\mathbf{x},t);\mathbf{x},t)$ is not necessarily located on $\partial\Omega$, but $X(\varepsilon;\mathbf{x},t) \in \Omega$, $\forall \varepsilon > 0$. Some additional regularity conditions are thus required to go back in time up to s = 0 and use $u_0(X(0);\mathbf{x},t)$ again as the initial condition.

5.3 Numerical schemes for the 1D transport equation

Let consider the 1D transport equation

$$\begin{cases} \frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} = 0 & x \in \mathbb{R}, t > 0 \\ u(x, 0) = u_0(x) & x \in \mathbb{R} \end{cases}$$
 with $c > 0$

Its exact solution is $u(x,t) = u_0(x-ct)$. The characteristic curves are straight lines x-ct = constant.

5.3.1 Euler one-sided explicit schemes

Let consider the two following first-order finite difference schemes (with usual notations):

▶ Downstream scheme:
$$\frac{u_j^{n+1} - u_j^n}{\delta t} + c \frac{u_{j+1}^n - u_j^n}{\delta x} = 0$$

▶ Upwind scheme:
$$\frac{u_j^{n+1} - u_j^n}{\delta t} + c \frac{u_j^n - u_{j-1}^n}{\delta x} = 0$$

A Fourier stability analysis (see §4.3.2) proves that the downstream scheme is unconditionally unstable, while the upwind scheme is stable for $C \leq 1$, where $C = c \frac{\delta t}{\delta x}$ is the Courant number.

Interpretation in terms of domain of dependence The true value for $u(j\delta x, (n+1)\delta t)$ is equal to $u(j\delta x - c\,\delta t, n\,\delta t)$ (see Figure 5.1).

▶ The downstream scheme can be rewritten as

$$u_{j}^{n+1} = u_{j}^{n} - C\left(u_{j+1}^{n} - u_{j}^{n}\right) = (1 + C)u_{j}^{n} - Cu_{j+1}^{n}$$

However the true location $j\delta x - c\,\delta t$ does not lie in the interval $[j\,\delta x;(j+1)\,\delta x]$ whatever the value of δt (see Figure 5.1), which gives some rationale to the fact that this scheme is unstable.

▶ The upwind scheme can be rewritten as

$$u_i^{n+1} = u_i^n - C(u_i^n - u_{i-1}^n) = (1 - C)u_i^n + Cu_{i-1}^n$$

This means that, if $C \leq 1$, u_j^{n+1} is a convex combination of u_{j-1}^n and u_j^n , while the true location $j\delta x - c\,\delta t$ is indeed in the interval $[(j-1)\,\delta x;j\,\delta x]$ (see Figure 5.1).




Figure 5.1: Schematic view of the transport from time t to time $t + \delta t$ w.r.t. the discretization grid. The dotted and dashed lines are characteristic lines, respectively for C > 1 and C < 1.

Interpretation in terms of equivalent PDE A Taylor expansion of the Euler scheme (see also Appendix C.3) leads to

$$\frac{u(j\,\delta x,(n+1)\delta t)-u(j\,\delta x,n\,\delta t)}{\delta t}=\frac{\partial u}{\partial t}(j\,\delta x,n\,\delta t)+\frac{\delta t}{2}\,\frac{\partial^2 u}{\partial t^2}(j\,\delta x,n\,\delta t)+\ldots$$

Moreover:

$$\frac{\partial^2 u}{\partial t^2} = \frac{\partial}{\partial t} \left(\frac{\partial u}{\partial t} \right) = \frac{\partial}{\partial t} \left(-c \frac{\partial u}{\partial x} \right) = -c \frac{\partial}{\partial x} \left(\frac{\partial u}{\partial t} \right) = c^2 \frac{\partial^2 u}{\partial x^2}$$

which leads to:

$$\frac{u(j\,\delta x,(n+1)\delta t)-u(j\,\delta x,n\,\delta t)}{\delta t}=\frac{\partial u}{\partial t}(j\,\delta x,n\,\delta t)+c^2\,\frac{\delta t}{2}\,\frac{\partial^2 u}{\partial x^2}(j\,\delta x,n\,\delta t)+\ldots$$

The leading order term of the error, $c^2 \frac{\delta t}{2} \frac{\partial^2 u}{\partial x^2}$, is thus an antidiffusive term, which continuously injects energy in the numerical solution (see Chapter 7 and Appendix C.4), and may thus lead to numerical instability. In order for the numerical scheme to be stable, the discretization of the spatial derivative must therefore compensate for this antidiffusive term.

Taylor expansions applied to the the downstream and upwind schemes (see also Appendix C.3) lead to:

$$\begin{cases} \frac{u((j+1)\delta x, n\,\delta t) - u(j\,\delta x, n\,\delta t)}{\delta x} = \frac{\partial u}{\partial x}(j\,\delta x, n\,\delta t) + \frac{\delta x}{2}\,\frac{\partial^2 u}{\partial x^2}(j\,\delta x, n\,\delta t) + \dots \\ \frac{u(j\,\delta x, n\,\delta t) - u((j-1)\,\delta x, n\,\delta t)}{\delta x} = \frac{\partial u}{\partial x}(j\,\delta x, n\,\delta t) - \frac{\delta x}{2}\,\frac{\partial^2 u}{\partial x^2}(j\,\delta x, n\,\delta t) + \dots \end{cases}$$

which implies the following equivalent PDEs:

$$\begin{cases} \text{downstream scheme:} & \frac{\partial u}{\partial t} + c \, \frac{\partial u}{\partial x} + \underbrace{\left(c^2 \frac{\delta t}{2} + c \frac{\delta x}{2}\right)}_{>0} \frac{\partial^2 u}{\partial x^2} + \ldots = 0 \\ \\ \text{upwind scheme:} & \frac{\partial u}{\partial t} + c \, \frac{\partial u}{\partial x} + \underbrace{\left(c^2 \frac{\delta t}{2} - c \frac{\delta x}{2}\right)}_{\leq 0 \text{ for } C \leq 1} \frac{\partial^2 u}{\partial x^2} + \ldots = 0 \end{cases}$$

CHAPTER 5. THE TRANSPORT EQUATION

The leading order term of the error is thus of antidiffusive nature for the downstream scheme, which is consistent with the fact that this scheme is unconditionnally unstable.

The leading order term of the error is of diffusive nature for the upwind scheme iff $C \leq 1$, which is also consistent with the stability condition found previously. The upwind scheme is then said to be a **diffusive scheme**, which means that the main effect of its error is to smooth and damp out the solution (see also Definition 2.1 and Appendix C.4: the exact plane wave solution $\exp(ik(x-ct))$ becomes $\exp(ik(x-ct))$ exp $(-\nu k^2 t)$ with $\nu = c(\delta x - c\delta t)/2 = c\delta x(1-C)/2$, and $\nu \geq 0$ since $C \leq 1$).

5.3.2 Lax-Wendroff scheme

The preceding upwind scheme is only first-order accurate. A way to increase the accuracy is to use a two-sided scheme for the space derivative. However

$$\frac{u((j+1)\,\delta x,n\,\delta t)-u((j-1)\,\delta x,n\,\delta t)}{2\,\delta x}=\frac{\partial u}{\partial x}(j\,\delta x,n\,\delta t)+\frac{\delta x^2}{6}\,\frac{\partial^3 u}{\partial x^3}(j\,\delta x,n\,\delta t)+\ldots$$

Such a discretization cannot therefore compensate for the leading error term $c^2 \frac{\delta t}{2} \frac{\partial^2 u}{\partial x^2}$ in the Euler scheme. The idea of the so-called Lax-Wendroff scheme is thus to compensate almost exactly for this term by introducing an artificial additional term. It reads:

$$\frac{u_j^{n+1} - u_j^n}{\delta t} + c \frac{u_{j+1}^n - u_{j-1}^n}{2\delta x} - c^2 \frac{\delta t}{2} \frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\delta x^2} = 0$$

Its equivalent PDE (see also Appendix C.3) then reads

$$\frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} + \frac{\delta t^2}{6} \frac{\partial^3 u}{\partial t^3} + c \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3} + \dots = 0$$

which proves that the scheme is second-order accurate in time and space.

A Fourier stability analysis (see §4.3.2) proves that this scheme is stable iff $C \leq 1$.

Since $\frac{\partial^3 u}{\partial t^3} = -c^3 \frac{\partial^3 u}{\partial x^3}$, the leading error term in the equivalent PDE can be rewritten as $\frac{c}{6} \left(\delta x^2 - c^2 \, \delta t^2\right) \frac{\partial^3 u}{\partial x^3}$. The Lax-Wendroff scheme is thus said to be a **dispersive scheme**, since the main effect of its error is to modify the transport velocity (see also Definition 2.2 and Appendix C.4: the exact plane wave solution $\exp(ik(x-ct))$ becomes $\exp(ik\left[x-(c-k^2\mu)t\right])$ with $\mu = c(\delta x^2 - c^2 \delta t^2)/6$). Since $C \leq 1$ for stability reasons, $\mu \geq 0$ and the numerical transport is slower than the exact continuous one.

5.3.3 Other schemes

Many other schemes are of course available for this transport equation, several of them being detailed in the corresponding exercise sheet.

Chapter 6

The wave equation

This chapter focuses on the wave equation $\frac{\partial^2 u}{\partial t^2}(\mathbf{x},t)-c^2\Delta u(\mathbf{x},t)=0$ (c>0), which is a prototype for linear hyperbolic second-order PDEs.

6.1 Some properties

6.1.1 Conservation of energy

Following some physical reasoning, the kinetic and potential energies of the solution are defined respectively by

$$\mathit{KE}(t) = \frac{1}{2} \int_{\Omega} \left(\frac{\partial u}{\partial t}(\mathbf{x}, t) \right)^2 d\mathbf{x} \quad \text{and} \quad \mathit{PE}(t) = \frac{c^2}{2} \int_{\Omega} \|\nabla u(\mathbf{x}, t)\|^2 d\mathbf{x}$$

If the domain $\Omega=\mathbb{R}^n$, or if it is bounded with either homogeneous Neumann boundary conditions $\frac{\partial u}{\partial \mathbf{n}}=0$ or steady-state Dirichlet conditions $u(\mathbf{x},t)=g(\mathbf{x}) \ \forall t$, then the total energy E(t)=KE(t)+PE(t) is conserved.

6.1.2 Initial conditions

Since the wave equation involves a second-order time derivative, two initial conditions are required for the problem to be well-posed. Typically one will provide the values of the solution and of its time derivative at initial time:

$$u(\mathbf{x},0) = u_0(\mathbf{x})$$
 and $\frac{\partial u}{\partial t}(\mathbf{x},0) = v_0(\mathbf{x}) \quad \forall \mathbf{x} \in \Omega$

with $u_0 \in \mathcal{C}^2(\Omega)$ and $v_0 \in \mathcal{C}^1(\Omega)$.

6.2 Analytical solutions

The wave equation can be solved analytically, at least in 1-D, by several techniques. The first technique presented in this section relies on a change of variables, and is rather specific to the wave equation. The two other techniques are widely used for computing analytical solutions of time-dependent linear PDEs: separation of variables, in the case where the domain is bounded (already seen for the Laplace equation), and Fourier transform w.r.t. space variables, in the case where the domain is \mathbb{R}^n .

6.2.1 1-D solution: change of variables

The 1-D wave equation reads $\frac{\partial^2 u}{\partial t^2}(x,t) - c^2 \frac{\partial^2 u}{\partial x^2}(x,t) = 0.$

Let $p(x,t)=rac{1}{c}rac{\partial u}{\partial t}$ and $q(x,t)=rac{\partial u}{\partial x}$. The wave equation can then be rewritten as

$$\frac{\partial p}{\partial t} - c \frac{\partial q}{\partial x} = 0 \tag{6.1}$$

while the link between p and q is:

$$\frac{\partial q}{\partial t} - c \frac{\partial p}{\partial x} = 0 \tag{6.2}$$

Adding and substracting (6.1) and (6.2) leads to the two following transport equations:

$$\begin{cases} \frac{\partial (p-q)}{\partial t} + c \frac{\partial (p-q)}{\partial x} = 0\\ \frac{\partial (p+q)}{\partial t} - c \frac{\partial (p+q)}{\partial x} = 0 \end{cases}$$

Hence, following §5.2.3, (p+q)(x,t)=A(x+ct) and (p-q)(x,t)=B(x-ct). This leads to

$$\begin{cases} p(x,t) = \frac{1}{c} \frac{\partial u}{\partial t} = \frac{1}{2} [A(x+ct) + B(x-ct)] \\ q(x,t) = \frac{\partial u}{\partial x} = \frac{1}{2} [A(x+ct) - B(x-ct)] \end{cases}$$

which yields

$$u(x,t) = F(x+ct) + G(x-ct) \qquad \text{with } F, G \in \mathcal{C}^2$$
(6.3)

This means that the solution is made of the superposition of two travelling waves, one propagating to the right at velocity c and the other one to the left at velocity -c (cf Figure 6.1). Similarly to linear first-order PDEs, lines x - ct = constant and x + ct = constant, where F(x + ct) and G(x - ct) are constant, are called *characteristic lines*.

Note that the same result can be obtained by the change of variables X=x+ct, Y=x-ct, which transforms the wave equation into $\frac{\partial^2 U}{\partial X\,\partial Y}(X,Y)=0$, where U(X,Y)=u(x,t).




Figure 6.1: A solution of the 1-D transport equation. Green curve: initial condition; red curve: solution a while later.

6.2.2 1-D d'Alembert solution

Let complement the 1-D wave equation in \mathbb{R} with initial conditions:

$$\begin{cases} \frac{\partial^2 u}{\partial t^2}(x,t) - c^2 \frac{\partial^2 u}{\partial x^2}(x,t) = 0 & x \in \mathbb{R}, t > 0 \\ u(x,0) = u_0(x) & u_0 \in \mathcal{C}^2(\mathbb{R}) \\ \frac{\partial u}{\partial t}(x,0) = v_0(x) & v_0 \in \mathcal{C}^1(\mathbb{R}) \end{cases}$$

Thus, since u(x,t) = F(x+ct) + G(x-ct) (from (6.3)), the initial conditions yield $F(x) + G(x) = u_0(x)$ and $c(F'(x) - G'(x)) = v_0(x)$. Integrating the last equation and combining it with the first one provides the expressions for F and G. Hence the so-called d'Alembert solution:

$$u(x,t) = \frac{1}{2} \left[u_0(x+ct) + u_0(x-ct) \right] + \frac{1}{2c} \int_{x-ct}^{x+ct} v_0(s) \, ds \tag{6.4}$$

This expression clearly shows that the domain of dependence of u(x,t) is the whole interval [x-ct;x+ct] (i.e. u(x,t) depends on the initial conditions on [x-ct;x+ct]).

The same kind of approach can be generalized to higher dimensions, but leading to much more complex analytical expressions for $u(\mathbf{x},t)$.

6.2.3 Analytical solutions through Fourier transform

Let now go back to the n-D case in \mathbb{R}^n with initial conditions

$$\begin{cases}
\frac{\partial^2 u}{\partial t^2}(\mathbf{x}, t) - c^2 \Delta u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ in } \mathbb{R}^n, t > 0 \\
u(\mathbf{x}, 0) = u_0(\mathbf{x}), & \frac{\partial u}{\partial t}(\mathbf{x}, 0) = v_0(\mathbf{x}) & \mathbf{x} \text{ in } \mathbb{R}^n
\end{cases}$$
(6.5)

with $\mathbf{x} \to u(\mathbf{x},t) \in \mathcal{L}^2(\mathbb{R}^n) \ \forall t$. A Fourier transform (see §A.2) of this problem in all spatial variables directly leads to the ODE

$$\begin{cases} \frac{\partial^2 \widehat{u}}{\partial t^2}(\boldsymbol{\xi}, t) + 4\pi^2 c^2 \, \|\boldsymbol{\xi}\|^2 \widehat{u}(\boldsymbol{\xi}, t) = 0 & \boldsymbol{\xi} \text{ in } \mathbb{R}^n, t > 0 \\ \widehat{u}(\boldsymbol{\xi}, 0) = \widehat{u}_0(\boldsymbol{\xi}) \, , \, \frac{\partial \widehat{u}}{\partial t}(\boldsymbol{\xi}, 0) = \widehat{v}_0(\boldsymbol{\xi}) & \boldsymbol{\xi} \text{ in } \mathbb{R}^n \end{cases}$$

which solution is $\widehat{u}(\boldsymbol{\xi},t) = A(\boldsymbol{\xi}) e^{2i\pi c\|\boldsymbol{\xi}\|t} + B(\boldsymbol{\xi}) e^{-2i\pi c\|\boldsymbol{\xi}\|t}$. $A(\boldsymbol{\xi})$ and $B(\boldsymbol{\xi})$ are obtained thanks to the initial conditions:

$$\begin{cases} A(\boldsymbol{\xi}) = \frac{\widehat{u}_0(\boldsymbol{\xi})}{2} + \frac{\widehat{v}_0(\boldsymbol{\xi})}{4i\pi c \|\boldsymbol{\xi}\|} \\ B(\boldsymbol{\xi}) = \frac{\widehat{u}_0(\boldsymbol{\xi})}{2} - \frac{\widehat{v}_0(\boldsymbol{\xi})}{4i\pi c \|\boldsymbol{\xi}\|} \end{cases}$$

Hence the solution by inverse Fourier transform.

In the 1-D case, one retrieves of course the d'Alembert solution (6.4).

6.2.4 Case of a bounded domain: separation of variables

We consider now the wave equation in a bounded domain $\Omega \subset \mathbb{R}^n$. As seen previously, if the domain is of infinite size, the solution $u(\mathbf{x},t)$ depends on the initial conditions in the ball $\mathcal{B}(\mathbf{x},ct)$. However, if the domain is bounded, this ball no longer entirely belongs to Ω for t sufficiently large. Moreover, additional boundary conditions are required.

A way to get the analytical solution in this case, at least for domains with simple geometry, is to use a separation of variables technique. Let the wave equation with null Dirichlet boundary conditions. The initial conditions will be provided later. This problem reads:

$$\begin{cases} \frac{\partial^2 u}{\partial t^2}(\mathbf{x}, t) - c^2 \Delta u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ in } \Omega, t > 0 \\ u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ on } \partial \Omega, t > 0 \end{cases}$$
(6.6)

Looking for a solution under the form $u(\mathbf{x},t) = X(\mathbf{x}) T(t)$ leads to

$$\begin{cases} \frac{1}{c^2} \frac{T''(t)}{T(t)} = \frac{\Delta X(\mathbf{x})}{X(\mathbf{x})} = \lambda & \forall \mathbf{x} \text{ in } \Omega, \forall t > 0 \\ X(\mathbf{x}) = 0 & \mathbf{x} \text{ on } \partial \Omega \end{cases}$$

The possible values for λ are thus the eigenvalues of the Laplacian operator on Ω with null Dirichlet boundary conditions. As explained in Appendix B, there is a countable set of such eigenvalues, which are all negative, and denoted $-\omega_k^2$, $k \in \mathbb{N}$. The associated eigenfunctions X_k form an orthonormal basis of $\mathcal{L}^2(\Omega)$.

For a given k, the corresponding function $T_k(t)$ satisfies $T_k''(t) + c^2 \omega_k^2 T_k(t) = 0$, i.e. $T_k(t) = \alpha_k \cos(c \omega_k t) + \beta_k \sin(c \omega_k t)$. We have thus built a family of functions $X_k(\mathbf{x}) T_k(t)$ which are

elementary solutions of (6.6). This PDE being linear, any linear combination of these elementary solutions is also a solution. Therefore a general solution of (6.6) reads:

$$u(\mathbf{x},t) = \sum_{k} X_k(\mathbf{x}) \left[\alpha_k \cos(c \omega_k t) + \beta_k \sin(c \omega_k t) \right]$$

Adding initial conditions will then determine the α_k s and β_k s.

Let apply this technique in the 1-D case, for $\Omega = (0, L)$. The equation reads:

$$\begin{cases} \frac{\partial^2 u}{\partial t^2}(x,t) - c^2 \frac{\partial^2 u}{\partial x^2}(x,t) = 0 & x \in (0,L), t > 0 \\ u(0,t) = u(L,t) = 0 & t > 0 \\ u(x,0) = u_0(x), & \frac{\partial u}{\partial t}(x,0) = v_0(x) & x \in (0,L) \end{cases}$$

The separation of variables yields $X_k''(x) + \omega_k^2 X_k(x) = 0$ with $X_k(0) = X_k(L) = 0$. Hence $X_k(x) = \sin\frac{k\pi x}{L}$, and $u(\mathbf{x},t) = \sum_{k=1}^\infty \sin\frac{k\pi x}{L} \left[\alpha_k \cos\frac{k\pi ct}{L} + \beta_k \sin\frac{k\pi ct}{L} \right]$.

The initial conditions imply $u_0(x)=\sum_{k=1}^\infty \alpha_k \sin\frac{k\pi x}{L}$ and $v_0(x)=\sum_{k=1}^\infty \beta_k \frac{k\pi c}{L} \sin\frac{k\pi x}{L}$. These expressions can be identified with expansions into Fourier series of 2L-periodic odd functions coinciding with u_0 and v_0 on (0,L). Hence

$$\alpha_k = \frac{2}{L} \int_0^L u_o(x) \sin \frac{k\pi x}{L}$$
 and $\beta_k = \frac{2}{k\pi c} \int_0^L v_o(x) \sin \frac{k\pi x}{L}$ $k = 1, 2, \dots$

6.3 Discretization schemes

6.3.1 Second-order standard explicit scheme

A simple standard explicit scheme for the 1-D wave equation is the following:

$$\frac{u_j^{n+1} - 2u_j^n + u_j^{n-1}}{\delta t^2} - c^2 \frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\delta x^2} = 0$$
 (6.7)

It is obviously second-order accurate both in time and space. Its stability condition can be easily computed by the Fourier method, and is of CFL type: $|c|\frac{\delta t}{\delta x} \leq 1$.

The equivalent PDE of (6.7) (see Appendix C.3) is

$$\frac{\partial^2 u}{\partial t^2} - c^2 \frac{\partial^2 u}{\partial x^2} + \frac{c^2 \delta x^2}{12} \left(c^2 \frac{\delta t^2}{\delta x^2} - 1 \right) \frac{\partial^4 u}{\partial x^4} + \dots = 0$$

The stability condition corresponds to a negative coefficient for the dominant error term, which effect is mainly to slow down the wave propagation for low frequencies, but also to modify their amplitude for high frequencies (see equations (C.4)-(C.5)).

6.3.2 Lax-Wendroff scheme

One can also use the structure of (6.1) and (6.2), and apply a Lax-Wendroff discretization to both (cf §5.3.2). This reads

$$\begin{cases}
\frac{p_{j}^{n+1} - p_{j}^{n}}{\delta t} - c \frac{q_{j+1}^{n} - q_{j-1}^{n}}{2\delta x} - \frac{\delta t}{2} c^{2} \frac{p_{j+1}^{n} - 2p_{j}^{n} + p_{j-1}^{n}}{\delta x^{2}} = 0 \\
\frac{q_{j}^{n+1} - q_{j}^{n}}{\delta t} - c \frac{p_{j+1}^{n} - p_{j-1}^{n}}{2\delta x} - \frac{\delta t}{2} c^{2} \frac{q_{j+1}^{n} - 2q_{j}^{n} + q_{j-1}^{n}}{\delta x^{2}} = 0
\end{cases}$$
(6.8)

These schemes are second-order accurate both in time and space. Then u_j^n can be obtained, with the same accuracy, for instance by defining

$$p_j^n = \frac{1}{c} \frac{u_j^{n+1} - u_j^{n-1}}{2\delta t}$$

Hence $u_j^{n+1} = u_j^{n-1} + 2c \, \delta t \, p_j^n$.

The stability of (6.8) can be investigated by a Fourier analysis. Let $p_j^n = P_n e^{ipj\,\delta x}$ and $q_j^n = Q_n e^{ipj\,\delta x}$. Then (6.8) reads

$$\begin{pmatrix} p_j^{n+1} \\ q_j^{n+1} \end{pmatrix} = \begin{pmatrix} 1 - C^2(1 - \cos(p\delta x)) & iC\sin(p\delta x) \\ iC\sin(p\delta x) & 1 - C^2(1 - \cos(p\delta x)) \end{pmatrix} \begin{pmatrix} p_j^n \\ q_j^n \end{pmatrix}$$

which implies that

$$\left(\begin{array}{c} p_j^n \\ q_j^n \end{array} \right) = A^n \, \left(\begin{array}{c} p_j^0 \\ q_j^0 \end{array} \right) \qquad \text{with } A = \left(\begin{array}{cc} 1 - C^2(1 - \cos(p\delta x)) & iC\sin(p\delta x) \\ iC\sin(p\delta x) & 1 - C^2(1 - \cos(p\delta x)) \end{array} \right)$$

Thus the scheme is stable iff the spectral radius of A is less or equal to 1, which leads after a few calculations to the same stability condition as the previous scheme: $|c| \frac{\delta t}{\delta x} \leq 1$.

Chapter 7

The diffusion equation

This chapter focuses on the diffusion equation $\frac{\partial u}{\partial t}(\mathbf{x},t) - \text{div } (k(\mathbf{x},t) \, \nabla u(\mathbf{x},t)) = f(\mathbf{x},t),$ which is a prototype for linear parabolic second-order PDEs.

7.1 Physical interpretation

Let a scalar quantity (heat, mass of some given chemical species. . .). Its conservation in a domain ω reads

$$\frac{d}{dt} \int_{\omega} u(\mathbf{x}, t) \, d\mathbf{x} = \underbrace{\int_{\omega} f(\mathbf{x}, t) \, d\mathbf{x}}_{\text{internal sources/sinks}} + \underbrace{\int_{\partial \omega} \phi(\sigma, t) \, d\sigma}_{\text{output fluxes}}$$

where u is its corresponding volumetric variable (volumetric enthalpy, in $J.m^{-3}$, for heat, volumetric mass, in $Kg.m^{-3}...$).

A common physical assumption (Fourier's law in the context of heat conservation, Fick's law in the context of the conservation of a chemical species) states that $\phi = k \nabla u.\mathbf{n}$ where \mathbf{n} is the outward normal vector to $\partial \omega$. k is called **diffusivity** or **diffusion coefficient**, and has positive values. Using this assumption, performing an integration by parts, and making the size of ω tend to zero leads to

$$\frac{\partial u}{\partial t}(\mathbf{x},t) - \text{div } (k(\mathbf{x},t) \nabla u(\mathbf{x},t)) = f(\mathbf{x},t)$$

In the particular case where k is a constant, this equation reduces to

$$\frac{\partial u}{\partial t}(\mathbf{x}, t) - k \,\Delta u(\mathbf{x}, t) = f(\mathbf{x}, t)$$

7.2 Analytical solutions in n-D

The diffusion equation can be solved analytically, at least for simple domain geometries. This allows for highlighting some properties of the solution, which are actually more general. As already seen in the case of the wave equation, two techniques are widely used for computing analytical solutions of time-dependent linear PDEs. The first one is the separation of variables, in the case

where the domaine is bounded. The second one is the Fourier transform w.r.t. spatial variables, in the case where the domain is \mathbb{R}^n .

7.2.1 Diffusion in a bounded domain $\Omega \subset \mathbb{R}^n$

Let $\Omega \subset \mathbb{R}^n$ a bounded domain, and consider the diffusion equation with constant diffusivity, no right-hand side, and null Dirichlet boundary conditions. The initial conditions will be added later. This problem reads:

$$\begin{cases} \frac{\partial u}{\partial t}(\mathbf{x}, t) - \nu \, \Delta u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ in } \Omega, t > 0 \\ u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ on } \partial \Omega, t > 0 \end{cases}$$
(7.1)

Looking for a solution under the form $u(\mathbf{x},t) = X(\mathbf{x}) T(t)$ leads to

$$\begin{cases} \frac{1}{\nu} \frac{T'(t)}{T(t)} = \frac{\Delta X(\mathbf{x})}{X(\mathbf{x})} = \lambda & \forall \mathbf{x} \text{ in } \Omega, \forall t > 0 \\ X(\mathbf{x}) = 0 & \mathbf{x} \text{ on } \partial \Omega \end{cases}$$

The possible values for λ are thus the eigenvalues of the Laplacian operator on Ω with null Dirichlet boundary conditions. As explained in Appendix B, there is a countable set of such eigenvalues, which are all negative, and denoted $-\omega_k^2$, $k \in \mathbb{N}$. The associated eigenfunctions X_k form an orthonormal basis of $\mathcal{L}^2(\Omega)$.

For a given k, the corresponding function $T_k(t)$ satisfies $T_k'(t) + \nu \, \omega_k^2 \, T(t) = 0$, i.e. $T_k(t) = \alpha_k e^{-\nu \omega_k^2 \, t}$. We have thus built a family of functions $X_k(\mathbf{x}) T_k(t)$ which are elementary solutions of (7.1). This PDE being linear, any linear combination of these elementary solutions is also a solution. Therefore a general solution of (7.1) reads

$$u(\mathbf{x},t) = \sum_{k} \alpha_k X_k(\mathbf{x}) e^{-\nu \omega_k^2 t}$$

Adding an initial condition will then determine the α_k s. See §7.3.1 for the application of this technique in the 1-D case.

7.2.2 Diffusion in \mathbb{R}^n

Let look now for solutions of

$$\begin{cases} \frac{\partial u}{\partial t}(\mathbf{x}, t) - \nu \, \Delta u(\mathbf{x}, t) = 0 & \mathbf{x} \text{ in } \mathbb{R}^n, t > 0 \\ u(\mathbf{x}, 0) = u_0(\mathbf{x}) & \mathbf{x} \text{ in } \mathbb{R}^n \end{cases}$$
(7.2)

with $\mathbf{x} \to u(\mathbf{x},t) \in \mathcal{L}^2(\mathbb{R}^n) \ \forall t$. A Fourier transform (see §A.2) of this problem in all spatial variables directly leads to

$$\left\{ \begin{array}{ll} \displaystyle \frac{\partial \widehat{u}}{\partial t}(\boldsymbol{\xi},t) + 4\pi^2\nu \, \|\boldsymbol{\xi}\|^2 \, \widehat{u}(\boldsymbol{\xi},t) = 0 & \boldsymbol{\xi} \text{ in } \mathbb{R}^n, t > 0 \\ \widehat{u}(\boldsymbol{\xi},0) = \widehat{u}_0(\boldsymbol{\xi}) & \boldsymbol{\xi} \text{ in } \mathbb{R}^n \end{array} \right.$$

which solution is $\widehat{u}(\xi,t)=\widehat{u}_0(\xi)\,e^{-4\pi^2\|\xi\|^2\nu t}$. Hence the solution by inverse Fourier transform:

$$u(\mathbf{x},t) = (u_0(.) * K(.,t)) (\mathbf{x})$$
 with $K = FT^{-1} \left(e^{-4\pi^2 \|\mathbf{\xi}\|^2 \nu t} \right)$

See §7.3.2 for the application of this technique in the 1-D case.

7.3 Analytical solutions in 1-D

7.3.1 1-D diffusion in a bounded interval

We consider here the case where the domain of interest is an interval (0, L). As explained in §7.2.1, the problem

$$\begin{cases} \frac{\partial u}{\partial t}(x,t) - \nu \frac{\partial^2 u}{\partial x^2}(x,t) = 0 & x \in (0,L), t > 0 \\ u(0,t) = u(L,t) = 0 & t > 0 \\ u(x,0) = u_0(x) & x \in (0,L) \end{cases}$$

can be solved by a separation of variables technique, i.e. looking for u(x,t) = X(x)T(t). This leads, after some algebra and a Fourier series expansion (see §A.1) of u_0 , to

$$u(x,t) = \sum_{k>1} \alpha_k e^{-\frac{k^2 \pi^2 \nu t}{L^2}} \sin \frac{k\pi x}{L} \qquad \text{with } \alpha_k = \frac{2}{L} \int_0^L u_0(x) \sin \frac{k\pi x}{L} dx$$

7.3.2 1-D diffusion in \mathbb{R}

The problem is now

$$\begin{cases} \frac{\partial u}{\partial t}(x,t) - \nu \frac{\partial^2 u}{\partial x^2}(x,t) = 0 & x \in \mathbb{R}, t > 0 \\ u(x,0) = u_0(x) & x \in \mathbb{R} \end{cases}$$

If we assume that the Fourier transform of u(x,t) w.r.t. x exists for all t, then this PDE is transformed, as in §7.2.2, into the ODE

$$\begin{cases} \frac{\partial \widehat{u}}{\partial t}(\xi, t) + 4\pi^2 \xi^2 \nu \, \widehat{u}(\xi, t) = 0 & t > 0 \\ \widehat{u}(\xi, 0) = \widehat{u}_0(\xi) \end{cases}$$

which solution is $\widehat{u}(\xi,t)=\widehat{u}_0(\xi)\,e^{-4\pi^2\xi^2\nu\,t}$. An inverse Fourier transform thus yields $u(x,t)=(u_0(.)*K(.,t))(x)$ where $K(x,t)=\frac{1}{2\sqrt{\pi\nu\,t}}\,e^{-x^2/4\nu\,t}$ is the **kernel of the 1-D heat equation**. Hence

$$u(x,t) = \frac{1}{2\sqrt{\pi\nu t}} \int_{\mathbb{R}} u_0(s) e^{-\frac{(x-s)^2}{4\nu t}} ds$$

Note however that this solution is not unique without further conditions on u, like a boundedness assumption for instance. Other solutions may indeed exist, for which a Fourier transform is not allowed (which implies that the preceding calculations do not hold in such cases).

7.3.3 Some properties of the 1-D solution in \mathbb{R}

Let work in this paragraph with this preceding 1-D solution in \mathbb{R} . It actually illustrates some general properties of solutions of diffusion equations, even if their exact formulations may vary, depending of course of the nature and of the regularity of the diffusivity $k(\mathbf{x},t)$, of the initial condition $u_0(\mathbf{x},t)$ and of the physical domain $\Omega \subset \mathbb{R}^n$. Adding a forcing term $f(\mathbf{x},t)$ may also obviously change some of these properties.

Damping of the solution If $u_0 \in L^1(\mathbb{R})$, then $|u(x,t)| \leq \frac{1}{2\sqrt{\pi\nu\,t}}\,\|u_0\|_{L^1}$. Thus it is clear that $u(x,t)\to 0$ as $t\to\infty$.

The extreme values of u(x,t) thus necessarily occur at the initial time, since diffusion progressively damps out the solution.

Positivity If $u_0(x) \ge 0$ (resp. ≤ 0) $\forall x \in \mathbb{R}$, then $u(x,t) \ge 0$ (resp. ≤ 0) $\forall x \in \mathbb{R}, \forall t > 0$.

Regularity If $u_0 \in \mathcal{C}^0(\mathbb{R})$, then $u(.,t) \in \mathcal{C}^\infty(\mathbb{R}) \ \forall t > 0$ (regularizing character of the diffusion equation).

Dependence on initial conditions and propagation speed As can be seen from the analytical expression of u(x,t), any change (even very local) in u_0 results in a change in u(x,t), $\forall x,t$. In other words, the information is immediately transmitted everywhere: its propagation speed is infinite.

Note also that, since an infinite speed does not exist in the real world, this property highlights a limitation in the mathematical diffusion model.

7.3.4 Adding a source term

Let now the problem

$$\begin{cases} \frac{\partial u}{\partial t}(x,t) - \nu \frac{\partial^2 u}{\partial x^2}(x,t) = f(x,t) & x \in \mathbb{R}, t > 0 \\ u(x,0) = u_0(x) & x \in \mathbb{R} \end{cases}$$

Using again the Fourier transform, we have to solve the ODE

$$\begin{cases} \frac{\partial \widehat{u}}{\partial t}(\xi, t) + 4\pi^2 \xi^2 \nu \, \widehat{u}(\xi, t) = \widehat{f}(\xi, t) & t > 0 \\ \widehat{u}(\xi, 0) = \widehat{u}_0(\xi) \end{cases}$$

This is a linear first-order non homogeneous ODE. Its solution is thus the sum of the general solution of the corresponding homogeneous ODE with a particular solution of the full ODE. The solution of the corresponding homogeneous equation is $\widehat{u}_h(\xi,t)=C(\xi)\,e^{-4\pi^2\xi^2\nu\,t}$ (see §7.3.2).

A particular solution of the ODE with its right-hand side can be obtained by the variation of constants method, looking for a solution that reads: $\widehat{u}_p(\xi,t) = C(\xi,t)\,e^{-4\pi^2\xi^2\nu\,t}$. One gets $C(\xi,t) = \int_0^t \widehat{f}(\xi,\tau)\,e^{4\pi^2\xi^2\nu\,\tau}\,d\tau$. Hence $\widehat{u}_p(\xi,t) = \int_0^t \widehat{f}(\xi,\tau)\,e^{-4\pi^2\xi^2\nu\,(t-\tau)}\,d\tau$. Since $\widehat{u}(\xi,t) = \widehat{u}_h(\xi,t) + \widehat{u}_p(\xi,t)$, and given the initial condition, one finally gets $\widehat{u}(\xi,t) = \widehat{u}_0(\xi)\,e^{-4\pi^2\xi^2\nu\,t} + \widehat{u}_p(\xi,t)$. This leads, by inverse Fourier transform, to:

$$u(x,t) = (u_0(.) * K(.,t))(x) + \int_0^t (f(.,\tau) * K(.,t-\tau))(x) d\tau$$
$$= (u_0(.) * K(.,t))(x) + \int_0^t \int_{\mathbb{R}} f(s,\tau) K(x-s,t-\tau) ds d\tau$$

7.3.5 Energy of the solution

Let consider here the more general formulation in $\Omega \subset \mathbb{R}^n$

$$\frac{\partial u}{\partial t}(\mathbf{x},t) - \operatorname{div}\,\left(k(\mathbf{x},t)\,\nabla u(\mathbf{x},t)\right) = f(\mathbf{x},t)$$

where $k(\mathbf{x},t) \geq 0$. Let $E(t) = \frac{1}{2} \int_{\Omega} u^2(\mathbf{x},t) d\mathbf{x}$ the energy of the solution. Assuming that u is regular enough, then

$$\frac{dE(t)}{dt} = \frac{1}{2} \int_{\Omega} \frac{\partial u^2}{\partial t}(\mathbf{x}, t) \, d\mathbf{x} = \frac{1}{2} \int_{\Omega} u(\mathbf{x}, t) \, \mathrm{div} \, \left(k(\mathbf{x}, t) \, \nabla u(\mathbf{x}, t) \right) \, d\mathbf{x} + \frac{1}{2} \int_{\Omega} u(\mathbf{x}, t) \, d\mathbf{x}$$

$$= -\frac{1}{2} \int_{\Omega} k(\mathbf{x},t) \, \|\nabla u(\mathbf{x},t)\|^2 \, d\mathbf{x} + \frac{1}{2} \int_{\partial \Omega} k(\sigma,t) \, u(\sigma,t) \, \frac{\partial u}{\partial \mathbf{n}}(\sigma,t) \, d\sigma + \frac{1}{2} \int_{\Omega} u(\mathbf{x},t) \, f(\mathbf{x},t) \, d\mathbf{x}$$

Therefore it is clear that, if there is no energy source in the domain (f=0) nor at the boundary $(u=0 \text{ or } \partial u/\partial \mathbf{n}=0 \text{ on } \partial\Omega)$, then the energy of the solution continuously decreases as time increases.

7.4 Numerical schemes for the diffusion equation

7.4.1 Usual Euler explicit scheme

The simplest discretization of the 1D diffusion equation reads

$$\frac{u_j^{n+1} - u_j^n}{\delta t} - \nu \frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\delta x^2} = 0$$

It can be rewritten as

$$u_j^{n+1} = \lambda \, u_{j-1}^n + (1-2\lambda) \, u_j^n + \lambda \, u_{j+1}^n \qquad \text{with } \lambda = \nu \, \frac{\delta t}{\delta x^2}$$

▶ **Stability** A Fourier stability analysis shows that this scheme is stable for $\lambda \leq \frac{1}{2}$. Stability can also be assessed by studying the spectral radius of the matrix of the system (see §4.3.3), which reads for example :

$$\begin{bmatrix} 1-2\lambda & \lambda & 0 & \cdots & 0 \\ \lambda & 1-2\lambda & \lambda & & \vdots \\ 0 & \ddots & \ddots & \ddots & 0 \\ \vdots & & \ddots & \ddots & \lambda \\ 0 & \cdots & 0 & \lambda & 1-2\lambda \end{bmatrix}$$

in the case of null boundary conditions.

► Accuracy and equivalent PDE Its equivalent PDE is

$$\frac{\partial u}{\partial t} - \nu \frac{\partial^2 u}{\partial x^2} + \left(\nu^2 \frac{\delta t}{2} - \nu \frac{\delta x^2}{12}\right) \frac{\partial^4 u}{\partial x^4} + \dots = 0$$

This scheme is first-order accurate in time and second-order accurate in space.

Since $\eta = \nu^2 \frac{\delta t}{2} - \nu \frac{\delta x^2}{12} = \frac{\nu \, \delta x^2}{2} \left(\lambda - \frac{1}{6}\right) > 0$ iff $\lambda > 1/6$, then, using the analysis presented in Appendix C.4, the main effect of the numerical error is to amplify the solution if $0 < \lambda < 1/6$ and to damp the solution if $1/6 < \lambda < 1/2$.

- **Positivity** If $\lambda \leq 1/2$, then u_j^{n+1} is a convex weighted average of u_{j-1}^n , u_j^n and u_{j+1}^n . Thus, if $u_0(x) \geq 0 \ \forall x$, then $u_j^n \geq 0 \ \forall j, n$. The positivity property of the exact solution is also satisfied by the numerical solution.
- Maximum principle If $\lambda \leq 1/2$, then $|u_j^{n+1}| \leq \lambda \, |u_{j-1}^n| + (1-2\lambda) \, |u_j^n| + \lambda \, |u_{j+1}^n|$. Thus $|u_j^{n+1}| \leq (\lambda + (1-2\lambda) + \lambda) \|u^n\|_{\infty} = \|u^n\|_{\infty}$. Hence $\|u^{n+1}\|_{\infty} \leq \|u^n\|_{\infty} \leq \ldots \leq \|u^0\|_{\infty}$. The maximum principle satisfied by the exact solution is also satisfied by the numerical solution.
- **Dependence w.r.t. initial conditions** In the exact solution, any local change in $u_0(x)$ instantaneously affects the whole solution. This property can obviously not be satisfied with such an explicit scheme. Here, u_i^n only depends on $u_l^0, l = j n, \ldots, j + n$.

7.4.2 Other schemes

Many other schemes are of course available for this diffusion equation, either in 1D or in 2D. Several of them are detailed in the corresponding exercise sheet.

Appendix A

Reminder on Fourier series and Fourier transforms

A.1 Fourier series expansion

Let f a integrable and periodic function, with period L. One can then define:

$$F(x) = a_0 + \sum_{n>1} \left(a_n \cos \frac{2\pi nx}{L} + b_n \sin \frac{2\pi nx}{L} \right)$$

with
$$a_0 = \frac{1}{L} \int_0^L f(x) dx$$
, $a_n = \frac{2}{L} \int_0^L f(x) \cos \frac{2\pi nx}{L} dx$, $b_n = \frac{2}{L} \int_0^L f(x) \sin \frac{2\pi nx}{L} dx$

F is the so-called **Fourier series expansion** of f.

This expansion also reads

$$F(x) = \sum_{n = -\infty}^{+\infty} c_n e^{\frac{2i\pi nx}{L}} \qquad \text{with } c_n = \frac{1}{L} \int_0^L f(x) e^{-\frac{2i\pi nx}{L}} dx$$

- ▶ If f is an even function, $b_n = 0 \quad \forall n \geq 1 \quad \text{(i.e. } c_n = c_{-n} \quad \forall n\text{)}$
- ▶ If f is an odd function, $a_n = 0 \quad \forall n \geq 0$ (i.e. $c_n = -c_{-n} \quad \forall n$)

Theorem A.1. (Pointwise convergence)

If f is $C^1(0, L)$, then F = f (note that some similar results exist which require less regularity for f)

Theorem A.2. (Parseval's equality, or conservation of energy) If $f \in \mathcal{L}^2(0,L)$, then

$$\frac{1}{L} \int_0^L |f(x)|^2 dx = a_0^2 + \frac{1}{2} \sum_{n=1}^{+\infty} (a_n^2 + b_n^2) = \sum_{n=-\infty}^{+\infty} |c_n|^2$$

A.2 Fourier transform

Let f integrable on \mathbb{R} . The **Fourier transform** of f is

$$FT[f](\xi) = \widehat{f}(\xi) = \int_{\mathbb{R}} f(x) e^{-2i\pi\xi x} dx$$

and the inverse Fourier transform of \widehat{f} is

$$FT^{-1}[\widehat{f}](x) = \int_{\mathbb{R}} \widehat{f}(\xi) e^{2i\pi\xi x} d\xi$$

Some properties of the Fourier transfom

- ▶ If $f \in \mathcal{C}^1(\mathbb{R})$ and if \widehat{f} is $L^1(\mathbb{R})$, then $FT^{-1}[\widehat{f}] = f$ (reciprocity of the Fourier transform)
- $\widehat{f} \ \widehat{g} = \widehat{f * g} \qquad \text{Reminder: convolution product } (a*b)(x) = \int_{\mathbb{R}} a(y) \, b(x-y) \, dy$
- $\widehat{f} * \widehat{g} = \widehat{fg}$
- $\widehat{f}'(\xi) = 2i\pi\xi \, \widehat{f}(\xi)$
- ▶ If $g(x) = f(x x_0)$, then $\widehat{g}(\xi) = e^{-2i\pi x_0 \xi} \widehat{f}(\xi)$
- The Fourier transform of the Gaussian function $\exp(-\pi \alpha x^2)$ is the Gaussian function $\frac{1}{\sqrt{\alpha}} \exp\left(-\frac{\pi}{\alpha}\xi^2\right)$
- ► The Fourier transform of the gate function $\Pi(x) = 1$ for $x \in (-1/2; 1/2)$ and 0 elsewhere is $\operatorname{sinc}(\pi\xi)$ where sinc is the cardinal sine function defined by $\operatorname{sinc} a = (\sin a)/a$.




Figure A.1: Plot of the cardinal sine function $\operatorname{sinc} u = \frac{\sin u}{u}$

Theorem A.3. (Parseval's equality, or conservation of energy) If $f \in \mathcal{L}^2(\mathbb{R})$, then

$$\int_{\mathbb{R}} |f(x)|^2 dx = \int_{\mathbb{R}} \left| \widehat{f}(\xi) \right|^2 d\xi$$

These definitions and properties of the Fourier transform in \mathbb{R} can be directly generalized to \mathbb{R}^n .

Appendix B

The Laplacian operator and its spectrum

B.1 General results

Let $\Omega \subset \mathbb{R}^n$ a bounded domain, and consider the following eigenvalue problem:

$$\begin{cases} \Delta X(\mathbf{x}) = \sum_{i=1}^{n} \frac{\partial^2 X}{\partial x_i^2}(x_1, \dots, x_n) = \lambda \, X(x_1, \dots, x_n) & \mathbf{x} \in \Omega \\ X(\mathbf{x}) = 0 & \text{on } \partial \Omega \end{cases}$$

Theorem B.1. There is a countable set of eigenvalues, all of them being negative: $\lambda_k = -\omega_k^2$. The corresponding eigenfunctions $X_k(\mathbf{x})$ form an orthonormal basis of $\mathcal{L}^2(\Omega)$.

The proof of this theorem can be found for instance in Evans (1998). It is quite long and technical, and is out of the scope of these notes, but note that two aspects at least are obvious:

All eigenvalues are negative:

$$(\Delta X - \lambda X = 0) \Longrightarrow \int_{\Omega} X \Delta X = -\int_{\Omega} \|\nabla X\|^2 = \lambda \int_{\Omega} X^2$$

Hence

$$\lambda = -\frac{\int_{\Omega} \|\nabla X\|^2}{\int_{\Omega} X^2} \le 0$$

Eigenfunctions associated to different eigenvalues are orthogonal: Let X_k and X_l two eigenfunctions associated to two different eigenvalues $-\omega_k^2$ and $-\omega_l^2$.

$$\begin{cases} \Delta X_k + \omega_k^2 X_k = 0 & \Longrightarrow \int_{\Omega} \Delta X_k X_l + \omega_k^2 \int_{\Omega} X_k X_l = -\int_{\Omega} \nabla X_k \nabla X_l + \omega_k^2 \int_{\Omega} X_k X_l = 0 \\ \Delta X_l + \omega_l^2 X_l = 0 & \Longrightarrow \int_{\Omega} \Delta X_l X_k + \omega_l^2 \int_{\Omega} X_l X_k = -\int_{\Omega} \nabla X_l \nabla X_k + \omega_l^2 \int_{\Omega} X_l X_k = 0 \end{cases}$$

Making the difference between those two equations yields $(\omega_k^2-\omega_l^2)\int_\Omega X_l\,X_k=0$, hence

 $\int_{\Omega} X_l \, X_k = 0. \ \text{Note that this also implies} \ \int_{\Omega} \nabla X_l \, \nabla X_k = 0. \ X_k \ \text{and} \ X_l \ \text{are orthogonal both in} \ L^2(\Omega) \ \text{and in} \ H^1(\Omega).$

B.2 The 1-D case

In the 1-D case, let consider $\Omega = (0, L)$. The eigenvalue problem reads

$$\begin{cases} X''(x) = \lambda X(x) & x \in (0, L) \\ X(0) = X(L) = 0 \end{cases}$$

As previously, λ is negative and can be written $\lambda=-\omega^2$. Hence $X''(x)+\omega^2X(x)=0$, which yields $X(x)=\alpha\sin\omega x+\beta\cos\omega x$. X(0)=0 implies $\beta=0$, while X(L)=0 implies $\alpha\sin\omega L=0$. Non zero solutions are then obtained for

$$\omega_k = \frac{k\pi}{L} \quad \text{ and } \quad X_k(x) = \sin\frac{k\pi x}{L} \quad , \, k \in \mathbb{N}$$

Appendix C

Some generic calculations related to finite difference schemes

C.1 Fourier analysis: computation of transfer functions and stability studies

Computing both transfer functions ($\S 2.2.4$) and stability criteria ($\S 4.3.2$) requires some repetitive calculations involving complex exponentials. Some generic formula are given below, in order to facilitate these computations.

Transfer functions With the same notations as in $\S 2.2.4$:

Scheme	Transfer function	
$\frac{u(x-h) + u(x+h)}{2}$	$\cos \omega$	
$\frac{u(x+h) - u(x)}{h}$	$e^{i\omega}-1$	$=e^{i\omega/2}\ 2i\ \sin(\omega/2)$
$\frac{u(x) - u(x - h)}{h}$	$1 - e^{-i\omega}$	$=e^{-i\omega/2} \ 2i \ \sin(\omega/2)$
$\frac{u(x+h) - u(x-h)}{2h}$	$i\sin\omega$	
$\frac{u(x+h) - 2u(x) + u(x-h)}{h^2}$	$2\left(\cos\omega-1\right)$	

Note that these results can be easily adapted to slightly different schemes. For instance, if the scheme $S_h=\frac{\dots}{h^p}$ has a transfer function $T(\omega)$, then the transfer function of $S_{\lambda h}$ is $\frac{1}{\lambda^p}T(\lambda\omega)$. This is useful typically for $\lambda=2$ or $\lambda=1/2$.

APPENDIX C. SOME GENERIC CALCULATIONS RELATED TO FINITE DIFFERENCE SCHEMES

Amplification factors With usual notations, replacing u_j^n by $\xi^n e^{ipj\delta x}$ in a numerical scheme, one will obtain this term $\xi^n e^{ipj\delta x}$ multiplied by an amplification factor.

Scheme	Amplification factor	
$\frac{u_j^{n-1} + u_j^{n+1}}{2}$	$\frac{1/\xi + \xi}{2}$	$=\frac{\xi^2+1}{2\xi}$
$\frac{u_j^{n+1} - u_j^n}{\delta t}$	$\frac{\xi-1}{\delta t}$	
$\frac{u_j^{n+1} - u_j^{n-1}}{2\delta t}$	$\frac{\xi - 1/\xi}{2\delta t}$	$=\frac{\xi^2-1}{2\xi\delta t}$
$\frac{u_j^{n+1} - 2u_j^n + u_j^{n-1}}{\delta t^2}$	$\frac{\xi - 2 + 1/\xi}{\delta t^2}$	$=\frac{(\xi-1)^2}{\xi\;\delta t^2}$
$\frac{u_{j-1}^n + u_{j+1}^n}{2}$	$\cos(p\delta x)$	
$\frac{u_{j+1}^n - u_j^n}{\delta x}$	$\frac{e^{ip\delta x} - 1}{\delta x}$	$=e^{ip\delta x/2}\frac{2i\sin(p\delta x/2)}{\delta x}$
$\frac{u_j^n - u_{j-1}^n}{\delta x}$	$\frac{1 - e^{-ip\delta x}}{\delta x}$	$= e^{-ip\delta x/2}\frac{2i\sin(p\delta x/2)}{\delta x}$
$\frac{u_{j+1}^n - u_{j-1}^n}{2\delta x}$	$\frac{i\sin(p\delta x)}{\delta x}$	
$\frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\delta x^2}$	$2 \frac{\cos(p\delta x) - 1}{\delta x^2}$	

Note that these results can be easily adapted to slightly different schemes, for instance by multiplying the amplification factor by ξ if the scheme is at time n+1 instead of n, or by replacing δx by $2\delta x$ if the scheme involves j-2 and j+2 instead of j-1 and j+1.

Examples Below are two applications of the previous tables.

▶ Let consider the Dufort-Frankel scheme for the 1-D diffusion equation:

$$\frac{u_j^{n+1} - u_j^{n-1}}{2\delta t} - \nu \frac{u_{j+1}^n - 2 \frac{u_j^{n-1} + u_j^{n+1}}{2} + u_{j-1}^n}{\delta x^2} = 0$$

Using the tables, replacing u_i^n by $\xi^n e^{ipj\delta x}$ immediatly leads to:

$$\frac{\xi^2 - 1}{2\xi \,\delta t} - \frac{\nu}{\delta x^2} \left(2\cos(p \,\delta x) - 2 \,\frac{\xi^2 + 1}{2\,\xi} \right) = 0$$

i.e.

$$(2\lambda + 1)\xi^2 - 4\lambda\cos(p\,\delta x)\,\xi + (2\lambda - 1) = 0$$
 with $\lambda = \frac{\nu\,\delta t}{\delta x^2}$

One has then to study the modulus of ξ to prove the stability of the scheme.

▶ Let consider the following scheme for the 1-D transport equation:

$$\frac{u_j^{n+1} - u_j^{n-1}}{2\delta t} + c \left(\frac{4}{3} \frac{u_{j+1}^{n+1} - u_{j-1}^{n+1}}{2\delta x} - \frac{1}{3} \frac{u_{j+2}^n - u_{j-2}^n}{4\delta x} \right) = 0$$

Using the tables, replacing u_i^n by $\xi^n e^{ipj\delta x}$ directly leads to:

$$\frac{\xi^2 - 1}{2\xi \, \delta t} + c \, \xi \left(\frac{4}{3} \, \, \frac{i \, \sin(p \, \delta x)}{\delta x} - \frac{1}{3} \, \, \frac{i \, \sin(2p \, \delta x)}{2\delta x} \right) = 0$$

Hence

$$\xi^{2} = \left[1 + i\frac{2c\,\delta t}{3\,\delta x}\left(4\sin(p\,\delta x) - \frac{1}{2}\sin(2p\,\delta x)\right)\right]^{-1}$$

which implies that $|\xi| \leq 1$.

C.2 Small o and big O

Definition C.1. $f(x) = o(x^p)$ (pronounce *small o*) in the vicinity of 0 iff $f(x) = x^p \varepsilon(x)$ with $\varepsilon(x) \to 0$ as $x \to 0$. In other words, f(x) is negligible w.r.t. x^p in the vicinity of 0.

Definition C.2. $f(x) = \mathcal{O}(x^p)$ (pronounce big o) in the vicinity of 0 iff there exists two positive constants α and β such that $\alpha |x|^p \le |f(x)| \le \beta |x|^p$ in a neighborhood of 0. In other words, f(x) is of the same order as x^p in the vicinity of 0.

C.3 Computation of equivalent PDEs

Computing equivalent PDEs requires linear combinations of Taylor expansions. Some formulas corresponding to frequently used schemes are given below, in order to facilitate these computations.

APPENDIX C. SOME GENERIC CALCULATIONS RELATED TO FINITE DIFFERENCE SCHEMES

$$\begin{split} \frac{u(x,t+\delta t)+u(x,t-\delta t)}{2} &= u(x,t) + \frac{\delta t^2}{2} \frac{\partial^2 u}{\partial t^2}(x,t) + \frac{\delta t^4}{24} \frac{\partial^4 u}{\partial t^4}(x,t) + \mathcal{O}(\delta t^6) \\ \frac{u(x,t+\delta t)-u(x,t)}{\delta t} &= \frac{\partial u}{\partial t}(x,t) + \frac{\delta t}{2} \frac{\partial^2 u}{\partial t^2}(x,t) + \frac{\delta t^2}{6} \frac{\partial^3 u}{\partial t^3}(x,t) + \mathcal{O}(\delta t^3) \\ \frac{u(x,t)-u(x,t-\delta t)}{\delta t} &= \frac{\partial u}{\partial t}(x,t) - \frac{\delta t}{2} \frac{\partial^2 u}{\partial t^2}(x,t) + \frac{\delta t^2}{6} \frac{\partial^3 u}{\partial t^3}(x,t) + \mathcal{O}(\delta t^3) \\ \frac{u(x,t+\delta t)-u(x,t-\delta t)}{2\delta t} &= \frac{\partial u}{\partial t}(x,t) + \frac{\delta t^2}{6} \frac{\partial^3 u}{\partial t^3}(x,t) + \frac{\delta t^4}{120} \frac{\partial^5 u}{\partial t^5}(x,t) + \mathcal{O}(\delta t^6) \\ \frac{u(x,t+\delta t)-2u(x,t)+u(x,t-\delta t)}{\delta t^2} &= \frac{\partial^2 u}{\partial t^2}(x,t) + \frac{\delta t^2}{12} \frac{\partial^4 u}{\partial t^4}(x,t) + \frac{\delta t^4}{360} \frac{\partial^6 u}{\partial t^6}(x,t) + \mathcal{O}(\delta t^6) \\ \frac{u(x+\delta x,t)+u(x-\delta x,t)}{2} &= u(x,t) + \frac{\delta x^2}{2} \frac{\partial^2 u}{\partial x^2}(x,t) + \frac{\delta x^4}{24} \frac{\partial^4 u}{\partial x^4}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x,t)}{\delta x} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x}{2} \frac{\partial^2 u}{\partial x^2}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \mathcal{O}(\delta x^3) \\ \frac{u(x,t)-u(x-\delta x,t)}{\delta x} &= \frac{\partial u}{\partial x}(x,t) - \frac{\delta x}{2} \frac{\partial^2 u}{\partial x^2}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \mathcal{O}(\delta x^3) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{\delta x} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta x^4}{120} \frac{\partial^5 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{2\delta x} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta x^4}{120} \frac{\partial^5 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{2\delta x} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta x^4}{120} \frac{\partial^5 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{2\delta x} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta x^4}{120} \frac{\partial^5 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{\delta x^2} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta x^2}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta x^4}{120} \frac{\partial^5 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{\delta x^2} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta u}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta u}{120} \frac{\partial^3 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u(x+\delta x,t)-u(x-\delta x,t)}{\delta x^2} &= \frac{\partial u}{\partial x}(x,t) + \frac{\delta u}{6} \frac{\partial^3 u}{\partial x^3}(x,t) + \frac{\delta u}{120} \frac{\partial^3 u}{\partial x^5}(x,t) + \mathcal{O}(\delta x^6) \\ \frac{u}{\delta x^5}(x$$

Example Let consider the following explicit scheme for the 1-D diffusion equation:

$$\frac{u_j^{n+1} - u_j^n}{\delta t} - \nu \frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\delta x^2} = 0$$

Using the previous table, its equivalent PDE follows:

$$\frac{\partial u}{\partial t}(x,t) + \frac{\delta t}{2} \frac{\partial^2 u}{\partial t^2}(x,t) + \mathcal{O}(\delta t^2) - \nu \left(\frac{\partial^2 u}{\partial x^2}(x,t) + \frac{\delta x^2}{12} \frac{\partial^4 u}{\partial x^4}(x,t) + \mathcal{O}(\delta x^4)\right) = 0$$
Since $\frac{\partial^2 u}{\partial t^2} = \frac{\partial}{\partial t} \left(\frac{\partial u}{\partial t}\right) = \frac{\partial}{\partial t} \left(\nu \frac{\partial^2 u}{\partial x^2}\right) = \nu \frac{\partial^2}{\partial x^2} \left(\frac{\partial u}{\partial t}\right) = \nu^2 \frac{\partial^4 u}{\partial x^4}$, it becomes:
$$\frac{\partial u}{\partial t}(x,t) - \nu \frac{\partial^2 u}{\partial x^2}(x,t) + \left(\nu^2 \frac{\delta t}{2} - \nu \frac{\delta x^2}{12}\right) \frac{\partial^4 u}{\partial x^4}(x,t) + \mathcal{O}(\delta t^2) + \mathcal{O}(\delta x^4) = 0 \tag{C.1}$$

Once an equivalent PDE has been computed, its dominant error term can be interpreted thanks to the following section.

C.4 Interpretation of the effect of the dominant error term

Let consider the generic 1-D PDE

$$\begin{cases} \frac{\partial u}{\partial t} + c \frac{\partial u}{\partial x} - \nu \frac{\partial^2 u}{\partial x^2} + \mu \frac{\partial^3 u}{\partial x^3} + \eta \frac{\partial^4 u}{\partial x^4} = 0 & x \in \mathbb{R}, t > 0 \\ u_0(x) = e^{ikx} & x \in \mathbb{R} \end{cases}$$
(C.2)

Looking for a plane wave solution $u(x,t)=e^{i(kx+\omega t)}$ leads almost directly to

$$u(x,t) = \exp\left(ik\left[x - (c - k^2\mu)t\right]\right) \exp\left(\left[-\nu - \eta k^2\right]k^2t\right) \tag{C.3}$$

This general expression can then be used to interpret the effect of the dominant error term of equivalent PDEs of finite difference schemes. As indicated in §2.2.4, a scheme will be said

- **dissipative** if it modifies the amplitude of the wave
- dispersive if it modifies the phase (i.e. the velocity) of the wave

Example Coming back to the preceding example, the equivalent PDE is given by (C.1). It thus corresponds to $c=\mu=0$ and $\eta=\nu^2\frac{\delta t}{2}-\nu\,\frac{\delta x^2}{12}$ in (C.2). Looking now to (C.3), it appears that the dominant error term creates the artificial multiplicative factor $\exp(-\eta k^4 t)$ with regard to the exact solution. It will thus result in an artificial damping or amplification of the solution, depending on the sign of η , i.e. depending on whether $\nu \delta t/\delta x^2$ is greater or larger than 1/6.

If we consider similarly the second-order in time equation

$$\begin{cases}
\frac{\partial^2 u}{\partial t^2} - c^2 \frac{\partial^2 u}{\partial x^2} + \eta \frac{\partial^4 u}{\partial x^4} = 0 & x \in \mathbb{R}, t > 0 \\
u_0(x) = e^{ikx} & x \in \mathbb{R}
\end{cases}$$
(C.4)

its plane wave solutions are

$$u(x,t) = A \exp\left(ik\left[x - (c^2 + \eta k^2)^{1/2}t\right]\right) + B \exp\left(ik\left[x + (c^2 + \eta k^2)^{1/2}t\right]\right) \tag{C.5}$$

REFERENCES

References

- [1] Allaire G., 2006: Analyse numérique et optimisation. Editions de l'Ecole Polytechnique.
- [2] Demailly J.-P., 1996: Analyse numérique et équations différentielles. Presses Universitaires de Grenoble.
- [3] Euvrard D., 1994: Résolution numérique des équations aux dérivées partielles. Masson.
- [4] Evans L., 1998: Partial Differential Equations. Graduate Studies in Mathematics, Vol 19, American Math. Society.
- [5] Lascaux P. et R. Théodor, 1986: Analyse numérique matricielle appliquée à l'art de l'ingénieur. Masson.
- [6] Leveque R. J., 2007: Finite difference methods for ordinary and partial differential equations. SIAM.
- [7] Mohammadi B. and J.H. Saiac, 2003: Pratique de l'analyse numérique. Dunod,
- [8] Sainsaulieu L., 1996: Calcul scientifique. Masson.
- [9] Trefethen L.N., 1996: Finite difference and spectral methods for ordinary and partial differential equations. Unpublished text, available on line.