Screen View Protocol

Josh Brown

November 24, 2021

Contents

1	Abs	stract		3
2	Def	inition	ıs	4
3	Rer	note V	Visual Display (RVD) Protocol	4
	3.1		shake - TCP	4
		3.1.1	ProtocolVersion	4
		3.1.2	Initialization	5
	3.2	Contr	rol messages - TCP	5
		3.2.1	DisplayChange	5
		3.2.2	DisplayChangeReceived - TCP	6
		3.2.3	MouseLocation - TCP/UDP	6
	3.3	-	- TCP/UDP	6
	0.0	3.3.1	MouseInput	7
		3.3.2	KeyInput	7
	3.4		oard - TCP	7
	0.1	3.4.1	ClipboardTypeRequest	7
		3.4.2	ClipboardTypeResponse	7
		3.4.3	CopyRequest	8
		3.4.4	CopyResponse	8
		3.4.4	A note on Pasting	8
	3.5			
	ა.ა	гташе	e Data - UDP	- 8

1 Abstract

Screen View is an end to end encrypted remote screen viewing and controlling software. This document describes the protocols necessary to make it function.

2 Definitions

The following definitions are used:

- Host The user that wants to share their screen to the Client
- Client The user that wants to view and control the Host's screen
- Server The intermediary server used for routing and proxying data between
- Display A rectangular visual region which may or may not be controllable.
- Controllable A *Display* that accepts keyboard and mouse input.

3 Remote Visual Display (RVD) Protocol

The RVD protocol is used to communicate mouse input, keyboard input, frame data, and clipboard data from the Host to the Client.

All messages can occur over either TCP or UDP but it is strongly recommended that the noted transport protocol is used.

With the exception of the *Handshake* messages. All RVD messages first byte contain a number to indicate the message type.

3.1 Handshake - TCP

3.1.1 ProtocolVersion

Handshaking begins by the Host sending the client a *ProtocolVersion* message. This lets the Client know the verison supported by the Host.

The *ProtocolVersion* message consists of 12 bytes interpreted as a string of ASCII characters in the format "RVD xxx.yyy" where xxx and yyy are the major and minor version numbers, padded with zeros.

The client replies back either 0 to indicate the version is not acceptable and that the handshake has failed or 1 if the version is acceptable to the client and the handshake as succeeded. If 0 is sent, all communication should cease and and error should be displayed to user.

$$\begin{array}{c} \text{Client} \rightarrow \text{Host} \\ \hline \text{ok (1 byte)} - \text{00000000 or 00000001} \end{array}$$

3.1.2 Initialization

Once the handshake has succeeded the Host responds with a DisplayChange message.

3.2 Control messages - TCP

Control messages are messages that instruct client about changes regarding the Host.

3.2.1 DisplayChange

A *DisplayChange* message informs the client about the available *Displays*. RVD supports up to 255 displays.

$Host \rightarrow Client$
type (1 byte) - 1
clipboard-readable (1 byte) - 0 or 1
number-of-displays (1 byte) - 1-255
displays-information (variable bytes)
DisplayInformation number-of-displays times

Each Display has an associated DisplayInformation. displays-information contains number-of-displays DisplayInformation's. A DisplayInformation is defined below:

display-id (1 byte)
width (2 bytes) - number of pixels of the width of this display
height (2 bytes) - number of pixels of the width of this display
cell-width (2 bytes) - number of pixels of the width of a cell in the grid
cell-height (2 bytes) - number of pixels of the height of a cell in the grid
access (1 byte) - defined below
name-length (1 byte) - length of the name
name (name-length bytes) - display name (UTF-8)

Restrictions:

- cell-width must be less than width. cell-height must be less than height.
- The *access* byte defines what type of access is available for the display. The bits of the *access* byte are described below in Big Endian.

Bit	Description
0	Flush
1	Controllable
2	
3	
4	Reserved for future
5	use
6	
7	

If the *Controllable* bit is 1 and the *clipboard-readable* byte is set to 1, then the clipboard is writable. The *Controllable* bit should be consistent throughout all displays.

The Flush bit indicates whether this display has changed, specifically if this display-id refers to a different Display than the same display-id did in the previous DisplayChange message. In initialization, this should always be 1 (as there is no previous DisplayChange). If the display hasn't changed (0) then the frame data may be maintained. If Flush is 0, width, height must remain the same as the previous DisplayChange specified for the display-id.

3.2.2 DisplayChangeReceived - TCP

The DisplayChangeReceived message is sent in reply after receiving a DisplayChange message. It indicates to the Host they may start sending FrameData referencing the new DisplayInformation in the most recent DisplayChange.

$$\begin{array}{c} \text{Client} \to \text{Host} \\ \hline \text{type (1 byte) - 2} \end{array}$$

3.2.3 MouseLocation - TCP/UDP

The MouseLocation message send information about where the mouse is currently on the screen. The Host sends this information periodically throughout the session. The Host should send a MouseLocation update when mouse input is received from the Host's system or in reply when it receives a MouseInput.

$-$ Host \rightarrow Client
type (1 byte) - 3
display-id (1 byte) - 0-255
x-location (2 bytes) - x coordinate of the mouse
y-location (2 bytes) - y coordinate of the mouse

3.3 Input - TCP/UDP

Input messages (including *MouseLocation*) can be sent over TCP or UDP. TCP is preferred in most situations. However, in situations where speed is prioritized over the guarantees TCP provides (such as gaming), UDP can be used.

3.3.1 MouseInput

Client \rightarrow Host
type (1 byte) - 4
display-id (1 byte) - 0-255
x-position (2 bytes) - x coordinate of the mouse
y-position (2 bytes) - y coordinate of the mouse
button-mask (1 byte) - described below

Indicates either pointer movement or a pointer button press or release. The pointer is now at (x-position, y-position), and the current state of buttons 1 to 8 are represented by bits 0 to 7 of button-mask respectively, 0 meaning up, 1 meaning down (pressed).

On a conventional mouse, buttons 1, 2 and 3 correspond to the left, middle and right buttons on the mouse. On a wheel mouse, each step of the wheel is represented by a press and release of a certain button. Button 4 means up, button 5 means down, button 6 means left and button 7 means right.

3.3.2 KeyInput

The KeyInput event sends key presses or releases.

$\text{Client} \to \text{Host}$
type (1 byte) - 5
down-flag (1 byte) - 0 or 1 to indicate whether the key is now pressed or released
key (4 bytes) - "keysym"

Details can be found at the RFB Spec

3.4 Clipboard - TCP

3.4.1 Clipboard Type Request

Used to request clipboard types the Host supports.

Client
$$\rightarrow$$
Host
type (1 byte) - 6

${\bf 3.4.2}\quad {\bf Clipboard Type Response}$

Response to the ClipboardTypeRequest

number-of-clipboard-types is always 0 if clipboard-readable is 0.

data contains number-of-clipboard-types Clipboard Types. Clipboard Type is defined below.

3.4.3 CopyRequest

This is a request for a keyboard contents. It can be made by either the Client or the Host.

$$\begin{array}{c} \text{Client} \leftrightarrow Host \\ \text{type (1 byte) - 8} \\ \\ \text{type-length (1 byte) - 0-255} \\ \\ \text{type-name}(type\text{-}length \text{ bytes}) - type \text{ name in ASCII} \\ \end{array}$$

3.4.4 CopyResponse

CopyResponse message is a response to a CopyRequest.

Client $\leftrightarrow Host$
type (1 byte) - 9
accepted (1 byte) - 0 or 1
type-length (1 byte) - 0-255
type-name(type-length bytes) - type name in ASCII
content-length (4 bytes) - the length of the content (maximum 2 ²⁴ bytes or 16MB)
data (content-length bytes)

accepted indicates whether the CopyRequest was accepted. If 0, the rest of the message is empty. If clipboard-readable is 0, accepted is always 0. A Client or Host many send this message without a request. If a CopyResponse is unsolicited, then accepted must be 1.

data is zlib compressed.

3.4.5 A note on Pasting

There is a no paste message. To paste data an unsolicited CopyResponse may be sent and then the keyboard shortcut (ctrl+v or cmd+v) should be sent via the KeyboardMessage

3.5 FrameData - UDP

The FrameData message contains an update of a particular cell on a particular Display.

type (1 byte) - 10
sequence-number (4 bytes)
cell-number (2 bytes)
size (2 bytes)
data (size bytes)

 $sequence-number \ {\rm is\ an\ incrementing\ 32-bit\ counter\ for\ each\ } FrameData\ {\rm sent}$ $data\ {\rm contains\ jpeg\ pixel\ data\ of\ the\ updated\ cell}.$