Package 'CNORode'

August 30, 2017

Date 2014-01-10
Author David Henriques, Thomas Cokelaer
Maintainer David Henriques <davidpcnet@hotmail.com></davidpcnet@hotmail.com>
biocViews CellBasedAssays, CellBiology, Proteomics, Bioinformatics, TimeCourse
Description ODE add-on to CellNOptR
License GPL-2
LazyLoad yes
Depends CellNOptR (>= 1.5.14), genalg
Enhances MEIGOR
NeedsCompilation yes
R topics documented:
cnolistCNORodeExample
CNORode
createLBodeContPars
defaultParametersGA
defaultParametersSSm
getLBodeContObjFunction
getLBodeDataSim

Type Package

Version 1.18.0

Title ODE add-on to CellNOptR

 getLBodeMINLPObjFunction
 9

 getLBodeModelSim
 10

 getLBodeSimFunction
 12

 getStates
 13

 incidence2Adjacency
 13

 indices
 14

 minlpLBodeSSm
 14

 model
 16

 parEstimationLBode
 16

 parEstimationLBodeGA
 18

 parEstimationLBodeSSm
 20

 plotLBodeFitness
 22

5

2 CNORode

	plotLBodeModelSin simdata2cnolist simulate																 			25
Index																				28
cnol	istCNORodeExample	A cr	noli	st f	ron	n C	Cell	'No	pt	R							 			

Description

A cnolist from CellNoptR to use with provided CNORode examples.

CNORode

Logic based ODE extension for CellNOptR

Description

This package is used for the simulation and fitting of logic based ODE models based on the Odefy approach.

Details

Package: CNORode
Type: Package
Version: 1.2.0
Date: 2012-03-14
License: GPL-3
LazyLoad: yes

Author(s)

David Henriques, Thomas Cokelaer Maintainer: David Henriques dhenriques@ebi.ac.uk

References

Dominik Wittmann, Jan Krumsiek, Julio S. Rodriguez, Douglas Lauffenburger, Steffen Klamt, and Fabian Theis. Transforming boolean models to continuous models: methodology and application to t-cell receptor signaling. BMC Systems Biology, 3(1):98+, September 2009.

Egea, J.A., Maria, R., Banga, J.R. (2010) An evolutionary method for complex-process optimization. Computers & Operations Research 37(2): 315-324.

Egea, J.A., Balsa-Canto, E., Garcia, M.S.G., Banga, J.R. (2009) Dynamic optimization of nonlinear processes with an enhanced scatter search method. Industrial & Engineering Chemistry Research 49(9): 4388-4401.

Jan Krumsiek, Sebastian Polsterl, Dominik Wittmann, and Fabian Theis. Odefy - from discrete to continuous models. BMC Bioinformatics, 11(1):233+, 2010.

createLBodeContPars 3

R. Serban and A. C. Hindmarsh, "CVODES: the Sensitivity-Enabled ODE Solver in SUNDIALS," Proceedings of IDETC/CIE 2005, Sept. 2005, Long Beach, CA. Also available as LLNL technical report UCRL-JP-200039.

C. Terfve, T. Cokelaer, A. MacNamara, D. Henriques, E. Goncalves, MK. Morris, M. van Iersel, DA Lauffenburger, J. Saez-Rodriguez. CellNOptR: a flexible toolkit to train protein signaling networks to data using multiple logic formalisms. BMC Systems Biology, 2012, 6:133:

See Also

CellNOptR, parEstimationLBode, getLBodeModelSim, parEstimationLBode plotLBodeFitness.

createLBodeContPars	Create a list with ODE parameter information needed to perform pa-
	rameter estimation

Description

Creates a list with the continuous parameters to simulate the model, upper and lower bounds for the parameter estimation, parameters names, indices of the parameters and other information.

Usage

```
createLBodeContPars(model, LB_n = 1, LB_k = 0.1, LB_tau = 0.01, UB_n = 5, UB_k = 0.9, UB_tau = 10, default_n = 3, default_k = 0.5, default_tau = 1, LB_in = c(), UB_in = c(), opt_n = TRUE, opt_k = TRUE, opt_tau = TRUE, random = FALSE)
```

Arguments

model	The logic model to be simulated.
LB_n	A numeric value to be used as lower bound for all parameters of type n.
LB_k	A numeric value to be used as lower bound for all parameters of type k.
LB_tau	A numeric value to be used as lower bound for all parameters of type tau.
UB_n	A numeric value to be used as upper bound for all parameters of type n.
UB_k	A numeric value to be used as upper bound for all parameters of type k.
UB_tau	A numeric value to be used as upper bound for all parameters of type tau.
default_n	The default parameter to be used for every parameter of type n.
default_k	The default parameter to be used for every parameter of type k.
default_tau	The default parameter to be used for every parameter of type tau.
LB_in	An array with the same length as ode_parameters\$parValues with lower bounds for each specific parameter.
UB_in	An array with the same length as ode_parameters\$parValues with upper bounds for each specific parameter.
opt_n	Add all parameter n to the index of parameters to be fitted.
opt_k	Add all parameter k to the index of parameters to be fitted.
opt_tau	Add all parameter tau to the index of parameters to be fitted.
random	logical value that determines that a random solution is for the parameters to be optimized.

4 defaultParametersGA

Value

parNames An array containing the names of the parameters.

parValues An array containing the values of the parameters, in the same order as the names.

index_opt_pars An array containing the indexes for the parameters to be fitted.

index_n An array containing the indexes of the parameters of type n.

index_k An array containing the indexes of the parameters of type k.

index_tau An array containing the indexes of the parameters of type tau.

LB An array containing the lower bound for each parameter.

An array containing the upper bound for each parameter.

Author(s)

UB

David Henriques, Thomas Cokelaer

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");
ode_parameters=createLBodeContPars(model, opt_n=FALSE,default_n=2,random=TRUE,LB_k=0.25,UB_k=0.8,LB_tau=0.01,UB_tau=10);
```

defaultParametersGA

Create default options to perform parameter estimation with a genetic algorithm.

Description

This function returns a list with several arguments for performing parameter estimation with the genetic algorithm from the package genalg.

Usage

```
defaultParametersGA()
```

Value

defaultParametersSSm 5

```
\begin{tabular}{lll} reltol & 1e-04 \\ atol & 0.001 \\ maxStepSize & Inf \\ maxNumSteps & 1e+05 \\ maxErrTestsFails & 50 \\ nan\_fac = 1 & 0 \\ \end{tabular}
```

Author(s)

David Henriques, Thomas Cokelaer

See Also

 ${\tt CellNOptR}\ parEstimation LBode\ parEstimation LBodeGA$

defaultParametersSSm Create default options to perform parameter estimation with scatter search meta-heuristic.

Description

This function returns a list with several arguments for performing parameter estimation with scatter search meta-heuristic algorithm from the package essR.

Usage

```
defaultParametersSSm()
```

Value

```
maxeval
                 Inf
{\tt maxtime}
                 100
                 NULL
ndiverse
dim_refset
                 NULL
local_solver
                 NULL
                 0
verbose
transfer_function
                 1e-04
reltol
                 0.001
atol
{\tt maxStepSize}
                 Inf
maxNumSteps
                 1e+05
maxErrTestsFails
                 50
nan_fac
                 1
```

Author(s)

David Henriques, Thomas Cokelaer

See Also

 ${\tt CellNOptR}\ par{\tt EstimationLBode}\ par{\tt EstimationLBodeSSm}$

getLBodeContObjFunction

Returns the objective function to perform parameter estimation.

Description

This function configures returns the objective function that can be used to evaluate the fitness of a logic based ODE model using a particular set of parameters. This function can be particularly useful if you are planing to couple a nonlinear optimization solver. The returned value of the objective function corresponds to the mean squared value normalized by the number of data points.

Usage

```
getLBodeContObjFunction(cnolist, model, ode_parameters, indices=NULL, time = 1,
verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001, maxStepSize = Inf,
maxNumSteps = 1e+05, maxErrTestsFails = 50, nan_fac = 1, useVariances = F,initial_state=0.1)
```

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

 $ode_parameters \quad A\ list\ with\ the\ ODEs\ parameter\ information.\ Obtained\ with\ {\tt createLBodeContPars}.$

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

time An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

nan_fac A penalty for each data point the model is not able to simulate. We recommend

higher than 0 and smaller that 1.

useVariances if True, use the variance in the fitness

initial_state initial state of the dynamic nodes (non-measured) (Defaults to 0.1)

getLBodeDataSim 7

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

Returns a function to evaluate the model fitness. This function receives a vector containing both continuous parameters and integer values representing which reactions should be kept in the model.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);
minlp_obj_function=getLBodeContObjFunction(cnolistCNORodeExample, model,ode_parameters,indices);

x=ode_parameters$parValues;

f=minlp_obj_function(x);
```

 ${\tt getLBodeDataSim}$

Simulate value signals a CNO list With Logic-Based ODEs.

Description

This function receives a set of inputs, namely the cnolist and the model and returns a list with the same size of the cnolist\$valueSignals.

Usage

```
getLBodeDataSim(cnolist, model, ode_parameters = NULL, indices = NULL,
timeSignals=NULL, time = 1, verbose = 0, transfer_function = 3,
reltol = 1e-04, atol = 0.001, maxStepSize = Inf, maxNumSteps = 1e+05,
maxErrTestsFails = 50, initial_state=0.1)
```

8 getLBodeDataSim

Arguments

cnolist A list containing the experimental design and data.

model A list with the ODEs parameter information. Obtained with createLBodeContPars.

ode_parameters A list with the ODEs parameter information. Obtained with makeParameterList

function.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

timeSignals An array containing a different timeSignals. If you use this argument, it will

also modify the dimensions from valueSignals.

time An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

initial_state initial state of the dynamic nodes (non-measured) (Defaults to 0.1)

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

Returns a list with simulated data that has the same structure as the cnolist\$valueSignals. One matrix for each time-point.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR parEstimationLBode parEstimationLBodeSSm

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");
dataSimulation=getLBodeDataSim(cnolistCNORodeExample, model,indices=indices);
```

getLBodeMINLPObjFunction

Get the objective function to evaluate the fitness of a given model structure and set of parameters.

Description

This function configures returns the objective function that can be used to evaluate the fitness of a logic based ODE model using a particular set of parameters and model structure. This function can be particular useful if you are planing to couple a mixed integer nonlinear programming optimization solver. The returned value of the objective function corresponds to the mean squared value.

Usage

```
getLBodeMINLPObjFunction(cnolist, model, ode_parameters, indices=NULL, time = 1,
verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001, maxStepSize = Inf,
maxNumSteps = 1e+05, maxErrTestsFails = 50, nan_fac = 1)
```

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

ode_parameters A list with the ODEs parameter information. Obtained with createLBodeContPars.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

time An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

nan_fac A penalty for each data point the model is not able to simulate. We recommend

higher than 0 and smaller that 1.

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

10 getLBodeModelSim

Value

Returns a function to evaluate the model fitness. This function receives a continuous parameter vector.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);
minlp_obj_function=getLBodeMINLPObjFunction(cnolistCNORodeExample, model,ode_parameters,indices);

n_int_vars=dim(model$interMat)[2];
x_int=round(runif(n_int_vars))
x_cont=ode_parameters$parValues;
x=c(x_cont,x_int);
f=minlp_obj_function(x);
```

getLBodeModelSim

Simulate the logic-based ODE model

Description

This function simulates a logic-based ODE model and return a list with one matrix for each time point. The input species in the model are filled with NA values. If the simulation of a particular set of initial conditions fails the solver will fill the experience row with NA values.

Usage

```
getLBodeModelSim(cnolist, model, ode_parameters = NULL, indices = NULL, timeSignals=NULL,
time = 1,verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001, maxStepSize = Inf,
maxNumSteps = 1e+05, maxErrTestsFails = 50)
```

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

ode_parameters A list with the ODEs parameter information. Obtained with createLBodeContPars.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

getLBodeModelSim 11

timeSignals An array containing a different timeSignals. If you use this argument, it will

also modify the dimensions from valueSignals.

An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

Returns a list with simulated data with similar structure to cnolist\$valueSignals. Contains one matrix for each time-point. Each matrix contains one row per experiment and one columns per model species.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

Examples

```
library(CNORode)
data('ToyCNOlist',package='CNORode');
data('ToyModel',package='CNORode');
data('ToyIndices',package='CNORode');
modelSimulation=getLBodeModelSim(cnolistCNORodeExample, model,indices=indices);
```

12 getLBodeSimFunction

getLBodeSimFunction Get a function to simulate a logic based ODE model.

Description

This function is internally used by CNORode to configure the simulation function with default arguments.

Usage

```
getLBodeSimFunction(cnolist1, model1, adjMatrix1, indices1, odeParameters1,
time1 = 1, verbose1 = 0, transfer_function1 = 3, reltol1 = 1e-04, atol1 = 0.001,
maxStepSize1 = Inf, maxNumSteps1 = 1e+05, maxErrTestsFails1 = 50,
initial_state1=0.1)
```

Arguments

cnolist1 A list containing the experimental design and data.

model1 The logic model to be simulated.

adjMatrix1 An adjacency matrix from the model.

indices 1 Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

 $ode Parameters 1 \quad A \ list \ with \ the \ ODEs \ parameter \ information. \ Obtained \ with \ create LBode ContPars.$

time1 An integer with the index of the time point to start the simulation. Default is 1.

verbose1 A logical value that triggers a set of comments.

transfer_function1

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol1 Relative Tolerance for numerical integration.

atol1 Absolute tolerance for numerical integration.

maxStepSize1 The maximum step size allowed to ODE solver.

maxNumSteps1 The maximum number of internal steps between two points being sampled be-

fore the solver fails.

 ${\tt maxErrTestsFails1}$

Specifies the maximum number of error test failures permitted in attempting one

step.

initial_state1 initial state of the dynamic nodes (non-measured) (Defaults to 0.1)

Value

A function that returns a simulated model.

Note

This function is for CNORode internal use.

Author(s)

David Henriques, Thomas Cokelaer

getStates 13

See Also

CellNOptR CNORode

getStates

Find which species in the model are states.

Description

Receives an adjacency matrix (model\$interMat from CellNoptR) and finds which species are states (i.e. not inputs).

Usage

```
getStates(adjacency)
```

Arguments

adjacency

An adjacency matrix from the model.

Value

A numeric vector with 0's for positions which are states and 1's for positions which are.

Note

For internal use of CNORode.

Author(s)

David Henriques, Thomas Cokelaer

See Also

incidence2Adjacency

incidence2Adjacency

Convert an incidence matrix into an adjacency matrix.

Description

Convert the incidence matrix (model representation of CellNoptR) into an adjacency matrix. Denotes the inputs/output relationships.

Usage

incidence2Adjacency(model)

Arguments

model

Model from CellNoptR.

14 minlpLBodeSSm

Value

Directed Adjacency matrix of size n_species by n_species.

Note

For internal use of CNORode.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR

÷	no	1:	ces	
	H.C.	ıт	Ces	

Indices that relate cnolist to model

Description

A list with indices that relate the cnolist with the model from CellNOptR

minlpLBodeSSm	Search for the best combination of continuous parameters and logic
	gates.

Description

This function uses essR to search for the best set of continuous parameters and model structure. The objective function is the same as the one provided by getLBodeMINLPObjFunction.

Usage

```
minlpLBodeSSm(cnolist, model, ode_parameters = NULL, int_x0=NULL, indices = NULL, maxeval = Inf,
maxtime = 100, ndiverse = NULL, dim_refset = NULL, local_solver = NULL, time = 1,
verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001, maxStepSize = Inf,
maxNumSteps = 1e+05, maxErrTestsFails = 50, nan_fac = 1)
```

Arguments

cnolist	A list containing the experimental design and data.
model	The logic model to be simulated.
ode_parameters	$A\ list\ with\ the\ ODEs\ parameter\ information.\ Obtained\ with\ \verb createlBodeContPars .$
int_x0	Vector with initial solution for integer parameters.
indices	Indices to map data in the model. Obtained with indexFinder function from CellNOptR.
maxeval	Maximum number of evaluation in the optimization procedure.
maxtime	Maximum number of evaluation spent in optimization procedure.

minlpLBodeSSm 15

ndiverse Duration of the optinisation procedure. dim_refset Number of diverse initial solutions. local_solver Local solver to be used in SSm.

An integer with the index of the time point to start the simulation. Default is 1. time

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

for normalized Hill function.

Relative Tolerance for numerical integration. reltol atol Absolute tolerance for numerical integration. The maximum step size allowed to ODE solver. maxStepSize

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

nan_fac A penalty for each data point the model is not able to simulate. We recommend

higher than 0 and smaller that 1.

Details

Check CellNoptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

LB_n	A numeric value to be used as lower bound for all parameters of type n.
LB_k	A numeric value to be used as lower bound for all parameters of type k.
LB_tau	A numeric value to be used as lower bound for all parameters of type tau.
UB_n	A numeric value to be used as upper bound for all parameters of type n.
UB_k	A numeric value to be used as upper bound for all parameters of type k.
UB_tau	A numeric value to be used as upper bound for all parameters of type tau.
default_n	The default parameter to be used for every parameter of type n.
default_k	The default parameter to be used for every parameter of type k.
default_tau	The default parameter to be used for every parameter of type tau.
LB_in	An array with the same length as ode_parameters\$parValues with lower bounds for each specific parameter.
UB_in	An array with the same length as ode_parameters\$parValues with upper bounds for each specific parameter.
opt_n	Add all parameter n to the index of parameters to be fitted.
opt_k	Add all parameter k to the index of parameters to be fitted.
opt_tau	Add all parameter tau to the index of parameters to be fitted.
random	A logical value that determines that a random solution is for the parameters to be optimised.
model	The best fitting found model structure.
smm_results	A list containing the information provided by the nonlinear optimization solver.

16 parEstimationLBode

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars essR

Examples

```
## Not run:
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);

#Visualize initial solution
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,ode_parameters,indices=indices)
ode_parameters=minlpLBodeSSm(cnolistCNORodeExample, model,ode_parameters);

model=ode_parameters$model;

#Visualize fitted solution
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,indices=indices);

## End(Not run)
```

model

 $A\ model\ from\ Cell Nopt R$

Description

A model from CellNoptR to use with provided examples

parEstimationLBode

Perform parameter estimation using a genetic algorithm (package genalg) or ssm (if package essm available).

Description

This function is an alias to the parEstimation LBode variants (parEstimation LBodeGA and parEstimation LBodeSSm)

Usage

```
parEstimationLBode(cnolist, model, method="ga", ode_parameters = NULL, indices = NULL,
paramsGA=NULL, paramsSSm=NULL)
```

parEstimationLBode 17

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

method Only "ga" or "essm" arguments are accepted.

ode_parameters A list with the ODEs parameter information. Obtained with createLBodeContPars.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

paramsGA A list of GA parameters. default is the list returned by defaultParametersGA.

A list of SSm parameters. default is the list returned by defaultParametersSSm.

Value

LB_n	A numeric value to be used as lower bound for all parameters of type n.
LB_k	A numeric value to be used as lower bound for all parameters of type k.
LB_tau	A numeric value to be used as lower bound for all parameters of type tau.
UB_n	A numeric value to be used as upper bound for all parameters of type n.
UB_k	A numeric value to be used as upper bound for all parameters of type k.
UB_tau	A numeric value to be used as upper bound for all parameters of type tau.
default_n	The default parameter to be used for every parameter of type n.
default_k	The default parameter to be used for every parameter of type k.
default_tau	The default parameter to be used for every parameter of type tau.
LB_in	An array with the same length as ode_parameters\$parValues with lower bounds for each specific parameter.
UB_in	An array with the same length as ode_parameters\$parValues with upper bounds for each specific parameter.
opt_n	Add all parameter n to the index of parameters to be fitted.
opt_k	Add all parameter k to the index of parameters to be fitted.
opt_tau	Add all parameter tau to the index of parameters to be fitted.
random	A logical value that determines that a random solution is for the parameters to be optimized.
res	A list containing the information provided by the solver.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars rbga

Examples

```
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);
#Visualize initial solution
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,ode_parameters,indices=indices)
paramsGA = defaultParametersGA()
paramsGA$maxStepSize = 1
paramsGA$popSize = 10
paramsGA$titer = 10
paramsGA$transfer_function = 2

ode_parameters=parEstimationLBode(cnolistCNORodeExample,model,ode_parameters=ode_parameters,
paramsGA=paramsGA)
#Visualize fitted solution
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,ode_parameters,indices=indices)
```

parEstimationLBodeGA Perform parameter estimation using a genetic algorithm (package genalg).

Description

This function uses a genetic algorithm (package genalg) to perform parameter estimation. The objective function is the same as the one provided by getLBodeContObjFunction.

Usage

```
parEstimationLBodeGA(cnolist, model, ode_parameters = NULL, indices = NULL, mutationChance = NA, pelitism = NA, time = 1, monitor = TRUE, verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001, maxStepSize = Inf, maxNumSteps = 1e+05, maxErrTestsFails = 50, nan_fac = 1, initial_state=0.1)
```

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

 $ode_parameters \quad A\ list\ with\ the\ ODEs\ parameter\ information.\ Obtained\ with\ createLBodeContPars.$

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

mutationChance the chance that a gene in the chromosome mutates. By default 1/(size+1). It af-

fects the convergence rate and the probing of search space: a low chance results in quicker convergence, while a high chance increases the span of the search

space.

popSize the population size.

iters the number of iterations.

elitism the number of chromosomes that are kept into the next generation. By default is

about 20% of the population size

An integer with the index of the time point to start the simulation. Default is 1. time

If TRUE a plot will be generated to monitor the objective function monitor

A logical value that triggers a set of comments. verbose

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration. Absolute tolerance for numerical integration. atol

maxStepSize The maximum step size allowed to ODE solver.

The maximum number of internal steps between two points being sampled bemaxNumSteps

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

nan_fac A penalty for each data point the model is not able to simulate. We recommend

higher than 0 and smaller that 1.

initial state of the dynamic nodes (non-measured) (Defaults to 0.1) initial_state

Value

LB_n	A numeric value to be used as lower bound for all parameters of type n.
LB_k	A numeric value to be used as lower bound for all parameters of type k.
LB_tau	A numeric value to be used as lower bound for all parameters of type tau.
UB_n	A numeric value to be used as upper bound for all parameters of type n.
UB_k	A numeric value to be used as upper bound for all parameters of type k.
UB_tau	A numeric value to be used as upper bound for all parameters of type tau.
default_n	The default parameter to be used for every parameter of type n.
default_k	The default parameter to be used for every parameter of type k.
default_tau	The default parameter to be used for every parameter of type tau.
LB_in	An array with the same length as ode_parameters\$parValues with lower bounds for each specific parameter.
UB_in	An array with the same length as ode_parameters\$parValues with upper bounds for each specific parameter.
opt_n	Add all parameter n to the index of parameters to be fitted.
opt_k	Add all parameter k to the index of parameters to be fitted.
opt_tau	Add all parameter tau to the index of parameters to be fitted.
random	A logical value that determines that a random solution is for the parameters to be optimized.
res	A list containing the information provided by the nonlinear optimization solver

Author(s)

David Henriques, Thomas Cokelaer

(genalg).

See Also

CellNOptR createLBodeContPars rbga

Examples

```
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);
#Visualize intial simulation
#simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,ode_parameters,indices=indices)

ode_parameters=parEstimationLBodeGA(cnolistCNORodeExample,model,ode_parameters=ode_parameters,
indices=indices,maxStepSize=1,atol=1e-3,reltol=1e-5,transfer_function=2,popSize=10,iter=40);
#Visual solution after optimization
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,indices=indices,ode_parameters=ode_parameters);
```

 $\verb"parEstimationLBodeSSm" \textit{ Perform parameter estimation using essR}.$

Description

This function uses essR to perform parameter estimation. The objective function is the same as the one provided by getLBodeContObjFunction.

Usage

```
parEstimationLBodeSSm(cnolist, model, ode_parameters = NULL, indices = NULL,
maxeval = Inf, maxtime = 100, ndiverse = NULL, dim_refset = NULL, local_solver = NULL,
time = 1, verbose = 0, transfer_function = 3, reltol = 1e-04, atol = 0.001,
maxStepSize = Inf, maxNumSteps = 1e+05, maxErrTestsFails = 50, nan_fac =1,
    useVariances=F,initial_state=0.1)
```

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

ode_parameters A list with the ODEs parameter information. Obtained with createLBodeContPars.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

maxeval Maximum number of evaluation in the optimization procedure.

maxtime Duration of the optimization procedure.

ndiverse Number of diverse initial solutions.

dim_refset Size of the reference set.

local_solver Local solver to be used in SSm.

time An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

nan_fac A penalty for each data point the model is not able to simulate. We recommend

higher than 0 and smaller that 1.

useVariances Uses variance if any

initial_state initial state of the dynamic nodes (non-measured) (Defaults to 0.1)

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

LB_n	A numeric value to be used as lower bound for all parameters of type n.
LB_k	A numeric value to be used as lower bound for all parameters of type k.
LB_tau	A numeric value to be used as lower bound for all parameters of type tau.
UB_n	A numeric value to be used as upper bound for all parameters of type n.
UB_k	A numeric value to be used as upper bound for all parameters of type k.
UB_tau	A numeric value to be used as upper bound for all parameters of type tau.
default_n	The default parameter to be used for every parameter of type n.
default_k	The default parameter to be used for every parameter of type k.
default_tau	The default parameter to be used for every parameter of type tau.
LB_in	An array with the same length as ode_parameters\$parValues with lower bounds for each specific parameter.
UB_in	An array with the same length as ode_parameters\$parValues with upper bounds for each specific parameter.
opt_n	Add all parameter n to the index of parameters to be fitted.
opt_k	Add all parameter k to the index of parameters to be fitted.
opt_tau	Add all parameter tau to the index of parameters to be fitted.
random	A logical value that determines that a random solution is for the parameters to be optimized.
smm_results	A list containing the information provided by the nonlinear optimization solver.

Author(s)

David Henriques, Thomas Cokelaer

22 plotLBodeFitness

See Also

CellNOptR createLBodeContPars

Examples

```
## Not run:
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");

ode_parameters=createLBodeContPars(model,random=TRUE);

#Visualize intial simulation
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,ode_parameters,indices=indices)

ode_parameters=parEstimationLBodeSSm(cnolistCNORodeExample,model,ode_parameters,
indices=indices,maxtime=20,ndiverse=50,dim_refset=6);

#Visualize fitterd solution
simulatedData=plotLBodeFitness(cnolistCNORodeExample, model,indices=indices,ode_parameters=ode_parameters);
## End(Not run)
```

plotLBodeFitness

Plot data against simulated values.

Description

Plots the simulated values with the logic-based ODE against the the data contained contained the data contained in the cnolist. The data values are represented with a black line and the simulated values with a blue line. Additionally this functions returns the the simulated values.

Usage

Arguments

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

ode_parameters A list with the ODEs parameter information. Obtained with createLBodeContPars.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

adjMatrix Model representation in the form of an adjacency matrix. When not provided

will be automatically computed based in the model.

time An integer with the index of the time point to start the simulation. Default is 1.

plotLBodeFitness 23

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

step.

plot_index_signals

In case you only want to plot some signals, provide an integer vector with the

indexes.

plot_index_experiments

In case you only want to plot some experiments, provide an integer vector with

the indexes.

plot_index_cues

In case you only want to plot some cues, provide an integer vector with the

indexes.

colormap Uses the same colormap as in CellNOptR by default. If set to "green", it uses

the deprecated colormap.

plotParams additional parameters to refine the ploggin. See plotOptimResultsPan function

in CellNOptR for more details.

initial_state initial state of the dynamic nodes (non-measured) (Defaults to 0.1)

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

Returns a list with simulated data that has the same structure as the cnolist\$valueSignals. One matrix for each time-point.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");
ode_parameters=createLBodeContPars(model,random=TRUE);
dataSimulation=plotLBodeFitness(cnolistCNORodeExample, model,indices=indices);
```

24 plotLBodeModelSim

plotLBodeModelSim Simulate the model and plot tal conditions.	the obtained with the different experimen-
---	--

Description

Plots the simulated values of the logic based ODE model. Only dynamic states are plotted, i.e. those that are not inputs. a blue line. Additionally this functions returns the the simulated values.

Usage

```
plotLBodeModelSim(cnolist, model, ode_parameters = NULL, indices = NULL,
adjMatrix = NULL, timeSignals=NULL, time = 1, verbose = 0, transfer_function = 3,
reltol = 1e-04, atol = 0.001, maxStepSize = Inf, maxNumSteps = 1e+05,
maxErrTestsFails = 50, large = FALSE, nsplit = 4, show=T)
```

Arguments

cnolist	A list containing the experimental design and data.	
model	The logic model to be simulated.	
ode_parameters	$A\ list\ with\ the\ ODEs\ parameter\ information.\ Obtained\ with\ {\tt createLBodeContPars}.$	
indices	Indices to map data in the model. Obtained with indexFinder function from CellNOptR.	
adjMatrix	Model representation in the form of an adjacency matrix. When not provided will be automatically computed based in the model.	
timeSignals	An array containing a different timeSignals. If you use this argument, it will also modify the dimensions from valueSignals.	
time	An integer with the index of the time point to start the simulation. Default is 1.	
verbose	A logical value that triggers a set of comments.	
transfer_function		
	The type of used transfer. Use 1 for no transfer function, 2 for Hill function and	

3 for normalized Hill function.

Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

 ${\tt maxErrTestsFails}$

Specifies the maximum number of error test failures permitted in attempting one

large Boolean variable defining if the plot should split into several subplots.

nsplit In case the large plot options is selected define how many subplots will exist.

Default is 4.

show show the error (defaults to TRUE)

simdata2cnolist 25

Value

Returns a list with simulated Model values. One matrix of size number of species by number of experimental conditions for each time-point.

Author(s)

David Henriques, Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");
modelSimulation=plotLBodeModelSim(cnolistCNORodeExample, model,indices=indices);
```

simdata2cnolist

converts output of getLBodeModelSim to cnolist

Description

This function converts the simulated data returned by getLBodeModelSim into a valid CNOlist data structure.

Usage

```
simdata2cnolist(sim_data, cnolist, model)
```

Arguments

sim_data structure returned by getLBodeModelSim

cnolist A list containing the experimental design and data.

model The logic model to be simulated.

Value

a CNOlist

Author(s)

Thomas Cokelaer

See Also

CellNOptR createLBodeContPars

26 simulate

Examples

```
data('ToyCNOlist',package='CNORode');
data('ToyModel',package='CNORode');
data('ToyIndices',package='CNORode');
simdata = getLBodeModelSim(cnolistCNORodeExample, model,indices=indices)
cnolist = simdata2cnolist(simdata, cnolistCNORodeExample, model)
cnolist = simdata2cnolist(simdata, cnolistCNORodeExample, model)
```

simulate

Simulate value signals a CNO list With Logic-Based ODEs.

Description

This function receives a set of inputs, namely the cnolist and the model and returns a list with the same size of the cnolist\$valueSignals.

Usage

```
simulate(cnolist, model, ode_parameters=NULL, indices=NULL,
adjMatrix=NULL, time=1, verbose=0, transfer_function=3,
reltol=1e-04, atol=0.001, maxStepSize=Inf, maxNumSteps=1e+05,
maxErrTestsFails=50)
```

Arguments

cnolist A list containing the experimental design and data.

 ${\color{blue} \textbf{model}} \qquad \qquad \textbf{A list with the ODEs parameter information. Obtained with {\color{blue} \textbf{createLBodeContPars.}}}$

ode_parameters A list with the ODEs parameter information. Obtained with makeParameterList

function.

indices Indices to map data in the model. Obtained with indexFinder function from

CellNOptR.

adjMatrix The adjacency matrix. Recomputed if not provided

time An integer with the index of the time point to start the simulation. Default is 1.

verbose A logical value that triggers a set of comments.

transfer_function

The type of used transfer. Use 1 for no transfer function, 2 for Hill function and

3 for normalized Hill function.

reltol Relative Tolerance for numerical integration.

atol Absolute tolerance for numerical integration.

maxStepSize The maximum step size allowed to ODE solver.

maxNumSteps The maximum number of internal steps between two points being sampled be-

fore the solver fails.

maxErrTestsFails

Specifies the maximum number of error test failures permitted in attempting one

simulate 27

Details

Check CellNOptR for details about the cnolist and the model format. For more details in the configuration of the ODE solver check the CVODES manual.

Value

Returns a list with simulated data that has the same structure as the cnolist\$valueSignals. One matrix for each time-point.

Author(s)

David Henriques, Thomas Cokelaer

See Also

 ${\tt CellNOptR}\ parEstimation LBode\ parEstimation LBodeSSm$

Examples

```
library(CNORode)
data("ToyCNOlist",package="CNORode");
data("ToyModel",package="CNORode");
data("ToyIndices",package="CNORode");
dataSimulation = simulate(cnolistCNORodeExample, model,indices=indices);
```

Index

*Topic CNORode	createLBodeContPars, 3, 6–12, 14, 16–18
CNORode, 2	20, 22–26
*Topic CVODES	
<pre>getLBodeSimFunction, 12</pre>	defaultParametersGA, 4
*Topic CellNOptR	defaultParametersSSm, 5
parEstimationLBode, 16	moti BodoContObiFunction (10 20
parEstimationLBodeGA, 18	getLBodeContObjFunction, 6, 18, 20
*Topic SSm	getLBodeDataSim, 7
defaultParametersSSm, 5	getLBodeMINLPObjFunction, 9, 14
*Topic adjacency	getLBodeModelSim, 3, 10
getStates, 13	getLBodeSimFunction, 12 getStates, 13
incidence2Adjacency, 13	getstates, 13
*Topic algorithm	incidence2Adjacency, 13, 13
defaultParametersGA,4	indices, 14
parEstimationLBode, 16	11101000, 111
parEstimationLBodeGA, 18	minlpLBodeSSm, 14
*Topic default	model, 16
defaultParametersGA, 4	
defaultParametersSSm, 5	parEstimationLBode, 3, 5, 6, 8, 16, 27
*Topic essR	parEstimationLBodeGA, 5, 16, 18
defaultParametersSSm, 5	parEstimationLBodeSSm, 6 , 8 , 16 , 20 , 27
*Topic genetic	plotLBodeFitness, 3, 22
defaultParametersGA, 4	plotLBodeModelSim, 24
parEstimationLBode, 16	17.00
parEstimationLBodeGA, 18	rbga, <i>17</i> , <i>20</i>
*Topic incidence	simdata2cnolist, 25
incidence2Adjacency, 13	simulate, 26
*Topic logic	Siliulate, 20
parEstimationLBode, 16	
parEstimationLBodeGA, 18	
*Topic matrix	
incidence2Adjacency, 13	
*Topic model	
parEstimationLBode, 16	
parEstimationLBodeGA, 18	
*Topic parameters	
defaultParametersGA,4	
*Topic states	
getStates, 13	
CellNOptR, 3, 5–11, 13–17, 20–23, 25, 27	
<pre>cnolistCNORodeExample, 2</pre>	
CNORode, 2, <i>13</i>	