# Package 'betaNB'

May 7, 2023

Title Bootstrap for Regression Effect Sizes
Version 1.0.1.9000
<b>Description</b> Generates nonparametric bootstrap confidence intervals (Efron & Tibshirani, 1993: <doi:10.1201 9780429246593="">) for standardized regression coefficients (beta) and other effect sizes, including multiple correlation, semipartial correlations, improvement in R-squared, squared partial correlations, and differences in standardized regression coefficients, for models fitted by lm().</doi:10.1201>
<pre>URL https://github.com/jeksterslab/betaNB,     https://jeksterslab.github.io/betaNB/</pre>
BugReports https://github.com/jeksterslab/betaNB/issues License MIT + file LICENSE Encoding UTF-8
LazyData true
Roxygen list(markdown = TRUE)
<b>Depends</b> R (>= $3.5.0$ )
Imports stats
Suggests knitr, rmarkdown, testthat
RoxygenNote 7.2.3
NeedsCompilation no
Author Ivan Jacob Agaloos Pesigan [aut, cre, cph] ( <a href="https://orcid.org/0000-0003-4818-8420">https://orcid.org/0000-0003-4818-8420</a> )
Maintainer Ivan Jacob Agaloos Pesigan <r.jeksterslab@gmail.com></r.jeksterslab@gmail.com>
R topics documented:
BetaNB

2 BetaNB

Betal	NB	Estin resp ping	ond				_				00											
Index																						17
	vcov.betanb			 •	 •	 •		 ٠	•	•		•	•	•	 •	٠	•	•	 •	•	•	16
	summary.betanb																					
	SCorNB																					13
	RSqNB																					12
	print.nb																					
	print.betanb																					
	PCorNB																					
	nas1982																					
	DiffBetaNB																					
	DeltaRSqNB								•												•	5

# Description

Estimate Standardized Regression Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

BetaNB(object)

## **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

The vector of standardized regression coefficients  $(\hat{\beta})$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $\hat{\beta}$ , where  $\alpha$  is the significance level.

## Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call.

object The function argument object.

thetahatstar Sampling distribution of \hat{\beta}.

jackknife Jackknife estimates.

est Vector of estimated \hat{\beta}.

fun Function used ("BetaNB").
```

coef.betanb 3

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

## **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
std <- BetaNB(nb)
# Methods ---------------------------------
print(std)
summary(std)
coef(std)
vcov(std)
confint(std, level = 0.95)</pre>
```

coef.betanb

Estimated Parameter Method for an Object of Class betanb

## **Description**

Estimated Parameter Method for an Object of Class betanb

# Usage

```
## S3 method for class 'betanb'
coef(object, ...)
```

#### **Arguments**

object Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), PCorNB(), or DiffBetaNB() functions.
 additional arguments.

#### Value

Returns a vector of estimated parameters.

# Author(s)

Ivan Jacob Agaloos Pesigan

4 confint.betanb

#### **Examples**

confint.betanb

Confidence Intervals Method for an Object of Class betanb

## **Description**

Confidence Intervals Method for an Object of Class betanb

## Usage

```
## S3 method for class 'betanb'
confint(object, parm = NULL, level = 0.95, type = "pc", ...)
```

## **Arguments**

object	Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), PCorNB(), or DiffBetaNB() functions.
parm	a specification of which parameters are to be given confidence intervals, either a vector of numbers or a vector of names. If missing, all parameters are considered.
level	the confidence level required.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
	additional arguments.

## Value

Returns a matrix of confidence intervals.

#### Author(s)

Ivan Jacob Agaloos Pesigan

DeltaRSqNB 5

## **Examples**

DeltaRSqNB

Estimate Improvement in R-Squared and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Description

Estimate Improvement in R-Squared and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
DeltaRSqNB(object)
```

## **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

The vector of improvement in R-squared ( $\Delta R^2$ ) is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $\Delta R^2$ , where  $\alpha$  is the significance level.

# Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
object The function argument object. 
thetahatstar Sampling distribution of \Delta R^2. 
vcov Sampling variance-covariance matrix of \Delta R^2. 
est Vector of estimated \Delta R^2. 
fun Function used ("DeltaRSqMC").
```

6 DiffBetaNB

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

## **Examples**

DiffBetaNB

Estimate Differences of Standardized Slopes and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Description

Estimate Differences of Standardized Slopes and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Usage

```
DiffBetaNB(object)
```

#### **Arguments**

object

Object of class mc, that is, the output of the MC() function.

## **Details**

The vector of differences of standardized regression slopes is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of differences of standardized regression slopes, where  $\alpha$  is the significance level.

nas1982

#### Value

Returns an object of class betanb which is a list with the following elements:

call Function call.

**object** The function argument object.

thetahatstar Sampling distribution of differences of standardized regression slopes.

vcov Sampling variance-covariance matrix of differences of standardized regression slopes.

est Vector of estimated differences of standardized regression slopes.

fun Function used ("DiffBetaMC").

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

## **Examples**

nas1982

1982 National Academy of Sciences Doctoral Programs Data

## **Description**

1982 National Academy of Sciences Doctoral Programs Data

## Usage

nas1982

NB

#### **Format**

Ratings of 46 doctoral programs in psychology in the USA with the following variables:

**QUALITY** Program quality ratings.

NFACUL Number of faculty members in the program.

NGRADS Number of program graduates.

**PCTSUPP** Percentage of program graduates who received support.

**PCTGRT** Percent of faculty members holding research grants.

NARTIC Number of published articles attributed to program faculty member.

PCTPUB Percent of faculty with one or more published article.

#### References

National Research Council. (1982). An assessment of research-doctorate programs in the United States: Social and behavioral sciences. doi:10.17226/9781. Reproduced with permission from the National Academy of Sciences, Courtesy of the National Academies Press, Washington, D.C.

NΒ

Generate the Sampling Distribution of Sample Covariances Using Nonparametric Bootstrapping

## Description

Generate the Sampling Distribution of Sample Covariances Using Nonparametric Bootstrapping

## Usage

```
NB(object, R = 5000, seed = NULL)
```

#### **Arguments**

object Object of class 1m.

R Positive integer. Number of bootstrap replications.

seed Integer. Seed number for reproducibility.

#### Value

Returns an object of class nb which is a list with the following elements:

call Function call.

args Function arguments.

lm\_process Processed 1m object.

thetahatstar Sampling distribution of sample covariances.

jackknife Jackknife estimates.

PCorNB 9

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### References

Efron, B., & Tibshirani, R. J. (1993) An introduction to the bootstrap. Chapman & Hall.

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), PCorNB(), RSqNB(), SCorNB()
```

#### **Examples**

```
# Fit the regression model object <- lm(QUALITY \sim NARTIC + PCTGRT + PCTSUPP), data = nas1982) # Generate the sampling distribution of sample covariances # (use a large R, for example, R = 5000 for actual research) NB(object, R = 100)
```

**PCorNB** 

Estimate Squared Partial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## **Description**

Estimate Squared Partial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Usage

PCorNB(object)

#### **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

The vector of squared partial correlation coefficients  $(r_p^2)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $r_p^2$ , where  $\alpha$  is the significance level.

10 print.betanb

#### Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
object The function argument object. 
thetahatstar Sampling distribution of r_p^2. 
vcov Sampling variance-covariance matrix of r_p^2. 
est Vector of estimated r_p^2. 
fun Function used ("PCorMC").
```

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), RSqNB(), SCorNB()
```

## **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rp <- PCorNB(nb)
# Methods -------
print(rp)
summary(rp)
coef(rp)
vcov(rp)
confint(rp, level = 0.95)</pre>
```

print.betanb

Print Method for an Object of Class betanb

## **Description**

Print Method for an Object of Class betanb

#### Usage

```
## S3 method for class 'betanb' print(x, alpha = c(0.05, 0.01, 0.001), type = "pc", digits = 4, ...)
```

print.nb 11

## **Arguments**

X	Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), PCorNB(), or DiffBetaNB() functions.
alpha	Significance level.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
digits	Digits to print.
	additional arguments.

#### Value

Prints a matrix of estimates, standard errors, number of bootstrap replications, and confidence intervals

## Author(s)

Ivan Jacob Agaloos Pesigan

## **Examples**

print.nb

Print Method for an Object of Class nb

#### **Description**

Print Method for an Object of Class nb

# Usage

```
## S3 method for class 'nb' print(x, ...)
```

#### **Arguments**

x Object of Class nb.... additional arguments.

12 RSqNB

#### Value

Prints the first six bootstrap covariance matrices.

#### Author(s)

Ivan Jacob Agaloos Pesigan

## **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate bootstrap covariance matrices
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
print(nb)</pre>
```

**RSqNB** 

Estimate Multiple Correlation Coefficients (R-Squared and Adjusted R-Squared) and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Description

Estimate Multiple Correlation Coefficients (R-Squared and Adjusted R-Squared) and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
RSqNB(object)
```

## **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

R-squared  $(R^2)$  and adjusted R-squared  $(\bar{R}^2)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $R^2$  and  $\bar{R}^2$ , where  $\alpha$  is the significance level.

## Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
 object The function argument object. 
 thetahatstar Sampling distribution of R^2 and \bar{R}^2.
```

SCorNB 13

```
vcov Sampling variance-covariance matrix of R^2 and \bar{R}^2.

est Vector of estimated R^2 and \bar{R}^2.

fun Function used ("RSqMC").
```

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), SCorNB()
```

## **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rsq <- RSqNB(nb)
# Methods ---------------------------------
print(rsq)
summary(rsq)
coef(rsq)
vcov(rsq)
confint(rsq, level = 0.95)</pre>
```

**SCorNB** 

Estimate Semipartial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# **Description**

Estimate Semipartial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
SCorNB(object)
```

## **Arguments**

object

Object of class mc, that is, the output of the MC() function.

14 SCorNB

#### **Details**

The vector of semipartial correlation coefficients  $(r_s)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $r_s$ , where  $\alpha$  is the significance level.

#### Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
 object The function argument object. 
 thetahatstar Sampling distribution of r_s. 
 vcov Sampling variance-covariance matrix of r_s. 
 est Vector of estimated r_s. 
 fun Function used ("SCorMC").
```

## Author(s)

Ivan Jacob Agaloos Pesigan

## See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB()
```

## **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rs <- SCorNB(nb)
# Methods -------
print(rs)
summary(rs)
coef(rs)
vcov(rs)
confint(rs, level = 0.95)</pre>
```

summary.betanb 15

summary.betanb	Summary Method for an Object of Class betanb	
----------------	--	--

# Description

Summary Method for an Object of Class betanb

#### Usage

```
## S3 method for class 'betanb' summary(object, alpha = c(0.05, 0.01, 0.001), type = "pc", digits = 4, ...)
```

## **Arguments**

object	Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), PCorNB(), or DiffBetaNB() functions.
alpha	Significance level.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
digits	Digits to print.
	additional arguments.

#### Value

Returns a matrix of estimates, standard errors, number of bootstrap replications, and confidence intervals.

# Author(s)

Ivan Jacob Agaloos Pesigan

# **Examples**

16 vcov.betanb

vcov.betanb	Sampling Variance-Covariance Matrix Method for an Object of Class betanb

## **Description**

Sampling Variance-Covariance Matrix Method for an Object of Class betanb

## Usage

```
## S3 method for class 'betanb'
vcov(object, ...)
```

## Arguments

```
object Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), PCorNB(), or DiffBetaNB() functions.... additional arguments.
```

## Value

Returns the variance-covariance matrix of estimates.

## Author(s)

Ivan Jacob Agaloos Pesigan

## **Examples**

# **Index**

* Beta Nonparametric Bootstrap Functions	.CI, 3, 6, 7, 9, 10, 13, 14
BetaNB, 2	
DeltaRSqNB, 5	BetaNB, 2, 6, 7, 9, 10, 13, 14
DiffBetaNB, 6	coef.betanb, 3
NB, 8	confint.betanb, 4
PCorNB, 9	com me. be camb, 4
RSqNB, 12	DeltaRSqNB, 3, 5, 7, 9, 10, 13, 14
SCorNB, 13	DiffBetaNB, 3, 6, 6, 9, 10, 13, 14
* betaNB	
BetaNB, 2	nas1982, <b>7</b>
DeltaRSqNB, 5	NB, 3, 6, 7, 8, 10, 13, 14
DiffBetaNB, 6	
NB, 8	PCorNB, 3, 6, 7, 9, 9, 13, 14
PCorNB, 9	print.betanb, 10
RSqNB, 12	print.nb,11
SCorNB, 13	RSqNB, 3, 6, 7, 9, 10, 12, 14
* data	Noque, 3, 6, 7, 9, 10, 12, 14
nas1982, 7	SCorNB, 3, 6, 7, 9, 10, 13, 13
* deltarsq	summary.betanb, 15
DeltaRSqNB, 5	,
* diff	vcov.betanb, 16
DiffBetaNB, 6	
* methods	
coef.betanb, 3	
confint.betanb,4	
print.betanb, 10	
print.nb, 11	
summary.betanb, 15	
vcov.betanb, 16	
* nb	
NB, 8	
* pcor	
PCorNB, 9	
* rsq	
RSqNB, 12	
* SCOT	
SCorNB, 13	
* std	
BetaNB, 2	