# Package 'betaNB'

April 8, 2023
<b>Title</b> Nonparametric Bootstrap Confidence Intervals for Standardized Regression Coefficients and Other Effect Sizes
Version 1.0.0.9000
<b>Description</b> Generates nonparametric bootstrap confidence intervals (Efron & Tibshirani, 1993: <doi:10.1201 9780429246593="">) for standardized regression coefficients and other effect sizes for models fitted by lm().</doi:10.1201>
<pre>URL https://github.com/jeksterslab/betaNB,</pre>
https://jeksterslab.github.io/betaNB/
<pre>BugReports https://github.com/jeksterslab/betaNB/issues</pre>
License MIT + file LICENSE
Encoding UTF-8
LazyData true
<b>Roxygen</b> list(markdown = TRUE)
<b>Depends</b> R (>= $3.5.0$ )
Imports stats, methods
Suggests knitr, rmarkdown, testthat
RoxygenNote 7.2.3
NeedsCompilation no
Author Ivan Jacob Agaloos Pesigan [aut, cre, cph] ( <a href="https://orcid.org/0000-0003-4818-8420">https://orcid.org/0000-0003-4818-8420</a> )
Maintainer Ivan Jacob Agaloos Pesigan <r.jeksterslab@gmail.com></r.jeksterslab@gmail.com>
R topics documented:
BetaNB

2 BetaNB

BetaNB		Estimate Standardized Regression Coefficients and Generate to responding Sampling Distribution Using Nonparametric Booping	
Index			17
	vcov.betanb		 16
	SCorNB		 13
	RSqNB		 12
	print.nb		 11
	print.betanb		 10
	PCorNB		 9
	NB		 8
	nas1982		 7

## **Description**

Estimate Standardized Regression Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# Usage

BetaNB(object)

# **Arguments**

object

Object of class mc, that is, the output of the MC() function.

# **Details**

The vector of standardized regression coefficients  $(\hat{\beta})$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $\hat{\beta}$ , where  $\alpha$  is the significance level.

# Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call.

object The function argument object.

thetahatstar Sampling distribution of \hat{\beta}.

jackknife Jackknife estimates.

est Vector of estimated \hat{\beta}.

fun Function used ("BetaNB").
```

coef.betanb 3

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

# **Examples**

coef.betanb

Estimated Parameter Method for an Object of Class betanb

# **Description**

Estimated Parameter Method for an Object of Class betanb

# Usage

```
## S3 method for class 'betanb'
coef(object, ...)
```

#### **Arguments**

object Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), or PCorNB() functions.additional arguments.

#### Value

Returns a vector of estimated parameters.

# Author(s)

Ivan Jacob Agaloos Pesigan

4 confint.betanb

## **Examples**

confint.betanb

Confidence Intervals Method for an Object of Class betanb

# **Description**

Confidence Intervals Method for an Object of Class betanb

# Usage

```
## S3 method for class 'betanb'
confint(object, parm = NULL, level = 0.95, type = "pc", ...)
```

# **Arguments**

object	Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), or PCorNB() functions.
parm	a specification of which parameters are to be given confidence intervals, either a vector of numbers or a vector of names. If missing, all parameters are considered.
level	the confidence level required.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
	additional arguments.

# Value

Returns a matrix of confidence intervals.

#### Author(s)

Ivan Jacob Agaloos Pesigan

DeltaRSqNB 5

## **Examples**

DeltaRSqNB

Estimate Improvement in R-Squared and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# Description

Estimate Improvement in R-Squared and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
DeltaRSqNB(object)
```

# **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

The vector of improvement in R-squared ( $\Delta R^2$ ) is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $\Delta R^2$ , where  $\alpha$  is the significance level.

# Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
object The function argument object. 
thetahatstar Sampling distribution of \Delta R^2. 
vcov Sampling variance-covariance matrix of \Delta R^2. 
est Vector of estimated \Delta R^2. 
fun Function used ("DeltaRSqMC").
```

6 DiffBetaNB

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

## **Examples**

DiffBetaNB

Estimate Differences of Standardized Slopes and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# Description

Estimate Differences of Standardized Slopes and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# Usage

```
DiffBetaNB(object)
```

#### **Arguments**

object

Object of class mc, that is, the output of the MC() function.

## **Details**

The vector of differences of standardized regression slopes is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of differences of standardized regression slopes, where  $\alpha$  is the significance level.

nas1982

#### Value

Returns an object of class betanb which is a list with the following elements:

call Function call.

**object** The function argument object.

thetahatstar Sampling distribution of differences of standardized regression slopes.

vcov Sampling variance-covariance matrix of differences of standardized regression slopes.

est Vector of estimated differences of standardized regression slopes.

fun Function used ("DiffBetaMC").

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), NB(), PCorNB(), RSqNB(), SCorNB()
```

## **Examples**

nas1982

1982 National Academy of Sciences Doctoral Programs Data

## **Description**

1982 National Academy of Sciences Doctoral Programs Data

## Usage

nas1982

NB

#### **Format**

Ratings of 46 doctoral programs in psychology in the USA with the following variables:

**QUALITY** Program quality ratings.

NFACUL Number of faculty members in the program.

NGRADS Number of program graduates.

**PCTSUPP** Percentage of program graduates who received support.

**PCTGRT** Percent of faculty members holding research grants.

NARTIC Number of published articles attributed to program faculty member.

PCTPUB Percent of faculty with one or more published article.

#### References

National Research Council. (1982). An assessment of research-doctorate programs in the United States: Social and behavioral sciences. doi:10.17226/9781. Reproduced with permission from the National Academy of Sciences, Courtesy of the National Academies Press, Washington, D.C.

NΒ

Generate the Sampling Distribution of Sample Covariances Using Nonparametric Bootstrapping

# Description

Generate the Sampling Distribution of Sample Covariances Using Nonparametric Bootstrapping

# Usage

```
NB(object, R = 5000, seed = NULL)
```

#### **Arguments**

object Object of class 1m.

R Positive integer. Number of bootstrap replications.

seed Integer. Seed number for reproducibility.

#### Value

Returns an object of class nb which is a list with the following elements:

call Function call.

args Function arguments.

lm\_process Processed 1m object.

thetahatstar Sampling distribution of sample covariances.

jackknife Jackknife estimates.

PCorNB 9

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### References

Efron, B., & Tibshirani, R. J. (1993) An introduction to the bootstrap. Chapman & Hall.

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), PCorNB(), RSqNB(), SCorNB()
```

#### **Examples**

```
# Fit the regression model object <- lm(QUALITY \sim NARTIC + PCTGRT + PCTSUPP), data = nas1982) # Generate the sampling distribution of sample covariances # (use a large R, for example, R = 5000 for actual research) NB(object, R = 100)
```

**PCorNB** 

Estimate Squared Partial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# **Description**

Estimate Squared Partial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

## Usage

PCorNB(object)

#### **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

The vector of squared partial correlation coefficients  $(r_p^2)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $r_p^2$ , where  $\alpha$  is the significance level.

10 print.betanb

#### Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
object The function argument object. 
thetahatstar Sampling distribution of r_p^2. 
vcov Sampling variance-covariance matrix of r_p^2. 
est Vector of estimated r_p^2. 
fun Function used ("PCorMC").
```

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), RSqNB(), SCorNB()
```

# **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rp <- PCorNB(nb)
# Methods -------
print(rp)
summary(rp)
coef(rp)
vcov(rp)
confint(rp, level = 0.95)</pre>
```

print.betanb

Print Method for an Object of Class betanb

# **Description**

Print Method for an Object of Class betanb

#### Usage

```
## S3 method for class 'betanb' print(x, alpha = c(0.05, 0.01, 0.001), type = "pc", digits = 4, ...)
```

print.nb 11

# **Arguments**

X	Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), or PCorNB() functions.
alpha	Significance level.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
digits	Digits to print.
	additional arguments.

#### Value

Prints a matrix of estimates, standard errors, number of bootstrap replications, and confidence intervals

## Author(s)

Ivan Jacob Agaloos Pesigan

# **Examples**

print.nb

Print Method for an Object of Class nb

#### **Description**

Print Method for an Object of Class nb

# Usage

```
## S3 method for class 'nb' print(x, ...)
```

#### **Arguments**

```
x Object of Class nb.... additional arguments.
```

12 RSqNB

#### Value

Prints the first six bootstrap covariance matrices.

#### Author(s)

Ivan Jacob Agaloos Pesigan

# **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate bootstrap covariance matrices
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
print(nb)</pre>
```

**RSqNB** 

Estimate Multiple Correlation Coefficients (R-Squared and Adjusted R-Squared) and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# Description

Estimate Multiple Correlation Coefficients (R-Squared and Adjusted R-Squared) and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
RSqNB(object)
```

# **Arguments**

object

Object of class mc, that is, the output of the MC() function.

#### **Details**

R-squared  $(R^2)$  and adjusted R-squared  $(\bar{R}^2)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $R^2$  and  $\bar{R}^2$ , where  $\alpha$  is the significance level.

# Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
 object The function argument object. 
 thetahatstar Sampling distribution of R^2 and \bar{R}^2.
```

SCorNB 13

```
vcov Sampling variance-covariance matrix of R^2 and \bar{R}^2.

est Vector of estimated R^2 and \bar{R}^2.

fun Function used ("RSqMC").
```

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), SCorNB()
```

# **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rsq <- RSqNB(nb)
# Methods ---------------------------------
print(rsq)
summary(rsq)
coef(rsq)
vcov(rsq)
confint(rsq, level = 0.95)</pre>
```

**SCorNB** 

Estimate Semipartial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

# **Description**

Estimate Semipartial Correlation Coefficients and Generate the Corresponding Sampling Distribution Using Nonparametric Bootstrapping

#### Usage

```
SCorNB(object)
```

# **Arguments**

object

Object of class mc, that is, the output of the MC() function.

14 SCorNB

#### **Details**

The vector of semipartial correlation coefficients  $(r_s)$  is estimated from bootstrap samples. Confidence intervals are generated by obtaining percentiles corresponding to  $100(1-\alpha)\%$  from the generated sampling distribution of  $r_s$ , where  $\alpha$  is the significance level.

#### Value

Returns an object of class betanb which is a list with the following elements:

```
call Function call. 
 object The function argument object. 
 thetahatstar Sampling distribution of r_s. 
 vcov Sampling variance-covariance matrix of r_s. 
 est Vector of estimated r_s. 
 fun Function used ("SCorMC").
```

# Author(s)

Ivan Jacob Agaloos Pesigan

## See Also

```
Other Beta Nonparametric Bootstrap Functions: .CI(), BetaNB(), DeltaRSqNB(), DiffBetaNB(), NB(), PCorNB(), RSqNB()
```

# **Examples**

```
# Fit the regression model
object <- lm(QUALITY ~ NARTIC + PCTGRT + PCTSUPP, data = nas1982)
# Generate the sampling distribution of sample covariances
# (use a large R, for example, R = 5000 for actual research)
nb <- NB(object, R = 50)
# Generate confidence intervals for standardized regression slopes
rs <- SCorNB(nb)
# Methods -------
print(rs)
summary(rs)
coef(rs)
vcov(rs)
confint(rs, level = 0.95)</pre>
```

summary.betanb 15

summary.betanb	Summary Method for an Object of Class betanb	

# Description

Summary Method for an Object of Class betanb

# Usage

```
## S3 method for class 'betanb' summary(object, alpha = c(0.05, 0.01, 0.001), type = "pc", digits = 4, ...)
```

# **Arguments**

object	Object of Class betanb, that is, the output of the $BetaNB()$ , $RSqNB()$ , $SCorNB()$ , $DeltaRSqNB()$ , or $PCorNB()$ functions.
alpha	Significance level.
type	Charater string. Confidence interval type, that is, type = "pc" for percentile; type = "bc" for bias corrected; type = "bca" for bias corrected and accelerated.
digits	Digits to print.
	additional arguments.

#### Value

Returns a matrix of estimates, standard errors, number of bootstrap replications, and confidence intervals.

# Author(s)

Ivan Jacob Agaloos Pesigan

# **Examples**

16 vcov.betanb

vcov.betanb	Sampling Variance-Covariance Matrix Method for an Object of Class betanb

# **Description**

Sampling Variance-Covariance Matrix Method for an Object of Class betanb

## Usage

```
## S3 method for class 'betanb'
vcov(object, ...)
```

# **Arguments**

```
object Object of Class betanb, that is, the output of the BetaNB(), RSqNB(), SCorNB(), DeltaRSqNB(), or PCorNB() functions.additional arguments.
```

# Value

Returns the variance-covariance matrix of estimates.

# Author(s)

Ivan Jacob Agaloos Pesigan

# **Examples**

# **Index**

* Beta Nonparametric Bootstrap Functions	.CI, 3, 6, 7, 9, 10, 13, 14
BetaNB, 2	
DeltaRSqNB, 5	BetaNB, 2, 6, 7, 9, 10, 13, 14
DiffBetaNB, 6	coef.betanb, 3
NB, 8	confint.betanb, 4
PCorNB, 9	com me. be camb, 4
RSqNB, 12	DeltaRSqNB, 3, 5, 7, 9, 10, 13, 14
SCorNB, 13	DiffBetaNB, 3, 6, 6, 9, 10, 13, 14
* betaNB	
BetaNB, 2	nas1982, 7
DeltaRSqNB, 5	NB, 3, 6, 7, 8, 10, 13, 14
DiffBetaNB, 6	
NB, 8	PCorNB, 3, 6, 7, 9, 9, 13, 14
PCorNB, 9	print.betanb, 10
RSqNB, 12	print.nb,11
SCorNB, 13	RSqNB, 3, 6, 7, 9, 10, 12, 14
* data	N34ND, 3, 0, 7, 9, 10, 12, 14
nas1982, 7	SCorNB, 3, 6, 7, 9, 10, 13, 13
* deltarsq	summary.betanb, 15
DeltaRSqNB, 5	,
* diff	vcov.betanb, 16
DiffBetaNB, 6	
* methods	
coef.betanb, 3	
confint.betanb,4	
print.betanb, 10	
print.nb, 11	
summary.betanb, 15	
vcov.betanb, 16	
* nb	
NB, 8	
* pcor	
PCorNB, 9	
* rsq	
RSqNB, 12	
* SCOT	
SCorNB, 13	
* std	
BetaNB, 2	