# Package 'fitDTVARMx'

July 24, 2024
<b>Title</b> Fit the Discrete-Time Vector Autoregressive Model
<b>Version</b> 0.0.0.9000
<b>Description</b> Fit the discrete-time vector autoregressive model using the 'OpenMx' package.
<pre>URL https://github.com/jeksterslab/fitDTVARMx,</pre>
https://jeksterslab.github.io/fitDTVARMx/
<pre>BugReports https://github.com/jeksterslab/fitDTVARMx/issues</pre>
License MIT + file LICENSE
Encoding UTF-8
Roxygen list(markdown = TRUE)
VignetteBuilder knitr
<b>Depends</b> R ( $>= 3.0.0$ ), OpenMx
Imports stats
Suggests knitr, rmarkdown, testthat, simStateSpace
RoxygenNote 7.3.2
NeedsCompilation no
Author Ivan Jacob Agaloos Pesigan [aut, cre, cph] ( <a href="https://orcid.org/0000-0003-4818-8420">https://orcid.org/0000-0003-4818-8420</a> )
Maintainer Ivan Jacob Agaloos Pesigan <r.jeksterslab@gmail.com></r.jeksterslab@gmail.com>
Contents
coef.fitdtvaridmx
coef.fitdtvarmx
FitDTVARIDMx
FitDTVARMx
print.fitdtvaridmx
print.fitdtvarmx
summary.fitdtvaridmx
summary.fitdtvarmx
vcov.induvaridiix

2 coef.fitdtvarmx

Index 14

coef.fitdtvaridmx Parameter Estimates
---------------------------------------

# Description

Parameter Estimates

# Usage

```
## S3 method for class 'fitdtvaridmx'
coef(object, alpha = FALSE, psi = FALSE, theta = FALSE, ...)
```

# Arguments

object	Object of class fitdtvaridmx.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.
	additional arguments.

#### Value

Returns a list of vectors of parameter estimates.

# Author(s)

Ivan Jacob Agaloos Pesigan

Parameter Estimates	f.fitdtvarmx Paramete	r Estimatas	,	
-arameier Esiimai	TITULVANIIX Parameio	r Estimai	es	ies

# Description

Parameter Estimates

#### Usage

```
## S3 method for class 'fitdtvarmx'
coef(object, alpha = FALSE, psi = FALSE, theta = FALSE, ...)
```

#### **Arguments**

object	Object of class fitdtvarmx.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.
	additional arguments.

#### Value

Returns a vector of parameter estimates.

#### Author(s)

Ivan Jacob Agaloos Pesigan

FitDTVARIDMx

Fit the First-Order Discrete-Time Vector Autoregressive Model by ID

#### **Description**

Fit the First-Order Discrete-Time Vector Autoregressive Model by ID

# Usage

```
FitDTVARIDMx(
  data,
  observed,
  id,
  alpha_fixed = TRUE,
  alpha_start = NULL,
  alpha_lbound = NULL,
  alpha_ubound = NULL,
  beta_start = NULL,
  beta_lbound = NULL,
  beta_ubound = NULL,
  psi_diag = TRUE,
  psi_start = NULL,
  psi_lbound = NULL,
  psi_ubound = NULL,
  theta_fixed = TRUE,
  theta_start = NULL,
  theta_lbound = NULL,
  theta_ubound = NULL,
```

```
mu0_fixed = TRUE,
 mu0_start = NULL,
 mu0_1bound = NULL,
 mu0\_ubound = NULL,
  sigma0_fixed = TRUE,
  sigma0_diag = TRUE,
  sigma0_start = NULL,
  sigma0_lbound = NULL,
  sigma0_ubound = NULL,
  try = 1000,
  ncores = NULL
)
```

#### **Arguments**

data	Data frame. A data frame object of data for potentially multiple subjects that contain a column of subject ID numbers (i.e., an ID variable), and at least one column of observed values.
observed	Character vector. A vector of character strings of the names of the observed variables in the data.
id	Character string. A character string of the name of the ID variable in the data.
alpha_fixed	Logical. If alpha_fixed = TRUE, the dynamic model intercept vector alpha is fixed at zero. If alpha_fixed = FALSE, the dynamic model intercept vector alpha is estimated.
alpha_start	Optional starting values for alpha. If alpha_fixed = TRUE, alpha_start will be used as fixed values. If alpha_fixed = FALSE, alpha_start will be used as starting values.
alpha_lbound	Optional lower bound for alpha. Ignored if alpha_fixed = TRUE.
alpha_ubound	Optional upper bound for alpha. Ignored if alpha_fixed = TRUE.

beta\_start Numeric matrix. Optional starting values for beta. beta\_lbound Numeric matrix. Optional lower bound for beta. Numeric matrix. Optional upper bound for beta. beta\_ubound Logical. If psi\_diag = TRUE, psi is a diagonal matrix. psi\_diag Numeric matrix. Optional starting values for psi. psi\_start Numeric matrix. Optional lower bound for psi. psi\_lbound

psi\_ubound Optional upper bound for psi.

theta\_fixed Logical. If theta\_fixed = TRUE, the measurement error matrix theta is fixed to

zero. If theta\_fixed = FALSE, estimate the diagonal measurement error matrix

Optional starting values for theta. Ignored if theta\_fixed = TRUE. theta\_start theta\_lbound Optional lower bound for theta. Ignored if theta\_fixed = TRUE. theta\_ubound Optional upper bound for theta. Ignored if theta\_fixed = TRUE.

mu0\_fixed Logical. If mu0\_fixed = TRUE, initial mean vector mu0 is fixed. If mu0\_fixed =

FALSE, initial mean vector mu0 is estimated.

mu0_start	Optional starting values for mu0. If mu0_fixed = TRUE, mu0_start will be used as fixed values. If mu0_fixed = FALSE, mu0_start will be used as starting values.
mu0_lbound	Optional lower bound for mu0. Ignored if mu0_fixed = TRUE.
mu0_ubound	Optional upper bound for mu0. Ignored if mu0_fixed = TRUE.
sigma0_fixed	Logical. If sigma0_fixed = TRUE, initial mean vector sigma0 is fixed. If sigma0_fixed = FALSE, initial mean vector sigma0 is estimated.
sigma0_diag	Logical. If sigma@_diag = TRUE, sigma@ is a diagonal matrix.
sigma0_start	Optional starting values for sigma0. If sigma0_fixed = TRUE, sigma0_start will be used as fixed values. If sigma0_fixed = FALSE, sigma0_start will be used as starting values.
sigma0_lbound	Optional lower bound for sigma0. Ignored if sigma0_fixed = TRUE.
sigma0_ubound	Optional upper bound for sigma0. Ignored if sigma0_fixed = TRUE.
try	Positive integer. Number of extra optimization tries.
ncores	Positive integer. Number of cores to use.

#### Value

Returns an object of class fitdtvaridmx which is a list with the following elements:

call Function call.

args List of function arguments.

fun Function used ("FitDTVARIDMx").

output A list of fitted OpenMx models.

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### References

Hunter, M. D. (2017). State space modeling in an open source, modular, structural equation modeling environment. *Structural Equation Modeling: A Multidisciplinary Journal*, 25(2), 307–324. doi:10.1080/10705511.2017.1369354

Neale, M. C., Hunter, M. D., Pritikin, J. N., Zahery, M., Brick, T. R., Kirkpatrick, R. M., Estabrook, R., Bates, T. C., Maes, H. H., & Boker, S. M. (2015). OpenMx 2.0: Extended structural equation and statistical modeling. *Psychometrika*, 81(2), 535–549. doi:10.1007/s1133601494358

#### See Also

Other DTVAR Functions: FitDTVARMx()

#### **Examples**

```
## Not run:
# Generate data using the simStateSpace package-----
set.seed(42)
beta_mu <- matrix(</pre>
 data = c(
   0.7, 0.5, -0.1,
   0.0, 0.6, 0.4,
   0, 0, 0.5
 ),
 nrow = 3
beta_sigma <- diag(3 * 3)</pre>
beta <- simStateSpace::SimBetaN(</pre>
 n = 5,
 beta = beta_mu,
 vcov_beta_vec_l = t(chol(beta_sigma))
)
sim <- simStateSpace::SimSSMVARIVary(</pre>
 n = 5,
 time = 100,
 mu0 = list(rep(x = 0, times = 3)),
 sigma0_l = list(t(chol(diag(3)))),
 alpha = list(rep(x = 0, times = 3)),
 beta = beta,
 psi_l = list(t(chol(diag(3))))
)
data <- as.data.frame(sim)</pre>
# Fit the model------
library(fitDTVARMx)
fit <- FitDTVARIDMx(</pre>
 data = data,
 observed = c("y1", "y2", "y3"),
 id = "id"
print(fit)
summary(fit)
coef(fit)
vcov(fit)
## End(Not run)
```

FitDTVARMx

Fit the First-Order Discrete-Time Vector Autoregressive Model

# **Description**

Fit the First-Order Discrete-Time Vector Autoregressive Model

#### Usage

```
FitDTVARMx(
  data,
  observed,
  id,
  alpha_fixed = TRUE,
  alpha_start = NULL,
  alpha_lbound = NULL,
  alpha_ubound = NULL,
  beta_start = NULL,
  beta_lbound = NULL,
  beta_ubound = NULL,
  psi_diag = TRUE,
  psi_start = NULL,
  psi_lbound = NULL,
  psi_ubound = NULL,
  theta_fixed = TRUE,
  theta_start = NULL,
  theta_lbound = NULL,
  theta_ubound = NULL,
 mu0_fixed = TRUE,
 mu0_start = NULL,
 mu0_lbound = NULL,
 mu0\_ubound = NULL,
  sigma0_fixed = TRUE,
  sigma0_diag = TRUE,
  sigma0_start = NULL,
  sigma0_lbound = NULL,
  sigma0_ubound = NULL,
  try = 1000,
 ncores = NULL
)
```

#### **Arguments**

data	Data frame. A data frame object of data for potentially multiple subjects that contain a column of subject ID numbers (i.e., an ID variable), and at least one column of observed values.
observed	Character vector. A vector of character strings of the names of the observed variables in the data.
id	Character string. A character string of the name of the ID variable in the data.
alpha_fixed	Logical. If alpha_fixed = TRUE, the dynamic model intercept vector alpha is fixed at zero. If alpha_fixed = FALSE, the dynamic model intercept vector alpha is estimated.
alpha_start	Optional starting values for alpha. If alpha_fixed = TRUE, alpha_start will be used as fixed values. If alpha_fixed = FALSE, alpha_start will be used as

starting values.

alpha_lbound	Optional lower bound for alpha. Ignored if alpha_fixed = TRUE.
alpha_ubound	Optional upper bound for alpha. Ignored if alpha_fixed = TRUE.
beta_start	Numeric matrix. Optional starting values for beta.
beta_lbound	Numeric matrix. Optional lower bound for beta.
beta_ubound	Numeric matrix. Optional upper bound for beta.
psi_diag	Logical. If psi_diag = TRUE, psi is a diagonal matrix.
psi_start	Numeric matrix. Optional starting values for psi.
psi_lbound	Numeric matrix. Optional lower bound for psi.
psi_ubound	Optional upper bound for psi.
theta_fixed	Logical. If theta_fixed = TRUE, the measurement error matrix theta is fixed to zero. If theta_fixed = FALSE, estimate the diagonal measurement error matrix theta.
theta_start	Optional starting values for theta. Ignored if theta_fixed = TRUE.
theta_lbound	Optional lower bound for theta. Ignored if theta_fixed = TRUE.
theta_ubound	Optional upper bound for theta. Ignored if theta_fixed = TRUE.
mu0_fixed	Logical. If mu0_fixed = TRUE, initial mean vector mu0 is fixed. If mu0_fixed = FALSE, initial mean vector mu0 is estimated.
mu0_start	Optional starting values for mu0. If mu0_fixed = TRUE, mu0_start will be used as fixed values. If mu0_fixed = FALSE, mu0_start will be used as starting values.
mu0_lbound	Optional lower bound for mu0. Ignored if mu0_fixed = TRUE.
mu0_ubound	Optional upper bound for mu0. Ignored if mu0_fixed = TRUE.
sigma0_fixed	Logical. If sigma0_fixed = TRUE, initial mean vector sigma0 is fixed. If sigma0_fixed = FALSE, initial mean vector sigma0 is estimated.
sigma0_diag	Logical. If sigma@_diag = TRUE, sigma@ is a diagonal matrix.
sigma0_start	Optional starting values for sigma0. If sigma0_fixed = TRUE, sigma0_start will be used as fixed values. If sigma0_fixed = FALSE, sigma0_start will be used as starting values.
sigma0_lbound	Optional lower bound for sigma0. Ignored if sigma0_fixed = TRUE.
sigma0_ubound	Optional upper bound for sigma0. Ignored if sigma0_fixed = TRUE.
try	Positive integer. Number of extra optimization tries.
ncores	Positive integer. Number of cores to use.

# Value

Returns an object of class fitdtvarmx which is a list with the following elements:

call Function call.

args List of function arguments.

fun Function used ("FitDTVARMx").

output A fitted OpenMx model.

#### Author(s)

Ivan Jacob Agaloos Pesigan

#### References

Hunter, M. D. (2017). State space modeling in an open source, modular, structural equation modeling environment. *Structural Equation Modeling: A Multidisciplinary Journal*, 25(2), 307–324. doi:10.1080/10705511.2017.1369354

Neale, M. C., Hunter, M. D., Pritikin, J. N., Zahery, M., Brick, T. R., Kirkpatrick, R. M., Estabrook, R., Bates, T. C., Maes, H. H., & Boker, S. M. (2015). OpenMx 2.0: Extended structural equation and statistical modeling. *Psychometrika*, 81(2), 535–549. doi:10.1007/s1133601494358

#### See Also

Other DTVAR Functions: FitDTVARIDMx()

#### **Examples**

```
## Not run:
# Generate data using the simStateSpace package-----
set.seed(42)
sim <- simStateSpace::SimSSMVARFixed(</pre>
 n = 5,
 time = 100,
 mu0 = rep(x = 0, times = 3),
 sigma0_l = t(chol(diag(3))),
 alpha = rep(x = 0, times = 3),
 beta = matrix(
   data = c(
     0.7, 0.5, -0.1,
     0.0, 0.6, 0.4,
     0, 0, 0.5
   ),
   nrow = 3
 ),
 psi_l = t(chol(diag(3)))
)
data <- as.data.frame(sim)</pre>
# Fit the model-------
library(fitDTVARMx)
fit <- FitDTVARMx(</pre>
 data = data,
 observed = c("y1", "y2", "y3"),
 id = "id"
print(fit)
summary(fit)
coef(fit)
vcov(fit)
```

10 print.fitdtvarmx

```
## End(Not run)
```

print.fitdtvaridmx

Print Method for Object of Class fitdtvaridmx

#### **Description**

Print Method for Object of Class fitdtvaridmx

# Usage

```
## S3 method for class 'fitdtvaridmx'
print(x, means = TRUE, ...)
```

#### Arguments

x an object of class fitdtvaridmx.

means Logical. If means = TRUE, return means. Otherwise, the function returns raw

estimates.

... further arguments.

#### Author(s)

Ivan Jacob Agaloos Pesigan

print.fitdtvarmx

Print Method for Object of Class fitdtvarmx

#### **Description**

Print Method for Object of Class fitdtvarmx

#### Usage

```
## S3 method for class 'fitdtvarmx'
print(x, ...)
```

#### **Arguments**

x an object of class fitdtvarmx.

... further arguments.

# Author(s)

Ivan Jacob Agaloos Pesigan

summary.fitdtvaridmx 11

summary.fitdtvaridmx Summary Method for Object of Class fitdtvaridmx

#### **Description**

Summary Method for Object of Class fitdtvaridmx

# Usage

```
## S3 method for class 'fitdtvaridmx'
summary(object, means = TRUE, ...)
```

#### Arguments

object an object of class fitdtvaridmx.

means Logical. If means = TRUE, return means. Otherwise, the function returns raw

estimates.

... further arguments.

#### Author(s)

Ivan Jacob Agaloos Pesigan

summary.fitdtvarmx Summary Method for Object of Class fitdtvarmx

#### **Description**

Summary Method for Object of Class fitdtvarmx

#### Usage

```
## S3 method for class 'fitdtvarmx'
summary(object, ...)
```

#### **Arguments**

object an object of class fitdtvarmx.
... further arguments.

#### Author(s)

Ivan Jacob Agaloos Pesigan

12 vcov.fitdtvarmx

	. علم ع ع	ا ا
VCOV	titatv	aridmx

Sampling Covariance Matrix of the Parameter Estimates

# Description

Sampling Covariance Matrix of the Parameter Estimates

#### Usage

```
## S3 method for class 'fitdtvaridmx'
vcov(object, alpha = FALSE, psi = FALSE, theta = FALSE, ...)
```

#### **Arguments**

object	Object of class fitdtvaridmx.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.
	additional arguments.

#### Value

Returns a list of sampling variance-covariance matrices.

#### Author(s)

Ivan Jacob Agaloos Pesigan

VCOV	fitdtvarmy	

Sampling Covariance Matrix of the Parameter Estimates

# Description

Sampling Covariance Matrix of the Parameter Estimates

#### Usage

```
## S3 method for class 'fitdtvarmx'
vcov(object, alpha = FALSE, psi = FALSE, theta = FALSE, ...)
```

vcov.fitdtvarmx 13

# Arguments

object	Object of class fitdtvarmx.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.
	additional arguments.

# Value

Returns a list of sampling variance-covariance matrices.

# Author(s)

Ivan Jacob Agaloos Pesigan

# **Index**

```
* DTVAR Functions
    FitDTVARIDMx, 3
    FitDTVARMx, 6
* fitDTVARMx
    FitDTVARIDMx, 3
    FitDTVARMx, 6
* fit
    FitDTVARIDMx, 3
    FitDTVARMx, 6
* methods
    coef.fitdtvaridmx, 2
    coef.fitdtvarmx, 2
    print.fitdtvaridmx, 10
    print.fitdtvarmx, 10
    summary.fitdtvaridmx, 11
    summary.fitdtvarmx, 11
    vcov.fitdtvaridmx, 12
    vcov.fitdtvarmx, 12
coef.fitdtvaridmx, 2
coef.fitdtvarmx, 2
FitDTVARIDMx, 3, 9
FitDTVARMx, 5, 6
print.fitdtvaridmx, 10
print.fitdtvarmx, 10
summary.fitdtvaridmx, 11
summary.fitdtvarmx, 11
vcov.fitdtvaridmx, 12
vcov.fitdtvarmx, 12
```