# Package 'fitDTVARMx'

July 5, 2024				
Title Fit The Discrete-Time Vector Autoregressive Model				
<b>Version</b> 0.0.0.9000				
<b>Description</b> Fit the discrete-time vector autoregressive model using the 'OpenMx' package.				
<pre>URL https://github.com/jeksterslab/fitDTVARMx,</pre>				
https://jeksterslab.github.io/fitDTVARMx/				
<pre>BugReports https://github.com/jeksterslab/fitDTVARMx/issues</pre>				
License MIT + file LICENSE				
Encoding UTF-8				
<b>Roxygen</b> list(markdown = TRUE)				
VignetteBuilder knitr				
<b>Depends</b> R ( $>= 3.0.0$ ), OpenMx				
Imports stats				
Suggests knitr, rmarkdown, testthat, simStateSpace				
RoxygenNote 7.3.2				
NeedsCompilation no				
Author Ivan Jacob Agaloos Pesigan [aut, cre, cph] ( <a href="https://orcid.org/0000-0003-4818-8420">https://orcid.org/0000-0003-4818-8420</a> )				
Maintainer Ivan Jacob Agaloos Pesigan <r.jeksterslab@gmail.com></r.jeksterslab@gmail.com>				
Contents				
coef.fitdtvaridmx FitDTVARIDMx print.fitdtvaridmx summary.fitdtvaridmx vcov.fitdtvaridmx				
Index				

2 FitDTVARIDMx

	fitdtvari	dmv
COET.	TILULVALI	UIIIX

Parameter Estimates

#### Description

Parameter Estimates

#### Usage

```
## S3 method for class 'fitdtvaridmx'
coef(object, psi = FALSE, theta = FALSE, ...)
```

#### Arguments

object Object of class fitdtvaridmx.

psi Logical. If psi = TRUE, include estimates of the psi matrix. If psi = FALSE,

exclude estimates of the psi matrix.

theta Logical. If theta = TRUE, include estimates of the theta matrix if available. If

theta = FALSE, exclude estimates of the theta matrix.

... additional arguments.

#### Value

Returns a list of vectors of parameter estimates.

#### Author(s)

Ivan Jacob Agaloos Pesigan

FitDTVARIDMx

Fit First Order Discrete-Time Vector Autoregressive Model by ID

#### **Description**

Fit First Order Discrete-Time Vector Autoregressive Model by ID

#### Usage

```
FitDTVARIDMx(
  data,
  observed,
  id,
  beta_start = NULL,
  beta_lbound = NULL,
  beta_ubound = NULL,
```

FitDTVARIDMx 3

```
psi_diag = TRUE,
 psi_start = NULL,
 psi_lbound = NULL,
 psi_ubound = NULL,
  theta_fixed = TRUE,
  theta_start = NULL,
  theta_lbound = NULL,
  theta_ubound = NULL,
 mu0_fixed = TRUE,
 mu0_start = NULL,
 mu0\_lbound = NULL,
 mu0\_ubound = NULL,
  sigma0_fixed = TRUE,
  sigma0_diag = TRUE,
  sigma0\_start = NULL,
  sigma0_lbound = NULL,
  sigma0_ubound = NULL,
  try = 1000,
 ncores = NULL
)
```

#### **Arguments**

data	Data frame. A data frame object of data for potentially multiple subjects that contain a column of subject ID numbers (i.e., an ID variable), and at least one column of observed values.
observed	Character vector. A vector of character strings of the names of the observed variables in the data.
id	Character string. A character string of the name of the ID variable in the data.
beta_start	Numeric matrix. Optional starting values for beta.
beta_lbound	Numeric matrix. Optional lower bound for beta.
beta_ubound	Numeric matrix. Optional upper bound for beta.
psi_diag	Logical. If psi_diag = TRUE, psi is a diagonal matrix.
psi_start	Numeric matrix. Optional starting values for psi.
psi_lbound	Numeric matrix. Optional lower bound for psi.
psi_ubound	Optional upper bound for psi.
theta_fixed	Logical. If theta_fixed = TRUE, the measurement error matrix theta is fixed to zero. If theta_fixed = FALSE, estimate the diagonal measurement error matrix theta.
theta_start	Optional starting values for theta. Ignored if theta_fixed = TRUE.
theta_lbound	Optional lower bound for theta. Ignored if theta_fixed = TRUE.
theta_ubound	Optional upper bound for theta. Ignored if theta_fixed = TRUE.
mu0_fixed	Logical. If mu0_fixed = TRUE, initial mean vector mu0 is fixed. If mu0_fixed = FALSE, initial mean vector mu0 is estimated.

4 print.fitdtvaridmx

mu0_start	Optional starting values for mu0. If mu0_fixed = TRUE, mu0_start will be used as fixed values. If mu0_fixed = FALSE, mu0_start will be used as starting values.
mu0_lbound	Optional lower bound for mu0. Ignored if mu0_fixed = TRUE.
mu0_ubound	Optional upper bound for mu0. Ignored if mu0_fixed = TRUE.
sigma0_fixed	Logical. If sigma0_fixed = TRUE, initial mean vector sigma0 is fixed. If sigma0_fixed = FALSE, initial mean vector sigma0 is estimated.
sigma0_diag	Logical. If sigma@_diag = TRUE, sigma@ is a diagonal matrix.
sigma0_start	Optional starting values for sigma0. If sigma0_fixed = TRUE, sigma0_start will be used as fixed values. If sigma0_fixed = FALSE, sigma0_start will be used as starting values.
sigma0_lbound	Optional lower bound for sigma0. Ignored if sigma0_fixed = TRUE.
sigma0_ubound	Optional upper bound for sigma0. Ignored if sigma0_fixed = TRUE.
try	Positive integer. Number of extra tries for OpenMx::mxTryHard().

#### Author(s)

ncores

Ivan Jacob Agaloos Pesigan

 $print.fitdtvaridmx \qquad \textit{Print Method for Object of Class} \ fitdtvaridmx$ 

Positive integer. Number of cores to use.

## Description

Print Method for Object of Class fitdtvaridmx

#### Usage

```
## S3 method for class 'fitdtvaridmx'
print(x, means = TRUE, ...)
```

#### **Arguments**

x an object of class fitdtvaridmx.

means Logical. If means = TRUE, return means. Otherwise, the function returns raw

estimates.

... further arguments.

#### Author(s)

Ivan Jacob Agaloos Pesigan

summary.fitdtvaridmx 5

summary.fitdtvaridmx Summary Method for Object of Class fitdtvaridmx

#### **Description**

Summary Method for Object of Class fitdtvaridmx

#### Usage

```
## S3 method for class 'fitdtvaridmx'
summary(object, means = TRUE, ...)
```

#### **Arguments**

object an object of class fitdtvaridmx.

means Logical. If means = TRUE, return means. Otherwise, the function returns raw

estimates.

... further arguments.

#### Author(s)

Ivan Jacob Agaloos Pesigan

vcov.fitdtvaridmx

Sampling Covariance Matrix of the Parameter Estimates

#### Description

Sampling Covariance Matrix of the Parameter Estimates

### Usage

```
## S3 method for class 'fitdtvaridmx'
vcov(object, psi = FALSE, theta = FALSE, ...)
```

#### **Arguments**

-1	Ola: 4 - f - 1	C : 4 d 4 d
obiect	Object of class	fitdtvaridmx.

psi Logical. If psi = TRUE, include estimates of the psi matrix. If psi = FALSE,

exclude estimates of the psi matrix.

theta Logical. If theta = TRUE, include estimates of the theta matrix if available. If

theta = FALSE, exclude estimates of the theta matrix.

... additional arguments.

6 vcov.fitdtvaridmx

#### Value

Returns a list of sampling variance-covariance matrices.

# Author(s)

Ivan Jacob Agaloos Pesigan

# **Index**

```
* Meta-Analysis of VAR Functions
    FitDTVARIDMx, 2
* fit
    FitDTVARIDMx, 2
* metaVAR
    FitDTVARIDMx, 2
*\ methods
    coef.fitdtvaridmx, 2
    print.fitdtvaridmx, 4
    summary.fitdtvaridmx, 5
    vcov.fitdtvaridmx,5
\verb|coef.fitdtvaridmx|, 2|
FitDTVARIDMx, 2
OpenMx::mxTryHard(), 4
print.fitdtvaridmx, 4
summary.fitdtvaridmx, 5
vcov.fitdtvaridmx, 5
```