



Sam Li¹

¹BioLegend



dx.doi.org/10.17504/protocols.io.7aghibw

BioLegend





ABSTRACT

BioLegend MojoSort™ nanobeads work in commonly used separation columns, based on our internal research as well as validation by external testing by academic labs. This simple protocol consists of following the MojoSort™ protocol to label the cells with pre-diluted MojoSort™ reagents and using the columns as indicated by the manufacturer.

Note: Due to the properties of our beads, it may be possible to use far fewer beads that with other commercial suppliers. We recommend a titration to find the best dilution factor. However, as a general rule, dilutions ranging from 1:3 to 1:20 for the Nanobeads can be used. Please contact BioLegend Technical Service (tech@biolegend.com) if further assistance is needed.

EXTERNAL LINK

https://www.biolegend.com/protocols/mojosort-human-anti-pe-nanobeads-column-protocol/4761/

GUIDELINES

MojoSort™ magnetic particles can be used with other commercially available magnetic separators, both free standing magnets and column-based systems. Because MojoSort™ protocols are optimized for the MojoSort™ separator, the protocols may need to be adjusted for other systems. Please contact BioLegend Technical Service (tech@biolegend.com) for more information and guidance. We do not recommend using MojoSort™ particles for BD's IMag™ or Life Technologies' DynaMag™.

MATERIALS

NAME ~	CATALOG # V	VENDOR ~
Human TruStain FcX™	422301	BioLegend
MojoSort™ Buffer	480017	BioLegend
MojoSort™ Human anti-PE Nanobeads	480091	BioLegend
PE-Conjugated Anti-Human Antibody	View	BioLegend

MATERIALS TEXT

Additional reagents:

- -commercially available cell separation columns
- -5 mL polypropylene tubes
- -70 µm cell strainer
 - Prepare cells from your tissue of interest or blood without lysing erythrocytes.
 - In the final wash of your sample preparation, resuspend the cells in MojoSort™ Buffer by adding up to 4 mL in a 5 mL (12 x 75 mm) polypropylene tube.

Note: Keep MojoSort™ Buffer on ice throughout the procedure.

5m

3 Filter the cells with a 70 µm cell strainer, centrifuge at 300xg for 5 minutes, and resuspend in an appropriate volume of MojoSort™ Buffer. Count and adjust the cell concentration to 1 x 10⁸ cells/mL by adding MojoSort™ Buffer.

10m

4 Aliquot 100 μL of cell suspension (10⁷ cells) into a new tube. Add 5 μL of Human TruStain FcX™ (Fc Receptor Blocking Solution), mix well and incubate at room temperature for 10 minutes. Scale up the volume accordingly if separating more cells. For example, add 50 μL of Human TruStain FcX™ for separating 1 x 10⁸ cells in 1 ml of MojoSort™ Buffer. When working with less than 10⁷ cells, use indicated volumes for 10⁷ cells.

15m

Check the recommended usage for flow cytometric staining of the PE-conjugated antibody indicated in the antibody technical datasheet. Calculate the volume to stain 10⁷ cells (or desired amount of cells). **Add the appropriate volume of pre-diluted PE-conjugated antibody** to the cell suspension, mix well and **incubate on ice for 15 minutes**.

Note: For the PE-conjugated antibodies, we recommend to do a titration to determine the optimal concentration.

5m

- $\label{eq:wash the cells by adding MojoSort $^{\mathtt{M}}$ Buffer up to 4 mL. Centrifuge the cells at 300xg for 5 minutes.}$
- 7 Discard the supernatant and resuspend cells in 100uL of MojoSort™ Buffer.

15m

Vortex the anti-PE Nanobeads (to resuspend) at max speed, 5 touches, and prepare the dilutions to test. **Add the appropriate volume pre-diluted anti-PE Nanobeads**. Mix well and **incubate on ice for 15 minutes**. Scale up the volume accordingly if separating more cells. For example, if the volume of pre-diluted Nanobeads for 1x10⁷ cells is 10 µL, add 100 µL of pre-diluted Nanobeads for separating 1 x 10⁸ cells in 1 ml of MojoSort™ Buffer. When working with less than 10⁷ cells, use indicated volumes for 10⁷ cells.

Note: The amount of Nanobeads to use always depends on the frequency of the target, among a few other factors. We recommend to do a titration to determine the optimal concentration.

5m

- 9 Wash the cells by adding MojoSort $^{\mathtt{M}}$ Buffer up to 4 mL. Centrifuge the cells at 300xg for 5 minutes.
- 10 Discard the supernatant.
- Add the appropriate amount of MojoSort™ Buffer and proceed to separation. At least 500 µL is needed for column separation.

 Note: There are several types of commercially available columns, depending on your application. Choose the one that fits best your experiment:

	Max. number of labeled cells	Max. number of total cells	Cell suspension volume	Column rinse volume	Cell wash volume	Elution volume
Small Capacity	1 x 10 ⁷	2 x 10 ⁸	500μL for up to 10 ⁸ cells	1ml	1 ml	1 ml
Medium Capacity	1 x 10 ⁸	2 x 10 ⁹	500µL for up to 10 ⁹ cells	3ml	3 ml	5 ml
Large Capacity	1 x 10 ⁹	2 x 10 ¹⁰	500µL for up to 10 ¹⁰ cells	20-50ml	30 ml	20 ml

Example of magnetic separation	with medium capacity columns:
--------------------------------	-------------------------------

- 12 Place the column in a magnetic separator that fits the column.
- 13 Rinse the column with 3 mL of cell separation buffer.
- 14 Add the labeled cell suspension to the column through a 30 µm filter and collect the fraction containing the unlabeled cells.
- Wash the cells in the column **3 times** with 3 mL of buffer and collect the fraction containing the unlabeled cells. Combine with the collected fraction from step 3. These cells may be useful as controls, to monitor purity/yield, or other purposes.
- Take away the column from the magnet and place it on a tube. Then add 5 mL of buffer and flush out the magnetically labeled fraction with a plunger or supplied device. These are the positively isolated cells of interest; do not discard. To increase the purity of the magnetically labeled fraction repeat the isolation process with a new, freshly prepared column.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited