Table of Contents

Raster Recipes

The Raster classes are in the **geoscript.layer** package.

Raster Properties

Read a Raster from a File

```
File file = new File("src/main/resources/earth.tif")
Format format = Format.getFormat(file)
Raster raster = format.read("earth")
```


Get the Raster's Bounds.

```
Bounds bounds = raster.bounds
println "Bounds: ${bounds}"
```

```
Bounds: (-179.99999999999997,-89.99999999998205,179.99999999996405,90.0,EPSG:4326)
```

Get the Raster's Projection.

```
Projection projection = raster.proj
println "Projection: ${projection}"
```

```
Projection: EPSG:4326
```

Get the Raster's Size.

```
List size = raster.size
println "Size: ${size[0]}x${size[1]}"
```

```
Size: 800x400
```

Get the Raster's number of columns and rows.

```
int cols = raster.cols
int rows = raster.rows
println "Columns: ${cols} Rows: ${rows}"
```

```
Columns: 800 Rows: 400
```

Get the Raster's Bands.

```
List<Band> bands = raster.bands
println "Bands:"
bands.each { Band band ->
    println "  ${band}"
}
```

```
Band:
  RED_BAND
  GREEN_BAND
  BLUE_BAND
```

Get the Raster's block size.

```
List blockSize = raster.blockSize
println "Block size: ${blockSize[0]}x${blockSize[1]}"
```

```
Block size: 800x8
```

Get the Raster's pixel size.

```
List pixelSize = raster.pixelSize
println "Pixel size: ${pixelSize[0]}x${pixelSize[1]}"
```

Pixel size: 0.44999999999995505x0.4499999999999551