CASA Task Reference Manual

CASA Group, eds

 $March\ 30,\ 2016$

Copyright ©2016 AUI

CASA Task Reference Manual.

The CASA Task Reference Manual contains the documentation on the task-based functionality within the system. There are three broad packages:

- General- modules that are of general use for astronomical processing
- \bullet Synthesis modules needed for processing synthesis data
- Utility non-astronomy specific functionality
- Third Party modules that interface to 3rd party packages

Contents

0.1	Tasks	- Module
	0.1.1	accum
	0.1.2	applycal
	0.1.3	asdmsummary
	0.1.4	bandpass
	0.1.5	blcal
	0.1.6	boxit
	0.1.7	browsetable
	0.1.8	calstat
	0.1.9	caltabconvert
	0.1.10	clean
	0.1.11	clearcal
	0.1.12	clearplot
	0.1.13	clearstat
	0.1.14	concat
	0.1.15	conjugatevis
	0.1.16	csvclean
	0.1.17	cvel
	0.1.18	cvel2
	0.1.19	deconvolve
	0.1.20	delmod
	0.1.21	exportasdm
	0.1.22	exportfits
	0.1.23	exportuvfits
	0.1.24	feather
	0.1.25	find
	0.1.26	fixplanets
	0.1.27	fixvis
	0.1.28	flagcmd
	0.1.29	flagdata
	0.1.30	flagmanager
	0.1.31	fluxscale
	0.1.32	ft
	0.1.33	gaincal
	0.1.34	gencal

0.1.35	hanningsmooth	186
0.1.36	8	191
0.1.37	•	195
0.1.38		197
0.1.39		206
0.1.40		214
0.1.41		214
0.1.41		$210 \\ 224$
0.1.42		229
0.1.44	r	233
0.1.44	1	235
0.1.46	1 1	237 237
0.1.40 $0.1.47$	•	231 244
0.1.47	-	244 251
0.1.48	r	251 253
	P	
0.1.50	1 0	255
0.1.51	1	257
0.1.52	importation to the term of the	259
0.1.53	1	261
0.1.54		265
0.1.55		269
0.1.56		271
0.1.57		280
0.1.58		286
0.1.59	8	294
0.1.60		298
0.1.61		301
0.1.62		306
0.1.63		311
0.1.64	listcal	314
0.1.65	listhistory	319
0.1.66	listfits	320
0.1.67	listobs	321
0.1.68	listpartition	326
0.1.69	listsdm	329
0.1.70	listvis	331
0.1.71	makemask	337
0.1.72	mosaic	344
0.1.73	msview	352
0.1.74	mstransform	355
0.1.75	msuvbin	368
0.1.76		372
0.1.77	~	374
0.1.78	1	380
0.1.79	1	382
0.1.80	1 1	386
3.1.00	P	

0.1.81	plotms				 							391
0.1.82	plotuv				 							402
0.1.83	plot weather $\ .$ $\ .$				 							406
0.1.84	partition				 							408
0.1.85	polcal				 							415
0.1.86	$\operatorname{predictcomp}$				 							422
0.1.87	$\mathrm{impv}\ .\ .\ .\ .\ .\ .$				 							426
0.1.88	$\operatorname{rmfit} \ldots \ldots$				 							431
0.1.89	rmtables				 							436
0.1.90	sdaverage				 							437
0.1.91	sdbaseline				 							443
0.1.92	sdbaseline 2				 							
0.1.93	$\operatorname{sdcal}.....$				 							459
0.1.94	$sdcal2 \dots$				 							467
0.1.95	$sdcoadd \dots$				 							477
0.1.96	$\operatorname{sdfit} \ \ldots \ \ldots \ .$				 							480
0.1.97	sdflag				 							488
0.1.98	sdflagmanager				 							495
0.1.99	$sdgrid \dots$				 							497
0.1.100	sdimaging				 							503
	sdimprocess											510
0.1.102	sdlist				 							514
0.1.103	$sdmath \dots$				 							516
0.1.104												522
	$sdreduce \ . \ . \ .$											532
0.1.106	$sdsave \dots \dots$				 							543
0.1.107	sdscale				 							548
0.1.108	$sdstat \dots$				 							551
	setjy											559
0.1.110	simalma				 							570
0.1.111	simobserve \dots				 							576
0.1.112	simanalyze											583
-	$slsearch \dots$											588
0.1.114	smoothcal				 							591
0.1.115	specfit				 							593
0.1.116	specsmooth				 							603
	splattotable				 							609
0.1.118	split				 							611
0.1.119	spxfit				 							617
0.1.120	statwt				 							623
0.1.121	$tclean \ldots \ldots$				 							629
0.1.122	testconcat				 							632
0.1.123	tsdbaseline				 							634
0.1.124	$\operatorname{tsdcal} \ \ldots \ \ldots$				 							643
0.1.125	$\operatorname{tsdfit} \ldots \ldots$				 							651
0 1 126	tedemooth											657

$0.1.127\mathrm{uvcontsub}$												661
$0.1.128\mathrm{uv}$ contsub3												666
$0.1.129\mathrm{uvmodelfit}$												670
$0.1.130\mathrm{uvsub}$												675
$0.1.131 \mathrm{viewer} \ldots \ldots$												677
$0.1.132 \text{wvrgcal} \dots$												680
$0.1.133\mathrm{virtual}$ concat .												684
$0.1.134 \text{vishead} \dots$												687
$0.1.135 \mathrm{visstat} \ldots \ldots$												690
$0.1.136 \mathrm{visstat2} \ldots .$												695
0.1.137 widebandpbcor												701
0.1.138 widefield												706
Tasks-Module.html												

0.1 Tasks - Module

CASA Tasks

accum-task.html

0.1.1 accum

Requires:

Synopsis

Accumulate incremental calibration solutions into a calibration table

Description

Accum will interpolate and extrapolate a calibration table onto a new table that has a regularly-space time grid.

The first run of accum defines the time grid and fills this table with the results from the input table.

Subsequent use of accum will combine additional calibration tables onto the same grid of the initial accum table to obtain an output accum table. See below for concrete examples.

Accum tables are similar to CL tables in AIPS Incremental tables are similar to SN tables in AIPS

Arguments

Inputs vis Name of input visibility file allowed: string Default: Input cumulative calibration table; use " on first run tablein allowed: string Default: incrtable Input incremental calibration table to add allowed: string Default: caltable Output (cumulative) calibration table allowed: string Default: field List of field names to process from tablein allowed: stringArrayDefault: calfield List of field names to use from incrtable. allowed: stringArray Default: interp Interpolation mode to use for resampling incrtable solutions allowed: string Default: linear accumtime Time-interval when create cumulative table allowed: anv

> variant 1.0Spectral window combinations to apply

> > intArray

-1

Default:

allowed:

Default:

Returns

spwmap

void

Example

Accum will interpolate and extrapolate a temporal calibration table onto a new table that has a regularly-space time grid.

The first run of accum defines the time grid and fills this table with the results from the input table.

Subsequent use of accum will combine additional calibration tables onto the same grid of the initial accum table to obtain an output accum table. See below for a concrete example.

Keyword arguments:

```
vis -- Name of input visibility file
        default: none. example: vis='ngc5921.ms'
tablein -- Input cumulative calibration table.
       default: '' means none
        On first execution of accum, tablein=''
        and accumtime is used to generate tablein with
        the specified time gridding.
accumtime -- The time separation when making tablein.
        default: 1.0 (1 second). This time should not be
        less than the visibility sampling time, but should
        be less than about 30% of a typical scan length.
incrtable -- The calibration data to be interpolated onto the
        tablein file.
        default: ''. Must be specified
caltable -- The output cumulated calibration file.
        default: '' means use tablein as the output file
field -- Select field(s) from tablein to process.
         ['go listobs' to obtain the list id's or names]
       default: ''= all fields
       If field string is a non-negative integer, it is assumed to
          be a field index otherwise, it is assumed to be a field name
       field='0~2'; field ids 0,1,2
       field='0,4,5~7'; field ids 0,4,5,6,7
       field='3C286,3C295'; field named 3C286 and 3C295
       field = '3,4C*'; field id 3, all names starting with 4C
calfield -- Select field(s) from incrtable to process.
       default: '' = all fields
interp -- Interpolation type (in time[,freq]) to use for each gaintable.
           When frequency interpolation is relevant (B, Df, Xf),
           separate time-dependent and freq-dependent interp
           types with a comma (freq _after_ the comma).
           Specifications for frequency are ignored when the
           calibration table has no channel-dependence.
          Time-dependent interp options ending in 'PD' enable a
           "phase delay" correction per spw for non-channel-dependent
           calibration types.
          For multi-obsId datasets, 'perobs' can be appended to
```

```
the time-dependent interpolation specification to
           enforce obsId boundaries when interpolating in time.
           default: '' --> 'linear, linear' for all gaintable(s)
                                       (in time, freq-dep will be
           example: interp='nearest'
                                        linear, if relevant)
                    interp='linear,cubic' (linear in time, cubic
                                            in freq)
                    interp='linearperobs,spline' (linear in time
                                                  per obsId,
                                                  spline in freq)
                    interp=',spline' (spline in freq; linear in
                                       time by default)
                    interp=['nearest,spline','linear'] (for multiple gaintables)
           Options: Time: 'nearest', 'linear'
                    Freq: 'nearest', 'linear', 'cubic', 'spline'
spwmap -- Spectral windows combinations to form for gaintable(s)
       default: [] (apply solutions from each spw to that spw only)
       Example: spwmap=[0,0,1,1] means apply the caltable solutions
                 from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                 spwmap=[[0,0,1,1],[0,1,0,1]] (for multiple gaintables)
async -- Run task in a separate process
        default: False; example: async=True
Examples:
  Create an accum table with 10-sec sampling, filling it with the calibration
     in 'first_cal' with the desired interpolation.
     taskname = 'accum'
        default()
       vis = 'mydata.ms'
        tablein = ''
        accumtime = 10
        incrtable = 'first_cal'
        caltable = 'accum1_cal'
        accum()
  If you plot 'accum1_cal' with plotcal, you can see how the incrtable was
        interpolated.
  Continue accumulating calibrations in accum1_cal from 'second_cal'
     taskname = 'accum'
        default()
       vis = 'mydata.ms'
       tablein = 'accum1_cal'
```

```
incrtable = 'second_cal'
caltable = 'accum1_cal'
accum()
```

applycal-task.html

0.1.2 applycal

Requires:

Synopsis

Apply calibrations solutions(s) to data

Description

Applycal reads the specified gain calibration tables, applies them to the (raw) data column (with the specified selection), and writes the calibrated results into the corrected column. This is done in one step, so all available calibration must be specified. Applycal will overwrite existing corrected data. Standard data selection is supported. See help par.selectdata for more information.

One or more calibration tables (both temporal, frequency, polarization calibrations) can be specified in the gaintable parameter. The calibration values associated with a restricted list of fields can also be selected for each table.

See task accum for instructions on forming calibration incrementally. See task split for saving corrected data in another visibility file.

Arguments

Inputs

callib

vis Name of input visibility file

allowed: string

Default:

field Select field using field id(s) or field name(s)

allowed: string

Default:

spw Select spectral window/channels

allowed: string

Default:

intent Select observing intent

allowed: string

Default:

selectdata Other data selection parameters

allowed: bool Default: True

timerange Select data based on time range

allowed: string

Default:

uvrange Select data within uvrange (default units meters)

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: string

Default:

scan Scan number range

allowed: string

Default:

observation Select by observation ID(s)

allowed: any Default: variant

msselect Optional complex data selection (ignore for now)

allowed: string

Default:

docallib Use callib or traditional cal apply parameters

allowed: bool Default: False

Cal Library filename

allowed: string

Default:

gaintable Gain calibration table(s) to apply on the fly

allowed: stringArray

Default:

gainfield Select a subset of calibrators from gaintable(s)

allowed: stringArray

Default: 12

interp type in time[,freq], per gaintable. de-

fault==linear,linear

allowed: stringArray

Default:

spwmap Spectral windows combinations to form for gaintables(s)

allowed: intArray

Default:

calwt Calibrate data weights per gaintable.

Example

Applycal reads the specified gain calibration tables or cal library, applies them to the (raw) data column (with the specified selection), and writes the calibrated results into the corrected column. This is done in one step, so all available calibration tables must be specified.

Applycal will overwrite existing corrected data, and will flag data for which there is no calibration available.

In the traditional interface (docallib=False), all calibration tables (both temporal, frequency, polarization calibrations) are specified in the gaintable parameter. The calibration values associated with a restricted list of fields can also be selected for each table in gainfield.

As of CASA v4.2, docallib=True provides specification of an ensemble of calibration tables and directives via a cal library file.

See task accum for instructions on forming calibration incrementally. See task split for copying out any portion of the data and selected columns to a new visibility file.

```
Keyword arguments:
```

```
vis -- Name of input visibility file
          default: < none>; example: vis='ngc5921.ms'
```

--- Data Selection: the data to which the calibration will be applied (see help par.selectdata for more detailed information)

```
field -- Select field id(s) or field name(s) to apply calibration.
        [run listobs to obtain the list id's or names]
        default: ''=all fields
        If field's string is an integer >=0, it is assumed to be an index
            otherwise, it is assumed to be a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5~7'; field ids 0,4,5,6,7
        field='3C286,3C295'; fields named 3C286 and 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
```

```
type 'help par.selection' for more examples.
      spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
      spw='<2'; spectral windows less than 2 (i.e. 0,1)
      spw='0:5~61'; spw 0, channels 5 to 61, INCLUSIVE
      spw='*:5~61'; all spw with channels 5 to 62
      spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
      spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
      spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                NOTE ';' to separate channel selections
      spw='0:0~10^2,1:20~30^5'; spw 0, channels 0,2,4,6,8,10,
            spw 1, channels 20,25,30
intent -- Select observing intent
          default: '' (no selection by intent)
          intent='*BANDPASS*' (selects data labelled with
                                BANDPASS intent)
selectdata -- Other data selection parameters
       default: True
timerange -- Select data based on time range:
       default = '' (all); examples,
       timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
       Note: if YYYY/MM/DD is missing, date defaults to first day in
             data set
       timerange='09:14:0~09:54:0' picks 40 min on first day
       timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
       timerange='09:44:00' data within one integration of time
       timerange='>10:24:00' data after this time
uvrange -- Select data within uvrange (default units meters)
       default: '' (all); example:
       uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
       uvrange='>4klambda';uvranges greater than 4 kilolambda
antenna -- Select data based on antenna/baseline
       default: '' (all)
       If antenna's string is an integer >=0, it is taken to be an index
         otherwise, it is assumed to be an antenna name
       antenna='5&6'; baseline between antenna index 5 and index 6.
       antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
       antenna='5\&6;7\&8'; baseline 5-6 and 7-8
       antenna='5'; all baselines with antenna index 5
       antenna='05'; all baselines with antenna name 05--vla antenna 5.
       antenna='5,6,10'; all baselines with antennas 5,6 and 10
scan -- Scan number range
observation -- Select by observation ID(s).
                default: '' = all
                example: '0~3,6'
msselect -- Optional complex data selection (ignore for now)
```

```
--- Calibration files to apply
docallib -- Control means of specifying the caltables:
        default: False ==> Use gaintable, gainfield, interp, spwmap, calwt
                 If True, specify a file containing cal library in callib
callib -- If docallib=True, specify a file containing cal
           library directives
gaintable -- Gain calibration table(s) to apply
        default: '' (none);
        examples: gaintable='ngc5921.gcal'
            gaintable=['n5921.ampcal', 'n5921.phcal', 'n5921.bpass']
        All gain table types: 'G', GSPLINE, 'T', 'B', 'BPOLY', 'D's'
            can be applied.
gainfield -- Select a subset of calibrators from each gaintable
        default:'' ==> all sources in table;
        'nearest' ==> nearest (on sky) available field in table
        otherwise, same syntax as field
        example: gainfield='0~3'
                 gainfield=['0~3','4~6'] (for multiple gaintables)
interp -- Interpolation type (in time[,freq]) to use for each gaintable.
         When frequency interpolation is relevant (bandpass solutions,
         frequency-dependent polcal solutions, ALMA Tsys)
         separate time-dependent and freq-dependent interp
         types with a comma (freq _after_ the comma).
         Specifications for frequency are ignored when the
         calibration table has no channel-dependence.
         Time-dependent interp options ending in 'PD' enable a
         "phase delay" correction per spw for non-channel-dependent
         calibration types.
         For multi-obsId datasets, 'perobs' can be appended to
         the time-dependent interpolation specification to
         enforce obsId boundaries when interpolating in time.
         Add 'flag' to the freq-dependent interpolation options
         to enforce channel-dependent flagging (rather than
         interpolation/extrapolation).
         default: '' --> 'linear, linear' for all gaintable(s)
         example: interp='nearest'
                                     (in time, freq-dep will be
                                      linear, if relevant)
                  interp='linear,cubic' (linear in time, cubic
                                          in freq)
                  interp='linearperobs, splineflag' (linear in time
                                                   per obsId,
                                                   spline in
                                                   freq with
                                                   channelized
                                                   flagging)
                  interp=',spline' (spline in freq; linear in
```

```
time by default)
                  interp=['nearest,spline','linear'] (for multiple gaintables)
         Options: Time: 'nearest', 'linear', 'nearestPD', 'linearPD'
                  Freq: 'nearest', 'linear', 'cubic', 'spline',
                        'nearestflag', 'linearflag', 'cubicflag', 'splineflag',
spwmap -- Spectral windows combinations to form for gaintable(s)
        default: [] (apply solutions from each spw to that spw only)
        Example: spwmap=[0,0,1,1] means apply the caltable solutions
                  from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                  spwmap=[[0,0,1,1],[0,1,0,1]] (for multiple gaintables)
   Complicated example:
     gaintable=['tab1','tab2','tab3']
     gainfield='3C286'
     interp=['linear', 'nearest']
     spwmap=[[],[0,0,2]]
     This means: apply 3 cal tables, selecting only solutions for 3C286
     from tab1 (but all fields from tab2 and tab3, indicated by
     no gainfield entry for these files). Linear interpolation
     (in time) will be used for 'tab1' and 'tab3' (default); 'tab2' will
     use nearest. For the 'tab2', the calibration spws map
     will be mapped to the data spws according to 0->0, 0->1, 2->2.
     (I.e., for data spw=0 and 2, the spw mapping is one to one,
     but data spw 1 will be calibrated by solutions from spw 0.)
parang -- If True, apply the parallactic angle correction. FOR ANY
       POLARIZATION CALIBRATION AND IMAGING, parang = True
        default: False
calwt -- Calibrate weights along with data for each gaintable
        default: True (for all specified gaintables)
        examples: calwt=False (for all specified gaintables)
                  calwt=[True,False,True] (specified per gaintable)
applymode -- Calibration apply mode:
        ''='calflag' (default) calibrate data and apply flags from solutions
        'trial' report on flags from solutions, dataset entirely unchanged
        'flagonly' apply flags from solutions only, data not calibrated
        'calonly' calibrate data only, flags from solutions NOT
             applied (use with extreme caution!)
        'calflagstrict' or 'flagonlystrict' same as above
             except flag spws for which calibration is
             unavailable in one or more tables (instead of
             allowing them to pass uncalibrated and
             unflagged)
```

 asd m summary-task.html

0.1.3 asdmsummary

Requires:

Synopsis

Summarized description of an ASDM dataset.

Description

Given an ASDM directory, this task will print informations about the content of the dataset contained in that directory (down to the level of a subscan).

Arguments

Inputs		
asdm	Name of in	put ASDM directory
	allowed:	string
	Default:	-

Returns

void

Example

The asdmsummary task prints to the CASA log a description of the content of an SDM dataset.

Example:

```
asdmsummary(sdm='10C-119_sb3070258_1.55628.42186299768')
```

Prints information about the requested ASDM dataset to the CASA logger.

Keyword argument:

asdm -- Name of input ASDM directory. example: sdm='10C-119_sb3070258_1.55628.42186299768' bandpass-task.html

0.1.4 bandpass

Requires:

Synopsis

Calculates a bandpass calibration solution

Description

Determines the amplitude and phase as a function of frequency for each spectral window containing more than one channel. Strong sources (or many observations of moderately strong sources) are needed to obtain accurate bandpass functions. The two solution choices are: Individual antenna/based channel solutions 'B'; and a polynomial fit over the channels 'BPOLY'. The 'B' solutions can determined at any specified time interval, and is recommended in most applications.

Arguments

Inputs

vis Name of input visibility file

allowed: string

Default:

caltable Name of output gain calibration table

allowed: string

Default:

field Select field using field id(s) or field name(s)

allowed: string

Default:

spw Select spectral window/channels

allowed: string

Default:

intent Select observing intent

allowed: string

Default:

selectdata Other data selection parameters

allowed: bool Default: True

timerange Select data based on time range

allowed: string

Default:

uvrange Select data within uvrange (default units meters)

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: string

Default:

scan Scan number range

allowed: string

Default:

observation Select by observation ID(s)

allowed: any
Default: variant

msselect Optional complex data selection (ignore for now)

allowed: string

Default:

solint Solution interval in time[,freq]

allowed: any
Default: variant inf

combine Data axes which to combine for solve (obs, scan, spw,

and/or field)

allowed: string
Default: scan

refant Reference antenna name(s)

allowed: string

Default:

minblperant Minimum baselines _per antenna_ required for solve

allowed: int Default: 4

minsnr Reject solutions below this SNR (only applies for band-

type = B

allowed: double Default: 3.0

Example

Determines the amplitude and phase as a function of frequency for each spectral window containing more than one channel. Strong sources (or many observations of moderately strong sources) are needed to obtain accurate bandpass functions. The two solution choices are: Individual antenna/based channel solutions 'B'; and a polynomial fit over the channels 'BPOLY'. The 'B' solutions can determined at any specified time interval, and is recommended if each channel has good signal-to-noise. Other, 'BPOLY' is recommended.

```
Keyword arguments:
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
caltable -- Name of output bandpass calibration table
        default: none; example: caltable='ngc5921.bcal'
--- Data Selection (see help par.selectdata for more detailed information)
field -- Select field using field id(s) or field name(s).
           [run listobs to obtain the list id's or names]
        default: ''=all fields
        If field string is a non-negative integer, it is assumed a field index
          otherwise, it is assumed a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5~7'; field ids 0,4,5,6,7
        field='3C286,3C295'; field named 3C286 adn 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
        default: ''=all spectral windows and channels
        spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
        spw='<2'; spectral windows less than 2 (i.e. 0,1)
        spw='0:5~61'; spw 0, channels 5 to 61
        spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
        spw='0~2:2:6'; spw 0,1,2 with channels 2 through 6 in each.
        spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                  NOTE: ';' to separate channel selections
        spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                 spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
intent -- Select observing intent
          default: '' (no selection by intent)
          intent='*BANDPASS*' (selects data labelled with
                                BANDPASS intent)
```

```
selectdata -- Other data selection parameters
        default: True
timerange -- Select data based on time range:
        default = '' (all); examples,
        timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
        Note: if YYYY/MM/DD is missing dat defaults to first day in data set
        timerange='09:14:0~09:54:0' picks 40 min on first day
        timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
        timerange='09:44:00' data within one integration of time
        timerange='>10:24:00' data after this time
uvrange -- Select data within uvrange (default meters)
       default: '' (all); example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
antenna -- Select data based on antenna/baseline
        default: '' (all)
        If antenna string is a non-negative integer, it is assumed an antenna index
          otherwise, it is assumed as an antenna name
        antenna='5&6'; baseline between antenna index 5 and index 6.
        antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8'; baseline 5-6 and 7-8
        antenna='5'; all baselines with antenna 5
        antenna='5,6,10'; all baselines with antennas 5, 6 and 10
 scan -- Select data based on scan number - New, under developement
         default: '' (all); example: scan='>3'
 observation -- Observation ID(s).
                default: '' = all
                example: '0~2,4'
 msselect -- Optional complex data selection (ignore for now)
 --- Solution parameters
 solint -- Solution interval in time (units optional), and (optionally)
             in frequency. Frequency pre-averaging can be
             specified after a comma in units of channels or Hz.
             If nothing is specified for frequency, no freq pre-averaging
             will be done.
 default: 'inf' ("infinite, up to boundaries controlled by combine,
                 with no pre-averaging in frequency)
        Options for time: 'inf' ("infinite), 'int' (per integration), any float
                 or integer value with or without units
        Options for freq: an integer with 'ch' suffix will enforce
                          pre-averaging by the specified number
                          of channels.
                          a numeric value suffixed with frequency
                          units (e.g., 'Hz', 'kHz', 'MHz') will enforce
                          pre-averaging by an integral number of
```

```
examples: solint='1min'; solint='60s', solint=60 --> 1 minute
                 solint='0s'; solint=0; solint='int' --> per integration
                 solint='-1s'; solint='inf' --> ~infinite, up to boundaries
                 enforced by combine
                 solint='inf,8Mhz' --> ~infinite in time, with
                                           8MHz pre-average in freq
                 solint='int,32ch' --> per-integration in time,
                                           with 32-channel pre-average
                                           in freq
combine -- Data axes to combine for solving
       default: 'scan' --> solutions will break at obs, field, and spw
               boundaries but may extend over multiple scans
               (per obs, field and spw) up to solint.
       Options: '', 'obs', 'scan', 'spw', field', or any comma-separated
                combination in a single string
       example: combine='scan,spw' --> extend solutions over scan boundaries
                (up to the solint), and combine spws for solving
refant -- Reference antenna name(s); a prioritized list may be specified
       default: '' (no reference antenna)
         example: refant='13' (antenna with index 13)
                  refant='VA04' (VLA antenna #4)
                  refant='EA02,EA23,EA13' (EVLA antenna EA02, use
                         EA23 and EA13 as alternates if/when EA02
                         drops out)
       Use 'go listobs' for antenna listing
minblperant -- Minimum number of baselines required per antenna for each solve
             Antennas with fewer baaselines are excluded from solutions. Amplitude
             solutions with fewer than 4 baselines, and phase solutions with fewer
             than 3 baselines are only trivially constrained, and are no better
             than baseline-based solutions.
             default: 4
             example: minblperant=10 => Antennas participating on 10 or more
                      baselines are included in the solve
minsnr -- Reject solutions below this SNR (only applies for bandtype = B)
       default: 3.0
solnorm -- Normalize bandpass amplitudes and phase for each
        spw, pol, ant, and timestamp
        default: False (no normalization)
bandtype -- Type of bandpass solution (B or BPOLY)
        default: 'B'; example: bandtype='BPOLY'
        'B' does a channel by channel solution for each
            specified spw.
        'BPOLY' is somewhat experimental. It will fit an
            nth order polynomial for the amplitude and phase
```

channels amounting to no more than the

specified bandwidth

```
as a function of frequency. Only one fit is made
             for all specified spw, and edge channels should be
             omitted.
         Use taskname=plotcal in order to compare the results from
             B and BPOLY.
 fillgaps -- Fill flagged solution channels by interpolation
        default: 0 (don't interpolate)
         example: fillgaps=3 (interpolate gaps 3 channels wide and narrower)
 degamp -- Polynomial degree for BPOLY amplitude solution
         default: 3; example: degamp=2
 degphase -- Polynomial degree for BPOLY phase solution
        default: 3; example: degphase=2
 visnorm -- Normalize data prior to BPOLY solution
        default: False; example: visnorm=True
 maskcenter -- Number of channels to avoid in center of each band
         default: 0; example: maskcenter=5 (BPOLY only)
 maskedge -- Fraction of channels to avoid at each band edge (in %)
        default: 5; example: maskedge=3 (BPOLY only)
 append -- Append solutions to the (existing) table. Appended solutions
            must be derived from the same MS as the existing
            caltable, and solution spws must have the same
            meta-info (according to spw selection and solint)
            or be non-overlapping.
         default: False; overwrite existing table or make new table
--- Other calibrations to apply on the fly before determining bandpass solution
docallib -- Control means of specifying the caltables:
         default: False ==> Use gaintable,gainfield,interp,spwmap,calwt
                  If True, specify a file containing cal library in callib
callib -- If docallib=True, specify a file containing cal
            library directives
gaintable -- Gain calibration table(s) to apply
         default: '' (none);
         examples: gaintable='ngc5921.gcal'
                   gaintable=['ngc5921.ampcal', 'ngc5921.phcal']
gainfield -- Select a subset of calibrators from gaintable(s)
         default:'' ==> all sources in table;
         'nearest' ==> nearest (on sky) available field in table
         otherwise, same syntax as field
         example: gainfield='0~3'
                  gainfield=['0~3','4~6']
interp -- Interpolation type (in time[,freq]) to use for each gaintable.
          When frequency interpolation is relevant (B, Df, Xf),
```

separate time-dependent and freq-dependent interp

```
types with a comma (freq _after_ the comma).
         Specifications for frequency are ignored when the
          calibration table has no channel-dependence.
         Time-dependent interp options ending in 'PD' enable a
          "phase delay" correction per spw for non-channel-dependent
          calibration types.
         For multi-obsId datasets, 'perobs' can be appended to
         the time-dependent interpolation specification to
          enforce obsId boundaries when interpolating in time.
         default: '' --> 'linear, linear' for all gaintable(s)
          example: interp='nearest'
                                      (in time, freq-dep will be
                                       linear, if relevant)
                   interp='linear, cubic' (linear in time, cubic
                                           in freq)
                   interp='linearperobs,spline' (linear in time
                                                 per obsId,
                                                 spline in freq)
                   interp=',spline' (spline in freq; linear in
                                      time by default)
                   interp=['nearest,spline','linear'] (for multiple gaintables)
          Options: Time: 'nearest', 'linear'
                   Freq: 'nearest', 'linear', 'cubic', 'spline'
spwmap -- Spectral windows combinations to form for gaintable(s)
         default: [] (apply solutions from each spw to that spw only)
          Example: spwmap=[0,0,1,1] means apply the caltable solutions
                    from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                    spwmap=[[0,0,1,1],[0,1,0,1]]
parang -- If True, apply the parallactic angle correction (required
         for polarization calibration)
         default: False
```

blcal-task.html
0.1.5 blcal
Requires:
Synopsis Calculate a baseline-based calibration solution (gain or bandpass)
Description

Arguments

Inputs vis Name of input visibility file

> allowed: string

Default:

caltable Name of output gain calibration table

> allowed: string

Default:

field Select field using field id(s) or field name(s)

> allowed: string

Default:

Select spectral window/channels spw

> allowed: string

Default:

intent Select observing intent

> allowed: string

Default:

selectdata Other data selection parameters

> allowed: bool Default: True

Select data based on time range timerange

> allowed: string

Default:

uvrange Select data within uvrange (default units meters)

> allowed: any Default: variant

Select data based on antenna/baseline antenna

> allowed: string

Default:

Scan number range scan

> allowed: string

Default:

observation Select by observation ID(s)

> allowed: any Default: variant

msselect Optional complex data selection (ignore for now)

> allowed: string

Default:

solint Solution interval

freqdep

allowed: any

Default: variant inf

combine Data axes which to combine for solve (obs, scan, spw,

and/or field)

allowed: string Default: scan

Solve for frequency dependent solutions

allowed: bool Default:

False calmode

Type of solution" ('ap', 'p', 'a')

allowed: string Default: ap

solnorm Normalize average solution amplitudes to 1.0

> allowed: bool Default: False

gaintable Gain calibration table(s) to apply on the fly

Example

This task determines a baseline by baseline gain (time) or bandpass (freq) for all baseline pairs in the data set. For the usual antenna-based calibration of interferometric data, this task gaincal is recommended, even with only one to three baselines. For arrays with closure errors, use blcal

```
Keyword arguments:
vis -- Name of input visibility file
default: none; example: vis='ngc5921.ms'
caltable -- Name of output Gain calibration table
default: none; example: caltable='ngc5921.gcal'
       --- Data Selection (see help par.selectdata for more detailed information)
        field -- Select field using field id(s) or field name(s).
                  [run listobs to obtain the list id's or names]
               default: ''=all fields
               If field string is a non-negative integer, it is assumed a field index
                 otherwise, it is assumed a field name
               field='0~2'; field ids 0,1,2
               field='0,4,5~7'; field ids 0,4,5,6,7
               field='3C286,3C295'; field named 3C286 adn 3C295
               field = '3,4C*'; field id 3, all names starting with 4C
        spw -- Select spectral window/channels
               default: ''=all spectral windows and channels
               spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
               spw='<2'; spectral windows less than 2 (i.e. 0,1)
               spw='0:5~61'; spw 0, channels 5 to 61
               spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
               spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
               spw='0:0^{-}10;15^{-}60'; spectral window 0 with channels 0-10,15-60
               spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                        spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
        intent -- Select observing intent
                  default: '' (no selection by intent)
                  intent='*BANDPASS*' (selects data labelled with
                                        BANDPASS intent)
        selectdata -- Other data selection parameters
               default: True
        timerange -- Select data based on time range:
               default = '' (all); examples,
               timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
```

```
timerange='09:14:0~09:54:0' picks 40 min on first day
       timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
       timerange='09:44:00' data within one integration of time
       timerange='>10:24:00' data after this time
uvrange -- Select data within uvrange (default units kilo-lambda)
      default: '' (all); example:
       uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
      uvrange='>4klambda';uvranges greater than 4 kilo lambda
      uvrange='0~1000km'; uvrange in kilometers
antenna -- Select data based on antenna/baseline
      default: ', (all)
       If antenna string is a non-negative integer, it is assumed an antenna index
         otherwise, it is assumed as an antenna name
       antenna='5&6'; baseline between antenna index 5 and index 6.
       antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
       antenna='5&6;7&8'; baseline 5-6 and 7-8
       antenna='5'; all baselines with antenna 5
       antenna='5,6,10'; all baselines with antennas 5 and 6
scan -- Scan number range - New, under developement
observation -- Observation ID(s).
              default: '' = all
               example: '0~2,4'
msselect -- Optional complex data selection (ignore for now)
solint -- Solution interval (units optional)
      default: 'inf' ("infinite, up to boundaries controlled by combine);
      Options: 'inf' ("infinite), 'int' (per integration), any float
               or integer value with or without units
      examples: solint='1min'; solint='60s', solint=60 --> 1 minute
                solint='0s'; solint=0; solint='int' --> per integration
                solint-'-1s'; solint='inf' --> ~infinite, up to boundaries
                enforced by combine
combine -- Data axes to combine for solving
      default: 'scan' --> solutions will break at obs, field, and spw boundaries,
                but may extend over multiple scans (per obs, field, and spw) up
                to solint.
      Options: '', 'obs', 'scan', 'spw', field', or any comma-separated
                combination in a single string
      example: combine='scan,spw' --> extend solutions over scan boundaries
               (up to the solint), and combine spws for solving
freqdep -- Solve for frequency dependent solutions
       default: False (gain; True=bandpass); example: freqdep=True
calmode -- Type of solution
       default: 'ap' (amp and phase); example: calmode='p'
```

Note: if YYYY/MM/DD is missing dat defaults to first day in data set

Options: 'p','a','ap'

```
normalization of amplitudes (only). For freqdep=T, each baseline
                   solution spectrum is separately normalized by its (complex) mean.
               default: False (no normalization)
        gaintable -- Gain calibration table(s) to apply
               default: '' (none);
               examples: gaintable='ngc5921.gcal'
                         gaintable=['ngc5921.ampcal', 'ngc5921.phcal']
        gainfield -- Select a subset of calibrators from gaintable(s)
               default:'' ==> all sources in table;
               'nearest' ==> nearest (on sky) available field in table
               otherwise, same syntax as field
               example: gainfield='0~3'
                        gainfield=['0~3','4~6']
        interp -- Interpolation type (in time[,freq]) to use for each gaintable.
                 When frequency interpolation is relevant (B, Df, Xf),
                 separate time-dependent and freq-dependent interp
                 types with a comma (freq _after_ the comma).
                 Specifications for frequency are ignored when the
                 calibration table has no channel-dependence.
                 Time-dependent interp options ending in 'PD' enable a
                 "phase delay" correction per spw for non-channel-dependent
                 calibration types.
                 For multi-obsId datasets, 'perobs' can be appended to
                 the time-dependent interpolation specification to
                 enforce obsId boundaries when interpolating in time.
                 default: '' --> 'linear, linear' for all gaintable(s)
                 example: interp='nearest'
                                             (in time, freq-dep will be
                                              linear, if relevant)
                          interp='linear,cubic' (linear in time, cubic
                                                  in freq)
                          interp='linearperobs, spline' (linear in time
                                                        per obsId,
                                                        spline in freq)
                          interp=',spline'
                                            (spline in freq; linear in
                                             time by default)
                          interp=['nearest,spline','linear'] (for multiple gaintables)
                 Options: Time: 'nearest', 'linear'
                          Freq: 'nearest', 'linear', 'cubic', 'spline'
spwmap -- Spectral windows combinations to form for gaintable(s)
               default: [] (apply solutions from each spw to that spw only)
               Example: spwmap=[0,0,1,1] means apply the caltable solutions
                          from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                          spwmap=[[0,0,1,1],[0,1,0,1]]
       parang -- If True, apply the parallactic angle correction (required
```

solnorm -- Normalize solutions. For freqdep=F, this is a global (per-spw)

for polarization calibration) default: False

boxit-task.html

0.1.6 boxit

Requires:

Synopsis

Box regions in image above given threshold value.

Description

Returns a list of boxes, one for each contiguous set of pixels above the threshold value. If given "regionfile", outputs boxes in regionfile+'.rgn'

Arguments

Inputs imagename Name of image to three

agename Name of image to threshold allowed: string

Default:

regionfile Output region file

allowed: string

Default:

threshold mJy Threshold value. Must include units.

allowed: doublemJy

Default: 0.0

maskname Output mask name (optional).

allowed: string

Default:

chanrange Range of channel ids

allowed: string

Default:

polrange Range of polarization ids

allowed: string

Default:

minsize Minimum number of pixels for a boxable island

allowed: int Default: 2

diag Count diagonal connections?

allowed: bool Default: False

olded pixels.
allowed: int
Default: 1

overwrite Overwrite existing region file?

allowed: bool
Default: False

Returns

void

Example

This tool finds all 2-dimensional (RA/dec) regions in the given

```
4D (only!) image which are contiguous sets of pixels (islands) above the given ] threshold. It creates a box for each island, a rectangular "cutout". The boxes are stored as regions in the output regionfile. Works on multi-plane images, but only boxes 2-D regions in each plane. (Doesn't create cubes/3D boxes.)
```

NOTE: THIS TASK WILL NOT WORK ON IMAGES THAT DO NOT HAVE 4 DIMENSIONS WHICH INCLUDE A DIRECTION COORDINATE, A SPECTRAL COORDINATE, AND A STOKES COORDINATE. If your image has, eg just a direction coordinate, you can add the required axes using ia.adddegaxe and remove them post-run with imsubimage with dropdeg=T.

```
imagename -- Name of input images:
        default: none; example: imagename='myimage.image'
regionfile -- Name of output region file (adds extension .rgn).
       default: none; if not given uses imagename+'.rgn'
threshold -- value (with units) to use for island threshold.
       default: 0.0.
maskname -- Optional output mask name.
       default: '' (do not write mask image)
chanrange -- Range of channel ids
       default: '' (find boxes for all channels)
       example: '5~7' (find boxes for channel 5,6,7
polrange -- Range of polarization ids
        default: '' (find boxes for all polarizations)
        example: '0~1' (find boxes for polarization 0,1
minsize -- minimum size of island to get a box (in number of pixels)
       default: 2
diag -- count diagonal connections as same island or not
       default: False
boxstretch -- number of pixels to increase outward size of each box; can
       range from -1 to 5.
        default: 1
overwrite -- Overwrite existing region file and/or mask?
        default: False. If False, gives warning if file exists.
```

 $browsetable\hbox{-}task.html$

0.1.7 browsetable

Requires:

Synopsis

Browse a table (MS, calibration table, image)

Description

Arguments

T .	
Inputs	
tablename	Name of input table
	allowed: string
	Default:
mightedit	Warning: the GUI seems to ignore whether the table tool
	is opened read-only - just be careful, esp. if filtering.
	allowed: bool
	Default: False
sortlist	Columns to sort by (ascending)
	allowed: any
	Default: variant
taql	TaQL query string for prefiltering the table.
	allowed: string
	Default:
skipcols	Columns to omit
-	allowed: any
	Default: variant

${\bf Returns}$

void

Example

This task brings up a browser that can open and display any CASA table. The tablename can be specified at startup, or any table can be loaded after the browser comes up.

Parameters:

tablename -- Name of table file on disk (vis, calibration table, image) default: none; example: tablename='ngc5921.ms'

mightedit -- If True disable the filtering options (below) and allow editing the table. Warning: the GUI appears to ignore whether the table tool is opened read-only - just be aware that you should not edit filtered tables unless you know what you are doing.

skipcols -- Columns to NOT display.

default: [] (none); example: skipcols='feed1, feed2'

Some comments on using browsetable (see cookbook also):

Most often you will browse a measurement set. Either specify the vis name as the tablename, or when the browser comes up,

click on <file> (upper left), then click on <open table>

If you want to look at sub-tables, use the tab table keywords along the left side to bring up a panel with the sub-tables listed (Fig 3.8), then choose (left-click) a table and View.

Note that one useful feature is that you can Edit any table and its contents. Use the Edit tab (to the right of the file tab). Be careful with this, and make a backup copy of the table before editing!

Use the Close Tables and Exit option from the Files menu to quit the casabrowser.

To get a plot of two table values, click on tools, then click on plot 2D. For example, to get a u-v plot, in the Plotter Option Gui,

set Rows: 0 to <Large Number>
X Axis: UVW Slice (set 0)
Y Axis: UVW Slice (set 1)

click 'Clear and Plot' on right.

For visibility plots X Axis: TIME

Y Axis: DATA Slice Amplitude click 'Clear and Plot' on right.

cal stat-task.html

0.1.8 calstat

Requires:

Synopsis

Displays statistical information on a calibration table

Default:

Arguments

Outputs	
xstat	Statistical information for the calibration table
	allowed: any
	Default: variant
Inputs	
caltable	Name of input calibration table
	allowed: string
	Default:
axis	Which values to use
	allowed: string
	Default: amplitude
datacolumn	Which data column to use
	allowed: string
	Default: gain
useflags	Take flagging into account? (not implemented)
	allowed: bool

True

Returns

void

Example

This task returns statistical information about a column in a calibration table.

The following values are computed: mean value, sum of values, sum of squared values median, median absolute deviation, quartile, minimum, maximum,

```
variance, standard deviation, root mean square.
Keyword arguments:
caltable -- Name of input calibration table
          default: '', example: vis='ggtau.1mm.amp.gcal'
axis -- Which data to analyze. The possible values are 'amp', 'amplitude', 'phase',
        'real', 'imag', 'imaginary'. Also, the name of any real valued MS column can
        given, e.g. TIME, POLY_COEFF_AMP, REF_ANT, ANTENNA1, FLAG, ...
        default: 'amplitude'
        axis='gain'
        The phase of a complex number is in radians in the range [-pi; pi[.
datacolumn -- Which data column to use if axis is 'amp', 'amplitude',
              'phase', 'real', 'imag' or 'imaginary'.
        default: 'gain'
        datacolumn='gain'
useflags -- Take MS flags into account (not implemented, this parameter
            has no effect!)
       default: False
       useflag=False
       useflag=True
If useflags=False, flagged values are included in the statistics.
If useflags=True, any flagged values are not used in the statistics.
```

caltabconvert-task.html

0.1.9 caltabconvert

Requires:

Synopsis

Convert old-style caltables into new-style caltables.

Description

This task converts old-style (up to CASA 3.3.0) caltables into new-style (CASA 3.4.0 and later) caltables. It is provided as a convenience and is strictly temporary. The information transferred should be enough for most calibration purposes. BPOLY and GSPLINE versions are not supported. Only simple bugs will be fixed. If there are other issues, it is suggested that a new-style caltable be created directly.

Arguments

Inputs	
caltabold	Name of the old-style caltable.
	allowed: string
	Default:
vis	Name of the visibility file (MS) associated with the old-
	style caltable.
	allowed: string
	Default:
ptype	Type of data in the new-format caltable ("complex" or
	"float"; default is "complex").
	allowed: string
	Default: complex
caltabnew	Name of the new-style caltable. If not specified, the suf-
	fix ".new" is appended to the name of old-style caltable.
	allowed: string
	Default:

Returns

boolean

Example

This task converts old-style (up to CASA 3.3.0) caltables into new-style (CASA 3.4.0 and later) caltables. It is provided as a convenience and is strictly temporary. The information transferred should be enough for most calibration purposes. BPOLY and GSPLINE versions are not supported. Only simple bugs will be fixed. If there are other issues, it is suggested that a new-style caltable be created directly.

```
Arguments:
caltabold -- Name of the old-style caltable.
default: none
example: caltabold='gronk.g0'
vis -- Name of the visibility file (MS) associated with the old-style
    caltable.
default: none
example: vis='blurp.ms'
ptype -- Type of data in the new-format caltable.
default: "complex"; allowed values: "complex" or "float"
example: ptype="complex"
NB: The old-style caltables do not have this information, so it is
imperative that users get it correct. "complex" refers to caltables that
have complex gains (e.g., produced by gaincal, bpcal, etc.). "float" refers
to caltables that real numbers such as delays (e.g., produced by gencal).
caltabnew -- Name of the new-style caltable.
default: "" --> the suffix ".new" is appended to the name of the old-style
    caltable
example: caltabold='gronk_new.g0'
```

clean-task.html

0.1.10 clean

Requires:

Synopsis

Invert and deconvolve images with selected algorithm

Description

Form images from visibilities. Handles continuum and spectral line cubes.

Arguments

Inputs

vis Name of input visibility file

allowed: any Default: variant

imagename Pre-name of output images

allowed: any Default: variant

outlierfile Text file with image names, sizes, centers for outliers

allowed: string

Default:

field Name or id

allowed: any Default: variant

spw Spectral windows e.g. $'0\sim3'$, " is all

allowed: any Default: variant

selectdata Other data selection parameters

allowed: bool Default: True

timerange Range of time to select from data

allowed: any Default: variant

uvrange Select data within uvrange

allowed: any
Default: variant

antenna Select data based on antenna/baseline

allowed: any Default: variant

scan Scan number range allowed: any

Default: variant

observation Observation ID range

allowed: any Default: variant

intent Scan Intent(s)

allowed: any
Default: variant

mode Spectral gridding type (mfs, channel, velocity, fre-

quency)

allowed: string Default: mfs

resmooth Re-restore the cube image to a common beam when True

allowed: bool Default: False

gridmode Gridding kernel for FFT-based transforms, default="

one

Returns

void

Example

The clean task has many options:

```
1) Make 'dirty' image and 'dirty' beam (psf)
       2) Multi-frequency-continuum images or spectral channel imaging
       3) Full Stokes imaging
       4) Mosaicking of several pointings
       5) Multi-scale cleaning
       6) Widefield cleaning
      7) Interactive clean boxing
      8) Use starting model (eg from single dish)
      vis -- Name(s) of input visibility file(s)
              default: none;
              example: vis='ngc5921.ms'
                       vis=['ngc5921a.ms', 'ngc5921b.ms']; multiple MSes
      imagename -- Pre-name of output images:
              default: none; example: imagename='m2'
              output images are:
                m2.image; cleaned and restored image
                       With or without primary beam correction
                m2.psf; point-spread function (dirty beam)
                m2.flux; relative sky sensitivity over field
m2.flux.pbcoverage; relative pb coverage over field
                                     (gets created only for ft='mosaic')
                m2.model; image of clean components
                m2.residual; image of residuals
                m2.interactive.mask; image containing clean regions
              To include outlier fields:
                imagename=['n5921','outlier1','outlier2']
      outlierfile --- Text file name which contains image names, sizes, field
                      centers (See 'HINTS ON CLEAN WITH FLANKING FIELDS' below
                      for the format of this outlier file.)
      field -- Select fields to image or mosaic. Use field id(s) or name(s).
                 ['go listobs' to obtain the list id's or names]
              default: ''= all fields
                If field string is a non-negative integer, it is assumed to
```

```
be a field index otherwise, it is assumed to be a
field name
                field='0~2'; field ids 0,1,2
                field='0,4,5~7'; field ids 0,4,5,6,7
                field='3C286,3C295'; field named 3C286 and 3C295
                field = '3,4C*'; field id 3, all names starting with 4C
                For multiple MS input, a list of field strings can be used:
                field = ['0^2','0^4']; field ids 0-2 for the first MS and 0-4
                        for the second
                field = '0~2'; field ids 0-2 for all input MSes
      spw -- Select spectral window/channels
             NOTE: channels de-selected here will contain all zeros if
                        selected by the parameter mode subparameters.
              default: ''=all spectral windows and channels
                spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
                spw='0:5~61'; spw 0, channels 5 to 61
                spw='<2'; spectral windows less than 2 (i.e. 0,1)
                spw='0,10,3:3~45'; spw 0,10 all channels, spw 3,
   channels 3 to 45.
                spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
                For multiple MS input, a list of spw strings can be used:
                spw=['0','0~3']; spw ids 0 for the first MS and 0-3 for the second
                spw='0~3' spw ids 0-3 for all input MS
                spw='3:10~20;50~60' for multiple channel ranges within spw id 3
                spw='3:10^20;50^60,4:0^30' for different channel ranges for spw ids 3 and 4
                spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                     spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
                spw='1~4;6:15~48' for channels 15 through 48 for spw ids 1,2,3,4 and 6
     selectdata -- Other data selection parameters
              default: True
>>> selectdata=True expandable parameters
             See help par.selectdata for more on these
              timerange -- Select data based on time range:
                  default: '' (all); examples,
                  timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
                  Note: if YYYY/MM/DD is missing date defaults to first
day in data set
                  timerange='09:14:0~09:54:0' picks 40 min on first day
                 timerange='25:00:00~27:30:00' picks 1 hr to 3 hr
   30min on NEXT day
                  timerange='09:44:00' pick data within one integration
            of time
```

timerange='>10:24:00' data after this time

```
used:
                 timerange=['09:14:0~09:54:0','>10:24:00']
                 timerange='09:14:0~09:54:0''; apply the same timerange for
                                               all input MSes
             uvrange -- Select data within uvrange (default units meters)
                 default: '' (all); example:
                 uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
                 uvrange='>4klambda';uvranges greater than 4 kilo lambda
                 For multiple MS input, a list of uvrange strings can be
                 uvrange=['0~1000klambda','100~1000klamda']
                 uvrange='0~1000klambda'; apply 0-1000 kilo-lambda for all
                                          input MSes
             antenna -- Select data based on antenna/baseline
                 default: '' (all)
                 If antenna string is a non-negative integer, it is
  assumed to be an antenna index, otherwise, it is
  considered an antenna name.
                 antenna='5&6'; baseline between antenna index 5 and
index 6.
                 antenna='VA05&VA06'; baseline between VLA antenna 5
      and 6.
                 antenna='5\&6;7\&8'; baselines 5-6 and 7-8
                 antenna='5'; all baselines with antenna index 5
                 antenna='05'; all baselines with antenna number 05
(VLA old name)
                 antenna='5,6,9'; all baselines with antennas 5,6,9
  index number
                 For multiple MS input, a list of antenna strings can be
                 used:
                 antenna=['5','5&6'];
                 antenna='5'; antenna index 5 for all input MSes
             scan -- Scan number range.
                default: '' (all)
                 example: scan='1~5'
                 For multiple MS input, a list of scan strings can be used:
                 scan=['0~100','10~200']
                 scan='0~100; scan ids 0-100 for all input MSes
                 Check 'go listobs' to insure the scan numbers are in order.
             observation -- Observation ID range.
                default: '' (all)
                 example: observation='1~5'
             intent -- Scan intent (case sensitive)
                default: '' (all)
                 example: intent='TARGET_SOURCE'
```

For multiple MS input, a list of timerange strings can be

```
example: intent='TARGET_SOURCE1,TARGET_SOURCE2'
                 example: intent='TARGET_POINTING*'
     mode -- Frequency Specification:
             NOTE: Channels deselected with spw parameter will contain all
                   zeros.
             See examples below.
             default: 'mfs'
               mode = 'mfs' means produce one image from all
      specified data.
               mode = 'channel'; Use with nchan, start, width to specify
                      output image cube.
               mode = 'velocity', channels are specified in velocity.
               mode = 'frequency', channels are specified in frequency.
>>> mode='mfs' expandable parameters
             Make a continuum image from the selected frequency
             channels/range using Multi-frequency synthesis
             algorithm for wide-band narrow field imaging.
             mode='mfs' examples:
             spw = '0,1'; mode = 'mfs'
                will produce one image made from all channels in spw
             spw='0:5~28^2'; mode = 'mfs'
                will produce one image made with channels
       (5,7,9,\ldots,25,27)
           nterms -- Number of Taylor terms to be used to model the
             frequency dependence of the sky emission. nterms=1 is
             equivalent to assuming no frequency dependence.
             nterms>1 runs the MS-MFS algorithm, and the choice of nterms
             should depend on the expected shape and SNR of the spectral
             structure, across the chosen bandwidth. Output images
             represent taylor-coefficients of the sky spectrum
             (images with file-name extensions of tt0,tt1,etc).
             A spectral index map is also computed as the ratio of the
             first two terms (following the convention of I(nu) = I(ref_nu) x (nu/nu_0)^a:
             Additionally, a spectral-index error image is made
             by treating taylor-coefficient residuals as errors, and propagating
             them through the division used to compute spectral-index.
             It is meant to be a guide to which parts of the spectral-index
             image to trust, and the values may not always represent a
             statistically-correct error.
```

For more details about this algorithm, please refer to

"A multi-scale multi-frequency deconvolution algorithm for synthesis

imaging in radio interferometry", Rau and Cornwell, AA, Volume 532, 2011

** Note that the software implementation of the MS-MFS algorithm for nterms>1 currently does not allow combination with mosaics, and pbcor.**

reffreq -- The reference frequency (for nterms>1) about which the Taylor expansion is done. reffreq='' defaults to the middle frequency of the selected range.

>>> mode='channel', 'velocity', and 'frequency' expandable parameters

nchan -- Total number of channels in the output image. Example: nchan=100.

Default: -1; Automatically selects enough channels to cover data selected by 'spw' consistent with 'start' and 'width'. It is often easiest to leave nchan at the default value.

start -- First channel, velocity, or frequency.

For mode='channel'; This selects the channel index number from the MS (0 based) that you want to correspond to the first channel of the output cube. The output cube will be in frequency space with the first channel having the frequency of the MS channel selected by start. start=0 refers to the first channel in the first selected spw, even if that channel is de-selected in the spw parameter. Channels de-selected by the spw parameter will be filled with zeros if included by the start parameter. For example, spw=3~8:3~100 and start=2 will produce a cube that starts on the third channel (recall 0 based) of spw index 3, and the first channel will be blank.

example:start=5

For mode='velocity' or 'frequency': default=''; starts at first input channel of first input spw examples: start='5.0km/s', or start='22.3GHz'.

width -- Output channel width

For mode='channel', default=1; >1 indicates channel averaging example: width=4.

For mode= 'velocity' or 'frequency', default=''; width of first input channel, or more precisely, the difference in frequencies between the first two selected channels.

- -- For example if channels 1 and 3 are selected with spw, then the default width will be the difference between their frequencies, and not the width of channel 1.
- -- Similarly, if the selected data has uneven channel-spacing,

channels. In this case, please specify the desired width. When specifying the width, one must give units examples: width='1.0km/s', or width='24.2kHz'. Setting width>0 gives channels of increasing frequency for mode='frequency', and increasing velocity for mode='velocity'. interpolation -- Interpolation type for spectral gridding onto the uv-plane. Options: 'nearest', 'linear', or 'cubic'. default = 'linear' Note: 'linear' and 'cubic' interpolation requires data points on both sides of each image frequency. Errors are therefore possible at edge channels, or near flagged data channels. When image channel width is much larger than the data channel width there is nothing much to be gained using linear or cubic thus not worth the extra computation involved. resmooth -- if the cube has a different restoring beam/channel. Restore image to a common beam or leave as is (default) options: True or False default = False chaniter -- specify how spectral CLEAN is performed, default: chaniter=False; example: chaniter=True; step through channels outframe -- For mode='velocity', 'frequency', or 'channel': default spectral reference frame of output image Options: '','LSRK','LSRD','BARY','GEO','TOPO','GALACTO', 'LGROUP','CMB' default: ''; same as input data example: frame='bary' for Barycentric frame veltype -- for mode='velocity' gives the velocity definition Options: 'radio', 'optical' default: 'radio' NOTE: the viewer always defaults to displaying the 'radio' frame, but that can be changed in the position tracking pull down. mode='channel' examples: spw = '0'; mode = 'channel': nchan=3; start=5; width=4 will produce an image with 3 output planes plane 1 contains data from channels (5+6+7+8)

the default width will be picked from the first two selected

plane 2 contains data from channels (9+10+11+12)

```
plane 3 contains data from channels (13+14+15+16)
             spw = '0:0~63^3'; mode='channel'; nchan=21; start = 0;
   width = 1
                will produce an image with 20 output planes
                Plane 1 contains data from channel 0
                Plane 2 contains date from channel 2
                Plane 21 contains data from channel 61
             spw = '0:0~40^2'; mode = 'channel'; nchan = 3; start =
   5; width = 4
                will produce an image with three output planes
                plane 1 contains channels (5,7)
                plane 2 contains channels (13,15)
                plane 3 contains channels (21,23)
     psfmode -- method of PSF calculation to use during minor cycles:
             default: 'clark': Options: 'clark', 'clarkstokes', 'hogbom'
             'clark' use smaller beam (faster, usually good enough);
              for stokes images clean components peaks are searched
             in the I^2+Q^2+U^2+V^2 domain
             'clarkstokes' locate clean components independently in
             each stokes image
             'hogbom' full-width of image (slower, better for poor
       uv-coverage)
             Note: psfmode will also be used to clean if imagermode = ''
     imagermode -- Advanced imaging e.g. mosaic or Cotton-Schwab clean
             default: imagermode='csclean': Options: '', 'csclean', 'mosaic'
             '' => psfmode cleaning algorithm used
     NOTE: imagermode 'mosaic' (and/or) any gridmode not blank
                       (and/or) nterms>1 : will always use CS style clean.
>>> gridmode='' expandable parameters
             The default value of '' has no effect.
>>> gridmode='widefield' expandable parameters
             Apply corrections for non-coplanar effects during imaging
             using the W-Projection algorithm (Cornwell et al. IEEE JSTSP
             (2008)) or faceting or a combination of the two.
             wprojplanes is the number of pre-computed w-planes used for
                 the W-Projection algorithm. wprojplanes=1 disables
                 correction for non-coplanar effects. default value wprojpanes=-1
                 means clean will determine the number to use.
             facets is the number of facets on each side of the image
                 (i.e. the total number of facets is 'facets x facets').
                 If wprojplanes>1, W-Projection is done for each facet.
 Usually when many wprojection convolution functions
```

sizes are above ~400 pixels ,

it might be faster to use a few facets with wprojection.

>>> gridmode='aprojection' expandable parameters

Corrects for the (E)VLA time-varying PB effects including polarization squint using the A-Projection algorithm (Bhatnagar et al., AandA, 487, 419 (2008)). This can optimally include w-projection also.

wprojplanes is the number of pre-computed w-planes used for W-Projection algorithm. wprojplanes=1 diables correction for non-coplanar effects.

cfcache is the name of the directory to store the convolution functions and weighted sensitivty pattern function.

rotpainc (in degrees) is the Parallactic Angle increment used for OTF rotation of the convolution function.

painc (in degrees) is the Parallactic Angle increment used to compute the convolution functions.

>>> imagermode='mosaic' expandable parameter(s):

Make a mosaic of the different pointings (uses csclean style too)

mosweight -- Individually weight the fields of the mosaic

default: False; example: mosweight=True

This can be useful if some of your fields are more sensitive than others (i.e. due to time spent

on-source); this parameter will give more weight to higher sensitivity fields in the overlap regions.

ftmachine -- Gridding method for the mosaic;

Options: 'ft' or 'mosaic'

default: 'mosaic';

'ft' implies standard interferometric gridding. The residual visibilities are imaged for each pointing and combined in the image plane with the appropriate PB to make the mosaic.

'mosaic' (grid using the Fourier transform of PB as convolution function and mosaic combination is done in visibilities).

ONLY if imagermode='mosaic' is chosen and ftmachine='mosaic', is heterogeneous imaging (CARMA, ALMA) or

wideband beam accounting possible using the right convolution derived from primary beams for each baseline and for different frequencies CAVEAT: ftmachine='mosaic' uses Fourier transforms of the primary beams/ for mosaicing. Making an image which is too small for the pointing covers aliasing due to standard Fourier transform wrap around. scaletype -- Controls scaling of pixels in the image plane. (controls what is seen if interactive=True) It does *not* affect the scaling of the *final* image that is done by pbcor. default='SAULT'; example: scaletype='PBCOR' Options: 'PBCOR', 'SAULT' 'SAULT' when interactive=True shows the residual with constant noise across the mosaic. Can also be achieved by setting pbcor=False. 'PBCOR' uses the SAULT scaling scheme for deconvolution, but if interactive=True shows the primary beam corrected image during interactive. cyclefactor -- Controls the threshhold at which the deconvolution cycle will pause to degrid and subtract the model from the visibilities. With poor PSFs, reconcile often (cyclefactor=4 or 5) for reliability. With good PSFs, use cyclefactor = 1.5 to 2.0 for speed. Note: threshold = cyclefactor * max sidelobe * max residual default: 1.5; example: cyclefactor=4 cyclespeedup -- The major cycle threshold doubles in this number of iterations. Default: -1 (no doubling) Example: cyclespeedup=3 Try cyclespeedup = 50 to speed up cleaning. flatnoise -- Controls whether searching for clean components is done in a constant noise residual image (True) or in an optimal signal-to-noise residual image (False) when ftmosaic='mosaic' is chosen. default=True >>> imagermode='csclean' expandable parameter(s): Image using the Cotton-Schwab algorithm in between major cycles cyclefactor -- See above, under imagermode='mosaic'.

cyclespeedup -- See above, under imagermode='mosaic'.

```
multiscale -- set of scales to use in deconvolution. If set,
             cleans with several resolutions using Hogbom clean. The
             scale sizes are in units of cellsize. So if
             cell='2arcsec', a multiscale scale=10 => 20arcsec. The
             first scale is recommended to be 0 (point), we suggest the
             second be on the order of synthesized beam, the third 3-5
             times the synthesized beam, etc.. Avoid making the largest
             scale too large relative to the image width or the scale of
             the lowest measured spatial frequency. For example, if the
             synthesized beam is 10" FWHM and cell=2", try
             multiscale = [0,5,15].
       default: multiscale=[] (standard CLEAN with psfmode algorithm,
             no multi-scale).
             Example: multiscale = [0,5,15]
>>> multiscale expandable parameter(s):
             negcomponent -- Stop component search when the largest scale
               has found this number of negative components;
               -1 means continue component search even if the largest
               component is negative. default: -1; example: negcomponent=50
             smallscalebias -- A bias toward smaller scales.
                 The peak flux found at each scale is weighted by
                 a factor = 1 - smallscalebias*scale/max_scale, so
                 that Fw = F*factor.
                 Typically the values range from 0.2 to 1.0.
                 default: 0.6
     imsize -- Image size in pixels (x, y). DOES NOT HAVE TO BE A POWER
               OF 2 (but has to be even and factorizable to 2,3,5,7 only).
             default = [256,256]; example: imsize=[350,350]
             imsize = 500 is equivalent to [500,500]
             If include outlier fields, e.g., [[400,400],[100,100]] or
             use outlierfile.
             Avoid odd-numbered imsize.
     cell -- Cell size (x,y)
             default= '1.0arcsec';
             example: cell=['0.5arcsec,'0.5arcsec'] or
             cell=['1arcmin', '1arcmin']
             cell = '1arcsec' is equivalent to ['1arcsec', '1arcsec']
             NOTE:cell = 2.0 => ['2arcsec', '2arcsec']
     phasecenter -- direction measure or fieldid for the mosaic center
             default: '' => first field selected ;
             example: phasecenter=6
                      phasecenter='J2000 19h30m00 -40d00m00'
                      phasecenter='J2000 292.5deg -40.0deg'
```

```
phasecenter='J2000 5.105rad -0.698rad'
        If include outlier fields,
        e.g. ['J2000 19h30m00 -40d00m00', J2000 19h25m00 -38d40m00']
        or use outlierfile.
restfreq -- Specify rest frequency to use for output image
        default='' Occasionally it is necessary to set this (for
        example some VLA spectral line data). For example for
       NH_3 (1,1) put restfreq='23.694496GHz'
stokes -- Stokes parameters to image
        default='I'; example: stokes='IQUV';
        Options: 'I','Q','U','V','IV','QU','IQ','UV','IQU','IUV','IQUV','RR','LL','X
niter -- Maximum number iterations,
        if niter=0, then no CLEANing is done ("invert" only).
        (niter=0 can be used instead of the 'ft' task to predict/save a model)
For cube or multi field images niter is the maximum number of iteration
        clean will use for each image plane.
        The number of iterations used may be less that niter if threshold value
        is reached
        default: 500; example: niter=5000
gain -- Loop gain for CLEANing
        default: 0.1; example: gain=0.5
threshold -- Flux level at which to stop CLEANing
       default: '0.0mJy';
        example: threshold='2.3mJy' (always include units)
                 threshold = '0.0023Jy'
                 threshold = '0.0023Jy/beam' (okay also)
interactive -- use interactive clean (with GUI viewer)
        default: interactive=False
        example: interactive=True
        interactive clean allows the user to build the cleaning
        mask interactively using the viewer. The viewer will
        appear every npercycle interation, but modify as needed
        The final interactive mask is saved in the file
        imagename_interactive.mask. The initial masks use the
        union of mask and cleanbox (see below).
```

>>> interactive=True expandable parameters

npercycle -- this is the number of iterations between each interactive update of the mask. It is important to modify this number interactively during the cleaning, starting with a low number like 20, but then increasing as more extended emission is encountered.

```
if the CLEAN component placement is limited by a mask to where
             real emission is expected to be. As long as the image has the
             same shape (size), mask images (e.g. from a previous interactive
             session) can be used for a new execution. NOTE: the initial
             clean mask actually used is the union of what is specified in mask
             and <imagename>.mask
             default: [] or '' : no masking; Possible specification types:
             (a) Cleanboxes, specified using the CASA region format
                  (http://casaguides.nrao.edu/index.php?title=CASA_Region_Format)
                  Example : mask='box [ [ 100pix , 130pix] , [120pix, 150pix ] ]'
                     mask='circle [ [ 120pix , 40pix] ,6pix ]'
                     mask='circle[[19h58m52.7s,+40d42m06.04s], 30.0arcsec]'
 If used with a spectral cube, it will apply to all channels.
 Multiple regions may be specified as a list of pixel ranges.
                  Example : mask= ['circle [ [ 120pix , 40pix] ,6pix ]',
                                               'box [ [ 100pix , 130pix] , [120pix, 150pix
             (b) Filename with cleanbox shapes defined using the CASA region format.
                 Example: mask='mycleanbox.txt'
                   The file 'mycleanbox.txt' contains :
                        box [ [ 100pix , 130pix ] , [ 120pix, 150pix ] ]
                        circle [ [ 150pix , 150pix] ,10pix ]
                        rotbox [ [ 60pix , 50pix ] , [ 30pix , 30pix ] , 30deg ]
             (c) Filename for image mask. Example: mask='myimage.mask'
 Multiple mask files may be specified.
 example : mask=[ 'mask1.mask', 'mask2.mask' ]
             (d) Filename for region specification (e.g. from viewer).
                 Example: mask='myregion.rgn'
             (e) Combinations of the above options.
                 Example: mask=['mycleanbox.txt', 'myimage.mask',
                                'myregion.rgn','circle [ [ 120pix , 40pix] ,6pix ]']
             (f) Threshold on primary-beam.
                 A number between 0 and 1, used as a threshhold of primary
                 beam coverage. The primary beam coverage map (imagename +
                 '.flux(.pbcoverage)') will be made and the CLEAN component
                 placement will be limited to where it is > the number.
             (g) True or False.
                 True: like (f), but use minpb as the number.
                 False: go maskless (and expect trouble).
          (For masks for multiple fields, please see 'HINTS ON CLEAN WITH FLANKING FIELDS
     uvtaper -- Apply additional uv tapering of the visibilities.
             default: uvtaper=False; example: uvtaper=True
>>> uvtaper=True expandable parameters
             outertaper -- uv-taper on outer baselines in uv-plane
```

[bmaj, bmin, bpa] taper Gaussian scale in uv or

```
the uv taper/200 (klambda).
                 default: outertaper=[]; no outer taper applied
   example: outertaper=['5klambda'] circular taper
FWHM=5 kilo-lambda
                          outertaper=['5klambda','3klambda','45.0deg']
                          outertaper=['10arcsec'] on-sky FWHM 10 arcseconds
                          outertaper=['300.0'] default units are lambda
        in aperture plane
             innertaper -- uv-taper in center of uv-plane
                 [bmaj,bmin,bpa] Gaussian scale at which taper falls to
   zero at uv=0
                 default: innertaper=[]; no inner taper applied
                 NOT YET IMPLEMENTED
     modelimage -- Name of model image(s) to initialize cleaning. If
             multiple images, then these will be added together to
             form initial staring model NOTE: these are in addition
             to any initial model in the <imagename>.model image file
             default: '' (none); example: modelimage='orion.model'
             modelimage=['orion.model','sdorion.image'] Note: if the
             units in the image are Jy/beam as in a single-dish
             image, then it will be converted to Jy/pixel as in a
             model image, using the restoring beam in the image
             header and zeroing negatives. If the image is in Jy/pixel then it is taken
             as is.
     When nterms>1, a one-to-one mapping is done between images
     in this list and Taylor-coefficients. If more than nterms
     images are specified, only the first nterms are used.
     It is valid to supply fewer than nterms model images.
     Example : Supply an estimate of the continuum flux from a
               previous imaging run.
     weighting -- Weighting to apply to visibilities:
             default='natural'; example: weighting='uniform';
             Options: 'natural', 'uniform', 'briggs',
       'superuniform', 'briggsabs', 'radial'
>>> Weighting expandable parameters
             For details on weighting please see Chapter3
             of late Dr. Brigg's thesis (http://www.aoc.nrao.edu/dissertations/dbriggs)
             For weighting='briggs' and 'briggsabs'
                 robust -- Brigg's robustness parameter
                 default=0.0; example: robust=0.5;
                 Options: -2.0 to 2.0; -2 (uniform)/+2 (natural)
             For weighting='briggsabs'
                 noise -- noise parameter to use for Briggs "abs"
```

angular units. NOTE: the on-sky FWHM in arcsec is roughly

```
weighting
              example noise='1.0mJy'
          npixels -- uv-box used for weight calculation
                         a box going from -npixel/2 to +npixel/2 on each side
                         around a point is used to calculate weight density.
                         O means box is pixel size
              example npixels=2
              Default = 0
  Exception: when choosing superuniform it does not make sense to
  use npixels=0 as it is uniform thus if npixels is 0 it will be forced to 6 or
  a box of -3pixels to 3pixels
  restoringbeam -- Output Gaussian restoring beam for CLEAN image
          [bmaj, bmin, bpa] elliptical Gaussian restoring beam
          default units are in arc-seconds for bmaj, bmin, degrees
          for bpa default: restoringbeam=[]; Use PSF calculated
          from dirty beam.
    example: restoringbeam=['10arcsec'] circular Gaussian
     FWHM 10 arcseconds example:
     restoringbeam=['10.0','5.0','45.0deg'] 10"x5"
             at 45 degrees
  pbcor -- Output primary beam-corrected image
           If pbcor=False, the final output image is NOT corrected for
           the PB pattern (particularly important for mosaics), and
           therefore is not "flux correct". Correction can also be
           done after the fact using immath to divide
           <imagename>.image by the <imagename>.flux image.
    default: pbcor=False; output un-corrected image
    example: pbcor=True; output pb-corrected image (masked outside
                   minpb)
  minpb -- Minimum PB level to use for pb-correction and pb-based masking.
               default=0.2;
               example: minpb=0.01
          When imagermode is *not* 'mosaic' :
             minpb is applied to the flux image (sensitivity-weighted pb).
             minpb is used to create a mask, only when pbcor=True
          When imagermode='mosaic':
     minpb is applied to the flux.pbcoverage image
                   (mosaic pb with equal weight per pointing)
              minpb is always used to create a mask (regardless of
```

usescratch -- if True will create scratch columns if they are not there. And after clean completes the predicted model

pbcor=True/False)

visibility is from the clean components are written to the ms. This increases the ms size by the data volume. if False then the model is saved in the ms header and the calculation of the visibilities is done on the fly when using calibration or plotms. Use True if you want to access the moedl visibilities in python, say.

False: Major cycle grids all channels. Minor cycle steps through all channels before the next major cycle.

True: Major and minor cycles are performed one chunk at a time, and output images cubes are concatenated.

async -- Run asynchronously

default = False; do not run asychronously

HINTS ON CLEAN WITH FLANKING FIELDS

There are two ways of specifying multi-field images for clean.

(a) Task parameters are used to define the first(main) field. A text file containing definitions of all additional fields is supplied to the 'outlierfile' task parameter.

This outlier file must contain the following parameters per field Required: imagename, imsize, phasecenter Optional: mask, modelimage

The parameter set for each field must begin with 'imagename'.

Parameters can be listed in a single line or span multiple lines.

Example: Three fields.

- Task Inputs:
 imagename = 'M1_0'
 outlierfile='outlier.txt'
 imsize = [1024,1024]
 phasecenter = 'J2000 13h27m20.98 43d26m28.0'
- Contents of outlier file 'outlier.txt':
 imagename = 'M1_1'
 imsize = [128,128]
 phasecenter = 'J2000 13h30m52.159 43d23m08.02'
 mask = ['out1.mask', 'circle[[40pix,40pix],5pix]']
 modelimage = 'out1.model'

```
imagename = 'M1_2'
imsize = [128,128]
phasecenter = 'J2000 13h24m08.16 43d09m48.0'
```

In this example, the first field 'M1_0' is defined using main task parameters. The next two 'M1_1' and 'M1_2' are listed in the file 'outlier.txt'. A mask and modelimage has been supplied only for the second field (M1_1). Fields with unspecified masks will use the full field for cleaning.

(b) Specify all fields as lists for each task parameter :

```
Parameters that support lists for multi-field specification : 'imagename', 'imsize', 'phasecenter', 'mask', 'modelimage'
```

Example: Three fields (same as above)

Note: All lists must have the same length.

```
In the examples for both (a) and (b), the following images will be made: M1_0.image, M1_1.image, M1_2.image cleaned images
M1.0.model, M1_1.model, M1_2.model model images
M1.0.residual, M1_1.residual, M1_2.residual residual images
```

Note: The old AIPS-style outlier-file and boxfile formats have been deprecated However, due to user-requests, they will continue be supported in CASA 3.4. Note that the old outlier file format does not support the specification of modelimage and mask for each field.

The new format is more complete, and less ambiguous, so please consider updating your scripts.

clearcal-task.html

0.1.11 clearcal

Requires:

Synopsis

Re-initializes the calibration for a visibility data set

Arguments

Inputs	
vis	Name of input visibility file (MS)
	allowed: string
	Default:
field	Select field using field id(s) or field name(s)
	allowed: string
	Default:
spw	Select spectral window/channel.
	allowed: string
	Default:
intent	Select observing intent
	allowed: string
	Default:
addmodel	Add MODEL_DATA scratch column
	allowed: bool
	Default: False

Returns

void

Example

Clearcal reinitializes the calibration columns in a measurement set. Specificially, it will set the MODEL_DATA column (if present) to unity in total intensity and zero in polarization, and it will set the CORRECTED_DATA column to the original (observed) DATA

in the DATA column. Use the field and spw parameters to select which data to initialize. If the dataset does not yet have the scratch columns, they will be created (MODEL_DATA only if addmodel=True) and initilized for the whole dataset (field, spw, and intent will be ignored in this case).

```
Keyword arguments:
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
field -- Select field using field id(s) or field name(s).
           [run listobs to obtain the list id's or names]
        default: ''=all fields
        If field string is a non-negative integer, it is assumed a field index
          otherwise, it is assumed a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5~7'; field ids 0,4,5,6,7
        field='3C286,3C295'; field named 3C286 adn 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window
        default: ''=all spectral windows and channels
        spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
        spw='<2'; spectral windows less than 2 (i.e. 0,1)
        spw='0:5~61'; spw 0, channels 5 to 61
        spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
        spw='0~2:2:6'; spw 0,1,2 with channels 2 through 6 in each.
       NB: Multiple channel ranges per spw are not supported in clearcal.
intent -- Select observing intent
         default: '' (no selection by intent)
          intent='*BANDPASS*' (selects data labelled with
                                BANDPASS intent)
addmodel -- add MODEL_DATA along with CORRECTED_DATA if True;
            otherwise it will add/reset only CORRECTED_DATA, model visibilities
            will then be evaluated when needed.
            default: False (model will not be added)
```

clearplot-task.html

0.1.12 clearplot

Requires:

Synopsis

Clear the matplotlib plotter and all layers

Arguments

Inputs

Returns

void

Example

Run the task clearplot when you want to clear completely the matplotlib, but keep it available for additional plotting.

Typing 'go clearplot()' will not change the current task being scrutinized
Typing 'clearplot() will change the current task assignment to clearplot
which is generally not what is desired.

clearstat-task.html

0.1.13 clearstat

Requires:

Synopsis

Clear all autolock locks

Arguments

Inputs

Returns

void

Example

This task is useful if another task that is running indicates that it is trying to obtain a lock on a file.

Typing 'go clearstat()' will not change the current task being scrutinized
Typing 'clearstat()' will change the current task assignment to clearpstat
which is generally not what is desired.

concat-task.html

0.1.14 concat

Requires:

Synopsis

Concatenate several visibility data sets.

Description

The list of data sets given in the vis argument are chronologically concatenated into an output data set in concatvis, i.e. the data sets in vis are first ordered by the time of their earliest integration and then concatenated. If there are fields whose direction agrees within the direction tolerance (parameter dirtol), the actual direction in the resulting, merged output field will be the one from the chronologically first input MS.

If concatvis already exists (e.g., it is the same as the first input data set), then the other input data sets will be appended to the concatvis data set. There is no limit to the number of input data sets.

If none of the input data sets have any scratch columns (model and corrected columns), none are created in the concatvis. Otherwise these columns are created on output and initialized to their default value (1 in model column, data in corrected column) for those data with no input columns.

Spectral windows for each data set with the same chanelization, and within a specified frequency tolerance of another data set will be combined into one spectral window.

A field position in one data set that is within a specified direction tolerance of another field position in any other data set will be combined into one field. The field names need not be the same—only their position is used.

Each appended dataset is assigned a new observation id (provided the entries in the observation table are indeed different).

Keyword arguments: vis – Name of input visibility files to be combined default: none; example: vis = ['src2.ms', 'ngc5921.ms', 'ngc315.ms'] concatvis – Name of visibility file that will contain the concatenated data note: if this file exits on disk then the input files are added to this file. Otherwise the new file contains the concatenated data. Be careful here when concatenating to an existing file. default: none; example: concatvis='src2.ms' example: concatvis='outvis.ms'

freqtol – Frequency shift tolerance for considering data to be in the same spwid. The number of channels must also be the same. default: " == 1 Hz example: freqtol='10MHz' will not combine spwid unless they are within 10

MHz. Note: This option is useful to combine spectral windows with very slight frequency differences caused by Doppler tracking, for example.

dirtol – Direction shift tolerance for considering data as the same field default: " == 1 mas (milliarcsec) example: dirtol='1arcsec' will not combine data for a field unless their phase center differ by less than 1 arcsec. If the field names are different in the input data sets, the name in the output data set will be the first relevant data set in the list.

respectname – If true, fields with a different name are not merged even if their direction agrees (within dirtol) default: False

timesort – If true, the output visibility table will be sorted in time. default: false. Data in order as read in. example: timesort=true Note: There is no constraint on data that is simultaneously observed for more than one field; for example multi-source correlation of VLBA data.

copypointing – Make a proper copy of the POINTING subtable (can be time consuming). If False, the result is an empty POINTING table. default: True visweightscale – The weights of the individual MSs will be scaled in the concatenated output MS by the factors in this list. SIGMA will be scaled by 1/sqrt(factor). Useful for handling heterogeneous arrays. Use plotms to inspect the "Wt" column as a reference for determining the scaling factors. See the cookbook for more details. example: [1.,3.,3.] - scale the weights of the second and third MS by a factor 3 and the SIGMA column of these MS by a factor 1/sqrt(3). default: [] (empty list) - no scaling

Arguments

Inputs vis Name of input visibility files to be concatenated allowed: stringArray Default: concatvis Name of output visibility file allowed: string Default: freqtol Frequency shift tolerance for considering data as the same spwid allowed: any Default: variant dirtol Direction shift tolerance for considering data as the same field allowed: any Default: variant respectname If true, fields with a different name are not merged even if their direction agrees allowed: bool Default: False timesort If true, sort by TIME in ascending order allowed: bool Default: False Copy all rows of the POINTING table. copypointing allowed: bool Default: True visweightscale List of the weight scaling factors to be applied to the individual MSs allowed: doubleArray

Example

```
concat(vis=['src2.ms','ngc5921.ms'], concatvis='src2.ms')
      will concatenate 'ngc5921.ms' into 'src2.ms', and the original
    src2.ms is lost

concat(vis=['src2.ms','ngc5921.ms'], concatvis='out.ms')
      will concatenate 'ngc5921.ms' and 'src2.ms' into a file named
      'out.ms'; the original 'ngc5921.ms' and 'src2.ms' are untouched.

concat(vis=['src2.ms','ngc5921.ms'], concatvis='out.ms', dirtol='0.5arcsec')
```

Default:

like the previous example but using a direction tolerance increased to $0.5~\rm arcsec$. Fields whose directions differ by less than this limit are merged into one field with the name and direction from the chronologically first input MS.

```
concat(vis=['v1.ms','v2.ms'], concatvis = 'vall.ms')
    then
concat(vis=['v3.ms','v4.ms'], concatvis = 'vall.ms')
    vall.ms will contains v1.ms+v2.ms+v4.ms
```

Note: run flagmanager to save flags in the concatvis

conjugatevis-task.html

0.1.15 conjugatevis

Requires:

Synopsis

Change the sign of the phases in all visibility columns.

Arguments

Inputs	
vis	Name of input visibility file.
	allowed: string
	Default:
spwlist	Spectral window selection
	allowed: any
	Default: variant ""
outputvis	Name of output visibility file
	allowed: string
	Default:
overwrite	Overwrite the output is if it exists.
	allowed: bool
	Default: False

Example

```
Change the sign of the phases in all visibility columns
```

Example:

conjugatevis(vis='NGC253.ms', spwlist=[0,1], outputvis='NGC253-conj.ms')

Will conjugate all visibilities for spectral windows 0 and 1 and store the modified data in NGC253-conj.ms.

csvclean-task.html

0.1.16 csvclean

Requires:

Synopsis

This task does an invert of the visibilities and deconvolve in the image plane.

Description

This task does an invert of the visibilities and deconvolve in the image plane. It does not do a uvdata subtraction (aka Cotton-Schwab major cycle) of model visibility as in clean. - For ALMA Commissioning

Arguments

Inputs

vis Name of input visibility file

allowed: string

Default:

imagename Name of image

allowed: string

Default:

field Select field using field id(s) or field name(s)

allowed: string

Default:

spw Select spectral window/channels

allowed: any
Default: variant

advise Boolean to determine if advice on image cell is requested

allowed: bool Default: False

mode define the mode to operate csyclean: option continuum,

cube

allowed: string
Default: continuum

nchan Number of channels (planes) in output image; -1 = all

allowed: int Default: -1

width of output spectral channels

allowed: variant Default: variant 1

imsize Image size in pixels (nx,ny), symmetric for single value

allowed: intArray Default: 256256

cell arcsec The image cell size in arcseconds [x,y].

allowed: doubleArrayarcsec

Default: 1.01.0

phasecenter Image center: direction or field index

allowed: any Default: variant

niter Maximum number of iterations

allowed: int
Default: 500
Type of weighting

weighting Type of weighting allowed: str

allowed: string Default: natural

restoring beam for CLEAN image

allowed: stringArray

Default:

interactive Create a mask2interactively or not.

allowed: bool Default: False

Example

```
of model visibility as in clean. - For ALMA Commissioning
Keyword arguments:
vis -- Name of input visibility file
         default: none; example: vis='ngc5921.ms'
imagename -- Name of output CASA image. (only the prefix)
                   default: none; example: imagename='m2'
                   output images are:
                 m2.image; cleaned and restored image
                        With or without primary beam correction
                 m2dirty.image; dirty image
                 m2psf.image; point-spread function (dirty beam)
                 m2.model; image of clean components
                 m2.mask; image containing clean regions, when interative=True
field -- Select fields in mosaic. Use field id(s) or field name(s).
                  ['go listobs' to obtain the list id's or names]
              default: ''= all fields
              If field string is a non-negative integer, it is assumed to
                  be a field index otherwise, it is assumed to be a
  field name
              field='0^2'; field ids 0,1,2
              field='0,4,5^{\sim}7'; field ids 0,4,5,6,7
              field='3C286,3C295'; field named 3C286 and 3C295
              field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
           NOTE: This selects the data passed as the INPUT to mode
           default: ''= all spectral windows and channels
                spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
                spw='0:5~61'; spw 0, channels 5 to 61
                spw='<2'; spectral windows less than 2 (i.e. 0,1)
                spw='0,10,3:3~45'; spw 0,10 all channels, spw 3,
   channels 3 to 45.
                spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
                spw='0:0~10;15~60'; spectral window 0 with channels
    0-10,15-60
                spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                      spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
```

This task does not do a uvdata subtraction (aka Cotton-Schwab major cycle)

```
requested. If set to True. It won't run clean but return
                  values for imszise and cell estimated for the longest
                  baseline in the data
imsize -- Image pixel size (x,y). DOES NOT HAVE TO BE A POWER OF 2
               default = [256,256]; example: imsize=[350,350]
               imsize = 500 is equivalent to [500,500].
               Avoid odd-numbered imsize.
cell -- Cell size (x,y)
               default= '1.0arcsec';
               example: cell=['0.5arcsec,'0.5arcsec'] or
               cell=['1arcmin', '1arcmin']
               cell = 'larcsec' is equivalent to ['larcsec', 'larcsec']
               NOTE:cell = 2.0 => ['2arcsec', '2arcsec']
       phasecenter \operatorname{\mathsf{--}} direction measure or fieldid for the mosaic center
                default: '' => first field selected ; example: phasecenter=6
                or phasecenter='J2000 19h30m00 -40d00m00'
mode -- this determines what kind of image to make
                continuum or cube. In continuum all the selected data
                channels are combined in a 1 channel image using
                multifrequency synthesis.
                options are 'cube' and 'continuum'
                default: 'continuum'
 >>> mode='cube' expandable parameters
               nchan -- sets the number of channel in the output
               image. e.g nchan=10
               width -- image channel width in terms of the number of
                        channel of the first spw of the data selected
                        e.g width=2
niter -- Maximum number of iterations,
               if niter=0, then no CLEANing is done ("invert" only)
               default: 500; example: niter=5000
weighting -- Weighting to apply to visibilities:
               default='natural'; example: weighting='uniform';
               Options: 'natural', 'uniform', 'briggs',
                       'superuniform', 'briggsabs', 'radial'
```

advise -- This determines whether advice for imsize and cell is

restoringbeam -- Output Gaussian restoring beam for CLEAN image
[bmaj, bmin, bpa] elliptical Gaussian restoring beam.

Default units are in arc-seconds for bmaj and bmin, and in degrees for bpa. Default: restoringbeam=[]; Use PSF calculated from dirty beam.

example: restoringbeam=['10arcsec'] or restorinbeam='10arcsec', circular Gaus FWHM 10 arcseconds example: restoringbeam=['10.0','5.0','45.0deg'] 10"x5" at 45 degrees

interactive -- Create a mask interactively or not.
 default=False; example: interactive=True
 The viewer will open with the image displayed. Select the
 region for the mask and double click in the middle of it.

cvel-task.html

0.1.17 cvel

Requires:

Synopsis

regrid an MS to a new spectral window / channel structure or frame

Description

The intent of cvel is to transform channel labels and the visibilities to a spectral reference frame which is appropriate for the science analysis, e.g. from TOPO to LSRK to correct for Doppler shifts throughout the time of the observation. Naturally, this will change the shape of the spectral feature to some extent. According to the Nyquist theorem you should oversample a spectrum with twice the numbers of channels to retain the shape. Based on some tests, however, we recommend to observe with at least 3-4 times the number of channels for each significant spectral feature (like 3-4 times the linewidth). This will minimize regridding artifacts in cvel.

If cvel has already established the grid that is desired for the imaging, clean should be run with exactly the same frequency/velocity parameters as used in cvel in order to avoid additional regridding in clean.

Hanning smoothing is optionally offered in cvel, but tests have shown that already the regridding process itself, if it involved a transformation from TOPO to a non-terrestrial reference frame, implies some smoothing (due to channel interpolation) such that Hanning smoothing may not be necessary.

Arguments

Inputs vis Name of input measurement set allowed: string Default: Name of output measurement set outputvis allowed: string Default: passall Pass through (write to output MS) non-selected data with no change allowed: bool Default: False field Select field using field id(s) or field name(s) allowed: any Default: variant Select spectral window/channels spw allowed: any Default: variant selectdata Other data selection parameters allowed: bool Default: True Select data based on antenna/baseline antenna allowed: string Default: timerange Range of time to select from data allowed: string Default: scan scan number range allowed: string Default: (sub)array indices array allowed: string Default: mode Regridding mode allowed: string Default: channel nchan Number of channels in output spw (-1=all) allowed: int Default: -1 First channel in input to use start allowed: any Default: variant 0 width Number of input channels to average allowed: any Default: variant 1 interpolation Spectral interpolation method

restfreq rest frequency (see help) allowed: string

phasecenter

allowed:

Default:

allowed:

Default:

string

linear

anv

variant

Phase center direction to be used for the spectral coor-

dinate transformation: position or field index

Returns

void

Example

```
vis -- Name of input visibility file
             default: none; example: vis='ngc5921.ms'
     outputvis -- Name of output measurement set (required)
             default: none; example: vis='ngc5921-regridded.ms'
     passall -- if False, data not meeting the selection is omitted/deleted
             or flagged (if in-row); if True, data not meeting the selection
             on field and spw is passed through without modification
     default: False; example:
             field='NGC5921'
             passall=False : only data from NGC5921 is included in output MS,
                       no data from other fields (e.g. 1331+305) is included
             passall=True: data from NGC5921 is transformed by cvel, all other
                       fields are passed through unchanged
     field -- Select fields in mosaic. Use field id(s) or field name(s).
                ['go listobs' to obtain the list id's or names]
            default: ''= all fields
            If field string is a non-negative integer, it is assumed to
                be a field index otherwise, it is assumed to be a
field name
            field='0~2'; field ids 0,1,2
            field='0,4,5~7'; field ids 0,4,5,6,7
            field='3C286,3C295'; field named 3C286 and 3C295
            field = '3,4C*'; field id 3, all names starting with 4C
     spw --Select spectral window/channels
            NOTE: This selects the data passed as the INPUT to mode
            default: ''=all spectral windows and channels
              spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
              spw='0:5~61'; spw 0, channels 5 to 61
              spw='<2'; spectral windows less than 2 (i.e. 0,1)
              spw='0,10,3:3~45'; spw 0,10 all channels, spw 3,
 channels 3 to 45.
              spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
```

```
spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                      spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
       selectdata -- Other data selection parameters
              default: True
  >>> selectdata=True expandable parameters
              antenna -- Select data based on antenna/baseline
                  default: ', (all)
                  If antenna string is a non-negative integer, it is
      assumed to be an antenna index, otherwise, it is
      considered an antenna name.
                  antenna='5&6'; baseline between antenna index 5 and
   index 6.
                  antenna='VA05&VA06'; baseline between VLA antenna 5
         and 6.
                  antenna='5\&6;7\&8'; baselines 5-6 and 7-8
                  antenna='5'; all baselines with antenna index 5
                  antenna='05'; all baselines with antenna number 05
  (VLA old name)
                  antenna='5,6,9'; all baselines with antennas 5,6,9
     index numbers
              timerange -- Select data based on time range:
                 default = '' (all); examples,
                  timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
                  Note: if YYYY/MM/DD is missing date defaults to first
day in data set
                  timerange='09:14:0~09:54:0' picks 40 min on first day
                  timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr
     30min on NEXT day
                  timerange='09:44:00' pick data within one integration
             of time
                  timerange='>10:24:00' data after this time
              scan -- Scan number range.
                  default: '' (all)
                  example: scan='1~5'
                  Check 'go listobs' to insure the scan numbers are in
  order.
              array -- Select data by (sub)array indices
                  default: '' (all); example:
```

spw='0:0~10;15~60'; spectral window 0 with channels

0-10,15-60

```
array='0~2'; arrays 0 to 2
   mode -- Frequency Specification:
             NOTE: See examples below:
             default: 'channel'
               mode = 'channel'; Use with nchan, start, width to specify
                       output spw. Produces equidistant grid based on first
                       selected channel. See examples below.
               mode = 'velocity', means channels are specified in
     velocity.
               mode = 'frequency', means channels are specified in
      frequency.
               mode = 'channel_b', alternative 'channel' mode.
       Does not force an equidistant grid. Faster.
>>> mode expandable parameters
             Start, width are given in units of channels, frequency
  or velocity as indicated by mode
             nchan -- Number of channels in output spw
               default: -1 = all channels; example: nchan=3
             start -- Start or end input channel (zero-based) depending on the sign of the
               default=0; example: start=5
             width -- Output channel width in units of the input
     channel width (sign indicates whether the start parameter is lower(+) or upper(-) end
               default=1; example: width=4
             interpolation -- Interpolation method (linear, nearest, cubic, spline, fftsh:
               default = 'linear'
         examples:
             spw = '0,1'; mode = 'channel'
                will produce a single spw containing all channels in spw
       0 and 1
             spw='0:5~28^2'; mode = 'channel'
                will produce a single spw made with channels
       (5,7,9,\ldots,25,27)
             spw = '0'; mode = 'channel': nchan=3; start=5; width=4
                will produce an spw with 3 output channels
                new channel 1 contains data from channels (5+6+7+8)
                new channel 2 contains data from channels (9+10+11+12)
                new channel 3 contains data from channels (13+14+15+16)
             spw = '0:0~63^3'; mode='channel'; nchan=21; start = 0;
   width = 1
                will produce an spw with 21 channels
                new channel 1 contains data from channel 0
                new channel 2 contains data from channel 2
                new channel 21 contains data from channel 61
             spw = '0:0~40^2'; mode = 'channel'; nchan = 3; start =
```

outframe -- output reference frame (not case-sensitive)

possible values: LSRK, LSRD, BARY, GALACTO, LGROUP, CMB, GEO, TOPO, or SOURCE
(SOURCE is meant for solar system work and corresponds to GEO + radial velocity correction for ephemeris objects).

default='' (keep original reference frame); example: outframe='BARY'

veltype -- definition of velocity (in mode)
 default = 'radio'

hanning -- if true, Hanning smooth frequency channel data to remove Gibbs ringing

NH_3 (1,1) put restfreq='23.694496GHz'

The intent of cvel is to transform channel labels and the visibilities to a spectral reference frame which is appropriate for the science analysis, e.g. from TOPO to LSRK to correct for Doppler shifts throughout the time of the observation. Naturally, this will change the shape of the spectral feature to some extent. According to the Nyquist theorem you should oversample a spectrum with twice the numbers of channels to retain the shape. Based on some tests, however, we recommend to observe with at least 3-4 times the number of channels for each significant spectral feature (like 3-4 times the linewidth). This will minimize regridding artifacts in cvel.

If cvel has already established the grid that is desired for the imaging, clean should be run with exactly the same frequency/velocity parameters as used in cvel in order to avoid additional regridding in clean.

Hanning smoothing is optionally offered in cvel, but tests have shown that already the regridding process itself, if it involved a transformation from TOPO to a non-terrestrial reference frame, implies some smoothing (due to channel interpolation) such that Hanning smoothing may not be necessary.

cvel2-task.html

0.1.18 cvel2

Requires:

Synopsis

Regrid an MS or MMS to a new spectral window, channel structure or frame

Description

The intent of cvel2 is to transform channel labels and the visibilities to a spectral reference frame which is appropriate for the science analysis, e.g. from TOPO to LSRK to correct for Doppler shifts throughout the time of the observation. Naturally, this will change the shape of the spectral feature to some extent. According to the Nyquist theorem you should oversample a spectrum with twice the numbers of channels to retain the shape. Based on some tests, however, we recommend to observe with at least 3-4 times the number of channels for each significant spectral feature (like 3-4 times the linewidth). This will minimize regridding artifacts in cvel2.

If cvel2 has already established the grid that is desired for the imaging, clean should be run with exactly the same frequency/velocity parameters as used in cvel2 in order to avoid additional regridding in clean.

Hanning smoothing is optionally offered in cvel2, but tests have shown that already the regridding process itself, if it involved a transformation from TOPO to a non-terrestrial reference frame, implies some smoothing (due to channel interpolation) such that Hanning smoothing may not be necessary. This version of cvel2 also supports Multi-MS input, in which case it will create an output Multi-MS too.

NOTE: The parameter passall is not supported in cvel2. The user may achieve the same results of passall=True by splitting out the data that will not be regridded with cvel2 and concatenate regridded and non-regridded sets at the end. In the case of Multi-MS input, the user should use virtualconcat to achieve a concatenated MMS.

Arguments

Inputs

vis Name of input Measurement set or Multi-MS.

allowed: string

Default:

outputvis Name of output Measurement Set or Multi-MS.

allowed: string

Default:

keepmms If the input is a Multi-MS the output will also be a

Multi-MS.

allowed: bool Default: True

passall HIDDEN parameter. Pass through (write to output MS)

non-selected data with no change

allowed: bool Default: False

field Select field using ID(s) or name(s).

allowed: any Default: variant

spw Select spectral window/channels.

allowed: any Default: variant

scan Select data by scan numbers.

allowed: any Default: variant

antenna Select data based on antenna/baseline.

allowed: any Default: variant

correlation Correlation: " ==> all, correlation='XX,YY'.

allowed: any Default: variant

timerange Select data by time range.

allowed: any Default: variant

intent Select data by scan intent.

allowed: any Default: variant

array Select (sub)array(s) by array ID number.

allowed: any Default: variant

uvrange Select data by paseline length.

allowed: any Default: variant

observation Select by observation ID(s).

allowed: any Default: variant

feed Multi-feed numbers: Not yet implemented.

Returns

void

Example

```
Detailed description of keyword arguments:
--- Input/Output parameters ---
    vis -- Name of input visibility file
        default: ''; example: vis='ngc5921.ms'
    outputvis -- Name of output visibility file or Multi-MS
        default: ''; example: outputvis='ngc5921.mms'
    keepmms -- Create a Multi-MS as the output if the input is a Multi-MS.
       default: True
    By default it will create a Multi-MS when the input is a Multi-MS.
    The output Multi-MS will have the same partition axis of the input MMS.
    See 'help partition' for more information on the MMS format.
   NOTE: It is not possible to combine the spws if the input MMS was partitioned with
          separationaxis='spw'. In this case, the task will abort with an error.
--- Data selection parameters ---
    field -- Select field using field id(s) or field name(s).
             [run listobs to obtain the list iof d's or names]
        default: ''=all fields If field string is a non-negative
           integer, it is assumed to be a field index
           otherwise, it is assumed to be a field name
           field='0~2'; field ids 0,1,2
           field='0,4,5~7'; field ids 0,4,5,6,7
           field='3C286,3C295'; fields named 3C286 and 3C295
           field = '3,4C*'; field id 3, all names starting with 4C
    spw -- Select spectral window/channels
        default: ''=all spectral windows and channels
           spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
```

spw='<2'; spectral windows less than 2 (i.e. 0,1)

```
spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw = '*:3~64' channels 3 through 64 for all sp id's
               spw = ':3^64' will NOT work.
           NOTE: mstransform does not support multiple channel ranges per
                 spectral window (';').
scan -- Scan number range
   default: ''=all
antenna -- Select data based on antenna/baseline
    default: '' (all)
        Non-negative integers are assumed to be antenna indices, and
        anything else is taken as an antenna name.
    examples:
        antenna='5&6': baseline between antenna index 5 and index 6.
        antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8': baselines 5-6 and 7-8
        antenna='5': all baselines with antenna 5
        antenna='5,6,10': all baselines including antennas 5, 6, or 10
        antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                               10. (cross-correlations only. Use &&
                               to include autocorrelations, and &&&
                               to get only autocorrelations.)
        antenna='!ea03,ea12,ea17': all baselines except those that
                                   include EVLA antennas ea03, ea12, or
correlation -- Correlation types or expression.
    default: '' (all correlations)
    example: correlation='XX,YY'
timerange -- Select data based on time range:
    default: '' (all); examples,
      timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date, timerange defaults to the
      first day in the dataset
      timerange='09:14:0~09:54:0' picks 40 min on first day
      timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
       on next day
      timerange='09:44:00' data within one integration of time
      timerange='>10:24:00' data after this time
```

spw='0:5~61'; spw 0, channels 5 to 61

```
array -- (Sub)array number range
      default: ''=all
  uvrange -- Select data within uvrange (default units meters)
      default: ''=all; example:
          uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
          uvrange='>4klambda';uvranges greater than 4 kilo-lambda
          uvrange='0~1000km'; uvrange in kilometers
  observation -- Select by observation ID(s)
      default: ''=all
  feed -- Selection based on the feed - NOT IMPLEMENTED YET
      default: ''=all
  datacolumn -- Which data column to use for processing (case-insensitive).
      default: 'all';
      options: 'data', 'model', 'corrected', 'all', 'float_data', 'lag_data',
               'float_data,data', 'lag_data,data'.
      example: datacolumn='data'
     NOTE: 'all' = whichever of the above that are present. If the requested
                    column does not exist, the task will exit with an error.
  mode -- Frequency Specification:
             NOTE: See examples below:
             default: 'channel'
               mode = 'channel'; Use with nchan, start, width to specify
                       output spw. Produces equidistant grid based on first
                       selected channel. See examples below.
               mode = 'velocity', means channels are specified in
      velocity.
               mode = 'frequency', means channels are specified in
      frequency.
               mode = 'channel_b', alternative 'channel' mode.
      Does not force an equidistant grid. Faster.
>>> mode expandable parameters
             Start, width are given in units of channels, frequency
  or velocity as indicated by mode
             nchan -- Number of channels in output spw
               default: -1 = all channels; example: nchan=3
             start -- Start or end input channel (zero-based) depending on the sign of the
               default=0; example: start=5
             width -- Output channel width in units of the input
     channel width (sign indicates whether the start parameter is lower(+) or upper(-) end
```

```
default=1; example: width=4
           interpolation -- Interpolation method (linear, nearest, cubic, spline, fftsh:
             default = 'linear'
       examples:
           spw = '0,1'; mode = 'channel'
              will produce a single spw containing all channels in spw
     0 and 1
           spw='0:5~28^2'; mode = 'channel'
              will produce a single spw made with channels
     (5,7,9,\ldots,25,27)
           spw = '0'; mode = 'channel': nchan=3; start=5; width=4
              will produce an spw with 3 output channels
              new channel 1 contains data from channels (5+6+7+8)
              new channel 2 contains data from channels (9+10+11+12)
              new channel 3 contains data from channels (13+14+15+16)
           spw = '0:0~63^3'; mode='channel'; nchan=21; start = 0;
 width = 1
              will produce an spw with 21 channels
              new channel 1 contains data from channel 0
              new channel 2 contains data from channel 2
              new channel 21 contains data from channel 61
           spw = '0:0~40^2'; mode = 'channel'; nchan = 3; start =
 5; width = 4
              will produce an spw with three output channels
              new channel 1 contains channels (5,7)
              new channel 2 contains channels (13,15)
              new channel 3 contains channels (21,23)
phasecenter -- Direction measure or fieldid. To be used in mosaics to indicate
           the center direction to be used in the spectral coordinate transformation.
        default: '' (first selected field)
        options: FIELD_ID (int) or center coordinate measure (str).
        example: phasecenter=6 or phasecenter='J2000 19h30m00 -40d00m00'
restfreq -- Specify rest frequency to use for output image
           default='' Occasionally it is necessary to set this (for
           example some VLA spectral line data). For example for
           NH_3 (1,1) put restfreq='23.694496GHz'
outframe -- output reference frame (not case-sensitive)
           possible values: LSRK, LSRD, BARY, GALACTO, LGROUP, CMB, GEO, TOPO, or SOURCE
           (SOURCE is meant for solar system work and corresponds to GEO + radial veloc:
           correction for ephemeris objects).
           default='' (keep original reference frame); example: outframe='BARY'
veltype -- definition of velocity (in mode)
```

default = 'radio'

hanning -- if true, Hanning smooth frequency channel data to remove Gibbs ringing

The intent of cvel2 is to transform channel labels and the visibilities to a spectral reference frame which is appropriate for the science analysis, e.g. from TOPO to LSRK to correct for Doppler shifts throughout the time of the observation. Naturally, this will change the shape of the spectral feature to some extent. According to the Nyquist theorem you should oversample a spectrum with twice the numbers of channels to retain the shape. Based on some tests, however, we recommend to observe with at least 3-4 times the number of channels for each significant spectral feature (like 3-4 times the linewidth). This will minimize regridding artifacts in cvel2.

If cvel2 has already established the grid that is desired for the imaging, clean should be run with exactly the same frequency/velocity parameters as used in cvel2 in order to avoid additional regridding in clean.

Hanning smoothing is optionally offered in cvel2, but tests have shown that already the regridding process itself, if it involved a transformation from TOPO to a non-terrestrial reference frame, implies some smoothing (due to channel interpolation) such that Hanning smoothing may not be necessary.

 ${\it deconvolve-task.html}$

0.1.19 deconvolve

Requires:

Synopsis

Image based deconvolver

Description

Several algorithms are available to deconvolve an image with a known psf (dirty beam), or a Gaussian beam. The algorithms available are clark and hogbom clean, a multiscale clean and a mem clean.

NOTE: Recommend using taskname=clean if psf is a dirty beam

Arguments

Inputs imagename Input image to deconvolve allowed: string Default: model Output image containing deconvolved point model allowed: string Default: Point spread function (dirty beam) psf allowed: stringArray Default: Algorithm to use (clark, hogbom, multiscale, mem) alg allowed: string Default: clark niter number of iteration in deconvolution process allowed: int Default: 10 CLEAN gain parameter gain allowed: double Default: 0.1 threshold mJylevel below which sources will not be deconvolved allowed: doublemJy Default: 0.0 image mask to limit region of deconvolution maskallowed: string Default: scales scale sizes (pixels) to deconvolve allowed: intArray Default: 0310 sigma mJvmem parameter: Expected noise in image allowed: doublemJy Default: 0.0 mem parameter: Estimated total flux in image targetflux Jyallowed: doubleJy Default: 1.0 mem parameter: prior image for mem search prior allowed: string

Returns

void

Example

Default:

Several algorithms are available to deconvolve an image with a known psf (dirty beam), or a Gaussian beam. The algorithms available are clark and hogbom clean, a multiscale clean and a mem clean. For more deconvolution control, use clean.

```
Keyword arguments:
imagename -- Name of input image to be deconvolved
model
         -- Name of output image containing the clean components
          -- Name of psf image (dirty beam) to use
psf
                example: psf='casaxmlf.image' .
              If the psf has 3 parameter, then a Gaussian
        psf is assumed with the values representing
                the major , minor and position angle values
                e.g psf=['3arcsec', '2.5arcsec', '10deg']
alg
          -- algorithm to use: default = 'clark'
                  options: clark, hogbom, multiscale or mem.
niter
         -- Maximum number of iterations
gain
          -- CLEAN gain parameter; fraction to remove from peak
threshold -- Halt deconvolution if the maximum residual image is
                below this threshold.
                default = '0.0Jy'
          -- mask image (same shape as image and psf) to limit region
mask
                where deconvoltion is to occur
-----parameters useful for multiscale only
scales
          -- in pixel numbers; the size of component to deconvolve.
                 default value [0,3,10]
                 recommended sizes are 0 (point), 3 (points per clean beam), and
                 10 (about a factor of three lower resolution)
-----parameters useful for mem only
          -- Estimated noise for image
targetflux -- Target total flux in image
          -- Prior image to guide mem
```

delmod-task.html

0.1.20 delmod

Requires:

Synopsis

Deletes model representations in the MS

Arguments

Inputs			
vis	Name of input visibility file (MS)		
	allowed: string		
	Default:		
otf	Delete the on-the-fly model data keywords		
	allowed: bool		
	Default: True		
field	Select field using field id(s) or field name(s)		
	allowed: string		
	Default:		
scr	Delete the MODEL_DATA scr col (if it exists)		
	allowed: bool		
	Default: False		

Returns

void

Example

This utility task is to be used to delete the model visibility data representations in the MS. The 'otf' representation is the new (as of v3.4) 'scratch-less' model data, stored as keywords in the MS header containing model data formation instructions. It is generated by the setjy, ft, and clean tasks (usescratch=F), and if present, overrides the old-fashioned MODEL_DATA column (if present). If a user

wishes to use the MODEL_DATA column _after_ having operated with the 'otf' representation, this task can be used to delete the 'otf' representation to make the MODEL_DATA column visible. (Create the MODEL_DATA column by using usescratch=T in setjy, ft, or clean; or by running the clearcal task with addmodel=T.)

If otf=T, specific fields can be selected for deletion using standard field selection semantics. If field='', all fields' models will be deleted.

For convenience, this method also provides a means for deleting the MODEL_DATA column by setting scr=T. Note that it is not possible to delete the MODEL_DATA column per field.

If otf=F and scr=F, delmod will provide a listing of the header field records.

 $exportasdm\hbox{-}task.html$

0.1.21 exportasdm

Requires:

Synopsis

Convert a CASA visibility file (MS) into an ALMA or EVLA Science Data Model

Arguments

Inputs MS name vis allowed: string Default: asdm Name of output ASDM directory (on disk) allowed: string Default: datacolumn specifies which MS data column is used to fill the visibilites in the ASDM allowed: string Default: data the X0 in uid://X0/X1/X<running> archiveid allowed: string Default: S0rangeid the X1 in uid://X0/X1/X<running> allowed: string Default: X1 subscanduration maximum duration of a subscan in the output ASDM allowed: string Default: 24hsbduration maximum duration of a scheduling block (and therefore exec block) in the output ASDM allowed: string Default: 2700sapcorrected data to be marked as having atmospheric phase correction allowed: bool Default: False verbose produce log output allowed: bool Default: True showversion Report the version of ASDM class set being used allowed: bool Default: True useversion Selects the version of MS2asdm to be used ('v3' (default and only option presently))

Returns

bool

Example

string

v3

allowed:

Default:

will produce an ASDM named 'uid___S021_X1418_X1' using the datacolumn 'corrected' in the MS 'ngc4826.ms' with minimal log output.

The sbduration parameter controls the number of execution blocks (EBs) into which exportasdm subdivides the visibilities from your input MS. If the total observation time in the MS is shorter than what is given in sbduration, a single EB will be created.

Note concerning ALMA data: exportasdm presently is not able to export from MSs containing WVR data. If you attempt to export such an MS, you will receive an error message saying that you can only export data of processor type "CORRELATOR". It will also give you the list of SPWs which contain CORRELATOR data. You will then have to split out these SPWs using the task "split" and run exportasdm on the resulting MS.

Also EVLA data can be exported. Note here that exportasdm does not produce online flags and that a subsequent reimport of the data must be done with online=False. Also, importevla will only work on your ASDM if you have exported it with apcorrected=False (the default).

importevla('xosrosdm', vis = 'xosro.ms')
exportasdm(vis='xosro.ms', asdm='xosrosdm', apcorrected=False)
importevla(asdm='xosro2asdm', vis='xosro2-reimp.ms', online=False)

export fits-task.html

0.1.22 exportfits

Requires:

Synopsis

Convert a CASA image to a FITS file

Description

CASA-produced images can be exported as FITS files for transporting to other software packages or publication. No subimaging of the fits image can be made with this task. The spectral reference frame can be changed prior to export using the task imreframe.

Arguments

Inputs Name of input CASA image imagename allowed: string Default: fitsimage Name of output image FITS file allowed: string Default: velocity Use velocity (rather than frequency) as spectral axis allowed: bool False Default: Use the optical (rather than radio) velocity convention optical allowed: bool Default: False bitpix Bits per pixel allowed: int Default: -32 minpix Minimum pixel value (if minpix > maxpix, value is automatically determined) allowed: any Default: variant 0 maxpix Maximum pixel value (if minpix > maxpix, value is automatically determined) allowed: any Default: variant -1 overwrite Overwrite pre-existing imagename allowed: bool False Default: dropstokes Drop the Stokes axis? allowed: bool Default: False Put Stokes axis last in header? stokeslast allowed: bool Default: True history Write history to the FITS image? allowed: bool Default: True dropdeg Drop all degenerate axes (e.g. Stokes and/or Frequency)? allowed: bool Default: False

Example

exportfits(imagename='NGC3256-continuum.image', fitsimage='NGC3256cont.fits', history=Fals

exi	nor	t.11x	fits-	tas]	k ł	$_{\rm tml}$
CV	DOL	uuv	TI UD.	- vas	м.т	101111

0.1.23 exportuvfits

Requires:

Synopsis Convert a CASA visibility data set to a UVFITS file:

Description

Arguments

Inputs

vis Name of input visibility file

allowed: string

Default:

fitsfile Name of output UV FITS file

allowed: string

Default:

datacolumn Visibility file data column

allowed: string
Default: corrected

field Select field using field id(s) or field name(s)

allowed: any
Default: variant

spw Select spectral window/channels

allowed: string

Default:

antenna Select data based on antenna/baseline

allowed: string

Default:

timerange Select data based on time range

allowed: string

Default:

avgchan Channel averaging width (value > 1 indicates averaging)

allowed: int Default: 1

writesyscal Write GC and TY tables, (Not yet available)

allowed: bool Default: False

multisource Write in multi-source format

allowed: bool Default: True

combinespw Export the spectral windows as IFs

allowed: bool Default: True

writestation Write station name instead of antenna name

allowed: bool Default: True

padwithflags Fill in missing data with flags to fit IFs

allowed: bool Default: False

overwrite Overwrite output file if it exists?

allowed: bool Default: False

Example

This task writes a UVFITS file, a general format data set used to transfer data between different software systems. It is written in floating point format. Different programs have different restrictions on what forms of UVFITS files they will use, especially whether they will accept multiple sources and/or spectral windows in the same file. See the spw, multisource, and combinespw descriptions below.

```
Keyword arguments:
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
fitsfile -- Name of output UV FITS file
        default: none; example='3C273XC1.fits'
datacolumn -- Visibility file data column
        default: => 'corrected'; example: datacolumn='model'
        Options: 'data' (raw), 'corrected', 'model', 'weight'
field -- Select field using field id(s) or field name(s).
          [run listobs to obtain the list id's or names]
       default: ''=all fields
       If field string is a non-negative integer, it is assumed a field index
       otherwise, it is assumed a field name
       field='0~2'; field ids 0,1,2
       field='0,4,5^{\sim}7'; field ids 0,4,5,6,7
       field='3C286,3C295'; field named 3C286 adn 3C295
       field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
         type 'help par.selection' for more examples.
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61, INCLUSIVE
       spw='*:5~61'; all spw with channels 5 to 62
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                 NOTE ';' to separate channel selections
       spw='0:0~10^2,1:20~30^5'; spw 0, channels 0,2,4,6,8,10,
             spw 1, channels 20,25,30
antenna -- Select data based on antenna/baseline
       default: '' (all)
       If antenna string is a non-negative integer, it is assumed
  an antenna index
```

```
otherwise, it is assumed as an antenna name
       antenna='5&6'; baseline between antenna index 5 and index 6.
       antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
       antenna='5\&6;7\&8'; baseline 5-6 and 7-8
       antenna='5'; all baselines with antenna index 5
       antenna='05'; all baselines with antenna name '05', vla antenna
       antenna='5,6,10'; all baselines with antennas 5, 6 and 10
timerange -- Select data based on time range:
       default = '' (all); examples,
       timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing dat defaults to first day in data set
       timerange='09:14:0~09:54:0' picks 40 min on first day
       timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
       timerange='09:44:00' data within one integration of time
       timerange='>10:24:00' data after this time
avgchan -- Channel averaging width (value > 1 indicates averaging)
       default =>1; example: avgchan=3
       output data will average channels in groups of three.
multisource -- Write in multi-source format
       default: => True;
           false if one source is selected
       True works with AIPS, but not difmap.
combinespw -- If True, export the spectral windows as IFs.
              Otherwise multiple windows will use multiple FREQIDs.
       default: => True;
           all spectral windows must have same shape.
       True is recommended for AIPS, and mandatory for difmap.
padwithflags -- If True, and combinespw is True, fill in missing
                data as needed to fit the IF structure. This is
                appropriate if the MS had a few frequency-dependent
                flags applied, and was then time-averaged by split, or
                when exporting for use by difmap. If the spectral
                windows were observed at different times,
                padwithflags=True will add a large number of flags,
                making the output file significantly longer. It does
                not yet support spectral windows with different widths.
writestation -- Write station name instead of antenna name
       default: True;
writesyscal -- Write GC and TY tables
       default: => False; Not yet available
overwrite -- Overwrite specified output file if it exists?
```

feather-task.html

0.1.24 feather

Requires:

Synopsis

Combine two images using their Fourier transforms

Description

The algorithm converts each image to the gridded visibility plane, combines them, and reconverts them into an combined image. Each image must include a well-defined beam shape (clean beam) in order for feathering to work well. The two images must have the same flux density normalization scale.

Arguments

Inputs				
imagename	Name of output feathered image			
	allowed:	string		
	Default:			
highres	Name of high	ne of high resolution (interferometer) image		
	allowed:	string		
	Default:			
lowres	Name of low resolution (single dish) image			
	allowed:	string		
	Default:			
sdfactor	Scale factor to apply to Single Dish image			
	allowed:	double		
	Default:	1.0		
effdishdiam	New effective SingleDish diameter to use in m			
	allowed:	double		
	Default:	-1.0		
lowpassfiltersd	passfiltersd Filter out the high spatial frequencies of the SD			
	allowed:	bool		
	Default:	False		

Example

Feathering is a simple method for combining two images with different spatial resolution. The processing steps are:

- 1. Regrid the low-resolution image to a temporary copy matching the resolution of the high-resolution image,
 - 2. Transform each image to the spatial-frequency plane (gridded).
 - 3. Scale the low-resolution image (uv-grid) by the ratio of the volumes of the two 'clean beams' (high-res/low-res).
 - 4. Add to this, the uv-grid of the high-resolution image, scaled by (1-wt) where 'wt' is the Fourier transform of the 'clean beam' defined in the low-resolution image.
 - 5. Transform back to the image plane.

Both input images must have a well-defined beam shape for this task to work. This could be a 'clean beam' for interferometric images, and a 'primary-beam' for a single-dish image.

The two images must also have the same flux density normalization scale.

Keyword arguments:

imagename -- Name of output feathered image

default: none; example: imagename='orion_combined.im'

highres -- Name of high resolution (interferometer) image

default: none; example: highres='orion_vla.im'

This image is often a clean image obtained from synthesis observations.

lowres -- Name of low resolution (single dish) image

default: none; example: lowres='orion_gbt.im'

This image is often a image from a single-dish observations

or a clean image obtained from lower resolution synthesis observations.

sdfactor -- value by which to scale the Single Dish image. Default is 1.0

Basically modifying the flux scale of the SD image

effdishdiam -- New effective SingleDish diameter to use in m. Obviously one can only reduce lowpassfiltersd -- If True the high spatial frequency in the SD image is rejected.

Any data outside the maximum uv distance that the SD has illuminated is filtered out.

Comments:

This task can be used as one method of combining single-dish and interferometric images after they have been separately made.

The clean task allows another method of combining single-dish and interferometric data. The single-dish image can be used as a starting model for the interferometric image-reconstruction. If there is some overlap between the spatial-frequencies contained in the single-dish image and the interferometer sampling function, then, such a starting model will help constrain the solutions on the short-baselines of the interferometric data.

find-task.html

0.1.25 find

Requires:

Synopsis

Find string in tasks, task names, parameter names:

Description

Lists the following: 1) All of the task names that have the string 2) All of the tasks whose contents (e.g., documentation, parameters, etc) have the string 3) All of the parameter names that have the string

Arguments

Inputs	
matchstring	String to match in the documentation
	allowed: string
	Default:

Example

Find string in tasks, task names, parameter names:

Lists the following:

- 1) All of the task names that have the string
- 2) All of the tasks whose contents (e.g., documentation, parameters, etc) have the string
- 3) All of the parameter names that have the string

```
Keyword arguments:
matchstring -- String to match in the documentation
    default: ''; example: matchstring='vis'
```

0.1.26 fixplanets

Requires:

Synopsis

Changes FIELD and SOURCE table entries based on user-provided direction or POINTING table, optionally fixes the UVW coordinates

Description

This task's main purpose is to correct observations which were performed with correct pointing and correlation but for which incorrect direction information was entered in the FIELD and SOURCE table of the MS. If you actually want to change the phase center of the visibilties in an MS, you should use task fixes

Input Parameters vis – Name of the input visibility set field – field selection string

fixuvw - recalc uvw coordinates? (default: False)

direction – if set, don't use pointing table but set direction to this value. The direction can either be given explicitly or as the path to a JPL Horizons ephemeris (for an example of the format, see directory

data/ephemerides/JPL-Horizons/). Alternatively, the ephemeris table can also be provided as mime format file, i.e. a saved email as obtained via the commands (for example): import recipes.ephemerides.request as jplreq jplreq.request_from_JPL(objnam='Mars',startdate='2012-01-

01',enddate='2013-12-31', date_incr='0.1 d', get_axis_orientation=False, get_axis_ang_orientation=True, get_sub_long=True, use_apparent=False, get_sep=False, return_address='YOUR_EMAIL_ADDESS',

mailserver='YOUR_MAIL_SERVER_ADDRESS') Note: some mail clients may not save the JPL mail properly. Confirmed to work is Thunderbird. default= " (use pointing table)

example: 'J2000 19h30m00 -40d00m00'

refant – if using pointing table information, use it from this antenna default: 0 (antenna id 0) examples: 'DV06' (antenna with name DV06) 3 (antenna id 3) reftime – if using pointing table information, use it from this timestamp default: 'first' examples: 'median' will use the median timestamp for the given field using only the unflagged maintable rows '2012/07/11/08:41:32' will use the given timestamp (must be within the observation time)

Arguments

Inputs
vis

Name of the input visibility set.

is Name of the input visibility set.
allowed: string

Default:

field Fields to operate on. Blank = all.

allowed: any

Default: variant ""

fixuvw recalc uvw?

allowed: bool Default: False

direction if set, don't use pointing table but set direction to this

value

allowed: any Default: variant

refant if using pointing table information, use it from this an-

tenna

allowed: any
Default: variant 0

reftime if using pointing table information, use it

from this timestamp ('first', 'median', or

YYYY/MM/DD/hh:mm:ss)

allowed: string Default: first

Example

Examples:

fixplanets('uid___A002_X1c6e54_X223.ms', 'Titan', True)

will look up the pointing direction from antenna O for field 'Titan' in the POINTING table based on the first timestamp in the main table rows for this field, enter this direction in the FIELD and SOURCE tables, and then recalculate the UVW coordinates for this field.

fixplanets('uid___A002_X1c6e54_X223.ms', 'Titan', True, 'Titan_55438-56292dUTC.tab') will attach the ephemeris table 'Titan_55438-56292dUTC.tab' to field 'Titan' and then recalculate the UVW coordinates for this field.

fixplanets('uid___A002_X1c6e54_X223.ms', 'Titan', False, 'J2000 12h30m15 -02d12m00')
 will set the directions for field 'Titan' in the FIELD and SOURCE table to the

given direction and not recalculate the UVW coordinates.

(This can be useful for several purposes, among them preparing a concatenation of datasets. Only fields with the same direction will be recognised as identical. fixplanets can then be run again after the concatenation using parameters as in the first example above.)

fixvis-task.html

0.1.27 fixvis

Requires:

Synopsis

Recalculates (u, v, w) and/or changes Phase Center

Description

Recalculates (u, v, w) and/or changes Phase Center

Arguments

Inputs vis Name of the input visibility set. allowed: string Default: outputvis Name of the output visibility set. (Can be the same as vis.) allowed: string Default: field Fields to operate on. " = all.allowed: any variant "" Default: refcode reference frame to convert UVW coordinates to allowed: string Default: base UVW calculation on the old values? reuse allowed: bool Default: True phasecenter use this direction as phase center allowed: string Default: distances (experimental) List of the distances (as quanta) of the fields selected by field. allowed: any variant "" Default: datacolumn when applying a phase center shift, modify visibilities only in this/these column(s) allowed: string Default: all

Example

If the phase center is changed, the corresponding modifications are applied to the visibility columns given by the parameter "datacolumn" which is by default set to "all" (DATA, CORRECTED, and MODEL).

refcode -- Reference frame to convert to, default: the refcode of PHASE_DIR in the FIELD table example: 'B1950'

reuse -- base recalculation on existing UVW coordinates? default=True ignored if parameter 'phasecenter' is set

phasecenter -- if set to a valid direction: change the phase center for the given field to this value

example: 'J2000 9h25m00s -05d12m00s'

If given without the equinox, e.g. '0h01m00s +00d12m00s', the parameter is interpreted as a pair of offsets in RA and DEC to the present phasecenter.

NOTE: The RA offset can be given in units of time or angle. If given as a time (i.e. as a single number with a time unit as in, e.g., 12s or in the XXhXXmXXs or XX:XX:XXX formats), it is applied as is. If given as an angle (e.g., 0.01deg), it is divided by the cos(DEC) before it is applied.

distances -- (experimental) List of the distances (as quanta) of the fields selected by to be used for refocussing.

If empty, the distances of all fields are assumed to be infinity. If not a list but just a single value is given, this is applied to all fields.

default: []

examples: ['2E6km', '3E6km'] '15au'

default: 'all' (DATA, CORRECTED, and MODEL)
example: 'DATA,CORRECTED' (will not modify MODEL)

Examples:

fixvis('NGC3256.ms','NGC3256-fixed.ms')

will recalculate the UVW coordinates for all fields based on the existing phase center information in the FIELD table.

fixvis('Moon.ms','Moon-fixed.ms','Moon', '', 'J2000 9h25m00s 05d12m00s')
 will set the phase center for field 'Moon' to the given direction and recalculate
 the UVW coordinates.

flagcmd-task.html

0.1.28 flagcmd

Requires:

Synopsis

Flagging task based on batches of flag-commands

Description

The flagcmd task allows several batch-operations using flag commands. Flag commands follow the mode and parameter names from the flagdata task (also explained below). The available modes are: manual, clip, shadow, quack, elevation, tfcrop, rflag and extend. The summary mode is not supported in this task. Use the flagdata task for that.

The flagcmd task will flag data based on the commands input on inpmode: table = input from FLAG_CMD table in MS list = input from text file or list of strings given in inpfile xml = input from Flag.xml in the MS given by vis Batch operations include: apply/unapply/list/plot/clear/extract IMPORTANT: The FLAG_CMD sub-table is meant only for meta-data selections such as online flags. Using it to save other parameters (from modes such as clip, quack, shadow, etc) is possible but carries a risk that in future releases these parameters maybe renamed or changed their default values. Use it at your own risk! There will be no automatic way to rename any parameter that changes in the future.

There is no way to guarantee that a command from the COMMAND column has been applied or not to the MS, even if the APPLIED column is set to True. If you use other ways to flag such as interactive flagging in plotms, the FLAG_CMD will not be updated! Use at your own risk.

NOTE on flagging calibration tables.

It is possible to flag cal tables using this task, although we recommend using the flagdata task for this.

When using this task to flag cal tables, only the 'apply' and 'list' actions are supported. Because cal tables do not have a FLAG_CMD sub-table, the default inpmode='table' can only be used if an MS is given in the 'inpfile' parameter so that flags from the MS are applied to the cal table. Otherwise, the flag commands must be given using inpmode='list', either from a file(s) or from a list of strings. See below for more information about these parameters. Data selection for calibration tables is limited to field, scan, antenna, time, spw and observation. If the calibration table was created before CASA 4.1, this task will create a dummy OBSERVATION column and OBSERVATION sub-table in the input calibration table to adapt it to the new cal table format.

Arguments

Inputs

vis Name of MS file or calibration table to flag

allowed: string

Default:

inpmode Input mode for flag commands(table/list/xml)

allowed: string Default: table

inpfile Source of flag commands

allowed: any Default: variant

tablerows Rows of inpfile to read

allowed: intArray

Default:

reason Select by REASON types

allowed: any

Default: variant any

useapplied Select commands whose rows have APPLIED column

set to True

allowed: bool Default: False

tbuff Time buffer (sec) to pad flags

allowed: double

Default: 0.0

ants Allowed flag antenna names to select by

allowed: string

Default:

action Action to perform in MS and/or in inpfile (ap-

ply/unapply/list/plot/clear/extract)

allowed: string
Default: apply

flagbackup Automatically backup the FLAG column before execu-

tion

allowed: bool Default: True

clearall Delete all rows from FLAG_CMD

allowed: bool Default: False

 ${\tt rowlist} \hspace{1.5cm} {\tt FLAG_CMD} \hspace{1mm} {\tt rows} \hspace{1mm} {\tt to} \hspace{1mm} {\tt clear}$

allowed: intArray

Default:

plotfile Name of output file to save plot

allowed: string

Default:

savepars Save flag commands to the MS or to a file

allowed: bool Default: False

outfile Name of output file to save commands

allowed: string

Default:

overwrite Overwrite an existing file to save the flag commands

allowed: bool Default: True

Returns

void

Example

```
Keyword arguments:
vis -- Name of input visibility file or calibration table.
        default: '' (none)
        example1: vis='uid___A002_X2a5c2f_X54.ms' or
        example2: vis='cal-X54.B1'
-- INPUT of flag commands --
inpmode -- Input mode for flag commands.
        options: 'table', 'list', 'xml'
        default: 'table'
   inpmode "table" -- input commands from FLAG_CMD table of MS.
      inpfile -- path to MS containing FLAG_CMD
           default: '' (read from FLAG_CMD table in the MS specified via 'vis')
           Main use is to read flags from internal FLAG_CMD,
           but by setting inpfile to a different MS you can
           use this to copy the flags from one MS to another.
           One use case is to read the flag commands from an MS given in
           inpfile and apply them to a cal table given in vis. Example:
         flagcmd(vis='cal-X54.B1', inpmode='table', inpfile='uid___A002_X2a5c2f_X54.ms'
      tablerows -- list of rows of the FLAG_CMD table to read
           default: [] (read all rows)
           example: [0,1,2,10]
           NOTE: currently only takes integer lists, not
           parseable strings with ranges. Use the Python
           range function to generate ranges, e.g.
              tablerows = range(0,30) + range(50,55)
```

instead of '0~29,50~54' for now.

```
matches this compound reason string only
   useapplied -- select the flag commands of rows that have column APPLIED=True
        options: True, False
        default: False
        If useapplied=True it will read in both applied and
        unapplied flags.
        IMPORTANT: The APPLIED column is set to True after a flag command is applied
                   to the MS. In order to re-apply the same flag command, this
                   parameter should be set to True.
inpmode "list" -- input commands from an ASCII file, a list of files or via a list of
                  NOTE: You can only apply the flags from a list; you will not be ab
                        to unapply them. Transfer the flag commands to the FLAG_CMD to
                        if you want to unapply the flags. For this, see action='list
   inpfile -- name of an ASCII file, list of files or a list of Python strings to app
              MS or cal table.
        default: ''
        options: [] with flag commands or
                 [] with filenames or
                 '' with a filename.
           IMPORTANT: string values must contain quotes around them or the parser
                      will not work. The parser evaluates the commands in the list
                      and considers only existing Python types.
           example1: the following commands can be saved to a file or group of files
                     and given to the task (e.g. save it to flags.txt).
```

mode='clip' clipminmax=[0,2] correlation='ABS_XX' clipoutside=False

spw='9' mode='tfcrop' correlation='ABS_YY' ntime=51.0

scan='1~3' mode='manual'

reason -- select flag commands based on REASON(s)

example: reason='FOCUS_ERROR'

NOTE: what is within the string is literally

and reason = 'FOCUS_ERROR, SUBREFLECTOR_ERROR'

mateched, e.g. reason='' matches only blank reasons,

reason=['FOCUS_ERROR','SUBREFLECTOR_ERROR']

```
flagcmd(vis, inpmode='list',inpfile='flags.txt') or
             flagcmd(vis, inpmode='list', inpfile=['onlineflags.txt','flags.txt'])
        example2: the same commands can be written in a Python list of strings and g
                      to the task.
              cmd=["scan='1~3' mode='manual'",
                   "mode='clip' clipminmax=[0,2] correlation='ABS_XX' clipoutside=Fai
                   "spw='9' mode='tfcrop' correlation='ABS_YY' ntime=51.0",
                   "mode='extend' extendpols=True"]
              flagcmd(vis, inpmode='list',inpfile=cmd)
  reason -- select flag commands to apply, based on REASON(s)
        default: 'any' (all flags regardless of reason)
                 can be a string, or list of strings
        example: reason='FOCUS_ERROR'
                 reason=['FOCUS_ERROR','SUBREFLECTOR_ERROR']
        If inpfile is a list of files, the reasons given in this
        parameter will apply to all the files.
       NOTE: what is within the string is literally
       mateched, e.g. reason='' matches only blank reasons,
        and reason = 'FOCUS_ERROR,SUBREFLECTOR_ERROR'
       matches this compound reason string only
inpmode "xml" -- input online flags from Flag.xml file in the MS. This mode
                 is not available for cal tables. This works only for MSs
                 imported using importevla. It will not work for ALMA MSs.
                 NOTE: You can only apply the flags from a XML file; you will not be
                       to unapply them. Transfer the flag commands to the FLAG_CMD ta
                       if you want to unapply the flags. For this, see action='list'
  tbuff -- (float) time padding buffer (seconds, default=1.0)
  ants -- select flags based on antenna,
             e.g. antenna='ea01'
        default: '' (all flags regardless of antenna)
  reason -- select flag commands based on REASON(s),
        default: 'Any' (all flags regardless of reason)
```

mode='extend' extendpols=True

can be a string, or list of strings
example: reason='FOCUS_ERROR'
 reason=['FOCUS_ERROR', 'SUBREFLECTOR_ERROR']

NOTE: what is within the string is literally mateched, e.g. reason='' matches only blank reasons, and reason = 'FOCUS_ERROR, SUBREFLECTOR_ERROR' matches this compound reason string only

--ACTIONS--

action "apply" -- apply flags to MS or cal table.

This operation will apply the commands chosen by inpmode. If inpmode='table' it will set the APPLIED column to True.

 $\hbox{flagbackup $--$ Automatically backup MS/cal table FLAG column before applying.}$

options: True, False default: True

action "unapply" -- unapply flags in MS. (Not available for cal tables).

This operation will unapply the commands chosen by inpmode='table' ONLY. After unapplying the commands, the task will update the APPLIED column to False.

flagbackup -- Automatically backup MS FLAG column before unapplying?

options: True,False
default: True

action "list" -- list and/or save flag commands.

This operation will list the commands chosen by inpmode on the screen and save them to the MS or to a file without applying. It will save the commands to outfile if the parameter savepars is set to True. If outfile is None, it will save the commands to the MS given in 'vis'.

action "plot" -- plot flags (ant vs. time). (Not available for cal tables)

This operation will plot the flags chosen by inpmode to a

matplotlib gui or to a file. These will be sorted by antenna vs. time. Most useful for showing the online flags.

plotfile -- output plot file
 default: '' (plot to matplotlib window)

WARNING: will only reliably plot individual flags per antenna and timerange (e.g. direct from xml)

action "clear" -- clear flags from FLAG_CMD in MS. (Not available for cal tables)

This operation will delete the selected flag rows from the internal FLAG_CMD table of the MS.

NOTE: choosing this option will disregard anything you set in inpmode and will always work on the ${\rm FLAG_CMD}$ table in vis.

clearall -- really clear all flags?
 default: False (will not clear)

rowlist -- list of FLAG_CMD rows to clear
 default: [] (all flags in table)
 example: [0,1,2,10]

NOTE: currently only takes integer lists, not parseable strings with ranges. Use the Python range function to generate ranges, e.g. rowlist = range(0,30) + range(50,55) instead of '0~29,50~54' for now.

WARNING: this can be dangerous, and you must set clearall=True to use this!!! This will delete the specified rows from the internal FLAG_CMD table for vis regardless of what mode is set to (useful for when you import from xml or file), and decide to redo it). This action will NOT unapply the commands.

action "extract" -- extract internal flag dictionary. (Not available for cal tables)

This option will return the internal flagging dictionary to python.

savepars -- Save the flag commands to the FLAG_CMD table of the MS or to an output text

```
default: False
options: True/False
outfile -- Name of output file to save the flag commands.
   default: ' '; it will save the commands in the FLAG_CMD table of the MS.
   example: outfile='flags.txt' will save the parameters in a text file.
overwrite -- Overwrite the existing file given in 'outfile'.
   options: True/False
   default: True; it will remove the existing file given in 'outfile' and save
                 commands to a new file with the same name. When set to False
                 an error message if the file exist.
```

```
-- Internal FLAG_CMD input 'inpmode' useage --
```

* It is a good idea to use action='list' first to see what is there before doing anything else, e.g.

```
inpmode = 'table'
action = 'list'
```

(For inpmode='table')

* To apply the flags stored in the FLAG_CMD table in the MS, simply set inpmode='table' and action='apply'. This is the default setup of flagcmd. Note that when a flag command is applied, the corresponding APPLIED column cell will be updated to True.

```
inpmode = 'table'
action = 'apply'
useapplied = False
```

* To re-apply the flags stored in the FLAG_CMD table in the MS, inpmode='table', action='apply' and useapplied=True.

```
inpmode = 'table'
action = 'apply'
useapplied = True
```

* To merely save to FLAG_CMD but not apply, then

```
inpmode = 'table'
inpfile = 'other.ms'
```

```
action = 'list'
```

* To save commands from a file into the MS without applying.

```
inpmode = 'list'
inpfile = 'flags.txt'
action = 'list'
```

If you need to select only certain rows from the FLAG_CMD table, use the tablerows parameter to control this. Currently this must be a list of individual row numbers (0-based), e.g.

```
tablerows = [0,1,2,3,10,11]
```

or

```
tablerows = range(29)
```

NOTE: the useapplied=True/False tag is important if you are going to (re)apply flags marked as APPLIED True in FLAG_CMD. It is common to have a "failed" flagging operation mark the flags as already applied and then they don't show up when you re-run (e.g. in 'list'). Set useapplied=True so that it will use these anyway.

* To apply the flag commands from an MS to a calibration table.

```
vis = 'mycaltable'
inpmode = 'table'
inpfile = 'myMS.ms'
action = 'apply'
```

-- Online flag input inpmode useage --

```
(For inpmode='xml')
```

* To list the online flags stored in the Flag.xml file in the MS, simply set:

```
inpmode = 'xml'
action = 'list'
savepars = False
```

* It is then straightforward to save these to FLAG_CMD

```
inpmode = 'xml'
action = 'list'
savepars = True
```

* To directly apply the online flags stored in the Flag.xml file in the MS, set inpmode='xml' and desired buffer, e.g.

```
inpmode = 'xml'
tbuff = 1.0  # pad flag times by 1 sec
action = 'apply'
set savepars to save or not the commands in the MS
```

* You can also specify a set of reasons (a comma separated list) for flags to apply, e.g.

```
reason = 'FOCUS_ERROR,SUBREFLECTOR_ERROR' # select these flags
reason = 'ANTENNA_NOT_ON_SOURCE'
```

NOTE: The online flag time buffer tbuff is specified in seconds, but in fact should be keyed to the intrinsic online integration time. This is particularly true for EVLA data, were a tbuff value of 0.5x to 1.5x the integration time is needed (currently you should use 1.5x for data taken in early 2011 or before).

Because the Flag.xml is copied to the MS by importevla, you can re-apply the online flags with an increased tbuff simply by running with inpmode='xml' and optype='apply', e.g.

```
inpmode = 'xml'
tbuff = 15.0  # pad flag times by 15 sec for 10sec integrations
optype = 'apply'
```

if you originally used a smaller value (e.g. 1.0) by mistake or you want to try longer values. Note these will be added to the FLAG_CMD table which you would have to clean up manually if you care about this.

```
-- Flag command useage --
(For inpmode='list')
```

* For example, a series of commands might be:

```
antenna='ea01' timerange='00:00:00~01:00:00'
```

```
antenna='ea11' timerange='00:00:00~03:00:00' spw='0~4'
     mode='clip' clipminmax=[0,5] correlation='ABS_ALL'
     mode='quack' quackmode='end' quackinterval=1.0
     mode='shadow'
   Any other mode can also use selection (see the help of flagdata):
    mode='shadow' antenna='ea01,ea02,ea03'
    mode='quack' quackmode='end' quackinterval=1.0 antenna='ea22'
   These commands can be saved in an ASCII file, e.g. "myflags.txt"
   and input using inpmode='list', e.g.
     flagcmd(vis='myvis.ms',inpmode='list',inpfile='myflags.txt')
   or input from the interface
     flagcmd(vis='myvis.ms',inpmode='list',
             inpfile=["mode='shadow'",
                      "mode='clip' clipminmax=[0,5] correlation='ABS_ALL'",
                      "mode='quack' quackmode='end' quackinterval=1.0",
                      "antenna='ea01' timerange='00:00:00~01:00:00'",
                      "antenna='ea11' timerange='00:00:00~03:00:00' spw='0~4'"])
-- ACTIONs --
   The action parameter controls what flagcmd will actually do with the
   flag commands:
   * action = 'apply'
     This will apply the selected commands to the data.
     If inpmode='table' and inpfile='' then the APPLIED column in FLAG_CMD
     will be set to True.
   * action = 'unapply'
     This will unapply any commands on the selected data that
     come from the FLAG_CMD table.
   * action = 'list'
    List what is selected and or save in the MS or in a file. It is wise to do
     this first before doing any other action. It will list the output in the logger
```

and save them to the FLAG_CMD table of the MS when savepars=True and outfile = '' to a file if outfile is non-blank.

* action = 'plot'

Will pop up a little matplotlib GUI (if outfile='') or plot to a file. Currently only gives an antenna vs time plot, mostly useful for looking at the online flags.

* action = 'clear'

DANGER! This can be used to totally delete rows from the FLAG_CMD table. It ignores what inpmode is pointing to and always works on FLAG_CMD. Use at your own peril but sometimes you need to just blow that table away, e.g.

```
vis = msfile
optype = 'clear'
rowlist = []  # all rows
clearall = True  # disarm the safety
```

Note you have to explicitly set clearall=True to arm the deletion (a minimal precaution).

* action = 'extract'

This option will return the internal flagging dictionary to python. This will allow a power-user to manipulate these commands directly (e.g. for plotting etc.). For example,

myflagd = flagcmd(vis=msfile,useapplied=True,action='extract')

will extract all the commands (including those already applied) in the FLAG_CMD MS table.

NOTE: There is no extant description of the format of this dictionary, as it is an internal device used by the flagcmd task. This action is provided for the convenience of advanced users.

----- FLAG COMMAND SYNTAX -----

The command syntax is based on the flagdata parameters.

Basic Syntax Rules

Commands are a string (which may contain internal "strings") consisting of KEY=VALUE pairs separated by whitespace (see examples below).

NOTE: There should be no whitespace between KEY=VALUE or within each KEY or VALUE, since the simple parser first breaks command lines on whitespace, then on "=".

Each key should only appear once on a given command line/string

There is an implicit "mode" for each command, with the default being 'manual' if not given.

Comment lines can start with '#' and will be ignored.

1. Data selection parameters (used by all flagging modes)

```
timerange=''
antenna=''
spw=''
correlation=''
field=''
scan=''
feed=''
array=''
uvrange=''
intent=''
observation=''
```

Note: a command consisting only of selection key-value pairs is a basic "manual" operation, ie. flag the data meeting the selection.

- 2. Modes specific parameters with default values (for further details and updated default values, refer to the task flagdata).
 - 2.1 Mode manual. autocorr=False
 - 2.2 Mode clip.
 datacolumn='DATA'
 clipminmax=[]
 clipoutside=True
 channelavg=False
 clipzeros=False

- 2.3 Mode shadow. tolerance=0.0 addantenna=''
- 2.4 Mode quack.
 quackinterval=1.0
 quackmode='beg'
 quackincrement=False
- 2.5 Mode elevation. lowerlimit=0.0 upperlimit=90.0
- 2.6 Mode tfcrop.
 ntime='scan'
 combinescans=False
 datacolumn='DATA'
 timecutoff=4.0
 freqcutoff=3.0
 timefit='line'
 freqfit='poly'
 maxnpieces=7
 flagdimension='freqtime'
 usewindowstats='none'
 halfwin=1
 extendflags=True
- 2.7 Mode extend.
 ntime='scan'
 combinescans=False
 extendpols=True
 growtime=50.0
 growfreq=50.0
 growaround=False
 flagneartime=False
 flagnearfreq=False
- 2.8 Mode rflag. ntime='scan' combinescans=False datacolumn='DATA' winsize=3 timedev='' freqdev='' timedevscale=5.0

freqdevscale=5.0 spectralmax=1000000.0 spectralmin=0.0 extendflags=True

- 2.9 Mode unflag.
- 3. Basic elaboration options for online and interface use

id=', # flag ID tag (not necessary) reason=', # reason string for flag

flagtime=', # a timestamp for when this flag was generated (for user history use)

> NOTE: there is no flagtime column in FLAG_CMD at this time, but we will propose to add this as an optional column

NOTE: These are currently ignored and not used.

4. Extended elaboration options for online and interface use Note: these are FLAG_CMD columns, but their use is not clear but included here for compatibility and future expansion

flagging "level" for flags with same reason level=N

Severity code for the flag, on a scale of 0-10 in order severity=N

of increasing severity; user specified

flagdata-task.html

0.1.29 flagdata

Requires:

Synopsis

All-purpose flagging task based on data-selections and flagging modes/algorithms.

Description

This task can flag a Measurement Set or a calibration table. It has two main types of operation. One type will read the parameters from the interface and flag using any of the various available modes. The other type will read the commands from a text file, a list of files or a Python list of strings, containing a list of flag commands (each line containing data selection parameters and any parameter specific for the mode being requested). Please see examples at the end of this help.

It is also possible to only save the parameters set in the interface without flagging. The parameters can be saved in the FLAG_CMD sub-table or in a text file. Note that when saving to an external file, the parameters will be appended to the given file.

The available flagging modes are: manual, clip, shadow, quack, elevation, tfcrop, rflag, extend, unflag and summary. For automatic flagging, it is recommended to combine auto-flag modes with extend, via the list mode. The current flags can be automatically backed up before applying new flags if the parameter flagbackup is set. Previous flag versions can be recovered using the flagmanager task.

NOTE on flagging calibration tables. —

Flagdata can flag many types of calibration tables using mode='manual'. It can only flag using the auto-flagging algorithms (clip, tfcrop or rflag), the cal tables that have the following data columns: CPARAM, FPARAM or SNR. The solution elements of the data columns are given in the correlation parameter using the names 'Sol1', 'Sol2', 'Sol3', or 'Sol4'. See examples at the end of this help on how to flag different cal tables.

When the input is a calibration table, the modes 'elevation' and 'shadow' will be disabled. Data selection for calibration tables is limited to field, scan, time, antenna, spw and observation. It is only possible to save the parameters to an external file. If the calibration table was created before CASA 4.1, this task will create a dummy OBSERVATION column and OBSERVATION sub-table in the input calibration table to adapt it to the new cal table format.

Selecting antennas in some calibration tables have a different meaning compared to selecting the MS. Some calibration tables such as the antenna-based ones, created with some modes of gencal or polcal, have the ANTENNA2 column set to -1. This means that when selecting antenna='ANT', will select the whole ANT and not the cross-correlations between ANT and the other antennas. Similarly, the baseline syntax do not apply to this type of calibration tables. Those values with ampersand do not have any meaning when selecting antenna/baselines in antenna-based cal tables.

The task will flag a subset of data based on the following modes of operation: list = list of flagging commands to apply to MS/cal table manual = flagging based on specific selection parameters clip = clip data according to values quack = remove/keep specific time range at scan beginning/end shadow = remove antenna-shadowed data elevation = remove data below/above given elevations tfcrop = automatic identification of outliers on the time-freq plane rflag = automatic detection of outliers based on sliding-window RMS filters extend = extend and/or grow flags beyond what the basic algorithms detect summary = report the amount of flagged data unflag = unflag the specified data

Arguments

Inputs vis Name of MS file or calibration table to flag allowed: string Default: mode Flagging mode allowed: string Default: manual autocorr Flag only the auto-correlations allowed: bool Default: False inpfile Input ASCII file, list of files or Python list of strings with flag commands. allowed: any Default: variant Select by REASON types reason allowed: any Default: variant any tbuff List of time buffers (sec) to pad timerange in flag commands allowed: any Default: variant 0.0 Spectral-window/frequency/channel: spw all, $spw = '0:17 \sim 19'$ allowed: any Default: variant field Field names or field index numbers: " ==> all, $field='0\sim2,3C286'$ allowed: any Default: variant Antenna/baselines: " ==> all, antenna ='3,VA04' antenna allowed: any Default: variant uvrange UV range: " ==> all; uvrange =' $0\sim100$ klambda', default units=meters allowed: any Default: variant timerange Time range: " ==> all,timerange='09:14:0 \sim 09:54:0' allowed: any

scan Scan numbers: "==> all

correlation

Default:

allowed:

Default:

allowed: any Default: variant

variant

any

133 variant

Correlation: " ==> all, correlation='XX,YY'

intent Scan intent: " ==> all, intent='CAL*POINT*'

allowed: any Default: variant

Returns

void

Example

```
---- Detailed description of keyword arguments ----
    vis -- Name of input visibility file or calibration table.
        default: '' (none)
        example1: vis='uid___A002_X2a5c2f_X54.ms' or
        example2: vis='cal-X54.B1'
        Any flagging will only be applied to the specified selections.
antenna -- Select data based on baseline
    default: '' (all); example: antenna='DV04&DV06' baseline DV04-DV06
    antenna='DV04&DV06;DV07&DV10' #baselines DV04-DV06 and DV07-DV10
    antenna='DV06' # all cross-correlation baselines between antenna DV06 and
            all other available antennas
    antenna='DV04,DV06' # all baselines with antennas DV04 and DV06
    antenna='DV06&&DV06' # only the auto-correlation baselines for antenna DV06
    antenna='DV04&&*' # cross and auto-correlation baselines between antenna DV04
                             and all other available antennas
    antenna='0~2&&&' # only the auto-correlation baselines for antennas
                                   in range 0~2
    Note that for some antenna-based calibration tables, selecting baselines with
    the & syntax do not apply.
spw -- Select data based on spectral window and channels
    default: '' (all); example: spw='1'
    spw='<2' #spectral windows less than 2
    spw='>1' #spectral windows greater than 1
    spw='1:0~10' # first 10 channels from spw 1
    spw='1:0~5;120~128' # multiple separated channel chunks.
    Note: For modes clip, tfcrop and rflag, channel-ranges can be excluded
    from flagging by leaving them out of the selection range. This is a way to
    protect known spectral-lines from being flagged by the autoflag algorithms.
    Example: if spectral-lines fall in channels 6~9, set the selection range to
```

spw='0:0~5;10~63'.

```
correlation -- Correlation types or expression.
    default: '' (all correlations)
            For modes clip, tfcrop or rflag, the default means ABS_ALL. If
            the input is cal table that does not contain a complex data column,
            the default will fall back to REAL_ALL.
    example: correlation='XX,YY' or
    options: Any of 'ABS', 'ARG', 'REAL', 'IMAG', 'NORM' followed by
             any of 'ALL', 'I', 'XX', 'YY', 'RR', 'LL', 'WVR'
             'WVR' refers to the water vapour radiometer of ALMA data.
                 For calibration tables, the solutions are: 'Sol1', 'Sol2', Sol3, Sol4.
    example: correlation='REAL_XX,XY'
  -->correlation selection is not supported for modes other than clip, tfcrop or
      rflag in cal tables.
   Note that the operators ABS, ARG, REAL, etc. are written only once as the first value.
    if more than one correlation is given, the operator will be applied to all of them.
    The expression is used only in modes clip, tfcrop and rflag.
field -- Select data based on field id(s) or name(s)
    default: '' (all); example: field='1'
    field='0~2' # field ids inclusive from 0 to 2
    field='3C*' # all field names starting with 3C
uvrange -- Select data within uvrange (default units meters)
    default: '' (all); example:
    uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
   uvrange='>4klamda';uvranges greater than 4 kilo-lambda
    uvrange='0~1000km'; uvrange in kilometers
  -->uvrange selection is not supported for cal tables.
timerange -- Select data based on time range:
    default = '' (all); example,
    timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
    Note: YYYY/MM/DD can be dropped as needed:
    timerange='09:14:0~09:54:0' # this time range
    timerange='09:44:00' # data within one integration of time
    timerange='>10:24:00' # data after this time
    timerange='09:44:00+00:13:00' #data 13 minutes after time
scan -- Select data based on scan number
```

default: '' (all); example: scan='>3'

list -- Flag according to the data selection and flag commands specified in the input Interest in the input list may come from a text file, a list of text files or from a Pythof strings. Each input line may contain data selection parameters and any passecific to the mode given in the line. Default values will be used for the parameters that are not present in the line. Each line will be taken as a command to the task. If data is pre-selected using any of the selection parameters, then flagging will apply only to that subset of the MS.

For optimization and whenever possible, the task will create a union of the parameters present in the list and select only that portion of the MS.

NOTE: the flag commands will be applied only when action='apply'. If action='calculate' the flags will be calculated, but not applied. This is useful if display is set to something other than 'none'. I action='' or 'none', the flag commands will not be applied either An empty action is useful only to save the parameters of the list to a file or to the FLAG_CMD sub-table.

inpfile -- Input ASCII file, list of files or a Python list of command string
 default: ''
 options: [] with flag commands or

[] with filenames or '' with a filename.

IMPORTANT: From CASA 4.3 onwards, the parser will be strict and accept of valid flagdata parameters in the list. It will check each parameter and type and exit with an error if any of them is wrong

String values must contain quotes around them or the parser will not work. The parser evaluates the commands in the list and considers only existing Python types.

NOTE: There should be no whitespace between KEY=VALUE since the parser first breaks command lines on whitespace, then on "=". Use only of to separate the parameters (no commas). Scroll down to the bottom a detailed description of the input list syntax.

Example1: the following commands can be saved to a file or group of file and given to the task (e.g. save it to flags.txt).

```
scan='1~3' mode='manual'
mode='clip' clipminmax=[0,2] correlation='ABS_XX' clipoutside=False
spw='9' mode='tfcrop' correlation='ABS_YY' ntime=51.0
mode='extend' extendpols=True
```

flagdata(vis, mode='list', inpfile='flags.txt') or
flagdata(vis, mode='list', inpfile=['onlineflags.txt','otherflags.txt']

Example2: the same commands can be given in a Python list on the command to the task.

```
cmd=["scan='1~3' mode='manual'",
```

"mode='clip' clipminmax=[0,2] correlation='ABS_XX' clipoutside=Fall
"spw='9' mode='tfcrop' correlation='ABS_YY' ntime=51.0",
"mode='extend' extendpols=True"]

flagdata(vis,mode='list',inpfile=cmd)

reason -- select flag commands based on REASON(s) .

default: 'any' (all flags regardless of reason)

can be a string, or list of strings

example: reason='FOCUS_ERROR'

reason=['FOCUS_ERROR', 'SUBREFLECTOR_ERROR']

If inpfile is a list of files, the reasons given in this parameter will apply to all the files.

NOTE: what is within the string is literally matched, e.g. reason='' matches only blank reasons, and reason = 'FOCUS_ERROR,SUBREFLECTOR_ERROR' matches this compound reason string only.

See the syntax for writing flag commands at the end of this help.

tbuff -- A time buffer or list of time buffers to pad the timerange parameter in flag commands. When a list of 2 time buffers is given, it will subtract the first value from the lower time and the second value we added to the upper time in the range. The 2 time buffer values can allowing to have an irregular time buffer padding to time ranges. If the list contains only one time buffer, it will use it to subtract from t0 and add to t1. If more than one list of input files is given the total the files of the flag commands that have timerange parameters and the files of the flag commands.

default: 0.0 (it will not apply any time padding)

The timeranges in the online.txt file are first converted to seconds. Then, 0.5 is subtracted from t0 and 0.8 is added to t1, where t0 and t1 are the two intervals given in timerange. Similarly tbuff will be applied to any timerange in userflags.txt.

IMPORTANT: This parameter assumes that timerange = t0 ~ t1, therefore
 not work if only t0 or t1 is given.

NOTE: The most common use-case for thuff is to apply the online flags that are created by importasdm when savecmds=True. The value of a regular time buffer should be thuff=0.5*max(integration time)

------ MANUAL MODE ------

manual -- Flag according to the data selection specified.

This is the default mode (used when the mode is not specified).

autocorr -- Flag only the auto-correlations. Note that this parameter is only active when set to True. If set to False it does NOT mean "do not flag auto-correlations". When set to True, it will only flag data from a processor of type CORRELATOR.

default: False
options: True,False

------ CLIP MODE -----

clip -- Clip data according to values of the following subparameters. The polarizat:

expression is given by the correlation parameter. For calibration tables, the solutions are also given by the correlation parameter.

datacolumn -- Column to use for clipping.

default: 'DATA'

options: MS columns: 'DATA', 'CORRECTED', 'MODEL', 'RESIDUAL', 'RESIDUAL

'WEIGHT_SPECTRUM', 'WEIGHT', 'FLOAT_DATA'.

Cal table columns: 'FPARAM', 'CPARAM', 'SNR', 'WEIGHT'.

NOTE1: RESIDUAL = CORRECTED - MODEL RESIDUAL_DATA = DATA - MODEL

NOTE2: when datacolumn is WEIGHT, the task will internally use WEIGHT_SI If WEIGHT_SPECTRUM does not exist, it will create one on-the-fly based on the values of WEIGHT.

clipminmax -- Range of data (Jy) that will NOT be flagged.

default: []; it will flag only NaN and Infs.

example: [0.0,1.5]

It will always flag the NaN/Inf data, even when a range is specified.

clipoutside -- Clip OUTSIDE the range?

default: True

example: False; flag data WITHIN the clipminmax range.

channelavg -- Pre-average data across channels before analyzing visibilities

Partially flagged data is not be included in the average unles

contributing to a given output channel is flagged. If present,

SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_S

CORRECTED_DATA and SIGMA_SPECTRUM for DATA).

default: False
options: True/False

NOTE1: Pre-average across channels is not supported in list mode. NOTE2: Pre-average across channels is not supported for calibration

chanbin -- Bin width for channel average in number of input channels.

If a list is given, each bin applies to one of the selected SPWs.

When chanbin is set to 1 all input channels are used considered for average to produce a single output channel, this behaviour aims to backwards compatibility with the previous pre-averaging feature of default: 1

timeavg -- Pre-average data across time before analyzing visibilities for flat Partially flagged data is not be included in the average unless a contributing to a given output channel is flagged. If present, WE:

SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_SPECCORRECTED_DATA and SIGMA_SPECTRUM for DATA). Otherwise WEIGHT/SIGN average together data from different integrations.

default: False
options: True/False

NOTE1: Pre-average across time is not supported in list mode.

NOTE2: Pre-average across time is not supported for calibration to

default: '0s'

clipzeros -- Clip zero-value data.

default: False

----- QUACK MODE -----

quack -- Option to remove specified part of scan beginning/end.

quackinterval -- Time in seconds from scan beginning or end to flag. Make times smaller than the desired time.

default: 0.0
quackmode -- Quack mode

default: 'beg'

options: 'beg' ==> flag an interval at the beginning of scan

'endb' ==> flag an interval at the end of scan

'tail' ==> flag all but an interval at the beginning of scan

'end' ==> flag all but an interval at end of scan

Visual representation of quack mode flagging one scan with 1s of The following diagram shows what is flagged for each quack mode quackinterval is set to 0.25s. The flagged part is represented

```
False ==> the quack interval is counted from the
                               beginning of the scan
                    True ==> the quack interval is counted from the
                               first unflagged data in the scan
shadow -- Option to flag data of shadowed antennas. This mode is not available
           for cal tables.
          All antennas in the antenna-subtable of the MS (and the corresponding
          diameters) will be considered for shadow-flag calculations.
          For a given timestep, an antenna is flagged if any of its baselines
          (projected onto the uv-plane) is shorter than radius_1 + radius_2 - tole
          The value of 'w' is used to determine which antenna is behind the other.
          The phase-reference center is used for antenna-pointing direction.
      tolerance -- Amount of shadowing allowed (or tolerated), in meters.
               A positive number allows antennas to overlap in projection
               A negative number forces antennas apart in projection
               Zero implies a distance of radius_1+radius_2 between antenna center;
          default: 0.0
      addantenna -- It can be either a file name with additional antenna names, pos
                and diameters, or a Python dictionary with the same information.
                You can use the flaghelper functions to create the dictionary from
          default: ''
          To create a dictionary inside casapy.
          > import flaghelper as fh
          > antdic = fh.readAntennaList(antfile)
          Where antfile is a text file in disk that contains information such as:
           name=VLA01
           diameter=25.0
           position=[-1601144.96146691, -5041998.01971858, 3554864.76811967]
           name=VLA02
           diameter=25.0
           position=[-1601105.7664601889, -5042022.3917835914, 3554847.245159178]
    ----- ELEVATION MODE ------
elevation -- Option to flag based on antenna elevation. This mode is not available
```

quackincrement -- Quack incrementally in time?

default: False

for cal tables.

lowerlimit -- Lower limiting elevation in degrees. Data coming from a baselin where one or both antennas were pointing at a strictly lower expectation of time), will be flagged.

default: 0.0

upperlimit -- Upper limiting elevation in degrees. Data coming from a baselin where one or both antennas were pointing at a strictly higher (as function of time), will be flagged.

default: 90.0

----- TFCROP MODE ------

tfcrop -- Flag using the TFCrop autoflag algorithm.

For each field, spw, timerange (specified by ntime), and baseline,

- (1) Average visibility amplitudes along time dimension to form an average spectrum
- (2) Calculate a robust piece-wise polynomial fit for the band-shape at the base of RFI spikes. Calculate 'stddev' of (data fit).
- (3) Flag points deviating from the fit by more than N-stddev
- (4) Repeat (1-3) along the other dimension.

This algorithm is designed to operate on un-calibrated data (step (2)), as well as calibrated data. It is recommended to extend the flags after running this algorithm. See the sub-parameter extendflags below.

options: 'scan' or any other float value or string containing the units

default: 'scan'
example: '1.5min'

: 1.2 (taken in seconds)

The dataset will be iterated through in time-chunks defined here. WARNING: if ntime='scan' and combinescans=True, all the scans will be loaded at once, thus requesting a lot of memory depending on the available spws.

combinescans -- Accumulate data across scans depending on the value of ntime default: False

This parameter should be set to True only when ntime is specified as time-interval (not 'scan'). When set to True, it will remove SCAN for sorting columns, therefore it will only accumulate across scans if ntime is not set to 'scan'.

datacolumn -- Column to use for flagging. (See also the datacolumn explanation default: 'DATA'
options: MS columns: 'DATA', 'CORRECTED', 'MODEL', 'RESIDUAL', 'RESIDUAL', 'WEIGHT_SPECTRUM', 'WEIGHT', 'FLOAT_DATA'.
Cal table columns: 'FPARAM', 'CPARAM', 'SNR', 'WEIGHT'.

timecutoff -- Flag threshold in time. Flag all data-points further than N-stofrom the fit. This threshold catches time-varying RFI spikes (narrow and broad-band), but will not catch RFI that is persisted default: 4.0
Flagging is done in upto 5 iterations. The stddev calculation is converges to a value that reflects only the data and no RFI. At each the same relative threshold is applied to detect flags. (Step (3)

default: 3.0

Same as timecutoff, but along the frequency-dimension. This threshold narrow-band RFI that may or may not be persistent in time.

timefit -- Fitting function for the time direction
 default: 'line'

options: 'line', 'poly'

A 'line' fit is a robust straight-line fit across the entire timerange by 'ntime').

A 'poly' fit is a robust piece-wise polynomial fit across the timerang Note: A robust fit is computed in upto 5 iterations. At each iteration between the data and the fit is computed, values beyond N-stdder and the fit and stdder are re-calculated with the remaining point This stdder calculation is adaptive, and converges to a value the only the data and no RFI. It also provides a varying set of flat that allows deep flagging only when the fit best represents the Choose 'poly' only if the visibilities are expected to vary significant timerange selected by 'ntime', or if there is a lot of strong but interpretations.

freqfit -- Fitting function for the frequency direction

default: 'poly'

options: 'line', 'poly'

Same as for the 'timefit' parameter.

Choose 'line' only if you are operating on bandpass-corrected data, and expect that the bandshape is linear. The 'poly' option works be uncalibrated bandpasses with narrow-band RFI spikes.

maxnpieces -- Maxinum number of pieces to allow in the piecewise-polynomial

default: 7
options: 1 - 9

This parameter is used only if 'timefit' or 'freqfit' are chosen as If there is significant broad-band RFI, reduce this number. Using to pieces could result in the RFI being fitted in the 'clean' bandpass In later stages of the fit, a third-order polynomial is fit per pieces to best results, please ensure that nchan/maxnpieces is at-least 10 pieces.

flagdimension -- Choose the directions along which to perform flagging
 default: 'freqtime'; first flag along frequency, and then along time
 options: 'time', 'freq', 'timefreq', 'freqtime'

For most cases, 'freqtime' or 'timefreq' are appropriate, and different where these choices are apparant only if RFI in one dimension is significantly stronger than the other. The goal is to flag the dom: If there are very few (less than 5) channels of data, then choose Similarly for 'freq'.

 $\hbox{\tt usewindowstats} \,\, \hbox{\tt --} \,\, \hbox{\tt Use sliding-window statistics to find additional flags}.$

default: 'none'

options: 'none', 'sum', 'std', 'both'

Note: This is experimental !

The 'sum' option chooses to flag a point, if the mean-value in a window centered on that point deviates from the fit by more than N-stddev/2.0.

Note: stddev is calculated between the data and fit as explained in This option is an attempt to catch broad-band or time-persistent RFI that the above polynomial fits will mistake as the clean band. It is an approximation to the sumThreshold method found to be effective by Offringa et.al (2010) for LOFAR The 'std' option chooses to flag a point, if the 'local' stddev in a window centered on that point is larger than N-stddev/2.0. This option is an attempt to catch noisy RFI that is not exclude polynomial fits, and which increases the global stddev, and rest fewer flags (based on the N-stddev threshold).

halfwin -- Half width of sliding window to use with 'usewindowstats'

default: 1 (a 3-point window size)

options: 1,2,3

Note: This is experimental !

extendflags -- Extend flags along time, frequency and correlation.

default: True

NOTE: It is usually helpful to extend the flags along time, frequency, and correlation using this parameter, which will run the "extend" mode after "tfcrop" and extend the flags if more than 50% of the timeranges are already flagged, and if more than 80% of the channel are already flagged. It will also extend the flags to the other

polarizations. The user may also set extendflags to False and run the "extend" mode in a second step within the same flagging run. Step example below:

example :

cmd=["mode='tfcrop' freqcutoff=3.0 usewindowstats='sum' extendflags="
"mode='extend' extendpols=True growtime=50.0 growaround=True"]

flagdata(vis, mode='list', inpfile=cmd)

channelavg -- Pre-average data across channels before analyzing visibilities

Partially flagged data is not be included in the average unles

contributing to a given output channel is flagged. If present,

SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_S

CORRECTED_DATA and SIGMA_SPECTRUM for DATA).

default: False
options: True/False

NOTE1: Pre-average across channels is not supported in list mode. NOTE2: Pre-average across channels is not supported for calibration

chanbin -- Bin width for channel average in number of input channels.

If a list is given, each bin applies to one of the selected SPWs.

When chanbin is set to 1 all input channels are used considered for average to produce a single output channel.

default: 1

timeavg -- Pre-average data across time before analyzing visibilities for flat Partially flagged data is not be included in the average unless a contributing to a given output channel is flagged. If present, WE SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_SPECTRUM for DATA). Otherwise WEIGHT/SIGN average together data from different integrations.

default: False
options: True/False

 ${\tt NOTE1:}\ {\tt Pre-average}\ {\tt across}\ {\tt time}\ {\tt is}\ {\tt not}\ {\tt supported}\ {\tt in}\ {\tt list}\ {\tt mode}.$

NOTE2: Pre-average across time is not supported for calibration to

timebin -- Bin width for time average in seconds.
 default: '0s'

------ RFLAG MODE ------

rflag -- Detect outliers based on the RFlag algorithm (ref. E.Greisen, AIPS, 2011).

The polarization expression is given by the correlation parameter.

Iterate through the data in chunks of time. For each chunk, calculate loca statistics, and apply flags based on user supplied (or auto-calculated) the

Step 1 : Time analysis (for each channel)

- -- calculate local rms of real and imag visibilities, within a sliding t
- -- calculate the median rms across time windows, deviations of local rms this median, and the median deviation
- -- flag if local rms is larger than timedevscale x (medianRMS + medianDev

Step 2 : Spectral analysis (for each time)

- -- calculate avg of real and imag visibilities and their rms across channels.
- -- calculate the deviation of each channel from this avg, and the median-
- -- flag if deviation is larger than freqdevscale x medianDev

It is recommended to extend the flags after running this algorithm. See the sub-parameter extendflags below.

Notice that by default the flag implementation in CASA is able to calculate thresholds and apply them on-the-fly (OTF). There is a significant performs gain with this approach, as the visibilities don't have to be read twice, and therefore is highly recommended (see example 1). Otherwise it is possil reproduce the AIPS usage pattern by doing a first run with 'calculate' mode a second run with 'apply' mode. The advantage of this approach is that the are calculated using the data from all scans, instead of calculating them one scan only (see example 3)

Example usage :

- (1) Calculate thresholds automatically per scan, and use them to find flag Specify scale-factor for time-analysis thresholds, use default for fre
 - flagdata('my.ms', mode='rflag',spw='9',timedevscale=4.0)
- (2) Supply noise-estimates to be used with default scale-factors.
 - flagdata(vis='my.ms', mode='rflag', spw='9', timedev=0.1, freqdev=0.5
- (3) Two-passes. This replicates the usage pattern in AIPS.
 - -- The first pass saves commands in an output text files, with auto-cathresholds. Thresholds are returned from rflag only when action='cathresholds this file before doing the second pass, but the python-dictionary structure must be preserved.
 - -- The second pass applies these commands (action='apply').

With action='calculate', display='report' will produce diagnostic postoring data-statistics and thresholds (the same thresholds as those written out to 'tdevfile.txt' and 'fdevfile.txt').

Note: The RFlag algorithm was originally developed by Eric Greisen AIPS (31DEC11).

AIPS documentation: Section E.5 of the AIPS cookbook (Appendix E: Special Considerations for EVLA data calibration and : http://www.aips.nrao.edu/cook.html#CEE)

Note1 : Since this algorithm operates with two passes through each chunk of data (time and freq axes), some data points get flagged twice. This can affect the flag-percentage estimate printed in the logger at runtime. An accurate estimate can be obtained via the summary mode.

Note2: RFlag calculates statistics across all selected correlations Therefore, if there is a significant amplitude difference between parallel-hand and cross-hand correlations, or between different solutions in a gain table, it is advisable to pre-select subsets correlations (or sols) on which to run one instance of RFlag. For example, correlation='RR,LL' or correlation='ABS sol1,sol2'.

ntime -- Timerange (in seconds or minutes) over which to buffer data before the algorithm.

options: 'scan' or any other float value or string containing the units default: 'scan'

example: '1.5min'

: 1.2 (taken in seconds)

The dataset will be iterated through in time-chunks defined here. WARNING: if ntime='scan' and combinescans=True, all the scans will be loaded at once, thus requesting a lot of memory depending on the available spws.

combinescans -- Accumulate data across scans depending on the value of ntime default: False

This parameter should be set to True only when ntime is specified as time-interval (not 'scan'). When set to True, it will remove SCAN from sorting columns, therefore it will only accumulate across scans if ntime is not set to 'scan'.

```
datacolumn -- Column to use for flagging. (See also the datacolumn explanation
     default: 'DATA'
     options: MS columns: 'DATA', 'CORRECTED', 'MODEL', 'RESIDUAL', 'RESIDUAL
              'WEIGHT_SPECTRUM', 'WEIGHT', 'FLOAT_DATA'.
              Cal table columns: 'FPARAM', 'CPARAM', 'SNR', 'WEIGHT'.
winsize -- number of timesteps in the sliding time window (fparm(1) in AIPS
     default: 3
timedev -- time-series noise estimate ( noise in AIPS ).
     default: []
     Examples:
          timedev = 0.5: Use this noise-estimate to calculate flags. Do not
          timedev = [[1,9,0.2], [1,10,0.5]]: Use noise-estimate of 0.2 for
                    \ensuremath{\text{spw}} 9, and noise-estimate of 0.5 for field 1, \ensuremath{\text{spw}} 10.
          timedev = [] : Auto-calculate noise estimates.
freqdev -- spectral noise estimate ( scutoff in AIPS ).
           This step depends on having a relatively-flat bandshape.
           Same parameter-options as 'timedev'.
     default: []
timedevscale -- For Step 1 (time analysis), flag a point if local rms around
                is larger than 'timedevscale' x 'timedev' (fparm(0) in A
     default: 5.0
freqdevscale -- For Step 2 (spectral analysis), flag a point if local rms are
                is larger than 'freqdevscale' x 'freqdev'
                                                                (fparm(10) in
     default: 5.0
spectralmax -- Flag whole spectrum if 'freqdev' is greater than spectralmax
     default: 1E6
spectralmin -- Flag whole spectrum if 'freqdev' is less than spectralmin (f
     default: 0.0
extendflags -- Extend flags along time, frequency and correlation.
     default: True
     NOTE: It is usually helpful to extend the flags along time, frequency,
           and correlation using this parameter, which will run the "extend"
```

mode after "rflag" and extend the flags if more than 50% of the timeranges are already flagged, and if more than 80% of the channel.

are already flagged. It will also extend the flags to the other polarizations. The user may also set extendflags to False and run the "extend" mode in a second step within the same flagging run. Step example below:

example:

cmd=["mode='rflag' freqdevscale=3.0 extendflags=False",
 "mode='extend' extendpols=True growtime=50.0 growaround=True"]

flagdata(vis, mode='list', inpfile=cmd)

channelavg -- Pre-average data across channels before analyzing visibilities

Partially flagged data is not be included in the average unles

contributing to a given output channel is flagged. If present,

SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_SCORRECTED_DATA and SIGMA_SPECTRUM for DATA).

default: False
options: True/False

NOTE1: Pre-average across channels is not supported in list mode. NOTE2: Pre-average across channels is not supported for calibration

chanbin -- Bin width for channel average in number of input channels.

If a list is given, each bin applies to one of the selected SPWs.

When chanbin is set to 1 all input channels are used considered for average to produce a single output channel.

default: 1

timeavg -- Pre-average data across time before analyzing visibilities for flat Partially flagged data is not be included in the average unless a contributing to a given output channel is flagged. If present, WE SIGMA_SPECTRUM are used to compute a weighted average (WEIGHT_SPECTRUM for DATA). Otherwise WEIGHT/SIGN average together data from different integrations.

default: False
options: True/False

NOTE1: Pre-average across time is not supported in list mode.

NOTE2: Pre-average across time is not supported for calibration to

timebin -- Bin width for time average in seconds.
 default: '0s'

----- EXTEND MODE ------

extend -- Extend and/or grow flags beyond what the basic algorithms detect.

This mode will extend the accumulated flags available in the MS,

regardless of which algorithm created them.

It is recommended that any autoflag (tfcrop, rflag) algorithm be followed up by a flag extension.

Extensions will apply only within the selected data, according to the set of extendpols, growtime, growfreq, growaround, flagneartime, flagnearfreq.

Note: Runtime summary counts in the logger can sometimes report larger flag percentages than what is actually flagged. This is because extensions onto already-flagged data-points are counted as new flag. An accurate flag count can be obtained via the summary mode.

ntime -- Timerange (in seconds or minutes) over which to buffer data before the algorithm.

options: 'scan' or any other float value or string containing the units default: 'scan'

example: '1.5min'

: 1.2 (taken in seconds)

The dataset will be iterated through in time-chunks defined here. WARNING: if ntime='scan' and combinescans=True, all the scans will be loaded at once, thus requesting a lot of memory depending on the available spws.

combinescans -- Accumulate data across scans depending on the value of ntime default: False

This parameter should be set to True only when ntime is specified as time-interval (not 'scan'). When set to True, it will remove SCAN from sorting columns, therefore it will only accumulate across scans if ntime is not set to 'scan'.

extendpols -- Extend flags to all selected correlations

default: True
options: True/False

For example, to extend flags from RR to only RL and LR, a data-sele of correlation='RR,LR,RL' is required along with extendpols=True.

growtime -- For any channel, flag the entire timerange in the current 2D chur set by 'ntime') if more than X% of the timerange is already flags default: 50.0

options: 0.0 - 100.0

This option catches the low-intensity parts of time-persistent RFI

growfreq -- For any timestep, flag all channels in the current 2D chunk (set data-selection) if more than X% of the channels are already flags default: 50.0

```
options: 0.0 - 100.0
```

This option catches broad-band RFI that is partially identified by

growaround -- Flag a point based on the number of flagged points around it.

default: False
options: True/False

For every un-flagged point on the 2D time/freq plane, if more the surrounding points are already flagged, flag that point. This option catches some wings of strong RFI spikes.

flagnear time $\operatorname{\mathsf{--}}$ Flag points before and after every flagged one, in the time-

default: False
options: True/False

Note: This can result in excessive flagging.

flagnearfreq -- Flag points before and after every flagged one, in the frequency $\frac{1}{2}$

default: False
options: True/False

This option allows flagging of wings in the spectral response of strong

Note: This can result in excessive flagging

----- UNFLAG MODE -----

unflag -- Unflag according to the data selection specified.

----- SUMMARY MODE -----

summary -- List the number of rows and flagged data points for the MS's meta-data. The resulting summary will be returned as a Python dictionary.

minrel -- Minimum number of flags (relative) to include in histogram default: 0.0

maxrel -- Maximum number of flags (relative) to include in histogram
 default: 1.0

minabs -- Minimum number of flags (absolute, inclusive) to include in histogradefault: 0

maxabs -- Maximum number of flags (absolute, inclusive) to include in histogram To indicate infinity, use any negative number.

default: -1

spwchan -- list the number of flags per spw and per channel.
 default: False

```
basecnt -- list the number of flags per baseline
               default: False
          fieldcnt -- produce a separated breakdown per field
               default: False
          name -- Name for this summary, to be used as a key in the returned
                  Python dictionary. It is possible to call the summary mode
                  multiple times in list mode. When calling the summary mode as a
                  command in a list, one can give different names to each one of
                  them so that they can be easily pulled out of the summary's dictional
               default: 'Summary'
               In summary mode, the task returns a dictionary of flagging statistics.
               Example1:
                   s = flagdata(..., mode='summary')
                Then s will be a dictionary which contains
               s['total'] : total number of data
               s['flagged'] : amount of flagged data
               Exmaple2: two summary commands in list mode, intercalating a manual flag
                   s = flagdata(..., mode='list', inpfile=["mode='summary' name='InitF"]
                                                         "mode='manual' autocorr=True
                                                         "mode='summary' name='Autoco
               The dictionary returned in 's' will contain two dictionaries, one for ea
               two summary modes.
               s['report0']['name'] : 'InitFlags'
               s['report1']['name'] : 'Autocorr'
----- ACTIONS ------
action -- Action to perform in MS/cal table or in the input list of parameters.
   options: 'none', 'apply', 'calculate'
   default: 'apply'
```

spwcorr -- list the number of flags per spw and per correlation.

default: False

'apply' -- Apply the flags to the MS.

display -- Display data and/or end-of-MS reports at run-time. It needs to rea a datacolumn for the plotting. The default for an MS is DATA, but will use FLOAT_DATA for a Sindle-dish MS.

default: 'none'

options: 'none', 'data', 'report', 'both'

'none' --> It will not display anything.

'data' --> display data and flags per-chunk at run-time, within an inte

This option opens a GUI to show the 2D time-freq planes of the data with old and new flags, for all correlations per baseline. -- The GUI allows stepping through all baselines (prev/next) in the current chunk (set by 'ntime'), and stepping to the next-chunk. -- The 'flagdata' task can be quit from the GUI, in case it becomes obvious that the current set of parameters is just wrong. -- There is an option to stop the display but continue flagging.

'report' --> displays end-of-MS reports on the screen.

'both' --> displays data per chunk and end-of-MS reports on the screen

flagbackup -- Automatically backup flags before running the tool.

Flagversion names are chosen automatically, and are based on the

mode being used.

default: True

options: True/False

'calculate' -- Only calculate the flags but do not write them to the MS. This is useful if used together with the display to analyse the results before writing to the MS.

display -- Display data and/or end-of-MS reports at run-time. See extended do above.

default: 'none'

options: 'none', 'data', 'report', 'both'

' ' -- When set to empty, the underlying tool will not be executed and no flags will be produced. No data selection will be done either. This is useful when used together with the parameter savepars to only save the current parameters (or list of parameters) to the FLAG_CMD sub-table or to an external file.

savepars -- Save the current parameters to the FLAG_CMD table of the MS or to an output Note that when display is set to anything other than 'none', savepars will be disabled. This is done because in an interactive mode, the user may skip data which may invalidate the initial input parameters and there is no way to save the interactive commands. When the input is a calibration table it is only possible to save the parameters to a file.

default: False
options: True/False

cmdreason -- A string containing a reason to save to the FLAG_CMD table or output text file given by the outfile sub-parameter. If the ing contains any reason, they will be replaced with this one. At the moment it is not possible to add more than one reason.

default: ' '; no reason will be added to output.

example: cmdreason='CLIP_ZEROS'

outfile -- Name of output file to save the current parameters.

default: ''; it will save the parameters to the FLAG_CMD table of the I example: outfile='flags.txt' will save the parameters in a text file.

overwrite -- Overwrite the existing file given in 'outfile'.

options: True/False

default: True; it will remove the existing file given in 'outfile' and sommands to a new file with the same name. When set to Fa an error message if the file exist.

---- EXAMPLES ----

NOTE: The vector mode of the flagdata task (pre-dating CASA 3.4) can be achieved with the by using it with mode='list' and the commands given in a list in inpmode=[]. Example 1.5 Example 2.5 Example

flagdata('my.ms', inpmode='list', inpfile=["mode='clip' clipzeros=True", "mode='shadow

1) Manually flag scans 1~3 and save the parameters to the FLAG_CMD sub-table.

flagdata('my.ms', scan='1~3, mode='manual', savepars=True)

2) Save the parameters to a file that is open in append mode.

flagdata('my.ms', scan='1~3, mode='manual', savepars=True, outfile='flags.txt')

3a) Flag all the commands given in the Python list of strings.

```
cmd = ["scan='1~3' mode='manual'",
           "spw='9' mode='tfcrop' correlation='ABS_RR,LL' ntime=51.0",
           "mode='extend' extendpols=True"]
    flagdata('my.ms', mode='list', inpfile=cmd)
3b) Flag all the commands given in the file called flags.txt.
    > cat flags.txt
    scan='1~3' mode='manual'
    spw='9' mode='tfcrop' correlation='ABS_RR,LL' ntime=51.0
    mode='extend' extendpols=True
    flagdata('my.ms', mode='list', inpfile='flags.txt')
4) Display the data and flags per-chunk and do not write flags to the MS.
    flagdata('my.ms', mode='list', inpfile='flags.txt', action='calculate', display='da
5) Flag all the antennas except antenna=5.
    flagdata(vis='my.ms', antenna='!5', mode='manual)
6) Clip the NaN in the data. An empty clipminmax will flag only NaN.
    flagdata('my.ms', mode='clip')
7) Clip only the water vapour radiometer data.
    flagdata('my.ms',mode='clip',clipminmax=[0,50], correlation='ABS_WVR')
8) Clip only zero-value data.
    flagdata('my.ms',mode='clip',clipzeros=True)
9a) Flag only auto-correlations of non-radiometer data using the autocorr parameter.
    flagdata('my.ms', autocorr=True)
9b) Flag only auto-correlations using the antenna selection.
    flagdata('my.ms', mode='manual', antenna='*&&&')
10a) Flag based on selected reasons from a file.
    > cat flags.txt
```

```
scan='1~3' mode='manual' reason='MYREASON'
    spw='9' mode='clip' clipzeros=True reason='CLIPZEROS'
   mode='manual' scan='4' reason='MYREASON'
    flagdata('my.ms', mode='list', inpfile='flags.txt', reason='MYREASON')
10b) The same result of 10a can be achieved using the task flagcmd.
    flagcmd('my.ms', inpmode='file', inpfile='flags.txt', action='apply', reason='MYREA
11) Automatic flagging using 'rflag', using auto-thresholds, and specifying
     a threshold scale-factor to use for flagging.
    flagdata('my.ms', mode='rflag',spw='9',timedevscale=4.0,action='apply')
12) Save the interface parameters to the FLAG_CMD sub-table of the MS. Add a reason
    to the flag command. This cmdreason will be added to the REASON column of the
   FLAG_CMD sub-table. Apply flags in flagcmd.
    flagdata('my.ms', mode='clip',channelavg=False, clipminmax=[30., 60.], spw='0:0~10'
              correlation='ABS_XX,XY', action='', savepars=True, cmdreason='CLIPXX_XY')
    > Select based on the reason.
    flagcmd('my.ms', action='apply', reason='CLIPXX_XY')
13) Flag antennas that are shadowed by antennas not present in the MS.
    > Create a text file with information about the antennas.
   > cat ant.txt
     name=VLA01
     diameter=25.0
     position=[-1601144.96146691, -5041998.01971858, 3554864.76811967]
     name=VLA02
     diameter=25.0
     position=[-1601105.7664601889, -5042022.3917835914, 3554847.245159178]
     name=VLA09
     diameter=25.0
     position=[-1601197.2182404203, -5041974.3604805721, 3554875.1995636248]
     name=VLA10
     diameter=25.0
     position=[-1601227.3367843349,-5041975.7011900628,3554859.1642644769]
    flagdata('my.vis', mode='shadow', tolerance=10.0, addantenna='ant.txt')
    The antenna information can also be given as a Python dictionary. To create the
```

dictionary using the flaghelper functions, do the following inside casapy:

- > import flaghelper as fh
- > antdic = fh.readAntennaList(antfile)

flagdata('my.vis', mode='shadow', tolerance=10.0, addantenna=antdic)

- 14) Apply the online flags that come from importasdm.
 - > In importasdm, save the online flags to a file.
 importasdm('myasdm', 'asdm.ms', process_flags=True, savecmds=True, outfile='online.
 - > You can edit the online_flags.txt to add other flagging commands or apply it direct flagdata('asdm.ms', mode='list', inpfile='online_flags.txt')
 - > The same result can be achieved using the task flagcmd.
 flagcmd('asdm.ms', inpmode='file', inpfile='online_flags.txt', action='apply')
- 15) Clip mode pre-averaging data across channels and across time

flagdata(vis='Four_ants_3C286.ms', flagbackup=False, mode='clip', datacolumn='DATA'
timeavg=True, timebin='2s', channelavg=True, chanbin=2)

----- EXAMPLES on FLAGGING CALIBRATION TABLES -----

16) Clip zero data from a bandpass calibration table.

flagdata('cal-X54.B1', mode='clip', clipzeros=True, datacolumn='CPARAM')

17) Clip data from a cal table with SNR <4.0.

flagdata('cal-X54.B1', mode='clip', clipminmax=[0.0,4.0], clipoutside=False, dataco

- 18) Clip the g values of a switched power caltable created using the gencal task. The g usually < 1.0.
 - flagdata('cal.12A.syspower',mode='clip',clipminmax=[0.1,0.3],correlation='Sol1,Sol3
- 19) Now, clip the Tsys values of the same table from above. The Tsys solutions have value 10 -- 100s.

flagdata('cal.12A.syspower', mode='clip', clipminmax=[10.0,95.0], correlation='Sol2, Sol

---- SYNTAX FOR COMMANDS GIVEN IN A FILE or LIST OF STRINGS ----

Basic Syntax Rules

Commands are strings (which may contain internal "strings") consisting of KEY=VALUE pairs separated by one whitespace only.

NOTE: There should be no whitespace between KEY=VALUE. The parser first breaks command lines on whitespace, then on "=".

Use only ONE white space to separate the parameters (no commas).

Each key should only appear once on a given command line/string.

There is an implicit "mode" for each command, with the default being 'manual' if not given.

Comment lines can start with '#' and will be ignored.

The parser used in flagdata will check each parameter name and type and exit with an error if the parameter is not a valid flagdata parameter or of a wrong type.

Example:

```
scan='1~3' mode='manual'
# this line will be ignored
spw='9' mode='tfcrop' correlation='ABS_XX,YY' ntime=51.0
mode='extend' extendpols=True
scan='1~3,10~12' mode='quack' quackinterval=1.0
```

 ${\it flagmanager-task.} html$

0.1.30 flagmanager

Requires:

Synopsis

Enable list, save, restore, delete and rename flag version files.

Description

These flag version files are copies of the flag column for a measurement set. They can be restored to the data set to get back to a previous flag version. On running importvla, a flag version call 'Original' is automatically produced.

Arguments

Inputs	
vis	Name of input visibility file (MS)
	allowed: string
	Default:
mode	Operation: list, save, restore, delete, rename
	allowed: string
	Default: list
versionname	Flag version name
	allowed: string
	Default:
oldname	Flag version to rename
	allowed: string
	Default:
comment	Short description of a versionname
	allowed: string
	Default:
merge	Merge option: replace will save or over-write the flags
	allowed: string
	Default: replace

Returns

void

Example

a previous flag version. On running importasdm, a flag version called 'Original' is produced by default. It is recommended to save a flagversion at the beginning or after serious editing. Keyword arguments: vis -- Name of input visibility file default: none. example: vis='ngc5921.ms' mode -- Flag version operation default: 'list'; to list existing flagtables 'save': will save the FLAG column from vis to a specified flag file. If the in versionname already exists, the task will give a warning and rena to a name with a suffix '.old.timestamp'. The respective entry in Fl will also be updated. 'restore': will place the specified flag file into vis 'delete': will delete specified flag file 'rename': will rename a specified flag file versionname -- Flag version name default: none; example: versionname='original_data' No imbedded blanks in the versionname comment -- Short description of a versionname, when mode is 'save' or 'rename' default: ''; example: comment='Clip above 1.85' comment = versionname oldname -- When mode='rename', the flag file to rename

The flag version files are copies of the FLAG column of a Measurement Set. They can be restored to the data set to obtain

Options: 'or', 'and', but not recommended for now.

merge -- Merge operation

fluxscale-task.html

0.1.31 fluxscale

Requires:

Synopsis

Bootstrap the flux density scale from standard calibrators

Description

Bootstrap the flux density scale from standard calibrators: After running gaincal on standard flux density calibrators (with or without an image model), and other calibrators with unknown flux densities (assumed 1 Jy), fluxscale applies the constraint that net system gain was, in fact, independent of field, on average, and that field-dependent gains in the input caltable are solely a result of the unknown flux densities for the calibrators. Using time-averaged gain amplitudes, the ratio between each ordinary calibrator and the flux density calibrator(s) is formed for each antenna and polarization (that they have in common). The average of this ratio over antennas and polarizations yields a correction factor that is applied to the ordinary calibrators' gains. (See also more detailed discussion in Example section below.)

Arguments

Outputs

fluxd Dictionary containing the transfer fluxes and their er-

rors.

allowed: any

Default: variant

Inputs

vis Name of input visibility file (MS)

allowed: string

Default:

caltable Name of input calibration table

allowed: string

Default:

fluxtable Name of output, flux-scaled calibration table

allowed: string

Default:

reference Reference field name(s) (transfer flux scale FROM)

allowed: stringArray

Default:

transfer field name(s) (transfer flux scale TO), "-> all

allowed: stringArray

Default:

listfile Name of listfile that contains the fit information. Default

is " (no file).

allowed: string

Default:

append Append solutions?

allowed: bool Default: False

refspwmap Scale across spectral window boundaries. See help fluxs-

cale

allowed: intArray

Default: -1

gainthreshold Threshold (% deviation from the median) on gain am-

plitudes to be used in the flux scale calculation

allowed: double

Default: -1.0

antenna antennas to include/exclude

allowed: string

Default:

timerange sub selection by timerange

allowed: string

Default:

scan sub selection by scan

allowed: string

Default:

incremental incremental caltable

allowed: bool Default: 165alse

fitorder order of spectral fitting

allowed: int Default: 1

display some statistics of flux scaling

allowed: bool Default: False

Returns

void

Example

After running gaincal on standard flux density calibrators (with or without an image model), and other calibrators with unknown flux densities (assumed 1 Jy), fluxscale applies the constraint that net system gain was, in fact, independent of field, on average, and that field-dependent gains in the input caltable are solely a result of the unknown flux densities for the calibrators. Using time-averaged gain amplitudes, the ratio between each ordinary calibrator and the flux density calibrator(s) is formed for each antenna and polarization (that they have in common). For incremental=False(default), the median of this ratio over antennas and polarizations yields a correction factor that is applied to the ordinary calibrators' gains. For incremental=True, only the correction factors are written out to the output fluxtable.

The square of the gain correction factor for each calibrator and spw is the presumed flux density of that calibrator, and is reported in the logger. The errors reported with this value reflect the scatter in gain ratio over antennas and polarizations, divided by the square root of the number of antennas and polarizations available. If the flux densities for multiple spws exist, fitted spectral index and (for nspw>2) curvature are also reported. The fit is done for log(flux density) = a_o + a_1*(log(frequency)) + a_2*(log(frequency))**2 where log(frequency) is with respect to the mean of log(frequency). This reference frequency is reported in the logger along with the flux density at that frequency. The fit results are also reported in the returned Python dictionary (the solutions are in 'spidx' in the following order: a_o [log(S) at the zero point], a_1 [spectral index], and a_2 [curvature]. And their errors are in 'spidxerr'). The MODEL_DATA column is currently _not_ revised to reflect the flux densities derived by fluxscale. Use setjy to set the MODEL_DATA column, if necessary.

The constant gain constraint is usually a reasonable assumption for the electronic systems on typical antennas. It is

important that external time- and/or elevation-dependent effects are separately accounted for when solving for the gain solution supplied to fluxscale, e.g., gain curves, opacity, etc. The fluxscale results can also be degraded by poor pointing during the observation. The parameters, gainthreshold and antenna (and timerange/scan) can be used to control the data to be used in the flux derivation in such cases. The gainthreshold parameter sets the range of the input gain to be used in terms of the percentage deviation from their median values (per field, per spectral window). When the antenna parameter is specified, the sub-parameters timerange and scan are also available to fine tune the data selection for the flux derivation. These parameters uses the general CASA data selection (msselection) syntax. And these are 'AND' operations except when the antenna selection is specified with a negation (e.g. antenna="!6"). In that case, timerange and scan applied to only those antennas appear in the antenna parameter. So, for example, timerange='>02:35:00' with antenna='!6,24', will include the data with time greater 02:35:00 for antenna ID 6 and 24 but for other antennas the timerange selection is no applied.

Keyword arguments:

vis -- Name of input visibility file

default: none; example: vis='ngc5921.ms'

caltable -- Name of input calibration table

default: none; example: caltable='ngc5921.gcal'

This cal table was obtained from task gaincal.

fluxtable -- Name of output, flux-scaled calibration table

default: none; example: fluxtable='ngc5921.gcal2'

The gains in this table have been adjusted by the

derived flux density each calibrator. The MODEL_DATA

column has NOT been updated for the flux density of the

calibrator. Use setjy to do this if it is a point source.

reference -- Reference field name(s)

The names of the fields with a known flux densities or visibilities that have been placed in the MODEL column

by setjy or ft for a model not in the CASA system.

The syntax is similar to field. Hence field index or names can be used.

default: none; example: reference='1328+307'

transfer -- Transfer field name(s)

The names of the fields with unknown flux densities.

These should be point-like calibrator sources

The syntax is similar to field. Hence source index or names can be used.

default: '' = all sources in caltable that are not specified
 as reference sources. Do not include unknown target sources

```
NOTE: All fields in reference and transfer must have solutions
        in the caltable.
listfile -- Fit listfile name
        The list file contains the flux density, flux density error,
          S/N, and number of solutions (all antennas and feeds) for each
          spectral window. NOTE: The nominal spectral window frequencies
          will be included in the future.
        default: '' = no fit listfile will be created.
append -- Append fluxscaled solutions to the fluxtable.
        default: False; (will overwrite if already existing)
        example: append=True
refspwmap -- Vector of spectral windows enabling scaling across
        spectral windows
        default: [-1] ==> none.
        Example with 4 spectral windows:
        if the reference fields were observed only in spw=1 & 3,
        and the transfer fields were observed in all 4 spws (0,1,2,3),
        specify refspwmap=[1,1,3,3].
        This will ensure that transfer fields observed in spws 0,1,2,3
        will be referenced to reference field solutions only in
        spw 1 or 3.
gainthreshold -- Threshold in the input gain solutions to be used in % deviation
        from median values.
        default: -1 (no threshold)
        example: gainthreshold=0.15 (only used the gain solutions within 15%
        (inclusive) of the median gain value (per field and per spw).
antenna --- Antenna selection to be included in the fluxscale determination.
        General ms selection syntax is accepted such as antenna id (given as a string
        and antenna name.
        default: '' (=All antennas will be used)
        example: antenna='!23' (exclude antenna id, 23)
  * Following sub-parameters are available when the antenna parameter is specified
  timerange --- Select time range using the msselection syntax.
        If the negation (e.g. '!23') is used in the antenna selection, it will apply
        the time range selection only to the negated antenna(s). Otherwise, the selection
        is global (i.e. applied to all antenna and to both reference and transfer fig
```

scan --- Select scan(s) using the msselection syntax. As in the case of the timeral the selection will be applied to only the negated antenna(s) if the antenna

example: transfer='1445+099, 3C84'; transfer = '0,4'

is used with the negation ("!").

default: '' (all timerange)
example: timerange=">0:58:00"

```
default: '' (all scans)
        example: '2~5'
incremental -- Create an incremental caltable containing only gain correction
        factors ( flux density= 1/(gain correction factor)**2)
        default: False; (older behavior = create flux-scaled gain table)
        example: incremental=True (output a caltable containing flux scale factors.)
       NOTE: If you use the incremental option, note that BOTH this incremental
        fluxscale table AND an amplitude vs. time table should be supplied in applyca
fitorder -- Polynomial order of the spectral fitting for valid flux densities
        with multiple spws. Currently only support 1 (spectral index only) or
        2 (spectral index and curvature). It falls back to a lower fitorder if
        there are not enough solutions to fit with the requested fitorder.
display -- Display statistics and/or spectral fitting results. Currently only a histo
        of the correction factors to derive the final flux density for each spectral
        will be plotted.
        default: False
        example: display=True
Returned dictionary:
         when it is run as fluxres = fluxscale(vis='my.ms',...), the determined flux
         densities and spectral index information are returned as a Python dictionar
         a format, {fieldIdstr: {spwIdstr: {'fluxd':array([I,Q,U,V]),
                                           'fluxdErr': corresponding errors,
                                            'numSol': corresponding no. of solutions
                                 'fieldName': field name,
                                 'fitFluxd': fitted flux density at the reference fre
                                 'fitFluxdErr': fitted flux density error,
                                 'fitRefFreq': reference frequency,
                                 'spidx': a_0, a_1, a_2
                                 'spidxerr': errors in a_0,a_1, a_2}
                    'freq': (center) spw frequencies
```

'spwID': list of spw IDs,

are field Id and spw Id in string type, respectively.

'spwName': list of spw names}, where fieldIdstr and spwIdstr

ft-task.html

0.1.32 ft

Requires:

Synopsis

Insert a source model a visibility set:

Description

A source model (souce.model image) or components list is converted into model visibilities that is inserted into the MODEL_DATA column or alternatively is stored in the header of the MS to be served on the fly when requested. This is needed to use more complicated sources than setjy provides; e.g resolved source or off centered sources in gaincal. (Setjy will automatically make this ft step.)

The sources currently available are 3C48, 3C138, 3C147, 3C286 at 1.4, 5.0, 8.4, 15, 22, 43 GHz. Their location is site dependent. In Charlottesville and at the SOC, the models are in /usr/lib/casapy/data/nrao/VLA/CalModels.

Arguments

Inputs

vis Name of input visibility file (MS)

allowed: string

Default:

field Field selection

allowed: string

Default:

spw Spw selection

allowed: string

Default:

model Name of input model image(s)

allowed: any Default: variant

nterms Number of terms used to model the sky frequency de-

pendence

allowed: int Default: 1

reffreq Reference frequency (e.g. '1.5e+9' or '1.5GHz')

allowed: string

Default:

complist Name of component list

allowed: string

Default:

incremental Add to the existing model visibility?

allowed: bool

Default: False

usescratch If True predicted visibility is stored in MODEL_DATA

column

allowed: bool Default: False

Returns

void

Example

A source model (souce.model image) or components list is converted into a model visibility that is inserted into the MODEL_DATA column. This is needed to use resolved source in gaincal and in fluxscale.

```
Setjy will automatically make this ft step on the sources currently available are 3C48, 3C138, 3C147, 3C286 at 1.4, 5.0, 8.4, 15, 22, 43 GHz. Their location is site dependent. In Charlottesville and at the AOC, the models are in /usr/lib(lib64)/casapy/data/nrao/VLA/CalModels.
```

```
Keyword arguments:
   vis -- Name of input visibility file
          default: none; example: vis='ngc5921.ms'
   field -- Field name list
           default: '' ==> all
           NOTE: BUT, only one source can be specified in a multi-source vis.
           field = '1328+307' specifies source '1328+307'
           field = '4' specified field with index 4
   spw -- Spw selection
           default: spw = '' (all spw)
   model -- Name of input model image
           default: '' ==> None;
           example: model='/usr/lib/casapy/data/nrao/VLA/CalModels/3C286_X.im'
           Note: The model visibilities are scaled from the model frequency
                 to the observed frequency of the data.
   nterms -- Number of terms used to model the sky frequency dependence
             default: 1 ==> one model image is required
             example : nterms=3 represents a 2nd order Taylor-polynomial in frequency
                       and should be used in conjuction with coefficient model images as
      model=['xxx.model.tt0','xxx.model.tt1', 'xxx.model.tt2']
         reffreq -- Reference-frequency about which this Taylor-expansion is defined.
            default: '' ==> reads the reference frequency from the model image
                    example : reffreq = '1.5GHz'
   complist -- Name of component list
           default: None; ; example: complist='test.cl'
           component lists are difficult to make.
   incremental -- Add model visibility to the existing model visibilties stored in the N
           default: False; example: incremental=True
   usescratch -- if True model visibilities will be stored in the scratch column
                        MODEL_DATA; when false the model visibilities will be generated
                        on the fly (this mode may save some disk space equivalent to
the volume of the observed data).
```

gaincal-task.html

0.1.33 gaincal

Requires:

Synopsis

Determine temporal gains from calibrator observations

Description

The complex gains for each antenna/spwid are determined from the data column (raw data), divided by the model column, for the specified fields. The gains can be obtained for a specified solution interval for each spectral window, or by a spline fit to all spectral windows simultaneously. Previous calibrations (egs. bandpass) should be applied on the fly.

Arguments

Inputs

solint

vis Name of input visibility file

allowed: string

Default:

caltable Name of output gain calibration table

allowed: string

Default:

field Select field using field id(s) or field name(s)

allowed: string

Default:

spw Select spectral window/channels

allowed: string

Default:

intent Select observing intent

allowed: string

Default:

selectdata Other data selection parameters

allowed: bool Default: True

timerange Select data based on time range

allowed: string

Default:

uvrange Select data within uvrange (default units meters)

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: string

Default:

scan Scan number range

allowed: string

Default:

observation Select by observation ID(s)

allowed: any
Default: variant

msselect Optional complex data selection (ignore for now)

allowed: string

Default:

Solution interval: egs. 'inf', '60s' (see help)

allowed: any Default: variant inf

combine Data axes which to combine for solve (obs, scan, spw,

and/or field)

allowed: string

Default:

preavg Pre-averaging interval (sec) (rarely needed)

allowed: plouble Default: -1.0

refant Reference antenna name(s)

allowed: string

Default:

minblperant Minimum baselines _per antenna_ required for solve

allowed: int Default: 4

minsnr Reject solutions below this SNR

Example

Keyword arguments:

The complex gains for each antenna/spwid are determined from the data column (raw data) divided by the model column. The gains can be obtained for a specified solution interval, spw combination and field combination. The GSPLINE spline (smooth) option is still under development.

Previous calibrations (egs, bandpass, opacity, parallactic angle) can be applied on the fly. At present with dual-polarized data, both polarizations must be unflagged for any solution to be obtained.

```
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
caltable -- Name of output gain calibration table
        default: none; example: caltable='ngc5921.gcal'
--- Data Selection (see help par.selectdata for more detailed information)
field -- Select field using field id(s) or field name(s).
           ['go listobs' to obtain the list id's or names]
        default: ''=all fields
        If field string is a non-negative integer, it is assumed a
          field index, otherwise, it is assumed a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5^{\sim}7'; field ids 0,4,5,6,7
        field='3C286,3C295'; field named 3C286 and 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
    DON'T FORGET TO INCLUDE THE FLUX DENSITY CALIBRATOR IF YOU HAVE ONE
spw -- Select spectral window/channels
         type 'help par.selection' for more examples.
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61, INCLUSIVE
       spw='*:5~61'; all spw with channels 5 to 61
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                 NOTE ';' to separate channel selections
       spw='0:0~10^2,1:20~30^5'; spw 0, channels 0,2,4,6,8,10,
             spw 1, channels 20,25,30
intent -- Select observing intent
```

```
default: '' (no selection by intent)
          intent='*BANDPASS*' (selects data labelled with
                                BANDPASS intent)
selectdata -- Other data selection parameters
       default: True
        Must set selectdata=True to use the following selections:
timerange -- Select data based on time range:
        default = '' (all); examples,
        timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
        Note: if YYYY/MM/DD is missing date defaults to first day in data set
        timerange='09:14:0~09:54:0' picks 40 min on first day
        timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on NEXT day
        timerange='09:44:00' pick data within one integration of time
        timerange='>10:24:00' data after this time
uvrange -- Select data within uvrange (default units meters)
        default: '' (all); example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo lambda
antenna -- Select data based on antenna/baseline
        default: '' (all)
        If antenna string is a non-negative integer, it is assumed an
          antenna index, otherwise, it is assumed as an antenna name
        antenna='5&6'; baseline between antenna index 5 and index 6.
        antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8'; baselines with indices 5-6 and 7-8
        antenna='5'; all baselines with antenna index 5
        antenna='05'; all baselines with antenna number 05 (VLA old name)
        antenna='5,6,10'; all baselines with antennas 5,6,10 index numbers
scan -- Scan number range.
        Check 'go listobs' to insure the scan numbers are in order.
observation -- Observation ID(s).
               default: '' = all
               example: '0~2,4'
msselect -- Optional complex data selection (ignore for now)
--- Solution parameters
gaintype -- Type of gain solution (G, T, or GSPLINE)
        default: 'G'; example: gaintype='GSPLINE'
        'G' means determine gains for each polarization and sp_wid
        'T' obtains one solution for both polarizations; Hence. their
         phase offset must be first removed using a prior G.
        'GSPLINE' makes a spline fit to the calibrator data. It is
             useful for noisy data and fits a smooth curve through the
             calibrated amplitude and phase. However,
```

```
at present GSPLINE is somewhat experimental. Use with
             caution and check solutions.
        'K' solves for simple antenna-based delays
             via FFTs of the spectra on baselines to the
             reference antenna. (This is not global
             fringe-fitting.) If combine includes 'spw',
             multi-band delays are determined; otherwise,
             per-spw single-band delays will be determined.
        'KCROSS' solves for a global cross-hand
             delay. Use parang=T and apply prior gain and
             bandpass solutions. Multi-band delay solves
             (combine='spw') not yet supported for KCROSS.
smodel -- Point source Stokes parameters for source model (experimental)
        default: [] (use MODEL_DATA column)
        example: [1,0,0,0] (I=1, unpolarized)
calmode -- Type of solution
        default: 'ap' (amp and phase); example: calmode='p'
       Options: 'p','a','ap'
solint -- Solution interval (units optional)
        default: 'inf' ("infinite, up to boundaries controlled by combine);
        Options: 'inf' (~infinite),
                 'int' (per integration)
                 any float or integer value with or without units
        examples: solint='1min'; solint='60s'; solint=60 --> 1 minute
                  solint='0s'; solint=0; solint='int' --> per integration
                  solint-'-1s'; solint='inf' --> ~infinite, up to boundaries
                  interacts with combine
combine -- Data axes to combine for solving
        default: '' --> solutions will break at obs, scan, field, and spw
                boundaries
        Options: '', 'obs', 'scan', 'spw', field', or any comma-separated
                 combination in a single string
        For gaintype='K', if combine includes 'spw', multi-band
        delays will be determined; otherwise, (per-spw)
         single-band delays will be determined.
        example: combine='scan,spw' --> extend solutions over scan boundaries
                 (up to the solint), and combine spws for solving
refant -- Reference antenna name(s); a prioritized list may be specified
        default: '' => no refant applied
        example: refant='4' (antenna with index 4)
                 refant='VA04' (VLA antenna #4)
                 refant='EA02,EA23,EA13' (EVLA antenna EA02, use
                          EA23 and EA13 as alternates if/when EA02
                          drops out)
        Use taskname=listobs for antenna listing
```

minblperant -- Minimum number of baselines required per antenna for each solve

```
default = 4
        Antennas with fewer baaselines are excluded from solutions.
        example: minblperant=10 => Antennas participating on 10 or more
                 baselines are included in the solve
        minblperant = 1 will solve for all baseline pairs, even if only
             one is present in the data set. Unless closure errors are
             expected, use taskname=gaincal rather than taskname=blcal to
             obtain more options in data analysis.
minsnr -- Reject solutions below this SNR
        default: 3.0
solnorm -- Normalize average solution amps to 1.0 after solution (G, T only)
        default: False (no normalization)
append -- Append solutions to the (existing) table. Appended solutions
           must be derived from the same MS as the existing
           caltable, and solution spws must have the same
           meta-info (according to spw selection and solint)
           or be non-overlapping.
        default: False; overwrite existing table or make new table
splinetime -- Spline timescale (sec); used for gaintype='GSPLINE'
        default: 3600 (1 hour); example: splinetime=1000
        Typical splinetime should cover about 3 to 5 calibrator scans.
npointaver -- Tune phase-unwrapping algorithm for gaintype='GSPLINE'
        default: 3; Keep at this value
phasewrap -- Wrap the phase for changes larger than this amoun (degrees)
        default: 180; Keep at this value
--- Other calibrations to apply on the fly before determining gaincal solution
docallib -- Control means of specifying the caltables:
         default: False ==> Use gaintable, gainfield, interp, spwmap, calwt
                  If True, specify a file containing cal library in callib
callib -- If docallib=True, specify a file containing cal
            library directives
gaintable -- Gain calibration table(s) to apply
         default: '' (none);
         examples: gaintable='ngc5921.gcal'
                   gaintable=['ngc5921.ampcal', 'ngc5921.phcal']
gainfield -- Select a subset of calibrators from gaintable(s) to apply
         default:'' ==> all sources in table;
         'nearest' ==> nearest (on sky) available field in table
         otherwise, same syntax as field
         example: gainfield='0~2,5' means use fields 0,1,2,5 from gaintable
                  gainfield=['0~3','4~6'] means use field 0 through 3
                    from first gain file, field 4 through 6 for second.
interp -- Interpolation type (in time[,freq]) to use for each gaintable.
```

```
When frequency interpolation is relevant (B, Df, Xf),
          separate time-dependent and freq-dependent interp
          types with a comma (freq _after_ the comma).
          Specifications for frequency are ignored when the
          calibration table has no channel-dependence.
          Time-dependent interp options ending in 'PD' enable a
          "phase delay" correction per spw for non-channel-dependent
          calibration types.
          For multi-obsId datasets, 'perobs' can be appended to
          the time-dependent interpolation specification to
          enforce obsId boundaries when interpolating in time.
          default: '' --> 'linear, linear' for all gaintable(s)
          example: interp='nearest'
                                      (in time, freq-dep will be
                                       linear, if relevant)
                   interp='linear,cubic'
                                         (linear in time, cubic
                                           in freq)
                   interp='linearperobs, spline' (linear in time
                                                 per obsId,
                                                 spline in freq)
                   interp=',spline'
                                     (spline in freq; linear in
                                      time by default)
                   interp=['nearest,spline','linear'] (for multiple gaintables)
          Options: Time: 'nearest', 'linear'
                   Freq: 'nearest', 'linear', 'cubic', 'spline'
spwmap -- Spectral windows combinations to form for gaintable(s)
          default: [] (apply solutions from each spw to that spw only)
          Example: spwmap=[0,0,1,1] means apply the caltable solutions
                    from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                    spwmap=[[0,0,1,1],[0,1,0,1]]
parang -- If True, apply the parallactic angle correction (required
         for polarization calibration)
         default: False
preavg -- Pre-averaging interval (sec)
        default=-1 (none).
         Rarely needed. Will average data over periods shorter than
           the solution interval first.
async -- Run asynchronously
        default = False; do not run asychronously
```

gencal-task.html

0.1.34 gencal

Requires:

Synopsis

Specify Calibration Values of Various Types

Description

Specify calibration externally.

Arguments

Name of input visibility file
allowed: string
Default:
The new/existing calibration table
allowed: string
Default:
The calibration type: 'amp', 'ph', 'sbd', 'mbd', 'antpos', 'antposvla', 'tsys', 'evlagain', 'opac', 'g
allowed: string
Default:
Input ancilliary file
allowed: string
Default:
Calibration spw(s) selection
allowed: string
Default:
Calibration antenna(s) selection
allowed: string
Default:
Calibration polarizations(s) selection
allowed: string
Default:
The calibration values
allowed: doubleArray
Default:

Returns

void

Example

The gencal task provides a means of specifying antenna-based calibration values manually. The values are put in designated tables and applied to the data using applycal. Several specialized calibrations are also generated with gencal.

```
Current antenna-based gencal options (caltype) are:
   'amp' = amplitude correction
   'ph' = phase correction
   'sbd'= single-band delay (phase-frequency slope for each spw)
   'mbd' = multi-band delay (phase-frequency slope over all spw)
   'antpos' = ITRF antenna position corrections
   'antposvla' = VLA-centric antenna position corrections
   'tsys' = Tsys from the SYSCAL table (ALMA)
   'swpow' = EVLA switched-power gains (experimental)
   'evlagain' (='swpow') (this syntax will deprecate)
   'rq' = EVLA requantizer gains _only_
   'swp/rq' = EVLA switched-power gains divided by requantizer gain
   'opac' = Tropospheric opacity
   'gc' = Gain curve (zenith-angle-dependent gain) (VLA only)
   'eff' = Antenna efficiency (sqrt(K/Jy)) (VLA only)
   'gceff' = Gain curve and efficiency (VLA only)
   'tecim' = Time-dep TEC image specified in infile (EXPERIMENTAL)
```

Generic calibration parameters should be specified in the 'parameter' argument as a list. The length of the list must correspond to the net length of the specific polarizations, antennas, and spws specified in the selection arguments. The specified parameters will be duplicated over all members of any unspecified selection axes. E.g., if pol=antenna=spw='', it only makes sense to specify a single parameter value, and this will be duplicated for all pols, antennas, and spws. If multiple parameter values are specified, at least one of the selection arguments must be non-trivial, and the number of specified parameters must be consistent with the explicit selection. E.g., if a non-trivial spw selection is specified, then the parameter list should match the number of spws specified, and

these values will be duplicated for all polarizations and antennas. If more than one selection argument is non-trivially specified, the number of parameters specified should match the product of the number specified selection elements. The parameter values should be sorted by pol (fastest), antenna, and spw (slowest). Un-specified elements on non-trivially specified axes will be filled with nominal values (i.e., it is not necessary to exhaustively specify all elements on any axis or use nominal parameter values explicitly). Please consult the examples provided below for additional guidance. There is currently no support for time-dependent parameter specification. The specified parameters will be assumed constant in time (though their impact on the data may be time-dependent, depending on the caltype). Some caltype options do not require parameter specifications; these are described in detail below.

The same caltable can be specified for multiple runs of gencal, in which case the specified parameters will be incorporated cumulatively. E.g., amplitude parameters (caltype='amp') multiply and phase-like parameters ('ph', 'sbd', 'mbd', 'antpos') add. 'amp' and 'ph' parameters can be incorporated into the same caltable (in separate runs), but each of the other types require their own unique caltable. A mechanism for specifying manual corrections via a text file will be provided in the future.

The caltables are applied to the data by using applycal. Other calibration tables may also be present, if applicable.

For antenna position corrections (caltype='antpos'), the antenna position offsets are specified in the ITRF frame. For EVLA, automated lookup of the antenna position corrections is enabled when antenna is unspecified (antenna='') for this caltype. Note that this requires internet connection to access the EVLA antenna position correction site.

For VLA position corrections in the VLA-centric frame, use caltype='antposvla', and gencal will rotate them to ITRF before storing them in the output caltable.

For Tsys (caltype='tsys', for ALMA) and EVLA switched power corrections (caltype='swpow'), the calibration parameters are derived from information contained in MS subtables. In these cases, specification of spw, antenna, pol, and parameter will be ignored.

EVLA switched power calibration is supported in three modes:

'swpow' (formerly 'evlagain', a syntax which will deprecate) yields the formal EVLA switched power calibration which describes voltage gain as sqrt(Pdif/Tcal) (used to correct the visibility data) and Tsys as Psum*Tcal/Pdif/2 (used to correct the weights). 'swpow' implicitly includes any requantizer gain scale and adjustments.

'rq' yields only the requantizer voltage gains (Tsys is set to 1.0 to avoid weight adjustments).

'swp/rq' yields the ordinary switched power voltage gains divided by the requantizer voltage gain (Tsys is calculate normally). The 'rq' and 'swp/rq' modes are are mainly intended for testing and evaluating the EVLA switched power systems.

For caltype='opac', specify the desired opacity(ies) in the parameter argument. At this time, only constant (in time) opacities are supported via gencal.

For gaincurve and efficiency (caltype='gc', 'gceff', or 'eff'), observatory-provided factors are determined per spw according to the observing frequencies. The parameter argument is ignored. These caltypes are currently only supported for VLA processing. (Appropriate factors for ALMA are TBD.)

For caltype='tecim', specify a TEC image in the infile parameter. The TEC image can be obtained via the tec_maps module; please consult the CASA Cookbook (section 4.3) for more details.

Keyword arguments:

vis -- Name of input visibility file default: none. example: vis='ngc5921.ms' caltable -- Name of input/output caltable. If it does not exist, it will be created. Specifying an existing table will result in the parameters being applied cumulatively. Only a single time-stamp for all calibrations are supported, currently. Do not use a caltable created by gaincal, bandpass, etc. default: none. example: caltable='test.G' caltype -- The calibration parameter type being specified. Options include: 'amp' = gain (G) amplitude (1 real parameter per pol, antenna, spw) 'ph' = gain (G) phase (deg) (1 real parameter per pol, antenna, spw) 'sbd' = single-band delays (nsec) (1 real parameter

```
per pol, antenna, spw)
            'mbd' = multi-band delay (nsec) (1 real parameter
                   per pol, antenna, spw)
            'antpos' = antenna position corrections (m) (3 real
                       ITRF offset parameters per antenna; spw, pol
                       selection will be ignored)
                       With antenna='', this triggers an automated lookup
                       of antenna positions for EVLA.
            'antposvla' = antenna position corrections (m) specified
                          in the old VLA-centric coordinate system
            'tsys' = Tsys from the SYSCAL table (ALMA)
            'evlagain' = EVLA switched-power gains (experimental)
            'opac' = Tropospheric opacity (1 real parameter
                    per antenna, spw)
            'gc' = Antenna zenith-angle dependent gain curve (auto-lookup)
            'gceff' = Gain curve and efficiency (auto-lookup)
            'eff' = Antenna efficiency (auto-lookup)
            'tecim' = Time-dep TEC image specified in infile (EXPERIMENTAL)
            default: none.
            example: caltype='ph'
infile -- For caltype='tecim', the input TEC image from tec_maps
           default: none
spw -- Spectral window selection for specified parameters.
        default: spw='' (specified parameters apply to all spws)
        example: spw = '2,3,4'
antenna -- Antenna selection for specified parameters.
            default: antenna='' (specified parameters apply to all antennas)
            example: antenna='ea02, ea03' (specified parameter(s) to
                      apply to ea02 and ea03 only)
pol -- Polarization selection for specified parameters.
        default: pol='' (specified parameters apply to all polarizations)
        example: pol='R' (specified parameters to apply to
                            R only)
parameter -- The calibration parameters, specified as a list, to
              store in the caltable for the spw, antenna, and pol
              selection. The required length of the list is
              determined by the caltype and the spw, antenna, pol
              selection. One "set" of parameters (e.g., one value
              for 'amp', 'ph', etc., three values for 'antpos')
              specified the same value for all indicated spw, antenna,
              and pol.
              OR,
              When specifying a long list of calibration parameter values,
              these should be ordered first (fastest) by pol (if pol!=''),
              then by antenna (if antenna!=''), and finally (sloweset) by
              spw (if spw!=''). Unspecified selection axes must not be
```

enumerated in the parameter list

Examples:

--> Antenna-based gain amplitude corrections for all spws, antennas, and polarizations will be multiplied by 3. When applied to visibility data, this correction will produce a corrected visibility than is (1/3*1/3) less than the uncorrected visibility.

--> Gain phase corrections for antennas ea03 and ea04
will be adjusted (additive) by 45 and 120
degrees (respectively), for all spws and polarizations.
When these phases are applied to visibility data, the
visibility phases will decrease or increase by the
specified amount where the selected antennas occur
first or second (respectively) in each baseline. E.g.,
the phase of baseline ea03-ea04 will change by (-45+120)
= + 75 degrees. Baseline ea01-ea03's phase will change
by +45 degrees; baseline ea04-ea05's phase will change
by -120 degrees. The same phase sign convention is
used for delay and antenna position corrections.

- --> Gain phase corrections for antennas ea05 and ea06 will be adjusted (additive) by 63 and -34 degrees (respectively), in R only, for all spws
- - --> Gain phase corrections in all spws will be adjusted for antenna ea09 by 14 deg in R and -23 deg in L, and for antenna ea10 by -130 deg in R and 145 deg in L.

--> Gain phases corrections in both polarizations will be adjusted for antenna ea09 by 14 deg in spw 2 and -23 deg in spw 3, and for antenna ea10 by -130 deg in spw 2 and 145 deg in spw 3.

--> Delay corrections in both polarizations will be adjusted for antenna ea09 by 14 nsec in spw 2 and -23 nsec in spw 3, and for antenna ea10 by -130 nsec in spw 2 and 145 nsec in spw 3. See the above example for caltype='ph' for details of the sign convention adopted when applying delay corrections.

```
gencal(vis='test.ms',caltable='test.G',caltype='antpos',antenna='')
```

--> *** Currently EVLA observations only ***

Antenna position corrections will be retrieved automatically over internet to generate the caltable with antenna=''.

--> Antenna position corrections in meters (in ITRF) for antenna ea09 (dBx=0.01, dBy=0.02, dBz=0.03) and for antenna ea10 (dBx=-0.03, dBy=-0.01, dBz=-0.02)

See the above example for caltype='ph' for details of the sign convention adopted when applying antpos corrections.

--> Antenna position corrections (in the traditional VLA-centric frame) will be introduced in meters for antenna ea09 (dBx=0.01, dBy=0.02, dBz=0.03) and for antenna ea10 (dBx=-0.03, dBy=-0.01, dBz=-0.02)

These offsets will be rotated to the ITRF frame before storing them in the caltable.

See the above example for caltype='ph' for details of the sign convention adopted when applying antpos corrections.

hanningsmooth-task.html

0.1.35 hanningsmooth

Requires:

Synopsis

Hanning smooth frequency channel data to remove Gibbs ringing

Description

This is the new

implementation of hanningsmooth.

* The old implementation is available for a short time as oldhanningsmooth. * Task hanningsmooth2 has been renamed to hanningsmooth. The hanningsmooth2 alias will be removed soon. * Please, update your scripts to call hanningsmooth instead.

Th new hanningsmooth task uses the MSTransform framework underneath but keeps roughly the same interface as the old hanningsmooth task. This function Hanning smooths the frequency channels with a weighted running average. The weights are 0.5 for the central channel and 0.25 for each of the two adjacent channels. The first and last channels are flagged. Inclusion of a flagged value in an average causes that data value to be flagged. If the 'CORRECTED' data column is requested for an MS that does not contain this column, it will use 'DATA' to calculate the smoothing and save it to 'DATA' in the output MS.

WARNING: by default, all visibility columns will be smoothed.

Arguments

Inputs

vis Name of input Measurement set or Multi-MS.

allowed: string

Default:

outputvis Name of output Measurement set or Multi-MS.

allowed: string

Default:

Multi-MS.

allowed: bool Default: True

field Select field using ID(s) or name(s).

allowed: any Default: variant

spw Select spectral window/channels.

allowed: any
Default: variant

scan Select data by scan numbers.

allowed: any
Default: variant

antenna Select data based on antenna/baseline.

allowed: any Default: variant

correlation Correlation: " ==> all, correlation='XX,YY'.

allowed: any Default: variant

timerange Select data by time range.

allowed: any Default: variant

intent Select data by scan intent.

allowed: any Default: variant

array Select (sub)array(s) by array ID number.

allowed: any Default: variant

uvrange Select data by baseline length.

allowed: any Default: variant

observation Select by observation ID(s).

allowed: any
Default: variant

feed Multi-feed numbers: Not yet implemented.

allowed: any Default: variant

datacolumn Input data column(s) to process.

Example

```
---- Detailed description of keyword arguments: -----
    vis -- Name of input visibility file (MS or MMS)
       default: ''; example: vis='ngc5921.ms'
    outputvis -- Name of output visibility file (MS or MMS)
        default: ''; example: outputvis='out_ngc5921.mms'
    keepmms -- Create a Multi-MS as the output if the input is a Multi-MS.
       default: True
       By default it will create a Multi-MS when the input is a Multi-MS.
       The output Multi-MS will have the same partition axis of the input MMS.
        See 'help partition' for more information on the MMS format.
--- Data selection parameters ---
    field -- Select field using field id(s) or field name(s).
             [run listobs to obtain the list iof d's or names]
        default: ''=all fields If field string is a non-negative
           integer, it is assumed to be a field index
           otherwise, it is assumed to be a field name
           field='0~2'; field ids 0,1,2
           field='0,4,5~7'; field ids 0,4,5,6,7
           field='3C286,3C295'; fields named 3C286 and 3C295
           field = '3,4C*'; field id 3, all names starting with 4C
    spw -- Select spectral window/channels
        default: ''=all spectral windows and channels
           spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
           spw='<2'; spectral windows less than 2 (i.e. 0,1)
           spw='0:5~61'; spw 0, channels 5 to 61
           spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
           spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
           spw = '*:3~64' channels 3 through 64 for all sp id's
                   spw = ':3^64' will NOT work.
               NOTE: mstransform does not support multiple channel ranges per
```

spectral window (';').

```
scan -- Scan number range
    default: ''=all
antenna -- Select data based on antenna/baseline
    default: '' (all)
        Non-negative integers are assumed to be antenna indices, and
        anything else is taken as an antenna name.
    examples:
        antenna='5&6': baseline between antenna index 5 and index 6.
        antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8': baselines 5-6 and 7-8
        antenna='5': all baselines with antenna 5
        antenna='5,6,10': all baselines including antennas 5, 6, or 10
        antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                                10. (cross-correlations only. Use &&
                                to include autocorrelations, and &&&
                                to get only autocorrelations.)
        antenna='!ea03,ea12,ea17': all baselines except those that
                                    include EVLA antennas ea03, ea12, or
correlation -- Correlation types or expression.
    default: '' (all correlations)
    example: correlation='XX,YY'
timerange -- Select data based on time range:
    default: '' (all); examples,
       timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
       Note: if YYYY/MM/DD is missing date, timerange defaults to the
       first day in the dataset
       timerange='09:14:0~09:54:0' picks 40 min on first day
       timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
       on next day
       timerange='09:44:00' data within one integration of time
       {\tt timerange='>10:24:00'} \ {\tt data} \ {\tt after} \ {\tt this} \ {\tt time}
array -- (Sub)array number range
    default: ''=all
uvrange -- Select data within uvrange (default units meters)
    default: ''=all; example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
        uvrange='0~1000km'; uvrange in kilometers
```

observation -- Select by observation ID(s)
 default: ''=all

feed -- Selection based on the feed - NOT IMPLEMENTED YET
 default: ''=all

datacolumn -- Which data column to use for processing (case-insensitive).
 default: 'all'; whichever of the visibility data columns that are present.
 options: 'data', 'model', 'corrected', 'all','float_data', 'lag_data'.

example1: datacolumn='data'; it will smooth the input DATA column and save the smoothed data in DATA of the output MS.

example2: datacolumn='corrected'; it will smooth the input CORRECTED_DATA column and save the smoothed data in DATA of the output MS.

example3: datacolumn='all', where the input MS has DATA, CORRECTED_DATA, MODEL_DATA.

It will smooth all three columns and save the smoothed data in

DATA, CORRECTED_DATA and MODEL_DATA of the output MS.

im collapse-task.html

0.1.36imcollapse

Requires:

Synopsis
Collapse image along one axis, aggregating pixel values along that axis.

Arguments

Inputs imagename Name of the input image allowed: string Default: function Aggregate function to apply. This can be set one of flux, max, mean, median, min, rms, stdev, sum, variance. Must be specified. allowed: string Default: Zero-based axis number(s) or minimal match strings to axes collapse. allowed: variant Default: [0] outfile Name of output CASA image. Must be specified. allowed: string Default: Rectangular region to select in direction plane. See "help box par.box" for details. Default is to use the entire direction plane. allowed: string Default: region Region selection. See "help par.region" for details. Default is to use the full image. allowed: string Default: chans Channels to use. See "help par.chans" for details. Default is to use all channels. allowed: string Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

Mask to use. See help par.mask. Default is none.

allowed: string

Default:

overwrite Overwrite exisiting out file if it exists?

allowed: bool

Default: False

stretch Stretch the mask if necessary and possible? See help

par.stretch

allowed: bool Default: False

Returns

mask

Example

PARAMETER SUMMARY

imagename Name of the input (CASA, FITS, MIRIAD) image

 $\hbox{function} \qquad \quad \hbox{Function used to compute aggregation of pixel values along the collapsed}$

axis. Supported functions are flux, max, mean, median, min, rms, stdev, sum, variance. Minimum match is supported for the function parameter (eg,

function="r" will compute the rms of the pixel values).

axis Zero-based axis number(s) or minimal match strings to compress.

outfile Name of output CASA image. Must be specified. overwrite Controls if an already existing file by the

same name can be overwritten. If true, the user is not prompted, the file

if it exists is automatically overwritten.

box Rectangular region to select in direction plane. See "help par.box"

for details. Default is to use the entire direction plane.

region Region selection. See "help par.region" for details. Default is to use

the full image.

chans Channels to use. See "help par.chans" for details. Default is to use

all channels.

stokes Stokes planes to use. See "help par.stokes" for details. Default is to use

all Stokes planes.

mask Mask to use. See help par.mask. Default is none.

stretch Stretch the input mask if necessary and possible. Only used if a mask is sp

See help par.stretch.

This task collapses an image along a specified axis or set of axes of N pixels to a single property specified axis. Both float valued and complex valued images are supported. It computes the supported function for pixel values along the specified axes

and places those values in the single remaining plane of those axes in the output image. It an image analysis tool containing the newly created collapsed image if wantreturn=True. Chos aggregate functions are: flux (see below for constraints), max, mean, median, min, rms, stde supported for the function parameter (eg, function="r" will compute the rms of the pixel value will compute the median).

If one specifies function='flux', the following constraints must be true:

- 1. The image must have a direction coordinate,
- 2. The image must have at least one beam,
- 3. The specified axes must be exactly the direction coordinate axes,
- 4. Only one of the non-directional axes may be non-degenerate,

5. The iamge brightness unit must be conformant with x*yJy/beam, where x is an optional unit and y is an optional SI prefix.

Axes can be specified as a single integer or array of integers indicating the zero-based axe which to collapse the image. Axes may also be specified as a single or array of strings which and uniquely match (ignoring case) world axes names in the image (eg "dec" or ["ri, "d"] for collapsing along the declination axis or along the right ascension and declination axes, respectively.

The reference pixel of the collapsed axis is set to 0 and its reference value is set to the of the the first and last values of that axis in the specified region of the input image.

```
# myimage.im is a 512x512x128x4 (ra,dec,freq,stokes) image
imagename = "myimage.im"
# collapse a subimage of it along its spectral axis avoiding the 8 edge
# channels at each end of the band, computing the mean value of the pixels
# resulting image is 256x256x1x4 in size.
outfile="collapse_spec_mean.im"
function="mean"
axis=2
box="127,127,383,383"
chans="8~119"
imcollapse(imagename=imagename, outfile=outfile, function=function, axes=axis, box=box, chandles)
```

imcontsub-task.html

0.1.37 imcontsub

Requires:

 ${\bf Synopsis}$ Estimates and subtracts continuum emission from an image cube

Arguments

Inputs			
imagename	Name of the input spectral line image		
	allowed: string		
	Default:		
linefile	Output continuum-subtracted image file name		
	allowed: string		
	Default:		
contfile	Output continuum image file name		
	allowed: string		
	Default:		
fitorder	Polynomial order for the continuum estimation		
	allowed: int		
	Default: 0		
region	Region selection. See "help par.region" for details. De-		
	fault is to use the full image.		
	allowed: string		
	Default:		
box	Rectangular region to select in direction plane. See "help		
	par.box" for details. Default is to use the entire direction		
	plane.		
	allowed: any		
	Default: variant		
chans	Channels to use for fitting. See "help par.chans" for		
	details. Default is to use all channels.		
	allowed: string		
	Default:		
stokes	Stokes planes to use. See "help par.stokes" for details.		
	Default is to use all Stokes planes.		
	allowed: string		
	Default:		
1			

Returns

void

Example

 $ch = '3^8, 54^60'$

For each (x, y) column in imagename (or a subset selected by region and/or box), this estimates the continuum by fitting a polynomial to one or more subsets of the channels. The continuum estimate is saved in contfile, and subtracted from imagename (or its subset) to make a spectral line estimate, which is saved in linefile.

```
Keyword arguments:
  imagename -- Input image cube
   Default: none; Example: imagename='ngc5921_task.im'
  linefile -- Name of output spectral line cube
   Default: none; Example: outline='ngc5921_line.im'
  contfile -- Name of output continuum cube
   Default: none; Example: contfile='ngc5921_cont.im'
  fitorder -- Polynomial order for the continuum estimation.
   Default: 0; Example fitorder=2
  region -- Region selection. See "help par.region" for details. Default is
            to use the full image.
  box -- Rectangular region to select in direction plane. See "help par.box"
          for details. Default is to use the entire direction plane.
  chans -- Channels to use for fitting. See "help par.chans" for details.
           Default is to use all channels.
           Example: chans='3~6;>40'
  stokes -- Stokes planes to use. See "help par.stokes" for details. Default is
            to use all Stokes planes.
Fit a second order polynomial (fitorder=2) to channels 3-8 and 54-60
to an RA x Dec x Frequency x Stokes cube, selecting the Stokes I plane
```

imcontsub(imagename="myimage.im", linefile="mycontsub.im", fitorder=2, chans=ch, fitorder=2

imfit-task.html

0.1.38 imfit

Requires:

 ${\bf Synopsis} \\ {\bf Fit \ one \ or \ more \ elliptical \ Gaussian \ components \ on \ an \ image \ region(s)} \\$

Arguments

Inputs

imagename Name of the input image

allowed: string

Default:

box Rectangular region(s) to select in direction plane. See

"help par.box" for details. Default is to use the entire

direction plane.

allowed: string

Default:

region Region selection. See "help par region" for details. De-

fault is to use the full image.

allowed: any Default: variant

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: any Default: variant

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use first Stokes plane.

allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: string

Default:

includepix Range of pixel values to include for fitting.

allowed: intArray

Default:

excludepix Range of pixel values to exclude for fitting.

allowed: intArray

Default:

residual Name of output residual image.

allowed: string

Default:

model Name of output model image.

allowed: string

Default:

estimates Name of file containing initial estimates of component

parameters.

allowed: string

Default:

logfile Name of file to write fit results.

allowed: string

Default:

append If logfile exists, append to it if True or overwrite it if

False

allowed: 1990ol Default: True

newestimates File to write fit results which can be used as initial esti-

mates for next run. allowed: string

Default:

complist Name of output component list table.

allowed: string

Default:

Returns

void

Example

PARAMETER SUMMARY

imagename Name of the input image

box Rectangular region(s) to select in direction plane. See "help par.box"

for details. Default is to use the entire direction plane. eg "100, 120, 200, 220, 300, 300, 400, 400" to use two boxes.

region Region selection. See "help par.region" for details. Default is to use

the full image.

chans Channels to use. See "help par.chans" for details. Default is to use all

channels.

stokes Stokes planes to use. See "help par.stokes" for details. Default is to

use first Stokes plane.

mask Mask to use. See help par.mask. Default is none.

includepix Range of pixel values to include for fitting. Array of two numeric

values assumed to have same units as image pixel values. Only one

of includepix or excludepix can be specified.

excludepix Range of pixel values to exclude for fitting. Array of two numeric

values assumed to have same units as image pixel values. Only one

of includepix or excludepix can be specified.

residual Name of the residual image to write.

model Name of the model image to write.

estimates Name of file containing initial estimates of component parameters

(see below for formatting details).

logfile Name of file to write fit results.

append If logfile exists, append to it (True) or overwrite it (False). newestimates File to write fit results which can be used as initial estimates

for next run.

complist Name of output component list table.

overwrite Overwrite component list table if it exists?
dooff Simultaneously fit a zero-level offset?

offset Initial estimate for the zero-level offset. Only used if dooff is True. fixoffset Hold zero-level offset constant during fit? Only used if dooff is True.

stretch Stretch the input mask if necessary and possible. Only used if a mask is sp

See help par.stretch.

rms RMS to use in calculation of various uncertainties, assumed to have units of

image. If not positve, the rms of the residual image is used.

noisefwhm Noise correlation beam FWHM. If numeric value, interpreted as pixel widths

quantity (dictionary, string), it must have angular units.

OVERVIEW

This application is used to fit one or more two dimensional gaussians to sources in an image well as an optional zero-level offset. Fitting is limited to a single polarization but can be performed over several contiguous spectral channels.

If the image has a clean beam, the report and returned dictionary will contain both the convand the deconvolved fit results.

When dooff is False, the method returns a dictionary with three keys, 'converged', 'results and 'deconvolved'. The value of 'converged' is a boolean array which indicates if the fit converged on a channel by channel basis. The value of 'results' is a dictionary representing a component list reflecting the fit results. In the case of an image containing beam information the sizes and position angles in the 'results' dictionary are those of the source(s) convolved with the restoring beam, while the same parameters in the 'deconvolved' dictionary represent source sizes deconvolved from the beam. In the case where the image does not contain a beam 'deconvolved' will be absent. Both the 'results' and 'deconvolved' dictionaries can be read into a component list tool (default tool is named cl) using the from record() method for easier inspection using tool methods, eg

cl.fromrecord(res['results'])

although this currently only works if the flux density units are conformant with Jy.

supply additional information. There is a 'peak' subdictionary for each component that prove peak intensity of the component. It is present for both 'results' and 'deconvolved' component There is also a 'sum' subdictionary for each component indicated the simple sum of pixel value the original image enclosed by the fitted ellipse. There is a 'channel' entry in the 'sp subdictionary which provides the zero-based channel number in the input image for which the applies. In addtion, if the image has a beam(s), then there will be a 'beam' subdictionary with each component in both the 'results' and 'deconvolved' dictionaries. This subdictionary have three keys: 'beamarcsec' will be a subdictionary giving the beam dimensions in arcsec, 'beampixels' will have the value of the beam area expressed in pixels, and 'beamster' will be value of the beam area epressed in steradians. Also, if the image has a beam(s), in the comp dictionaries will be an 'ispoint' entry with an associated boolean value describing if the cis consistent with a point source.

There are also values in each component subdictionary not used by cl.fromrecord() but meant

If dooff is True, in addtion to the specified number of gaussians, a zero-level offset will also be fit. The initial estimate for this offset is specified using the offset parameter. Units are assumed to be the same as the image brightness units. The zero level offset can be held constant during the fit by specifying fixoffset=True. In the case of dooff=True, the returned dictionary contains two additional keys, 'zerooff' and 'zeroofferr', which are both dictionaries containing 'unit' and 'value' keys. The values associated with the 'value' keys are arrays containing the the fitted zero level offset value and its error, respective for each channel. In cases where the fit did not converge, these values are set to NaN.

The value associated with 'unit' is just the image brightness unit.

The region can either be specified by a box(es) or a region.
Ranges of pixel values can be included or excluded from the fit. If specified using the box parameter, multiple boxes can be given using the format box="blcx1, blcy1, trcx1, trcy1, blcx2, blcy2, trcx2, trcy2, ..., blcxN, blcyN, trcxN, trcy where N is the number of boxes. In this case, the union of the specified boxes will be used

If specified, the residual and/or model images for successful fits will be written.

If an estimates file is not specified, an attempt is made to estimate initial parameters and fit a single Gaussian. If a multiple Gaussian fit is desired, the user must specify initial estimates via a text file (see below for details).

The user has the option of writing the result of the fit to a log file, and has the option of either appending to or overwriting an existing file.

The user has the option of writing the (convolved) parameters of a successful fit to a file which can be fed back to fitcomponents() as the estimates file for a subsequent run.

If specified and positive, the value of rms is used to calculate the parameter uncertainties otherwise, the rms in the selected region in the relevant channel is used for these calculates the results of the results o

The noisefwhm parameter represents the noise-correlation beam FWHM. If specified as a quantitic should have angular units. If specified as a numerical value, it is set equal to that numerical value, it is set equal to that numerical value, it is used to calculate parameter uncertainties using the correlated noise equations (see below). If it is specified less than a pixel width, the the uncorrelated noise equations (see below) are used to compute the parameter uncertainties. If it is not specified and the image has a restoring bethe the correlated noise equations are used to compute parameter uncertainties using the geometric mean of the relevant beam major and minor axes as the noise-correlation beam FWHM noisefwhm is not specified and the image does not have a restoring beam, then the uncorrelation see equations are used to compute the parameter uncertainties.

SUPPORTED UNITS

Currently only images with brightness units conformant with Jy/beam, Jy.km/s/beam, and K are supported for fitting. If your image has some other base brightness unit, that unit will be to be equivalent to Jy/pixel and results will be calculated accordingly. In particular, the flux density (reported as Integrated Flux in the logger and associated with the "flux" line the returned component subdictionary(ies)) for such a case represents the sum of pixel value.

Note also that converting the returned results subdictionary to a component list via cl.fromonly works properly if the flux density units in the results dictionary are conformant with

If you need to be able to run cl.fromrecord() on the resulting dictionary you can first mode flux density units by hand to be (some prefix)Jy and then run cl.fromrecord() on that diction bearing in mind your unit conversion.

If the input image has units of K, the flux density of components will be reported in units of [prefix]K*rad*rad, where prefix is an SI prefix used so that the numerical value is between 1 and 1000. To convert to units of K*beam, determine the area of the appropriate beam, which is given by pi/(4*ln(2))*bmaj*bmin, where bmaj and bmin are the major and minor axes of the beam, and convert to steradians (=rad*rad). This value is included in the beam portion of the component subdictionary (key 'beamster'). Then divide the numerical value of the logged flux density by the beam area in steradians. So, for example

```
\begin{verbatim}
# run on an image with K brightness units
res = imfit(...)
# get the I flux density in K*beam of component 0
comp = res['results']['component0']
flux_density_kbeam = comp['flux']['value'][0]/comp['beam']['beamster']
```

FITTING OVER MULTIPLE CHANNELS

For fitting over multiple channels, the result of the previous successful fit is used as the estimate for the next channel. The number of gaussians fit cannot be varied on a channel by channel basis. Thus the variation of source structure should be reasonably smooth in frequency to produce reliable fit results.

MASK SPECIFICATION

Mask specification can be done using an LEL expression. For example mask = "myimage" ¿5' will use only pixels with values greater than 5. INCLUDING AND EXCLUDING PIXELS

Pixels can be included or excluded from the fit based on their values using these parameters. Note that specifying both is not permitted and will cause an error. If specified, both take an array of two numeric values.

ESTIMATES

Initial estimates of fit parameters may be specified via an estimates text file. Each line of this file should contain a set of parameters for a single gaussian. Optionally, some of these parameters can be fixed during the fit. The format of each line is

peak intensity, peak x-pixel value, peak y-pixel value, major axis, minor axis, position angle, fixed

The fixed parameter is optional. The peak intensity is assumed to be in the same units as the image pixel values (eg Jy/beam). The peak coordinates are specified in pixel coordinates. The major and minor axes and the position angle are the convolved parameters if the image has been convolved with a clean beam and are specified as quantities. The fixed parameter is optional and is a string. It may contain any combination of the following characters 'f' (peak intensity), 'x' (peak x position), 'y' (peak y position), 'a' (major axis), 'b' (minor axis), 'p' (position angle).

In addition, lines in the file starting with a # are considered comments. An example of such a file is:

```
# peak intensity must be in map units
120, 150, 110, 23.5arcsec, 18.9arcsec, 120deg
90, 60, 200, 46arcsec, 23arcsec, 140deg, fxp
```

This is a file which specifies that two gaussians are to be simultaneously fit, and for the second gaussian the specified peak intensity, x position, and position angle are to be held fixed during the fit.

ERROR ESTIMATES

Error estimates are based on the work of Condon 1997, PASP, 109, 166. Key assumptions made are: * The given model (elliptical Gaussian, or elliptical Gaussian plus constant offset) is an adequate representation of the data * An accurate estimate of the pixel noise is provided or can be derived (see above). For the case of correlated noise (e.g., a CLEAN map), the fit region should contain many "beams" or an independent value of rms should be provided. The signal-to-noise ratio (SNR) or the Gaussian component is large. This is necessary because a Taylor series is used to linearize the problem. Condon (1997) states that the fractional bias in the fitted amplitude due to this assumption is of order 1/(S*S), where S is the overall SNR of the Gaussian with respect to the given data set (defined more precisely below). For a 5 sigma "detection" of the Gaussian, this is a 4% effect. * All (or practically all) of the flux in the component being fit falls within the selected region. If a constant offset term is simultaneously fit and not fixed, the region of interest should be even larger. The derivations of the expressions summarized in this note assume an effectively infinite region.

Two sets of equations are used to calculate the parameter uncertainties, based on if the noise is correlated or uncorrelated. The rules governing which set of equations are used have been described above in the description of the noisefwhm parameter.

In the case of uncorrelated noise, the equations used are

$$f(A) = f(I) = f(M) = f(m) = k*s(x)/M = k*s(y)/m = (s(p)/sqrt(2))*((M*M-m*m)/(M*m)) = sqrt(2)/S$$

where s(z) is the uncertainty associated with parameter z, f(z) = s(z)/abs(z) is the fractional uncertainty associated with parameter z, A is the peak intensity, I is the flux density, M and m are the FWHM major and minor axes, p is the position angle of the component, and $k = \operatorname{sqrt}(8*\ln(2))$. s(x) and s(y) are the direction uncertainties of the component measured along the major and minor axes; the resulting uncertainties measured along the principle axes of the image direction coordinate are calculated by propagation of errors using the 2D rotation matrix which enacts the rotation through the position angle plus 90 degrees. S is the overall signal to noise ratio of the component, which, for the uncorrelated noise case is given by

$$S = (A/(k*h*r))*sqrt(pi*M*m)$$

where h is the pixel width of the direction coordinate and r is the rms noise (see the discussion above for the rules governing how the value of r is determined).

For the correlated noise case, the same equations are used to determine the uncertainties as in the uncorrelated noise case, except for the uncertainty in I (see below). However, S is given by

S = (A/(2*r*N)) * sqrt(M*m) * (1 + ((N*N/(M*M)))**(a/2)) * (1 + ((N*N/(m*m)))**(b/2))

where N is the noise-correlation beam FWHM (see discussion of the noisefwhm parameter for rules governing how this value is determined). "**" indicates exponentiation and a and b depend on which uncertainty is being calculated. For sigma(A), a = b = 3/2. For M and x, a = 5/2 and b = 1/2. For m, y, and p, a = 1/2 and b = 5/2. f(I) is calculated in the correlated noise case according to

 $f(I) = \operatorname{sqrt}(\ f(A)*f(A) + (N*N/(M*m))*(f(M*f(M) + f(m)*f(m))))$ Note well the following caveats: * Fixing Gaussian component parameters will tend to cause the parameter uncertainties reported for free parameters to be overestimated. * Fitting a zero level offset that is not fixed will tend to cause the reported parameter uncertainties to be slightly underestimated. * The parameter uncertainties will be inaccurate at low SNR (a $\sim\!10\%$ for SNR = 3). * If the fitted region is not considerably larger than the largest component that is fit, parameter uncertainties may be mis-estimated. * An accurate rms noise measurement, r, for the region in question must be supplied. Alternatively, a sufficiently large signal-free region must be present in the

selected region (at least about 25 noise beams in area) to auto-derive such an estimate. * If the image noise is not statistically independent from pixel to pixel, a reasonably accurate noise correlation scale, N, must be provided. If the noise correlation function is not approximately Gaussian, the correlation length can be estimated using

 $N = \operatorname{sqrt}(2*\ln(2)/\operatorname{pi})*$ double-integral(dx dy C(x,y))/sqrt(double-integral(dx dy C(x,y)*C(x,y)))

where C(x,y) is the associated noise-smoothing function * If fitted model components have significan spatial overlap, the parameter uncertainties are likely to be mis-estimated (i.e., correlations between the parameters of separate components are not accounted for). * If the image being analyzed is an interferometric image with poor uv sampling, the parameter uncertainties may be significantly underestimated.

The deconvolved size and position angle errors are computed by taking the maximum of the absolute values of the differences of the best fit deconvolved value of the given parameter and the deconvolved size of the eight possible combinations of (FWHM major axis +/- major axis error), (FWHM minor axis +/- minor axis error), and (position andle +/- position angle error). If the source cannot be deconvolved from the beam (if the best fit convolved source size cannot be deconvolved from the beam), upper limits on the deconvolved source size are sometimes reported. These limits simply come from the maximum major and minor axes of the deconvolved gaussians taken

from trying all eight of the aforementioned combinations. In the case none of these combinations produces a deconvolved size, no upper limit is reported. EXAMPLE:

Here is how one might fit two gaussians to multiple channels of a cube using the fit from the previous channel as the initial estimate for the next. It also illustrates how one can specify a region in the associated continuum image as the region to use as the fit for the channel.

```
default imfit
imagename = "co_cube.im"
# specify region using region from continuum
region = "continuum.im:source.rgn"
chans = "2~20"
# only use pixels with positive values in the fit
excludepix = [-1e10,0]
# estimates file contains initial parameters for two Gaussians in channel 2
estimates = "initial_estimates.txt"
logfile = "co_fit.log"
# append results to the log file for all the channels
append = "True"
imfit()
```

imhead-task.html

0.1.39 imhead

Requires:

Synopsis

List, get and put image header parameters

Arguments

Inputs	
imagename	Name of the input image
	allowed: string
	Default:
mode	Mode of operation: "add", "del", "get", "history",
	"list", "put", or "summary". Modes "add", "del", and
	"put" will not work if the image is read-only (eg a FITS
	image).
	allowed: string
	Default: summary
hdkey	The associated keyword for modes "add", "del", "get",
	or "put". Only "get" will work if the image is read-only
	(eg, a FITS image).
	allowed: string
	Default:
hdvalue	Value of keyword for modes add or put.
	allowed: any
	Default: variant
verbose	Give a full listing of beams or just a short summary?
	Only used when the image has multiple beams and
	mode="summary".
	allowed: bool
	Default: False

${\bf Returns}$

variant

Example

PARAMETER SUMMARY

imagename Input image name. example: imagename='ngc5921_task.image'

mode Mode of operation. Supported values: 'list', 'summary', 'history',

'get', 'put', 'add', 'del'.

NOTE: 'add', 'del', and 'put' should be used with caution, and will not work in

read-only (eg FITS images are read-only in CASA).

hdkey Keyword to use with get, put, add, or del. example: hdkey='telescope'

hdvalue keyword value used for modes "put" and "add". Also used for mode="del" when

hdvalue="masks. example: hdvalue='VLA'

This task allows the user to manipulate metadata associated with a CASA image. Both float and complex valued images are fully supported. The supported mode values

add Add a new metadata value to the image.

del Delete a key or reset its value to a fidicual value if possible.

Ignores all but imagename, mode, and hdkey parameters.

get Return the specified keyword value. Ignores all but imagename, mode, and hdkey par

history Log image history. Ignores all but imagename and mode parameters.

list Show supported keywords and their values. Ignores all but imagename and mode parameters.

put Modify the specified value associated with the keyword.

summary Log a summary of the image and return a dictionary of various metadata values.

Ignores all but imagename and mode parameters.

See below for details about how these modes act for specific keywords.

NOTE: Only limited checking is implemented to ensure modifying a specific value will leave the image metadata in a consistent state, so, if one is not careful, one could end up with an image that has an inconsistent set of metadata and is therefore, nonsensical and useless That is, PROCEED AT YOUR OWN RISK when using modes add, del, or put

NOTE: For measurement sets, the task vishead should be used.

Supported keywords can be listed using mode = 'list'

beammajor/bmaj Major axis of the clean beam beamminor/bmin Minor axis of the clean beam beampa/bpa Position angle of the clean beam

NOTE: If the image contains multiple beams, use mode="summary" to list them

with verbose=True.

bunit Image units (K, Jy/beam, etc)

cdeltn Pixel size, nth axis. n is one-based.

crpixn The pixel designated as the reference location, nth axis n is one-based.

crvaln World coordinate value of the reference pixel for the nth axis. n is one-base

ctypen Name of nth axis. n is one-based. cunitn Units of nth axis. n is one based.

datamax Maximum pixel value. datamin Minimum pixel value.

date-obs Date (epoch) of the observation.
equinox Direction reference frame.
imtype Image type (eg Intensity)

minpos World coordinate position of minimum pixel value.
minpixpos Pixel coordinate position of minimum pixel value.
maxpos World coordinate position of maximum pixel value.
maxpixpos Pixel coordinate position of maximum pixel value.

object Source name observer Observer name

projection Direction coordinate projection (eg 'SIN', 'TAN', or 'ZEA').

reffreqtype Spectral reference frame.

restfreq Rest Frequency.

shape Number of pixels along each axis.

telescope Telescope name.

NOTES on mode="add"

The behavior of mode="add" depends on the keyword. Below is a summary of the per keyword behavior of this mode. In general, the return value will be True if the operation succeeds, or False if it fails or is not supported. If unsuccessful or not supported, a message is normally logged which describes the failure. In most cases, you probably want to use mode='put' rather than mode='add'. We continue to support mode='add' mainly for backward compatibility.

		•	
Kevword	Rehavior	for	mode="del"

beammajor or bmaj	If image has no beam(s), a single, global, circular beam of diameter
	specified in hdvalue is added. hdvalue must be a valid angular quant:
	or dictionary) or the operation will fail and False will be returned
	If the image has a beam(s), the operation fails and False is returned
	Examples of acceptable values of hdvalue are "4arcsec", qa.quantity(
	{'unit': 'arcsec', 'value': 4.0}.

If you wish an image to have multiple beams, use ia.setrestoringbeam beamminor or bmin Behavior is the same as that for beammajor or bmaj.

became in the part of barrier of

beammajor, bmaj, beamminor, or bmin.

bunit If image has no brightness unit, add the value specified in hdvalue

be a unit supported by CASA. Else do nothing and return False.

cdelt* No effect. Addition of coordinate system parameters is not supported

False. Use the cs tool to add coordinates.

crpix* No effect. Addition of coordinate system parameters is not supported

False. Use the cs tool to add coordinates.

crval* No effect. Addition of coordinate system parameters is not supported

False. Use the cs tool to add coordinates.

No effect. Addition of coordinate system parameters is not supported ctype*

False. Use the cs tool to add coordinates.

cunit* No effect. Addition of coordinate system parameters is not supported

False. Use the cs tool to add coordinates.

datamax No effect. Addition of statistical parameters is not supported. No effect. Addition of statistical parameters is not supported. datamin

No effect. date-obs or epoch No effect. equinox

imtype If image type does not exist, add the type specified in hdvalue. hdva

"Undefined", "Intensity", "Beam", "Column Density", "Depolarization 1 "Kinetic Temperature", "Magnetic Field", "Optical Depth", "Rotation I "Rotational Temperature", "Spectral Index", "Velocity", or "Velocity I

masks No effect. Addition of masks is not supported. Use ia.calcmask(). No effect. Addition of statistical parameters is not supported. maxpos No effect. Addition of statistical parameters is not supported. maxpixpos No effect. Addition of statistical parameters is not supported. minpos No effect. Addition of statistical parameters is not supported. minpixpos

object If image has no object, add the value specified in hdvalue. Else do If image has no observer, add the value specified in hdvalue. Else do observer

projection No effect. No effect. reffreqtype

If image has a spectral coordinate and no rest frequency, set the res restfreq

> to the value specified in hdvalue. This value must be a valid CASA qu units. Else do nothing and return False. Examples of valid values are

{'unit': 'GHz', 'value': 1.0}

shape No effect.

telescope If image has no telescope, add the value specified in hdvalue. Else any user defined key Add the key-value pair if the key does not exist. Else do nothing and

NOTES on mode="del"

The behavior of mode="del" depends on the keyword. Below is a summary of the per keyword behavior of this mode. In general, the return value will be True if the operation succeeds, or False if it fails or is not supported. If unsuccessful or not supported, a warning message is normally logged which describes the failure.

Keyword Behavior for mode="del"

beammajor or bmaj Deletes all beams. Returns False if the image has no beams. beamminor or bmin Deletes all beams. Returns False if the image has no beams. beampa or bpa Deletes all beams. Returns False if the image has no beams.

Sets the associated value to the empty string. bunit

cdelt* No effect. Deletion of coordinate system parameters is not supported No effect. Deletion of coordinate system parameters is not supported crpix*

crval* No effect. Deletion of coordinate system parameters is not supported ctype* No effect. Deletion of coordinate system parameters is not supported cunit* No effect. Deletion of coordinate system parameters is not supported

datamax No effect. Deletion of statistical parameters is not supported.
datamin No effect. Deletion of statistical parameters is not supported.

date-obs or epoch No effect. equinox No effect. imtype No effect.

masks Deletes the single mask specified in hdvalue, or if hdvalue="", deleter maying.

maxpos No effect. Deletion of statistical parameters is not supported.
maxpixpos No effect. Deletion of statistical parameters is not supported.
minpos No effect. Deletion of statistical parameters is not supported.
minpixpos No effect. Deletion of statistical parameters is not supported.

object Sets the associated value to the empty string. observer Sets the associated value to the empty string.

projection No effect.
reffreqtype No effect.
restfreq No effect.
shape No effect.

telescope Sets the associated value to the empty string.

any user defined key Deletes the key-value pair.

NOTES ON mode='get'

The data type of the value returned by imhead when mode='get' depends on the keyword. Below is a list of keywords on the data type that will be returned when mode='get' for each. A "quantity dictionary" is a dictionary with 'value' and 'unit' keys that can be used as input to various methods of the qa tool.

keyword data type returned when mode='get'

beammajor quantity dictionary
beamminor quantity dictionary
beampa quantity dictionary
bmaj quantity dictionary
bmin quantity dictionary
bpa quantity dictionary

bunit string

cdelt* quantity dictionary

crpix* float

crval* quantity dictionary, unless the value

for the stokes axis is requested in which case

an array of strings is returned

ctype* string
cunit* string

datamax image pixel data type datamin image pixel data type

date-obs or epoch string (YYYY/MM/DD/hh:mm:ss format)

equinox string imtype string

masks string array maxpos string

maxpixpos integer array

minpos string

minpixpos integer array

objectstringobserverstringprojectionstringreffreqtypestring

restfreq quantity dictionary

shape integer array

telescope string any user defined key string

NOTES on mode='put'

In general, mode='put' will modify the specified key to the specified value, with the following examples. True is returned if the metadatum was successfully modified, False otherwise. Normally, a diagnostic message is logged if there is a failure. Only the parameter specified is modified; eg, no modification of reference direction occurs to implicate account for precession to a new reference frame. The following are the exceptional cases for

beammajor or bmaj Will always fail if image has multiple beams. Use ia.setrestoringbear in this case. If image has no beam(s), a single, global, circular beauspecified in hdvalue is added. hdvalue must be a valid angular quant:

or dictionary) or the operation will fail and False will be returned If the image has a single beam, the value of the major axis will be unless the specified value is smaller than the minor axis of the exist

in which case nothing is modified and False is returned.

Examples of acceptable values of hdvalue are "4arcsec", qa.quantity(

{'unit': 'arcsec', 'value': 4.0}.

beamminor or bmin Behavior is the same for bmaj, although of course if the image alread

a single beam, the specified value must be less than the existing ma

axis value, or nothing is modified and False is returned.

False is returned. Angular units are required.

bunit Fails if hdvalue is not a supported CASA unit.

cdelt* One-based axis must be less than or equal to the number of axes in the

hdvalue type must be a number (in which case the unit of the corresponding assumed) or a quantity (string or dictionary). If a quantity, the

conform to the existing axis unit.

crpix* One-based axis must be less than or equal to the number of axes in the

hdvalue type must be a number. Will fail if the polarization axis.

crval* One-based axis must be less than or equal to the number of axes in the

If not the polarization/stokes axis, hdvalue type must be a number (case the unit of the corresponding axis is assumed), a quantity (structure dictionary), or a valid measure format (such as a sexigesimal direct specification for an axis with angular units). If a quantity, the unconform to the existing axis unit. If the stokes/polarization axis, or provide an array of stokes/polarization strings (["I", "Q", "XX"]) the same length as the stokes axis. If the stokes axis is degenerate, one alternatively provide a string indicating the stokes value (eg "U").

ctype*

One-based axis must be less than or equal to the number of axes in the

hdvalue type must be a string.

cunit*

One-based axis must be less than or equal to the number of axes in the unit must conform to the existing axis unit. Will fail if stokes/pole

datamax This cannot be modified. False is always returned. datamin This cannot be modified. False is always returned.

date-obs or epoch

A valid time specification must be given.

equinox imtype

A valid direction reference frame specification string must be given A CASA-supported image type string must be given or the image type \mathbf{w} :

be set to 'Intensity'

masks Masks may not be modified. False is always returned.

maxpos This cannot be modified.
maxpixpos This cannot be modified.
minpos This cannot be modified.
minpixpos This cannot be modified.
object hdvalue must be a string.

observer hdvalue must be a string.

projection hdvalue must be a string a

projection hdvalue must be a string representing a supported CASA projection sperifreqtype hdvalue must be a string representing a supported CASA velocity reference.

specification.

restfreq

hdvalue can be a number (in which case frequency axis units are assurquantity string or quantity dictionary in which case the unit must country the active rest frequency may be modified. For more functionalist

cs.setrestfrequency().

shape This cannot be modified. telescope hdvalue must be a string.

any user defined key hdvalue can be practically any supported input parameter type.

EXAMPLES

```
# mode='get'. Image has direction and spectral coordinates
epoch = imhead(imagename=imagename, mode="get", hdkey="date-obs")
observer = imhead(imagename=imagename, mode="get", hdkey="observer")
projection = imhead(imagename=imagename, mode="get", hdkey="projection")
restfreq = imhead(imagename=imagename, mode="get", hdkey="restfreq")
```

mode='add'

if imhead(imagename=imagename, mode="add", hdkey="mykey", hdvalue="myvalue"):

```
print "mykey added".
else:
   print "addition of mykey failed".
# mode="del"
if imhead(imagename=imagename, mode="del", hdkey="mykey"):
   print "mykey deleted".
else:
   print "deletion of mykey failed".
# mode="put"
# change the reference RA value
key = 'crval1'
imhead(imagename=imagename, mode="put", hdkey=key, hdvalue="3:00:00")
# or equivalently
imhead(imagename=imagename, mode="put", hdkey=key, hdvalue="45deg")
# change the direction reference frame (NOTE, no precession of the existing
# reference values is done!)
imhead(imagename=imagename, mode="put", hdkey="equinox", hdvalue="GALACTIC")
# change the object
imhead(imagename=imagename, mode="put", hdkey="object", hdvalue="Milliways, also known as Tl
```

imhistory-task.html

0.1.40 imhistory

Requires:

Synopsis

Retrieve and modify image history

Arguments

Name of the input image
allowed: string
Default:
Mode to run in, "list" to retrieve history, "append" to
append a record to history.
allowed: string
Default: list
Write history to logger if mode="list"?
allowed: bool
Default: True
Origin of appended message. Only used for
mode="append".
allowed: string
Default: imhistory
eMessage to append. Only used of mode="append".
allowed: string
Default:

Returns

variant

Example

PARAMETER SUMMARY

imagename Name of the input (CASA, FITS, MIRIAD) image mode Operating mode. Either "list" or "append" is accepted.

verbose Log history if mode="list"?

origin Origin of appended message if mode="append".

message Message to append if mode="append".

This task provides access to the logtable of an image, where generally history information stored. Two operation modes are supported. When mode="list", the history messages are return as an array of strings. If verbose=True, this information is also written to the logger. When mode="append", a specified message (along with its specified origin) are appended to the log and True is returned if successful.

```
# get history and list to logger
imhistory("my.im", mode="list", verbose=True)
```

append a message
imhistory("my.im", origin="myorigin", "ETI signal found in this image!")

immath-task.html

0.1.41 immath

Requires:

Synopsis
Perform math operations on images

Description

math on images

Inputs

expr

imagename a list of input images

allowed: any Default: variant

mode mode for math operation (evalexpr, spix, pola, poli)

allowed: string
Default: evalexpr

outfile File where the output is saved

allowed: string

Default: immath_results.im

Mathematical expression using images

allowed: string Default: IM0

varnames a list of variable names to use with the image files

allowed: any Default: variant

sigma standard deviation of noise for debiasing

allowed: string

Default: 0.0mJy/beam

polithresh Threshold in linear polarization intensity image below

which to mask pixels. allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: string

Default:

box Rectangular region to select in direction plane. See "help

par.
box" for details. Default is to use the entire direction
 $\,$

plane.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

stretch Stretch the mask if necessary and possible? See help

stretch.par

allowed: ½97l Default: False

imagemd An image name from which metadata should be copied.

The input can be either an image listed under imagename or any other image on disk. Leaving this parameter unset may copy header metadata from any of the

input images, which one is not guaranteed.

allowed: string

Default:

Returns

bool

Example

This task evaluates mathematical expressions involving existing image files. The results of the calculations are stored in the designated output file. Options are available to specify mathematical expression directly or pre-defined expression for calculation of spectral index image, and polarization intensity and position angle images are available. The image file names imbedded in the expression or specified in the imagename parameter for the pre-defined calculations may be CASA images or FITS images.

NOTE: Index values start at 0 Use the imhead task to see the range of index values for each axes.

Keyword arguments:

imagename input image name(s)

Default: none;

Examples: mode='evalexpr'; imagename=['image1.im', 'image2.im'] The text 'IMO' is replaced by 'image1.im' in the expression and 'IM1' is repalced with 'image2.im' mode='spix'; imagename=['image1.im', 'image2.im'] will calculate an image of log(S1/S2)/log(f1/f2), where S1 and S2 are fluxes and f1 and f2 are frequencies

mode='pola'; imagename='multistokes.im' (where that image contains both Q and stokes planes) or imagename=['imageQ.im','imageU.im'] will calculate an image of polarization angle distribution, where imageQ.im and imageU.im are Stokes Q and U images, respectively. Calculate 0.5*arctan(U/Q) mode='poli'; imagename=['imageQ.im','imageU.im','imageV.im'] will calculate total polarization intensity image, where imageQ.im, imageU.im, imageV.im are Stokes Q, U, and V images, respectively. Alternatively, with imagename = ['imageQ.im','imageU.im'] the linear polarization intensity image will be calculated. In the case where imagename is a single multi-stoke image, the total polarization image will be calculated if all of the Q, U, and V stokes planes are present, and the linear polarization intensity image will be calculated if the Q and U (but not V) planes are present.

```
mode for mathematical operation
mode
           Default: evalexpr
           Options: 'evalexpr' : evalulate a mathematical expression defined in 'expr'
                    'spix' : spectalindex image
                    'pola' : polarization position angle image
                    'poli' : polarization intesity image
          >>> mode expandable parameters
                      (for mode='poli') standard deviation of noise of Stokes images with
          sigma
                      Jy/beam to correct for bias
                      Default: '0.0Jy/beam' (= no debiasing)
                      (for mode='pola') Quantity (eg '30uJy/beam') describing the linear
                      the stokes V contribution is not included) polarization threshold
                      is written to the output image and is False for all corresponding
                      values below this threshold. This parameter overrides the mask in
                      (below). Default ('') means use the value given in mask, or no mas
                      value is empty as well.
                      (for mode='evalexpr') A LEL expression with images.
          expr
                  Image file names are specified in the imagenames paramter, and
                      the variables IMO, IM1, ... (or optionally via the varnames parame
                      are used to represent these files
                      in the expression. Explicit notations of file names in the
                      expression are also supported, in which cases the file names must
                      be enclosed in double quotes (") and imagename is ignored.
                  Examples:
                      Make an image that is image1.im - image2.im
                      expr=' (IMO - IM1 )'
                      or with an explicit notation,
                      expr='("image1.im" - "image2.im")'
                      Clip an image below a value (0.5 in this case)
                      expr = 'iif(IMO >= 0.5, IMO, 0.0)'
                      Note: iif (a, b, c)
                                            a is the boolean expression
                                            b is the value if true
                                            c is the value if false
                      Take the rms value of two images
                      expr = ' sqrt(IMO * IMO + IM1 * IM1) '
                      Note: No exponentiaion available?
                      Build an image pixel by pixel from the minimum of (image2.im, 2*in
                      expr='min(IM1,2*max(IM0))'
                      For mode="evalexpr". Instead of the default variable names IMO, I
           varnames
                      the names in this array to represent the input images.
           The output image. Overwriting an existing outfile is not permitted.
outfile
       Default: immath_results.im; Example: outfile='results.im'
mask
           Mask to use. See help par.mask. Default is none. Also see polithresh.
           Stretch the input mask if necessary and possible. See below.
stretch
region
           Region selection. See "help par.region" for details. Default is to use the for
           Rectangular region to select in direction plane. See "help par.box" for deta:
box
```

is to use the entire direction plane.

Example: box='10,10,50,50'

chans Channels to use. See "help par.chans" for details. Default is to use all chars stokes Stokes planes to use. See "help par.stokes" for details. Default is to use a Not used in for cases of mode='poli' or mode='pola'

imagemd The image from which metadata should be copied to the output. Default means which image is used. The image must exist and should conform to the output:

Available functions in the expr and mask parameters: pi(), e(), sin(), sinh(), asinh(), cos(), cosh(), tan(), tanh(), atan(), exp(), log(), log10(), pow(), sqrt(), complex(), conj() real(), imag(), abs(), arg(), phase(), amplitude(), min(), max() round(), isgn(), floor(), ceil(), rebin(), spectralindex(), pa(), iif(), indexin(), replace(), ...

If the mask has fewer dimensions than the image and if the shape of the dimensions the mask and image have in common are the same, the mask will automatically have the missing dimensions added so it conforms to the image.

For a full description of the allowed syntax see the Lattice Expression Language (LEL) documentation on the at: http://aips2.nrao.edu/docs/notes/223/223.html

NOTE: where indexing and axis numbering are used in the above functions they are 1-based, ie. numbering starts at 1.

If stretch is true and if the number of mask dimensions is less than or equal to the number of image dimensions and some axes in the mask are degenerate while the corresponding axes in the image are not, the mask will be stetched in the degenerate axis dimensions. For example, if the input image has shape [100, 200, 10] and the input mask has shape [100, 200, 1] and stretch is true, the mask will be stretched along the third dimension to shape [100, 200, 10]. However if the mask is shape [100, 200, 2], stretching is not possible and an error will result.

Note that when multiple image are used in the expression, there is no garauntee about which of those images will be used to create the metadata of the output image, unless imagemd is specified. If imagemd is specified, the following rules of metadata copying will be followed:

- 1. The pixel data type of the image specified by imagemd and the output image must be the same.
- 2. The metadata copied include the coordinate system (and so of course the dimensionalithe output image must correspond to the coordinate system to be copied), the image_info

```
(which contains things like the beam(s)), the misc_info record (should one exist in the
specified by imagemd), and the units.
3. If the output image is a spectral image, the brightness units are set to the empty states
4. If the ouptut image is a polarization angle image, the brightness unit is set to "deg
the stokes coordinate is set to have a single plane of type of Pangle.
Examples:
# Double all values in an image.
immath( imagesname='myimage.im', expr='IM0*2', outfile='double.im' )
# or with an explicit notation,
immath( expr='"myimage.im"*2', outfile='double.im' )
# Taking the sin of an image and adding it to another
# Note that the images need to be the same size
immath(images=['image1.im', 'image2.im'], expr='sin(IM1)+IM0;',outfile='newImage.im')
# Adding only the plane associated with the 'V' stokes value and
# the 1st channel together in two images
immath(imagename=[image1', 'image2'], expr='IMO+IM1',chans='1',stokes='V')
# Selecting a single plane (5th channel), of the 3-D cube and
# adding it to the original image. In this example the 2-D plane
# gets expanded out and the values are applied to each plane in the
# 3-D cube.
default('immath')
imagename='ngc7538.image'
outfile='chanFive.im'
expr='IMO'
chans='5'
go
default('immath')
imagename=['ngc7538.image', chanFive.im']
outfile='ngc7538_chanFive.im'
expr='IMO+IM1'
go
# Selecting and saving the inner 3/4 of an image for channels 40,42,44
# as well as channels less than 10
default('immath')
imagename='my_image.im'
expr='IMO'
box='25,25,123,123'
chans='<10;40,42,44'
```

outfile='my_image_inner.im')

go

```
# Dividing an image by another, making sure we aren't dividing by zero
default('immath')
imagename=['orion.image', 'my.image']
expr='IMO/iif(IM1==0,1.0,IM1)'
outfile='my_orion.image'
# Applying a mask to all of the images in the expression
default('immath')
imagename=['ngc7538.image', 'ngc7538_clean.image']
expr='(IMO*10)+IM1'
mask='"ngc7538.mask"'
outfile='really_noisy_ngc7538.image'
go
# Applying a pixel mask contained in the image information
default('immath')
imagename='ngc5921.image'
expr='IM0*10'
mask='mask("ngc5921.mask")'
outfile='ngc5921.masked.image'
# Creating a total polarization intensity image from an multi-stokes image
# containing IQUV.
default('immath')
outfile='pol_intensity'
stokes=',
# in imagename, you can also specify a list containing single stokes images
# of Q and U (for linear polarization intensity) and V (for total
# polarization intensity)
imagename='3C138_pcal'
mode='poli'
go
# Creating a polarization position angle image
default('immath')
outfile='pol_angle.im'
mode='pola'
# you can also do imagename=['Q.im','U.im'] for single stokes images, order of
# the two Stokes images does not matter
imagename='3C138_pcal' # multi-stokes image containing at least Q and U stokes
go
```

```
# same as before but write a mask with values of False for pixels for which the
# corresponding linear polarization ( sqrt(Q*Q+U*U)) is less than 30 microJy/beam
polithresh='30uJy/beam'
go
# Creating a spectral index image from the images at two different observing frequencies
default('immath')
outfile='mySource_sp.im'
mode='spix'
imagename=['mySource_5GHz.im', 'mySource_8GHz.im']
```

TEMPORARY IMAGES

At this time, it is usually necessary for this task to create intermediate, temporary do the names of these images start with '_immath' and are created in the directory in which is run. The task makes reasonable attempts to remove these images before it exits, but to conceivably instances where the temporary images may not be automatically deleted. It is safe to delete them by hand, assuming no immath instance is currently in progress.

The hope and plan is that the necessity of these images will decrease in the future (ie will require only RAM and not temporary persistent storage of intermediate results).

	sk html

0.1.42 immoments

Requires:

Synopsis

Compute moments from an image

Description

Inputs

imagename Name of the input image

allowed: string

Default:

moments List of moments you would like to compute

allowed: intArray

Default: 0

axis The momement axis: ra, dec, lat, long, spectral, or

stokes

allowed: any

Default: variant spectral

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any
Default: variant

box Rectangular region(s) to select in direction plane. See

"help par.box" for details. Default is to use the entire

direction plane.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: string
Default: variant

includepix Range of pixel values to include

allowed: any

Default: variant -1

excludepix Range of pixel values to exclude

allowed: any

Default: variant -1

outfile Output image file name (or root for multiple moments)

allowed: string

Default:

stretch Stretch the mask if necessary and possible?

allowed: bool Default: False

Returns

bool

Example

The spectral moment distributions at each pixel are determined. See the cookbook and User Reference Manual for mathematical details.

The main control of the calculation is given by parameter moments:

moments=-1 - mean value of the spectrum
moments=0 - integrated value of the spectrum
moments=1 - intensity weighted coordinate; traditionally used to get
 'velocity fields'
 moments=2 - intensity weighted dispersion of the coordinate; traditionally
 used to get "velocity dispersion"
moments=3 - median of I
moments=4 - median coordinate
moments=5 - standard deviation about the mean of the spectrum
moments=6 - root mean square of the spectrum
moments=7 - absolute mean deviation of the spectrum
moments=8 - maximum value of the spectrum
moments=9 - coordinate of the maximum value of the spectrum

moments=11 - coordinate of the minimum value of the spectrum

moments=10 - minimum value of the spectrum

Keyword arguments:

imagename Name of input image default: none; example: imagename="ngc5921_task.image" List of moments you would like to compute moments default: 0 (integrated spectrum); example: moments=[0,1] see list above The moment axis axis default: (spectral axis); example: axis=spec options: ra, dec, lattitude, longitude, spectral, stokes Mask to use. See help par.mask. Default is none. mask stretch Stretch the input mask if necessary and possible. See below. Region selection. See "help par.region" for details. Default region is to use the full image. Rectangular region to select in direction plane. See box

```
Example: box="10,10,50,50"
            box = "10,10,30,30,35,35,50,50" (two boxes)
chans
            Channels to use. See "help par.chans" for details. Default is to use
            all channels.
            See "help par.chans" for examples.
           Stokes planes to use. See "help par.stokes" for details. Default is to
stokes
           use all Stokes planes.
           Example: stokes="IQUV";
           Example:stokes="I,Q"
includepix Range of pixel values to include
           default: [-1] (all pixels); example=[0.02,100.0]
excludepix Range of pixel values to exclude
           default: [-1] (don"t exclude pixels); example=[100.,200.]
outfile
            Output image file name (or root for multiple moments)
            default: "" (input+auto-determined suffix); example: outfile="source_moment"
```

"help par.box" for details. Default is to use the entire direction plane.

If stretch is true and if the number of mask dimensions is less than or equal to the number of image dimensions and some axes in the mask are degenerate while the corresponding axes in the image are not, the mask will be stetched in the degenerate axis dimensions. For example, if the input image has shape [100, 200, 10] and the input mask has shape [100, 200, 1] and stretch is true, the mask will be stretched along the third dimension to shape [100, 200, 10]. However if the mask is shape [100, 200, 2], stretching is not possible and an error will result.

```
Example for finding the 1-momment, intensity-weighted coordinate, often used for finding velocity fields.
immoments( axis="spec", imagename="myimage", moment=1, outfile="velocityfields" )

Example finding the spectral mean, -1 moment, on a specified region of the image as defined by the box and stokes parameters taskname="immoments" default() imagename = "myimage" moment = -1

axis = "spec"
```

stokes = "I" box = [55,12,97,32] go

Example using a mask created with a second file to select the data used to calculate the O-moments, integrated values. In

this case the mask is from the calibrated.im file and all values

that have a value greater than 0.5 will be positive in the mask.. immoments("clean.image", axis="spec", mask="calibrated.im>0.5", outfile="mom_withmage", axis="spec", mask="spec", mask="spec

If an image has multiple (per-channel beams) and the moment axis is equal to the spectral axis, each channel will be convolved with a beam that is equal to the beam having the largest area in the beamset prior to moment determination.

impbcor-task.html

impbcor 0.1.43

Requires:

 ${\bf Synopsis}$ Construct a primary beam corrected image from an image and a primary beam pattern.

Inputs

imagename Name of the input image

allowed: string

Default:

pbimage Name of the primary beam image which must exist or

array of values for the pb response. Default ""

allowed: any

Default: variant ""

outfile Output image name. If empty, no image is written. De-

fault ""

allowed: string

Default:

overwrite Overwrite the output if it exists? Default False

allowed: bool Default: False

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane.

allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any Default: variant

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels. allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: string

Default:

mode Divide or multiply the image by the primary beam im-

age. Minimal match supported. Default "divide"

allowed: string
Default: divide

cutoff PB cutoff. If mode is "d", all values less than this will

be masked. If "m", all values greater will be masked.

Less than 0, no cutoff. Default no cutoff

allowed: double Default: -1.0

stretch Stretch the mask if necessary and possible? See help

par.stretch

allowed: b230l Default: False

Returns

bool

Example

imagename

pbimage

PARAMETER SUMMARY

outfile	Name of output CASA image. Must be specified.
overwrite	If output file is specified, controls if an already existing file by the
	same name can be overwritten. If true, the user is not prompted, the file
	if it exists is automatically overwritten.
box	Rectangular region to select in direction plane. See "help par.box" for det
	is to use the entire direction plane.
region	Region selection. See "help par.region" for details. Default is to use the
chans	Channels to use. See "help par.chans" for details. Default is to use all ch
stokes	Stokes planes to use. See "help par.stokes" for details. Default is to use
1-	M1- +

Name of the image (CASA, FITS, MIRIAD) of the primary beam pattern or an ar

Name of the input (CASA, FITS, MIRIAD) image

mask Mask to use. See help par.mask. Default is none.

stretch Stretch the input mask if necessary and possible. See help par.mask.

mode Divide or multiply the image by the primary beam image. Minimal match support

cutoff PB cutoff. If mode is "d", all values less than this will be masked. If "m

DESCRIPTION

Correct an image for primary beam attenuation using an image of the primary beam pattern. The primary beam pattern can be provided as an image, in which case 1. it must have the same shape as the input image and its coordinate system must be the same, or 2. it must be a 2-D image in which case its coordinate system must consist of a (2-D) direction coordinate which is the same as the direction coordinate in the input image and its direction plane must be the same shape as that of the input image. Alternatively, pbimage can be an array of pixel values in which case the same dimensionality and shape constraints apply.

One can choose between dividing the image by the primary beam pattern (mode="divide") or multiplying the image by the primary beam pattern (mode="multiply"). One can also choose to specify a cutoff limit for the primary beam pattern. For mode="divide", for all pixels below this cutoff in the primary beam pattern, the output image will be masked. In the case of mode="multiply", all pixels in the output will be masked corresponding to pixels with values greater than the cutoff in the primary beam pattern. A negative value for cutoff means that no cutoff will be applied, which is the default.

EXAMPLE

impbcor(imagename="attunuated.im", pbimage="mypb.im", outname="pbcorred.im", mode="divide",

importate a-task.html

0.1.44 importatca

Requires:

Synopsis

Import ATCA RPFITS file(s) to a measurement set

Description

Imports an arbitrary number of ATCA RPFITS format data sets into a casa measurement set. If more than one band is present, they will be put in the same measurement set but in a separate spectral window. The task will handle both old ATCA and new CABB (after April 2009) archive data.

Inputs files Name of input ATCA RPFits file(s) allowed: stringArray Default: Name of output visibility file (MeasurementSet) vis allowed: string Default: options Processing options: birdie, reweight, noxycorr, fastmosaic, hires, noac (comma separated list) allowed: string Default: Specify the spectral windows to use, default=all spw allowed: intArray Default: Number of scans to skip followed by number of scans to nscans allowed: intArray Default: 0,0GHz Lowest reference frequency to select lowfreq allowed: doubleGHz Default: 0.1 highfreq GHzHighest reference frequency to select allowed: doubleGHz Default: 999 List of field names to select fields allowed: stringArray Default: Percentage of edge channels to flag. For combined edge zooms, this specifies the percentage for a single zoom window allowed: double Default: 8

Example

importatca(['2001-01-02_1*.C999','2001-01-03_0*.C999'],'c999.ms', options='birdie,reweight',edge=10)

Imports a number of ATCA RPFITS-format data sets into a casa measurement set. We are applying birdie flagging and lag spectrum reweighting (as approriate for old 33 channel continuum data) as well as flagging the 10% edge changes approximate to the set of the s

importasap-task.html

0.1.45 importasap

Requires:

Synopsis

Convert ASAP Scantable data into a CASA visibility file (MS)

Arguments

Inputs		
infile	Name of input ASAP Scantable data	
	allowed: string	
	Default:	
outputvis	Root name of the ms to be created. Note the .ms is	
	NOT added	
	allowed: string	
	Default:	
flagbackup	Back up flag column before applying flags.	
	allowed: bool	
	Default: True	
overwrite	Over write an existing MS(s)	
	allowed: bool	
	Default: False	

Returns

bool

Example

 $\begin{tabular}{ll} $\tt flagbackup & \tt -- Backup original flags in >ms<.flagversions \\ & default: True \\ \end{tabular}$

overwrite $\,\,$ -- overwrite an existing MS

default: False (do not overwrite)

importasdm-task.html

0.1.46 importasdm

Requires:

Synopsis

Convert an ALMA Science Data Model observation into a CASA visibility file (MS)

Inputs

asdm Name of input asdm directory (on disk)

allowed: string

Default:

vis Root name of the ms to be created. Note the .ms is

NOT added

allowed: string

Default:

createmms Create a multi-MS output

allowed: bool Default: False

separationaxis Axis to do parallelization across(scan, spw, baseline,

auto)

allowed: string Default: auto

numsubms The number of SubMSs to create (auto or any number)

allowed: any

Default: variant auto

corr_mode specifies the correlation mode to be considered on input.

A quoted string containing a sequence of ao, co, ac,or

all separated by whitespaces is expected

allowed: string
Default: all

srt specifies the spectral resolution type to be considered on

input. A quoted string containing a sequence of fr, ca,

bw, or all separated by whitespaces is expected

allowed: string Default: all

time_sampling specifies the time sampling (INTEGRATION and/or

SUBINTEGRATION) to be considered on input. A quoted string containing a sequence of i, si, or all sepa-

rated by whitespaces is expected

allowed: string Default: all

ocorr_mode output data for correlation mode AUTO_ONLY (ao) or

CROSS_ONLY (co) or CROSS_AND_AUTO (ca)

allowed: string Default: ca

compression Flag for turning on data compression

allowed: bool Default: False

lazy Make the MS DATA column read the ASDM Binary

data directly (faster import, smaller MS)

allowed: bool Default: False

asis Creates verbatim copies of the ASDMtables in the ouput

measurement set. Value given must be a string of table names separated by spaces; A * wildcard is allowed.

allowed: string

Default:

wvr_corrected_data Specifies which values are considered in the SDM binary

data to fill the DATA column in the MAIN table of the MS. Expected values for this option are: no, for uncorrected data (default), yes, for the corrected data, and both, for for corrected and uncorrected data. Note if both is selected two measurement sets are created, one

Returns

void

Example

- 1 Maximize the scan/spw/field distribution across sub-MSs
- 2 Generate sub-MSs with similar size
- * The 'scan' or 'spw' axes will partition the MS into scan or spw. The individual not be balanced with respect to the number of rows.
- * The 'baseline' axis is mostly useful for Single-Dish data. This axis will part based on the available baselines. If the user wants only auto-correlations, us ocorr_mode='ao'. Note that if numsubms='auto', partition will try to create as the number of available servers in the cluster. If the user wants to have one set the numsubms parameter to a number higher than the number of baselines to

```
numsubms -- The number of sub-MSs to create in the Multi-Ms.

default: 'auto'

Options: any integer number (example: numsubms=4)
```

The default 'auto' is to partition using the number of available servers given If the task is unable to determine the number of running servers, or the use

using mpicasa, numsubms will use 8 as the default.

Example: Launch CASA with 5 engines, where 4 of them will be used to create engine is used as the MPIClient.

mpicasa -n 5 casa --nogui --log2term
CASA> importasdm('uid__A1', createmms=True)

corr_mode -- correlation mode to be considered on input. Could
 be one or more of the following, ao, co, ac, or all
 default: 'all'

srt -- spectral resolution type. Could be one or more of the following, fr, ca, bw, or all default: 'all'

time_sampling -- specifies the time sampling, INTEGRATION and/or SUBINTEGRAION. could be one or more of the following i, si, or all.

default: 'all'

ocorr_mode -- output data for correlation mode AUTO_ONLY (ao) or CROSS_ONLY (co) or CROSS_AND_AUTO (ca)

default: 'ca'

compression -- produces comrpressed columns in the resulting measurement set.

default: False

-- Make the MS DATA column read the ASDM Binary data directly (faster import, smaller MS). Instead of writing a copy of the visibilities into a standard DATA column, lazy=True will make importasdm only write a lookup-table such that later access to the DATA column will read the ASDM binary visibility data directly. This requires that the ASDM not be removed from its location as long the the DATA column is needed.

Use method ms.asdmref() to query and manipulate the reference to the ASDM. lazy=True will save ca. 50% disk space and accelerate the DATA column access by ca. 10%.

lazy=True will only work when there is visibility data in the ASDM, not with pure radiometer data.

default: False

asis -- creates verbatim copies of the ASDM tables in the output measurement set. The value given to this option must be a list of table names separated by space characters; the wildcard character '*' is allowed in table names.

default: none

wvr_corrected_data -- specifies wich values are considered in the

ASDM binary data to fill the DATA column in

the MAIN table of the MS. Expected values for
this option are 'no' for the uncorrected data
(this is the default), 'yes' for the corrected
data and 'both' for corrected and uncorrected
data. In the latter case, two measurement sets
are created, one containing the uncorrected
data and the other one, whose name is suffixed
by '-wvr-corrected', containing the corrected
data.

default: 'no'

scans -- processes only the scans specified in the option's value. This value is a semicole separated list of scan specifications. A scan specification consists in an followed by the character ':' followed by a comma separated list of scan index ranges. A scan index is relative to the exec block it belongs to. So 1-based while exec blocks's are 0-based. '0:1' or '2:2~6' or '0:1,1:2~6,8 are valid values for the option. '3:' alone will be interpreted as 'all the exec block#3'. An scan index or a scan index range not preceded by an exec be interpreted as 'all the scans with such indexes in all the exec blocks all the scans are considered.

default: none (all scans)

ignore_time -- All the rows of the tables Feed, History, Pointing, Source, SysCal, CalDevice and Weather are processed independently of the time range of the selected exceedefault: False

process_flags -- Create online flags based on the Flag.xml, Antenna.xml and SpectralWindow and copy them to the FLAG_CMD sub-table of the MS. The flags will NOT be the parameter applyflags is set to True. Optionally, the flags can also an external ASCII file if savecmds is set to True.

default: True

>>> process_flags expandable parameter

tbuff -- Time padding buffer (in seconds)
 default: 0.0

NOTE: this time is in seconds. You should currently set the value of tbuff to be 1.5x the correlator integration time if greater than 1 second. For example, if the SDM has integrations of 3 seconds, set tbuff=4.5. Likewise, set tbuff=15.0 for 10-sec integrations.

applyflags -- Apply the online flags to the MS. default: False

savecmds -- Save the flag commands to an ASCII file given by the parameter of default: False

outfile -- Filename or list of filenames where to save the online flag commodefault: ' ' --> by default it will save on a filename composed from the Example: vis='uid_A02.ms', the outfile will be 'uid_A02_cmd.txt'.

vis='uid_A02-wvr-corrected.ms', the outfile will be 'uid_A02-wvr-corrected.ms',

verbose -- produce log output as asdm2MS is being run default: False

overwrite -- overwrite an existing MS or MS(s), if the option wvr_corrected_data='both' default: False (do not overwrite)

NOTE: the overwrite parameter affects all the output of the task. If any of exist, it will not overwrite them. MS(s), .flagversions, online flag : True, it will overwrite the MS, .flagversions and online flag file.

showversion -- report the version of the asdm2MS being used. default: False

useversion -- Selects the version of asdm2MS to be used (\'v3\' (default, should work for a default: v3

with_pointing_correction -- add (ASDM::Pointing::encoder - ASDM::Pointing::pointingDirection

to be written in MS::Pointing::direction

convert_ephem2geo -- ALMA uses ephemerides with observer location equal to the ALMA site.

For later processing of the radial velocity information in, e.g. cvel, a geocentric ephemeris is needed.

Setting this option to True will perform the conversion of positions as velocities on all attached ephemerides in the imported MS.

This will neither change the time-spacing nor the duration of the epher No interpolation in time is done. importevla-task.html

0.1.47 importevla

Requires:

Synopsis

Convert an Science Data Model observation into a CASA Measurement Set

Inputs

asdm Name of input asdm directory (on disk)

allowed: string

Default:

vis Root name of the ms to be created. Note the .ms is

NOT added

allowed: string

Default:

ocorr_mode Fill correlation mode AUTO_ONLY (ao),

CROSS_ONLY (co) or CROSS_AND_AUTO (ca)

allowed: string
Default: co

compression Flag for turning on data compression

allowed: bool Default: False

asis Create verbatim copies of these SDM tables in the MS.

allowed: string

Default:

scans List of scans to fill (default is all scans).

allowed: string

Default:

verbose Output lots of information while the filler is working

allowed: bool Default: False

overwrite Over write an existing MS

allowed: bool
Default: False

online Create online flags

allowed: bool Default: True

tbuff Time padding buffer (in seconds)

allowed: double Default: 0.0

flagzero Create flag commands for zero points

allowed: bool Default: True

flagpol Create flag commands for cross-hand correlations

allowed: bool Default: True

shadow Create flag commands for shadowed data

allowed: bool Default: True

tolerance Amount of shadow allowed (in meters)

allowed: double Default: 0.0

addantenna File name or dictionary with additional antenna names,

positions and diameters

allowed: 2459
Default: variant

applyflags Apply flag commands to MS

allowed: bool Default: False

savecmds Save flag commands to an ASCII file

allowed: bool Default: False

Returns

void

Example

Convert a Science Data Model (SDM) dataset into a CASA Measurement Set (MS). Will place online flags and specified clip/shadow flags into FLAG_CMD table and optionally apply to MS.

Warning: This version is under development and is geared to handling EVLA specific flag and system files, and is otherwise identical to importasdm.

HISTORY: Task created v1.0 S.T. Myers 2010-03-11 (3.0.1)

Last updated v9.0 S.M. Castro 2012-03-13 (3.4) code+doc

Keyword arguments:

asdm -- Name of input SDM file (directory)

default: none;

Example: asdm='ExecBlock3'

vis -- Root ms or scantable name, note a .ms is NOT appended to name

default: none

ocorr_mode -- output data for correlation mode AUTO_ONLY

(ao) or CROSS_ONLY (co) or CROSS_AND_AUTO (ca)

default: co (for EVLA)

compression -- produces comrpressed columns in the resulting measurement set.

default: False

asis -- creates verbatim copies of the ASDM tables in

the output measurement set. The value given to

this option must be a list of table names separated

by space characters; the wildcard character '*' is

allowed in table names.

scans -- processes the scans requested in this parameter (default is

all scans). For simplest use provide a comma-separated list of

scan ranges, e.g. scans='1~3,5,10~20'.

default: '' = all scans

NOTE: A scan specification tecnically consists of an ExecBlock

index followed by the character ':' followed by a comma separated list of scan indexes or scan index ranges. The EVLA does not currently include more than one ExecBlock in a SDM so this specification prefix is not needed.

By default all the scans are considered.

overwrite -- Over write an existing MS

verbose -- produce log output as asdm2MS is being run

EVLA-specific parameters:

online -- create

-- create flagging commands for online flags. The commands will be saved to the sub-table of the MS. Optionally, it can also be saved to an ASCII file when to True.

default: True

>>> online expandable parameters

tbuff -- (float) time padding buffer (in seconds)

default: 0.0

NOTE: this time is in seconds. You should currently set the value of tbuff to be 1.5x the correlator integration time if greater than 1 second. For example, if the SDM has integrations of 3 seconds, set tbuff=4.5. Likewise, set tbuff=15.0 for 10-sec integrations.

flagzero

-- create flags to clip out visibilities with zero values. The command will be sub-table of the MS. Optionally, it can also be saved to an ASCII file when to True.

default: True

>>> flagzero expandable parameter(s)
 flagpol -- (boolean) also zero-clip on cross-hands (default=False)

shadow

-- create flags for antennas that are shadowed. The command will be saved to the sub-table of the MS. Optionally, it can also be saved to an ASCII file when to True.

default: True

>>> shadow expandable parameter
 tolerance -- Amount of shadowing allowed in meters.

```
default: 0.0
                 addantenna -- It can be either a file name with additional antenna names,
                               and diameters, or a Python dictionary with the same informat:
                               You can use the flaghelper functions to create the dictionary
                   default: ''
                   To create a dictionary inside casapy.
                   > import flaghelper as fh
                   > antdic = fh.readAntennaList(antfile)
                   Where antfile is a text file in disk that contains information such as:
                    name=VLA01
                    diameter=25.0
                    position=[-1601144.96146691, -5041998.01971858, 3554864.76811967]
                    name=VLA02
                    diameter=25.0
                    position=[-1601105.7664601889, -5042022.3917835914, 3554847.245159178]
applyflags
            -- apply the online and specified flags to the MS
                default: False
savecmds
           -- Save the flag commands to an ASCII file given by the parameter outfile. It will
              flag commands from online, flagzero and/or shadow if they are set to True.
                default: False
            >>> savecmds expandable parameter
                             -- Filename where to save the flag commands.
                default: ' ' --> by default it will save on a filename composed from the MS
                    Example: vis='evla.ms', the outfile will be 'evla_cmd.txt'.
                    NOTE: The file is open to save in append mode.
             -- Backup original flags in >ms<.flagversions
                default: True
       Examples:
```

1) Produces MS CLowTest_000.ms with autocorrelations. You will find the online, zero, and shadow flags in the FLAG_CMD table for later application. Does not apply any flags.

```
importevla(asdm='CLowTest_000',ocorr_mode='ca')
```

2) Produces MS CLowTest_000.ms without autocorrelations.

```
importevla(asdm='CLowTest_000')
```

3) Will apply online flags and uses a more conservative 2sec buffer before the start and after the end timeranges.

```
importevla(asdm='CLowTest_000',online=True,tbuff=2.0,applyflags=True)
```

4) This will create the FLAG_CMD sub-table using online flags only, but will not apply them to the MS.

```
importevla(asdm='CLowTest_000',online=True,flagzero=False,shadow=False)
```

- 5) This will write the online flags to the FLAG_CMD table. It will also save command to clip zeros and to flag shadowed antennas to the table. The commands will be applied to the data and the APPLIED column of the FLAG_CMD will be updated to Table 1.
 - importevla(asdm='CLowTest_000',online=True,flagzero=True,shadow=True,applyflags=
- 6) Import only scans 1, 2, 3, 5, 7, 9, save the online, shadow and clip commands to do not apply the flags. The commands will be saved to CLowTest_000_cmd.txt.

You can use either flagdata or flagcmd to apply the flags later with the follower

```
Apply all the flags in the file using flagdata flagdata('CLowTest_000.ms', mode='list', inpfile='CLowTest_000_cmd.txt')
```

Apply all the flags in the file using flagcmd flagcmd('CLowTest_000.ms',inpmode='list',inpfile='CLTest_000_cmd.txt',action

HISTORY: Task last updated v9.0 S.M. Castro 2012-03-8 (3.4.0) Docs last updated v9.0 S.M. Castro 2012-03-13 (3.4.0)

importfits-task.html

0.1.48 importfits

Requires:

Synopsis

Convert an image FITS file into a CASA image

Description

Convert an image FITS file into a CASA image

Keyword arguments: fitsimage – Name of input image FITS file default: none; example='3C273XC1.fits' imagename – Name of output CASA image default: none; example: imagename='3C273XC1.image' whichrep – If fits image has multiple coordinate reps, choose one. default: 0 means first; example: whichrep=1 whichhdu – If fits file contains multiple images, choose this one (0 == first) default=-1 use the first valid one; example: whichhdu=1 zeroblanks – Set blanked pixels to zero (not NaN) default=True; example: zeroblanks=True overwrite – Overwrite pre-existing imagename default=False; example: overwrite=True defaultaxes – Add the default 4D coordinate axes where they are missing default=False, example: defaultaxes=True defaultaxesvalues – List of values to assign to added degenerate axes when defaultaxes==True (ra,dec,freq,stokes) default = [], example: defaultaxesvalues=['13.5h', '-2.5deg', '88.5GHz', 'Q'] beam – List of values to be used to define the synthesized beam [BMAJ,BMIN,BPA] (as in the FITS keywords) default = [] (i.e.take from FITS file), example: beam=['0.35arcsec', '0.24arcsec', '25deg']

Inputs fitsimage Name of input image FITS file allowed: string Default: Name of output CASA image imagename allowed: string Default: If fits image has multiple coordinate reps, choose one. whichrep allowed: int Default: 0 whichhdu If its file contains multiple images, choose one (0 = first)HDU, -1 = first valid image). allowed: int Default: -1 zeroblanks Set blanked pixels to zero (not NaN) allowed: bool Default: True Overwrite pre-existing imagename overwrite allowed: bool Default: False defaultaxes Add the default 4D coordinate axes where they are missing allowed: bool Default: False defaultaxesvalues List of values to assign to added degenerate axes when defaultaxes==True (ra,dec,freq,stokes) variant allowed: Default: List of values to be used to define the synthesized beam beam [BMAJ,BMIN,BPA] (as in the FITS keywords) allowed: variant Default:

Example

importfits(fitsimage='ngc3256.fits', imagename='ngc3256.im', overwrite=True)

import fit sidi-task.html

0.1.49 importfitsidi

Requires:

Synopsis

Convert a FITS-IDI file to a CASA visibility data set

Description

Convert a FITS-IDI file to a CASA visiblity data set.

Arguments

Inputs				
fitsidifile	Name(s) of input FITS-IDI file(s)			
	allowed: stringArray			
	Default:			
vis	Name of output visibility file (MS)			
	allowed: string			
	Default:			
constobsid	If True, give constant obs ID==0 to the data from all			
	input fitsidi files (False = separate obs id for each file)			
	allowed: bool			
	Default: False			
scanreindexgap_s	min time gap (seconds) between integrations to start a			
	new scan			
	allowed: double			
	Default: 0.			

Example

If several files are given, they will be concatenated into one MS.

importgmrt-task.html

0.1.50 importgmrt

Requires:

Synopsis

Convert a UVFITS file to a CASA visibility data set

Description

Convert a GRMT FITS file to a CASA visiblity data set. Also read GMRT flag file(s) and flag data based on the contents of the files.

Arguments

Inputs			
fitsfile	Name of input UV FITS file		
	allowed: string		
	Default:		
flagfile	Name of output visibility file (MS)		
	allowed: any		
	Default: variant		
vis	Name of output visibility file (MS)		
	allowed: string		
	Default:		

Example

Note: Don't forget to flag autocorrections using taskname flagdata, autocorr = true

importmiriad-task.html

0.1.51 importmiriad

Requires:

Synopsis

Convert a Miriad visibility file into a CASA MeasurementSet

Description

Convert a Miriad visibility file into a CASA MeasurementSet with optional selection of spectral windows and weighting scheme

Arguments

Inputs				
mirfile	Name of input Miriad visibility file			
	allowed: string			
	Default:			
vis	Name of output MeasurementSet			
	allowed: string			
	Default:			
tsys	Use the Tsys to set the visibility weights			
	allowed: bool			
	Default: False			
spw	Select spectral windows			
	allowed: string			
	Default: all			
vel	Select velocity reference (TOPO,LSRK,LSRD)			
	allowed: string			
	Default:			
linecal	(CARMA) Apply line calibration			
	allowed: bool			
	Default: False			
wide	(CARMA) Select wide window averages			
	allowed: string			
	Default: all			
debug	Display increasingly verbose debug messages			
	allowed: int			
	Default: 0			

$\begin{array}{c} \textbf{Returns} \\ \text{void} \end{array}$

Example

importmiriad(mirfile='ngc5921.uv', vis='ngc5921.ms',tsys=True)

importuv fits-task.html

0.1.52 importuvfits

Requires:

Synopsis

Convert a UVFITS file to a CASA visibility data set

Description

Convert a UVITS file to a CASA visiblity data set. Don't forget to flag autocorrelations using taskname flagdata, autocorr = true

Arguments

Inputs				
fitsfile	Name of input UV FITS file			
	allowed: string			
	Default:			
vis	Name of output visibility file (MS)			
	allowed: string			
	Default:			
antnamescheme	VLA/EVLA/CARMA only; 'new' or 'old'; 'VA04' or			
	'04' for VLA ant 4			
	allowed: string			
	Default: old			

Example

```
Convert a UVFITS file to a CASA visibility data set:

Keyword arguments:
fitsfile -- Name of input UV FITS file
default = none; example='3C273XC1.fits'
vis -- Name of output visibility file (MS)
default = none; example: vis='3C273XC1.ms'
antnamescheme -- Naming scheme for VLA/JVLA/CARMA antennas
```

default = old;

old: Antenna name is a number, '04'
This option exists for backwards compatibility
but can lead to ambiguous results when antenna
indices are used for data selection.

new: Antenna name is not a number, e.g., 'VA04' or 'EA04' With this scheme, data selection via antenna names and indices is non-ambiguous.

async -- Run asynchronously
 default = false; do not run asychronously

Note: Don't forget to flag autocorrections using taskname flagdata, autocorr = true

importvla-task.html

0.1.53 importvla

Requires:

Synopsis

Import VLA archive file(s) to a measurement set

Description

Imports an arbitrary number of VLA archive-format data sets into a casa measurement set. If more than one band is present, they will be put in the same measurement set but in a separate spectral window. The task will handle old style and new style VLA (after July 2007) archive data and apply the tsys to the data and to the weights.

Arguments

Inputs archivefiles Name of input VLA archive file(s) allowed: stringArray Default: Name of output visibility file vis allowed: string Default: bandname VLA frequency band name:"=>obtain all bands in the archive file allowed: string Default: frequencytol HzFrequency shift to define a unique spectra window (Hz) allowed: doubleHz Default: 150000.0 project Project name: " => all projects in files allowed: string Default: starttime start time to search for data allowed: string Default: end time to search for data stoptime string allowed: Default: applytsys apply nominal sensistivity scaling to data and weights bool allowed: Default: True import autocorrelations to ms, if set to True autocorr allowed: bool Default: False antnamescheme 'old' or 'new'; 'VA04' or '04' for VLA ant 4 allowed: string Default: new keepblanks Fill scans with blank (empty) source names (e.g. tipping scans) allowed: bool Default: False evlabands Use updated eVLA frequencies and bandwidths for bands and wavelengths allowed: bool

Example

False

Default:

Imports an arbitrary number of VLA archive-format data sets into a casa measurement set. If more than one band is present, they will be put in the same measurement set but in a separate spectral window. The task will handle old style and new style VLA (after July 2007) archive data and apply the tsys to the data and to the weights.

```
Keyword arguments:
archivefiles -- Name of input VLA archive file(s)
        default: none. Must be supplied
        example: archivefiles = 'AP314_A959519.xp1'
        example: archivefiles=['AP314_A950519.xp1','AP314_A950519.xp2']
vis -- Name of output visibility file
        default: none. Must be supplied.
        example: vis='NGC7538.ms'
        Will not over-write existing ms of same name.
        A backup flag-file version 'Original' will be made in
         vis.flagversions. See help flagmanager
bandname -- VLA Frequency band
       default: => '' = all bands
        example: bandname='K'
        Options: '4'=48-96 MHz, 'P'=298-345 MHz, 'L'=1.15-1.75 GHz,
        'C'=4.2-5.1 GHz,'X'=6.8-9.6 GHz,'U'=13.5-16.3 GHz,
        'K'=20.8-25.8 GHz,'Q'=38-51 GHz
frequencytol -- Tolerance in frequency shift in making spectral windows
        default: => 150000 (Hz). For Doppler shifted data, <10000 Hz may
        may produce too many unnecessary spectral windows.
        example: frequencytol = 1500000.0 (units = Hz)
project -- Project name to import from archive files:
        default: '' => all projects in file
        example: project='AL519'
        project = 'al519' or AL519 will work. Do not include
        leading zeros; project = 'ALO519' will not work.
starttime -- Time after which data will be considered for importing
        default: '' => all: Date must be included.
        syntax: starttime = '2003/1/31/05:05:23'
stoptime -- Time before which data will be considered for importing
        default: '' => all: Date must be included.
        syntax: stoptime = '2003/1/31/08:05:23'
applytsys -- Apply data scaling and weight scaling by nominal
        sensitivity (~Tsys)
        default: True. Strongly recommended
autocorr -- import autocorrelations to ms
        default: => False (no autocorrelations)
antnamescheme -- 'old' or 'new' antenna names.
```

default => 'new' gives antnenna names
 'VA04' or 'EA13 for VLA telescopse 04 and 13 (EVLA)
 'old' gives names '04' or '13'

keepblanks -- Should sources with blank names be filled into the data base
 default => false. Do not fill

These scans are tipping scans (as of June 1, 2009) and should not be filled in the visibility data set.

evlabands -- Use the EVLA's center frequency and bandwidths for frequencies specified via wavelength or band.

default => True.

async -- Run asynchronously

default = False; do not run asychronously

imrebin-task.html

0.1.54 imrebin

Requires:

Synopsis Rebin an image by the specified integer factors

Arguments

Inputs

imagename Name of the input image

allowed: string

Default:

outfile Output image name.

allowed: string

Default:

factor Binning factors for each axis. Use imhead or ia.summary

to determine axis ordering. allowed: intArray

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any Default: variant

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes. Stokes planes cannot

be rebinned.

allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: string

Default:

dropdeg Drop degenerate axes?

stretch

allowed: bool

Default: False

overwrite Overwrite the output if it exists? Default False

allowed: bool

Default: False

Stretch the mask if necessary and possible? See help

par.stretch

allowed: bool Default: False

crop Remove pixels from the end of an axis to be rebinned if

there are not enough to form an integral bin?

allowed: bool Default: True

266

Returns

bool

Example

PARAMETER SUMMARY

Name of the input (CASA, FITS, MIRIAD) image imagename outfile Name of output CASA image. Must be specified.

factor Array of binning factors for each axis, eg [2,3]. Use imhead or ia.summary

to determine order of axes in your image.

Region selection. See "help par.region" for details. Default is to use the region

Rectangular region to select in direction plane. See "help par.box" for box

details. Default is to use the entire direction plane.

chans Channels to use. See "help par.chans" for details. Default is to use all cl

Stokes planes to use. See "help par.stokes" for details. Default is to use stokes

Stokes planes. Stokes planes cannot be rebiined.

Mask to use. See help par.mask. Default is none. mask

dropdeg Drop degenerate axes?

If true, the file if it exists is automatically overwritten.

stretch Stretch the input mask if necessary and possible. See help par.mask.

Only considered if the length of the input axis is not an integral multiple crop

the associated binning factor. If True, pixels at the end of the axis that form a complete bin are not included in the binning. If False, the remaining

Should the image of the same name as specified in outfile be overwritten?

pixels are averaged to form the final bin along the axis.

DESCRIPTION

overwrite

This application rebins the specified image by the specified integer binning factors for each axis. It supports both float valued and complex valued images. The corresponding output pixel value is the average of the input pixel values. The output pixel will be masked False if there were no good input pixels. A polarization axis cannot be rebinned.

The binning factors array must contain at least one element and no more elements than the number of input image axes. If the number of elements specified is less than the number of image axes, then the remaining axes not specified are not rebinned. All specified values must be positive. A value of one indicates that no rebinning of the associated axis will occur. Should this array contain any float values, they will be rounded to the next lowest integer. Note that in many images with both frequency and polarization axes, the polarization axis preceeds the frequency axis. If you wish to rebin the frequency axis, it is recommended that you inspect your image with imhead or ia.summary() to determine the axis ordering.

Binning starts from the origin pixel of the bounding box of the selected region or the origin pixel of the input image if no region is specified. The value of crop is used to determine how to handle cases where there are pixels at the end of the axis that do not form a complete bin. If crop=True, extra pixels at the end of the axis are discarded. If crop=False, the remaining pixels are averaged into the final bin along that axis. Should the length of the axis to be rebinned be an integral multiple of the associated binning factor, the value of crop is irrelevant.

A value of dropdeg=True will result in the output image not containing axes that are degenerate in the specified region or in the input image if no region is specified. Note that, however, the binning factors array must still account for degenerate axes, and the binning factor associated with a degenerate axis must always be 1.

EXAMPLE

rebin the first two axes (normally the direction axes)
imrebin(imagename="my.im", outfile="rebinned.im", factor=[2,3])

rebin the frequency axis, which is the fourth axis in this image
imrebin(imagename="my2.im", outfile="rebinned2.im", factor=[1,1,1,4])

imreframe-task.html

0.1.55 imreframe

Requires:

Synopsis

Change the frame in which the image reports its spectral values

Arguments

age
alues
e.g
GHz"
7

Returns

void

Example

imagename $\operatorname{--}$ name of casa image file to process on

```
\mbox{--} name of output image \mbox{\ ''} means modify the input image itself
   output
                default: '';
                -- new spectral frame in which the frequency or
   outframe
                                  velocity will be reported for.
                Options: 'lsrk', 'lsrd', 'bary', 'geo', 'topo', 'galacto',
                          'lgroup','cmb'
default: 'lsrk'
           >>>
                          -- when outframe is 'topo' or 'geo' a time in UTC is needed
                                 to decide when to do the frequency conversion. '' is to use
                                 the epoch of the input image
                      default= ''
           restfreq -- Specify rest frequency to use for output image
              default=''; '' means use the restfrequency already in input image
              For example for
              NH_3 (1,1) put restfreq='23.694496GHz'
```

im regrid-task.html

0.1.56 imregrid

Requires:

Synopsis

regrid an image onto a template image

Description

Imregrid will regrid an input image onto a new coordinate system from a template image or to a new directional reference frame. If a template image is used, then the input and template images must have the same coordinate structure.

Arguments

Inputs imagename Name of the source image allowed: string Default: template A dictionary, refcode, or name of an image that provides the output shape and coordinate system allowed: any Default: variant get Name for the regridded image output allowed: string Default: asvelocity Regrid spectral axis in velocity space rather than frequency space? allowed: bool Default: True The pixel axes to regrid. -1 => all. axes allowed: intArray Default: shape Shape of the output image. Only used if template is an image. If not specified (-1), the output image shape will be the same as the template image shape along the axes that are regridded and the same as input image shape along the axes which are not regridded. allowed: intArray Default: interpolation The interpolation method. One of "nearest", "linear", "cubic". allowed: string Default: linear decimate Decimation factor for coordinate grid computation allowed: int Default: 10 Replicate image rather than regrid? replicate allowed: bool Default: False Overwrite (unprompted) pre-existing output file? overwrite allowed: bool Default: False

Example

The imregrid task currently finds the nearest input pixel center and interpolates to the outline No averaging is done in any direction!

Imregrid will regrid an input image onto a new coordinate system from a template image or to a new directional reference frame. If a template image is used, then the input and template images must have the same coordinate structure.

Keyword arguments:

imagename Name of the source image that needs to be regridded. Must be specified.

example: imagename='orion.image'

template Dictionary, directional reference code, or imagename defining the new

shape and coordinate system, or 'get' to return the template

dictionary for imagename. Recognized directional reference codes are:

'J2000', 'B1950', 'B1950_VLA', 'GALACTIC', 'HADEC', 'AZEL', 'AZELSW', 'AZELNE', 'ECLIPTIC', 'MECLIPTIC', 'TECLIPTIC',

and 'SUPERGAL'.

default: 'get'; example: template='orion_j2000.im' (for a template image),

 ${\tt template='J2000'} \ ({\tt to\ regrid\ the\ input\ image\ to\ J2000\ coordinates}).$

shape Shape of the output image. Only used if template is an image.

If not specified (-1), the output image will be the same as the template image shape along the axes which are regridded and the same as the input image shape along the axes which are not regridded. If specified and the axis ordering the input image and the template are not the same, the values in the array of the axis ordering of the input image; the output image will have the same

ordering as the input image. Ignored if template is set equal to a reference code. If template is a dictionary, the output shape is retrieved from the dictionary so the shape input parameter is ignored.

output Name for the regridded image. Must be specified.

example: imagename='orion_shifted.im'

asvelocity If True, regrid spectral axis with respect to velocity, not frequency. If Fa

regrid with respect to frequency. default: True

axes The pixel axes to regrid. Default value [-1] => all except Stokes. Ignored

if template is set equal to a reference code (in which case only the direct:

axes are regridded). If specified, this should

be provided as an array. example axes=[0,1] (only regrid the first two axes

are normally the directional axes).

interpolation The interpolation method. One of 'nearest', 'linear', 'cubic'.

decimate Decimation factor for coordinate grid computation

replicate Replicate image rather than regrid?

overwrite"> Overwrite (unprompted) pre-existing output file? async Run task in a separate process (return CASA prompt)

default: False; example: async=True

The new coordinate system is defined by the template parameter, which can be:

* a recognized directional reference frame string. This will rotate the image and the country the new reference frame's axes are aligned to the cardinal directions (left-right, up-

Rotation occurs about the center direction pixel. If this pixel is not the reference patemporary copy of the original image is created and the coordinate system is adjusted the center direction pixel is the reference pixel. The coordinate system of the input is not modified and the output image's reference direction pixel is the center pixel. Note that the conversion between one frame and another in general becomes less accurate as distance from the output image's reference pixel increases. Before the rotation occimage is padded with masked pixels to ensure that all good pixels are used in the rotationers of the image are not cropped after the rotation). After the image is rotated, remaining along the edges of the image in the directional coordinate are cropped, so no masked slices in the directional coordinate along the edges of the final image.

- * a {'csys': [valid coordinate system dictionary], 'shap': [int array describing the out This is normally obtained by first running regrid with template='get'. In this case in necessary dictionary.
- * 'get', which does not regrid but returns the template dictionary for imagename, suitable for modification and reuse (see the point immediately above), * the name of an image from which to get the coordinate system and shape.
- * the name of an image from which to get the coordinate system and shap.

 The input and template images must have the same coordinate structure.

Regridding of complex-valued images is supported. The real and imaginary parts are regridded independently and the resulting regridded pixel values are combined to form the regridded, complex-valued image.

The argument {\stfaf replicate} can be used to simply replicate pixels rather than regridding them. Normally ({\stfaf replicate=F}), for every output pixel, its world coordinate is computed and the corresponding input pixel found (then a little interpolation grid is generated). If you set {\stfaf replicate=T}, then what happens is that for every output axis, a vector of regularly sampled input pixels is generated (based on the ratio of the output and input axis shapes). So this just means the pixels get replicated (by whatever interpolation scheme you use) rather than regridded in world coordinate space. This process is much faster, but its not a true world coordinate based regrid.

As decribed above, when {\stfaf replicate} is False, a coordinate is computed for each output pixel; this is an expensive operation. The argument {\stfaf decimate} allows you to decimate the computation of that coordinate grid to a sparse grid, which is then filled in via fast interpolation. The default for {\stfaf decimate} is 10. The number of pixels per axis in the sparse grid is the number of output pixels for that axis divided by the decimation factor. A factor of 10 does pretty well. You may find that for very non-linear coordinate systems (e.g. very close to the pole) that you have to reduce the decimation factor. You may also have to reduce the decimation factor if the number of pixels in the output image along an axis to be regridded is less than about 50, or the output image may be completely masked.

If one of the axes to be regridded is a spectral axis and asvelocity=T, the axis will be regridded to match the velocity, not the frequency, coordinate of the template coordinate system. Thus the output pixel values will correspond only to the velocity, not the frequency, of the output axis.

A variety of interpolation schemes are provided (only the first three characters to be specified). The cubic interpolation is substantially slower than linear, and often the improvement is modest. By default linear interpolation is used.

If an image has per-plane beams and one attempts to regrid the spectral axis, an exception is thrown.

RULES USED FOR GENERATING OUTPUT IMAGES IN SPECIFIC CASES

There are numerous rules governing the shape and coordinate system of the output image depending on the input image, template image, and wheher default values of the axes and shape parameters are used. They are enumerated below.

NOTE: If you want to be certain of what type of output you will get, it is highly recommended you specify both axes and shape to avoid any ambiguity.

1. Rules governing Stokes axes

- 1.1. If the input image has no stokes axis, then the output image will have no stokes as
- 1.2. If the input image has a stokes axis, but the template image/coordinate system does and if the default value of the shape parameter is used or if shape is specified as specified value for the length stokes axis in equal to the length of the input image stokes axis, then all stokes in the input image will be present in the output image
- 1.3. If the input image has a stokes axis, but the template image/coordinate system does and if the value of the shape parameter is specified but the length of the resulting axis is not equal to the length of the input image's stokes axis, a failure will on
- 1.4. If the input image has a stokes axis, if the template parameter is an image name, a template image has a degenerate stokes axis, if the axes parameter is not specified but does not contain the input stokes axis number, and if the shape parameter is not all stokes planes in the input image will be present in the output image.
- 1.5. If the input image has a stokes axis, if the template parameter is an image name, a template image has a degenerate stokes axis, if the axes parameter is not specified but does not contain the input stokes axis number, if the shape parameter is specified length of the stokes axis is not equal to the length of the input stokes a failure will occur.
- 1.6. If the input image has a stokes axis, if the template parameter is an image name, template image has a degenerate stokes axis, if the axes parameter is specified con input stokes axis number, then use the applicable rule of rules 1.7. and 1.8. for

image having a nondegenerate stokes axis.

- 1.7. If the input image has a stokes axis, if the template parameter is an image name, template image has a nondegenerate stokes axis, and if axes is not specified or if the input stokes axis number, then only the stokes parameters common to both the inthe template image will be present in the output image. If the input image and the have no common stokes parameters, failure will occur. If shape is specified and the specified stokes axis is not equal to the number of common stokes parameters in the template image, then failure will result.
- 1.8. If the input image has a stokes axis, if the template parameter is an image name, template image has a nondegenerate stokes axis, and if axes is specified but does not image stokes axis number, then all stokes present in the input image will be present if shape is also specified but the length of the specified stokes axis does not equal the input stokes axis, then failure will result.

2. Rules governing spectral axes

In all cases, if the shape parameter is specified, the spectral axis length must be consone would normally expect in the special cases, or a failure will result.

- 2.1. If the input image does not have a spectral axis, then the output image will not have
- 2.2. If the input image has a degenerate spectral axis, if the template parameter is an template image has a spectral axis, if axes is not specified or if it is and does contain the input image spectral axis number, then the spectral coordinate of the to the output image and the output image will have a degenerate spectral axis.
- 2.3. If the input image has a degenerate spectral axis, if the template parameter is an template image has a spectral axis, if axes is specified and it contains the input image spectral axis number, then the spectral coordinate of the to the output image. If shape is not specified, the output image will have the same as the input image. If shape is specified, the output image will have the number of in shape for the spectral axis. In these cases, the pixel and mask values for all will be identical; the regridded single spectral plane is simply replicated n times number of channels in the output image.
- 2.4. If the input image has a spectral axis, if the template parameter is an image name template image does not have a spectral axis, if axes is not specified or if it is contain the input image spectral axis number, then the spectral coordinate of the to the output image and the output image will have the same number of channels as
- 2.5. If the input image has a spectral axis, if the template parameter is an image name template image does not have a spectral axis, if axes is specified it contains the input image spectral axis number, then failure will result.
- 2.6. If the input image has a spectral axis, if the template parameter is an image name template image has a degenerate spectral axis, and if axes is unspecified or if it contain the spectral axis number of the input image, the spectral coordinate of the copied to the output image and the output image will have the same number of channel image.
- 2.7. If the input image has a spectral axis, if the template parameter is an image name template image has a nondegenerate spectral axis, and if axes is unspecified or if contains the spectral axis number of the input image, regrid the spectral axis of match the spectral axis of the template.

IMPORTANT NOTE ABOUT FLUX CONSERVATION

in general regridding is inaccurate for images that the angular resolution is poorly sampled. A check is done for such cases and a warning message is emitted if a beam present. However, no such check is done if there is no beam present. To add a restoring beam to an image, use ia.setrestoringbeam().

Basic Examples

Regrid an image to the "B1950" or "GALACTIC" coordinate systems

```
imregrid(imagename="input.image", output="output.image", template="B1950")
imregrid(imagename="input.image", output="output.image", template="GALACTIC")
```

Note that when regridding to another coordinate system in the manner above, if the input image's direction coordinate is already in the frame specified by template, a straight copy of the image is made. No regridding is actually done.

Obtain a template dictionary from an image and then use it to regrid another image

```
temp_dict = imregrid(imagename="target.image", template="get")
imregrid(imagename="input.image", output="output.image", template=temp_dict)
```

In this example, the template="get" option is used in the first command in order to characterize the desired shape and coordinate system used, and a new dictionary, temp_dict, is generated accordingly. This is then used when performing the actual regridding of input.image in the second command.

More Advanced Examples

It is also possible to directly use a template image for regridding with imregrid. For this to work reliably and predictably, the dimensionality (i.e. which dimensions are present in an image) and the axis ordering of the input image must be the same. The type and ordering of the axes of both the input and template images can (and should) first be examined using the CASA imhead task. Any necessary reordering of axes can be performed using the CASA imtrans task.

Unless the user explicitly specifies which dimensions to regrid using the axes parameter (see the following example), imregrid will also attempt to regrid degenerate axes (i.e. image axes of length one pixel). Stokes axes are never regridded.

In the case where template is an image name and the default value of shape is specified, the output image's shape will be the same as the template image's shape along the axes which are regridded and the same as the input image's shape along the axes which are not regridded So for example, if the input image has a shape of [20, 30, 40] and the template image has a of [10, 40, 70] and only axes=[0, 1], the output image will have a shape of [10, 40, 40]. In the output image will have a shape of [20, 30, 70].

Regrid input.image by directly using target.image as a template

imregrid(imagename="input.image", output="output.image", template="target.image", shape=

In this example, it is assumed that the axis order of the input image is of the form (direction_x, direction_y, spectral, Stokes), where 'direction_x' and 'direction_y' are the directional coordinates on the sky (in some reference frame), 'spectral' is a velocity/frequency axis, and 'Stokes' contains polarization information. In this example, input.image might typically be a data cube of shape [100, 100, 40, 1]. Note that the default value of asvelocity (True) will be used so the spectral axis will be regridded to the same velocity system as that of the template image

Regrid only the first two axes of an image

Firstly, the user should inspect the type and ordering of the axes with imhead, and then correct with imtrans if necessary.

imregrid(imagename="input.image", output="output.image", template="target.image", axes=[0]

The above command will regrid only the first two axes (normally the directional axes) of in leave all other axes unchanged. The output image will have the shape of the template image axes [0, 1] and the shape of the input image along the other axes since the shape parameter explicitly specified.

Regrid the third axis, considering velocity rather than frequency units

imregrid(imagename="input.image", output="output.image", template="target.image", axes=[2

This example regrids the spectral axis (zero-based axis number 2) with respect to velocity has been set to True. This is useful when eg, regridding a cube containing one spectral line of another cube containing a different spectral line.

Regrid the third axis, considering velocity rather than frequency units but first set the

```
imhead("input.image", mode="put", hdkey="restfreq", hdvalue="110GHz")
imregrid(imagename="input.image", output="output.image", template="target.image", axes=[2]
```

The first command in this example uses the imhead task to set the value of the image rest frequency to a value of 110GHz in input.image. The following

imregrid command then performs a frequency units regridding only of the third axis listed (zero-based axis) (2), taking account of the input.image rest frequency in the

imsmo		

0.1.57 imsmooth

Requires:

Synopsis
Smooth an image or portion of an image

Description

Arguments

Inputs

imagename Name of the input image. Must be specified.

allowed: string

Default:

kernel Type of kernel to use. Acceptable values are "b", "box",

or "boxcar" for a boxcar kernel, "g", "gauss", or "gaussian" for a gaussian kernel, "c", "common", or "commonbeam" to use the common beam of an image with multiple beams as the gaussian to which to convolve all the planes, "i" or "image" to use an image as the kernel.

allowed: string Default: gauss

major Major axis for the kernels. Standard quantity represen-

tation. Must be specified for kernel="boxcar". Exam-

ple: "4arcsec".
allowed: any
Default: variant

minor Minor axis. Standard quantity representation. Must be

specified for kernel="boxcar". Example: "2arcsec".

allowed: any Default: variant

pa Position angle used only for gaussian kernel. Standard

quantity representation. Example: "40deg".

allowed: any Default: variant

targetres If gaussian kernel, specified parameters are to be reso-

lution of output image (True) or parameters of gaussian $\,$

to convolve with input image (False).

allowed: bool
Default: False

kimage Kernel image name. Only used if kernel="i" or "image".

allowed: string

Default:

scale Scale factor. -1.0 means auto-scale. Only used if ker-

nel="i" or "image". allowed: double Default: -1.0

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any Default: variant

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane. 281 allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

Returns

any

Example

minor

рa

beam

targetres

This task performs a Fourier-based convolution to 'smooth' the direction plane of an image. Smoothing is typically performed in order to reduce the noise an image.

Keyword arguments:

Input image name. Must be specified. imagename outfile Output smoothed image file name. Must be specified. kernel Type of kernel to use when smoothing ("g", "gauss", or "gaussian" for a gaussia kernel or "b", "box", or "boxcar" for a boxcar kernel), or if the image has multiple channels and kernel="commonbeam" (or "c", or "common"), com all channels to the smallest beam that encloses all beams in the input image, to use an image as the kernel. For boxcar smoothing, the major axis is parallel to the y-axis of the image and the minor axis is parallel to the x-axis. For a Gaussian, the orientation is specified by a position angle. A value of 0 degrees means the major axis is parallel to the y-axis and an increasing value of the position angle results in a counter-clockwise rotation of the ellipse. default: 'gauss' major Major axis of kernel which must be specified for boxcar smoothing. For

Major axis of kernel which must be specified for boxcar smoothing. For Gaussian smoothing, the kernel parameters can alternatively be specified in the beam parameter. Standard quantity representations are supported. Example "4arcsec".

Minor axis of kernel which must be specified for boxcar smoothing. For Gaussian smoothing, the kernel parameters can alternatively be specified in the beam parameter. Standard quantity representations are supported. Example "3arcsec".

Position angle to use for gaussian kernel, unused for boxcar. The Gaussian kernel parameters can alternatively be specified in the beam parameter. Standard quantity representations are supported. Example "40deg".

Record specifying Gaussian beam parameters. Do not specify any of major, minor, or pa if you choose to specify this parameter.

Example: {"major": "5arcsec", "minor": "2arcsec", "pa": "20deg"}

Boolean used only for kernel='gauss'. If True, kernel parameters (major/minor/] or beam) are the resolution of the output image. If false, a gaussian with these parameters is convolved with the input image to produce

282

the output image.

kimage The image to be used as the convolution kernel. Only used if kernel="image" or scale Scale factor to use if kernel="i" or "image". -1.0 means auto-scale, which is

mask Mask to use. See help par.mask. Default is none.

region Region selection. See "help par.region" for details. Default is to use the full box Rectangular region to select in direction plane. See "help par.box" for details

Default is to use the entire direction plane.

Example: "5, 10, 100, 200".

chans Channels to use. See "help par.chans" for details. Default is to use all channels stokes Stokes planes to use. See "help par.stokes" for details. Default is to use

all Stokes planes.

Example: 'I'

GAUSSIAN KERNEL

The direction pixels must be square. If they are not, use imregrid to regrid your image onto of square pixels.

Under the hood, ia.convolve2d() is called with scale=-1 (auto scaling). This means that, who has a restoring beam, pixel values in the output image are scaled in such a way as to conserve

Major and minor are the full width at half maximum (FWHM) of the Gaussian. pa is the position of the Gaussian. The beam parameter offers an alternate way of describing the convolving Gaussian. The beam parameter minor, nor pa can be specified. The beam parameter must have exactly fields: "major", "minor", and "pa" (or "positionangle"). This is the record format for the of ia.restoringbeam(). For example

beam = {"major": "5arcsec", "minor": "2arcsec", "pa": "20deg"}

If both beam and any of major, minor, and/or pa is specified for a Gaussian kernel, an exception will be thrown.

Alternatively, if the input image has multiple beams, setting kernel='commonbeam' will result smallest beam that encloses all beams in the image to be used as the target resolution to who convolve all planes.

In addition, the targetres parameter indicates if the specified Gaussian is to be the resolution of the final image (True) or if it is to be used to convolve the input image. If True, the input image must have a restoring beam. Use imhead() or ia.restoringbeam() to check for its existence. If the image has multiple beams and targetres=True, all planes in the image will be convolved so that the resulting resolution is that specified by the kernel parameters. If the image has multiple beams and targetres=False, each plane will be convolved with a Gaussian specified by beam (and hence, in general, the output image will also have multiple beams that vary with spectral channel and/or polarization).

If the units on the original image include Jy/beam, the units on the output image will be rescaled by the ratio of the input and output beams as well as rescaling by the area of convolution kernel.

If the units on the original image include K, then only the image convolution kernel rescaling is done.

BOXCAR KERNEL

major is length of the box along the y-axis and minor is length of the box along the x-axis pa is not used and beam should not be specified. The value of targetres is not used.

IN GENERAL

The major, minor, and pa parameters can be specified in one of three ways

Quantity -- for example major=qa.quantity(1, 'arcsec')

Note that you can use pixel units, such as

major=qa.quantity(1, 'pix')

String -- for example minor='1pix' or major='0.5arcsec'

(i.e. a string that the Quanta quantity function accepts).

Numeric -- for example major=10.

In this case, the units of major and minor are assumed to be in arcsec and units of pa are assumed to be degrees.

Note: Using pixel units allows you to convolve axes with different units.

IMAGE KERNEL

If kernel="i" or "image", the image specified by kimage is used to convolve the input image The coordinate system of the convolution image is ignored; only the pixel values are considerable.

Fourier-based convolution is performed.

The provided kernel can have fewer dimensions than the image being convolved. In this case, it will be padded with degenerate axes. An error will result if the kernel has more dimensions than the image.

The scaling of the output image is determined by the argument {\stfaf scale}. If this is left unset, then the kernel is normalized to unit sum. If {\stfaf scale} is not left unset, then the convolution kernel will be scaled (multiplied) by this value.

Masked pixels will be assigned the value 0.0 before convolution.

The output mask is the combination (logical OR) of the default input \pixelmask\ (if any) and the OTF mask. Any other input \pixelmasks\

will not be copied. The function maskhandler should be used if there is a need to copy other masks too.

EXAMPLES

- # smoothing with a gaussian kernel 20arseconds by 10 arseconds
 imsmooth(imagename='my.image', kernel='gauss', major='20arcsec', minor='10arcsec', pa="0deg
- # the same as before, just a different way of specifying the kernel parameters
 mybeam = {'major': '20arcsec', 'minor': '10arcsec', 'pa': '0deg'}
 imsmooth(imagename='my.image', kernel='gauss', beam=mybeam)
- # Smoothing using pixel coordinates and a boxcar kernel.
 imsmooth(imagename='new.image', major='20pix', minor='10pix', kernel='boxcar')

imstat-task.html

0.1.58 imstat

Requires:

 ${\bf Synopsis}$ Displays statistical information from an image or image region

Arguments

Inputs imagename Name of the input image allowed: string Default: List of axes to evaluate statistics over. Default is all axes axes. allowed: any Default: variant -1 Region selection. See "help par.region" for details. Deregion fault is to use the full image. allowed: string Default: box Rectangular region(s) to select in direction plane. See "help par.box" for details. Default is to use the entire direction plane. allowed: string Default: chans Channels to use. See "help par.chans" for details. Default is to use all channels. allowed: string Default: stokes Stokes planes to use. See "help par.stokes" for details. Default is to use all Stokes planes. allowed: string Default: listit Print stats and bounding box to logger? allowed: bool Default: True verbose Print additional messages to logger? allowed: bool Default: True Mask to use. See help par.mask. Default is none. maskallowed: string Default: stretch Stretch the mask if necessary and possible? See help par.stretch allowed: bool Default: False logfile Name of file to write fit results. allowed: string Default: append If logfile exists, append to it if True or overwrite it if False allowed: bool Default: True Algorithm to use. Supported values are "chauvenet", algorithm "classic", "fit-half", and "hinges-fences". Minimum

Default: -1 center Center to use for fit-half. Valid choices are "mean"

string

classic

double

Fence value for hinges-fences. A negative value means

use the entire data set (ie default to the "classic" algorithm). Ignored if algorithm is not "hinges-fences".

match is supported.

allowed:

Default:

allowed:

fence

Returns

void

Example

Many parameters are determined from the specified region of an image. For this version, the region can be specified by a set of rectangular pixel coordinates, the channel ranges and the Stokes.

For directed output, run as myoutput = imstat()

Keyword arguments:

chans

imagename Name of input image

Default: none; Example: imagename='ngc5921_task.im' axes to compute statistics over. -1 => all axes. axes

region Region selection. See "help par.region" for details. Default is

to use the full image.

box Rectangular region(s) to select in direction plane. See

"help par.box" for details. Default is to use the entire direction plane.

Channels to use. See "help par.chans" for details. Default is to use all channels

Example: box='10,10,50,50'

box = '10, 10, 30, 30, 35, 35, 50, 50' (two boxes)

Example: chans='3~20'

stokes Stokes planes to use. See "help par.stokes" for details. Default is to

> use all Stokes planes. Example:stokes='I,Q'

listit Print stats and bounding box to logger? Print additional messages to logger? verbose

Mask to use. See help par.mask. Default is none. mask

Stretch the mask if necessary and possible? See help par.stretch stretch

Name of file to write fit results. logfile

If logfile exists, append to it (True) or overwrite it (False). append

alogortihm Algorithm to use to compute statistics. Supported values are "classic"

and "hinges-fences" (minimum match supported.)

fence Fence factor when algorithm = "hinges-fences". Negative values are not

applicable and in these cases, the classic algorithm is used.

Center to use for "fit-half". Valid choices are "mean" (mean value of the center

> selected pixels), "median" (median value of the selected pixels), and "zero" (0.0 is used as the center value). Ignored if algorithm is not "fit-half".

lside For fit-half, use values <= center for the real data? If false, use values >= center as the real data. Ignored if algorithm is not "fit-half" zscore For chauvenet, this is the target maximum number of standard deviations data

may have to be included. If negative, use Chauvenet's criterion. Ignored if algorithm is not "chauvenet".

maxiter For chauvenet, this is the maximum number of iterations to attempt. Iterating will stop when either this limit is reached, or the zscore criterion is met. If negative, iterate until the zscore criterion is met. Ignored if algorithm is not "chauvenet".

clmethod Method to use for calculating classical statistics. Supported methods are "auto" "tiled", and "framework". Ignored if algorithm is not "classic".

General procedure:

- 1. Specify inputs, then
- 2. myoutput = imstat()
 or specify inputs directly in calling sequence to task
 myoutput = imstat(imagename='image.im', etc)
- myoutput['KEYS'] will contain the result associated with any of the keys given below

KEYS CURRENTLY AVAILABLE

blc - absolute PIXEL coordinate of the bottom left corner of the bounding box surrounding the selected region

blcf - Same as blc, but uses WORLD coordinates instead of pixels

trc - the absolute PIXEL coordinate of the top right corner

of the bounding box surrounding the selected region

 ${\sf trcf}$ - Same as ${\sf trc}$, but uses WORLD coordinates instead of pixels

flux - the flux or flux density. See below for details.

npts - the number of unmasked points used

max - the maximum pixel value

min - minimum pixel value

maxpos - absolute PIXEL coordinate of maximum pixel value

maxposf - Same as maxpos, but uses WORLD coordinates instead of pixels

minpos - absolute pixel coordinate of minimum pixel value

minposf - Same as minpos, but uses WORLD coordinates instead of pixels

sum - the sum of the pixel values: \$\sum I_i\$

sumsq - the sum of the squares of the pixel values: \$\sum I_i^2\$

mean - the mean of pixel values:

 $\alpha I_i = \sum_i / n$

sigma - the standard deviation about the mean:

 $\alpha^2 = (\sum_{i=1}^{n-1} - \sum_{i=1}^{n-1}$

289

ALGORITHMS

Several types of statistical algorithms are supported:

- * classic: This is the familiar algorithm, in which all unmasked pixels are used. One may clone of two methods, which vary only by performance, for computing classic statistics, via clmethod parameter. The "tiled" method is the old method and is fastest in cases where the a large number of individual sets of statistics to be computed and a small number of data per set. This can occur when one sets the axes parameter, which causes several individual statistics to be computed. The "framework" method uses the new statistics framework to constatistics. This method is fastest in the regime where one has a small number of individual of statistics to calculate, and each set has a large number of points. For example, this is fastest when computing statistics over an entire image in one go (no axes specified). A option, "auto", chooses which method to use by predicting which be faster based on the numpixels in the image and the choice of the axes parameter.
- * fit-half: This algorithm calculates statistics on a dataset created from real and virtual The real values are determined by the input parameters center and lside. The parameter center tells the algorithm where the center value of the combined real+virtual dataset should be are the mean or the median of the input image's pixel values, or at zero. The lside parameter algorithm on which side of this center the real pixel values are located. True indicates the real pixel values to be used are <= center. False indicates the real pixel values to are >= center. The virtual part of the dataset is then created by reflecting all the real through the center value, to create a perfectly symmetric dataset composed of a real and a component. Statistics are then calculated on this resultant dataset. These two parameters ignored if algorithm is not "fit-half". Because the maximum value is virtual if lside is minimum value is virtual if lside is False, the value of the maximum position (if lside=Talse) is not reported in the returned record.
- * hinges-fences: This algorithm calculates statistics by including data in a range between Q1 f*D and Q3 + f*D, inclusive, where Q1 is the first quartile of the distribute of unmasked data, subject to any specified pixel ranges, Q3 is the third quartile, D = Q3 (the inner quartile range), and f is the user-specified fence factor. Negative values of indicate that the full distribution is to be used (ie, the classic algorithm is used). Sur large values of f will also be equivalent to using the classic algorithm. For f = 0, only in the inner quartile range is used for computing statistics. The value of fence is silent

ignored if algorithm is not "hinges-fences".

* chauvenet: The idea behind this algorithm is to eliminate outliers based on a maximum z-se A z-score is the number of standard deviations a point is from the mean of a distribution method thus is meant to be used for (nearly) normal distributions. In general, this is an process, with successive iterations discarding additional outliers as the remaining points closer to forming a normal distribution. Iterating stops when no additional points lie be specified zscore value, or, if zscore is negative, when Chauvenet's criterion is met (see The parameter maxiter can be set to a non-negative value to prematurely abort this iteration process. When verbose=T, the "N iter" column in the table that is logged represents the notice of iterations that were executed.

Chauvenet's criterion allows the target z-score to decrease as the number of points in the distribution decreases on subsequent iterations. Essentially, the criterion is that the proof having one point in a normal distribution at a maximum z-score of z_max must be at least z_max is therefore a function of (only) the number of points in the distribution and is given

```
npts = 0.5/erfc(z_max/sqrt(2))
```

where erfc() is the complementary error function. As iterating proceeds, the number of repoints decreases as outliers are discarded, and so z_max likewise decreases. Convergence all remaining points fall within a z-score of z_max. Below is an illustrative table of z_rand their corresponding npts values. For example, it is likely that there will be a 5-sign bump" in a perfectly noisy image with one million independent elements.

z_max	npts
1.0	1
1.5	3
2.0	10
2.5	40
3.0	185
3.5	1,074
4.0	7,893
4.5	73,579
5.0	872,138
5.5	13,165,126
6.0	253,398,672
6.5	6,225,098,696
7.0	195,341,107,722

NOTES ON FLUX DENSITIES AND FLUXES

Fluxes and flux densities are not computed if any of the following conditions is met:

- 1. The image does not have a direction coordinate
- 2. The image does not have a intensity-like brightness unit. Examples of such units

are Jy/beam (in which case the image must also have a beam) and K.

- 3. There are no direction axes in the cursor axes that are used.
- 4. If the (specified region of the) image has a non-degenerate spectral axis, and the image has a tablular spectral axis (axis with varying increments)
- 5. Any axis that is not a direction nor a spectral axis that is included in the cursor axes is not degenerate within in specified region

Note that condition 4 may be removed in the future.

In cases where none of the above conditions is met, the flux density(ies) (intensities integrated over direction planes) will be computed if any of the following conditions are met:

- 1. The image has no spectral coordinate
- 2. The cursor axes do not include the spectral axis
- 3. The spectral axis in the chosen region is degenerate

In the case where there is a nondegenerate spectral axis that is included in the cursor axes, the flux (flux density integrated over spectral planes) will be computed. In this case, the spectral portion of the flux unit will be the velocity unit of the spectral coordinate if it has one (eg, if the brightness unit is Jy/beam and the velocity unit is Jy/beam and the velocity unit is Jy/beam and the velocity unit is Jy/beam and the frequency unit of the spectral axis (eg, if the brightness unit is Jy/beam and the frequency unit is Jy/beam and Jy/beam and the frequency unit is Jy/beam and Jy/beam a

In both cases of flux density or flux being computed, the resulting numerical value is assigned to the "flux" key in the output dictionary.

ADDITIONAL EXAMPLES

```
s1 = imstat( 'myimage', stokes='Q' )
s2 = imstat( 'myimage', stokes='I')
       print "
               | MIN | MAX | MEAN"
       print " Q
                 | ",s1['min'][0]," | ",s1['max'][0]," | ",," | ",s1['mean'][0]
       # evaluate statistics for each spectral plane in an ra x dec x frequency image
myim = "noisy.im"
ia.fromshape(myim, [20,30,40])
# give pixels non-zero values
ia.addnoise()
ia.done()
# These are the display axes, the calculation of statistics occurs
# for each (hyper)plane along axes not listed in the axes parameter,
# in this case axis 2 (the frequency axis)
# display the rms for each frequency plane (your mileage will vary with
# the values).
stats = imstat(imagename=myim, axes=[0,1])
stats["rms"]
 Out[10]:
array([ 0.99576014, 1.03813124, 0.97749186, 0.97587883, 1.04189885,
       1.03784776, 1.03371549, 1.03153074, 1.00841606, 0.947155 ,
       0.97335404, 0.94389403, 1.0010221, 0.97151822, 1.03942156,
       1.01158476, 0.96957082, 1.04212773, 1.00589049, 0.98696715,
       1.00451481, 1.02307892, 1.03102005, 0.97334671, 0.95209879,
       1.02088714, 0.96999902, 0.98661619, 1.01039267, 0.96842754,
       0.99464947, 1.01536798, 1.02466023, 0.96956468, 0.98090756,
       0.9835844 , 0.95698935, 1.05487967, 0.99846411, 0.99634868])
```

im sub im age-task.html

0.1.59imsubimage

Requires:

 $\begin{array}{c} \textbf{Synopsis} \\ \textbf{Create a (sub)image from a region of the image} \end{array}$

Arguments

Inputs image name. Default is unset.

allowed: string

Default:

outfile Output image name. Default is unset.

allowed: string

Default:

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane.

allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

mask Mask to use. See help par.mask. Default is none.

allowed: any Default: variant

dropdeg Drop degenerate axes

allowed: bool
Default: False

overwrite Overwrite (unprompted) pre-existing output file?

allowed: bool

Default: False

verbose Post additional informative messages to the logger

allowed: bool Default: True

stretch Stretch the mask if necessary and possible?

allowed: bool Default: False

Returns

image

Example

PARAMETER SUMMARY

imagename Name of the input image

outfile Name of output file. Must be specified.

box Rectangular region to select in direction plane. See "help par.box"

for details. Default is to use the entire direction plane.

region Region selection. See "help par.region" for details. Default is to use

the full image.

chans Channels to use. See "help par.chans" for details. Default is to use

all channels.

stokes Stokes planes to use. See "help par.stokes" for details. Default is to

use all Stokes planes.

mask Mask to use. See help par.mask. Default ("") is none.

dropdeg If True, all degenerate axes in the input image will be excluded in the our overwrite If True, a pre-existing file of the same name as outfile will be overwritten.

verbose Post additional informative messages to the logger.

stretch Stretch the input mask if necessary and possible. Only used if a mask is s

See help par.stretch.

OVERVIEW

This task copies all or part of the image to a new image specified by outfile. Both float and complex valued images are supported.

Sometimes it is useful to drop axes of length one (degenerate axes). Set {\stfaf dropdeg} equal to True if you want to do this.

The output mask is the combination (logical OR) of the default input \pixelmask\ (if any) and the OTF mask. Any other input \pixelmasks\ will not be copied. Use function maskhandler if you need to copy other masks too.

If the mask has fewer dimensions than the image and if the shape of the dimensions the mask and image have in common are the same, the mask will automatically have the missing dimensions added so it conforms to the image.

If stretch is true and if the number of mask dimensions is less than or equal to the number of image dimensions and some axes in the mask are degenerate while the corresponding axes in the image are not, the mask will be stetched in the degenerate dimensions. For example, if the input image has shape [100, 200, 10] and the input mask has shape [100, 200, 1] and stretch is true, the mask will be

stretched along the third dimension to shape [100, 200, 10]. However if the mask is shape [100, 200, 2], stretching is not possible and an error will result.

EXAMPLES

```
# make a subimage containing only channels 4 to 6 of the original image,
imsubimage(imagename="my.im", outfile="first.im", chans="4~6")

# Same as above command, just specifying chans in an alternate, more verbose
# way
imsubimage(imagename="my.im", outfile="second.im", chans="range=[4pix,6pix]")

# Same as the above command, but even more verbose way of specifying the spectral
# selection. Assumes the direction axes are axes numbers 0 and 1.
ia.open("my.im")
shape = ia.shape()
axes = ia.coordsys().names()
ia.done()
xmax = shape[axes.index("Right Ascension")] - 1
ymax = shape[axes.index("Declination")] - 1
reg = "box[[Opix,Opix],[" + str(xmax) + "pix, " + str(ymax) + "pix]] range=[4pix,6pix]"
imsubimage(imagename="my.im", outfile="third.im", region=reg)
```

imtrans-task.html

0.1.60 imtrans

Requires:

Synopsis

Reorder image axes

Arguments

Inputs imagename Name of the input image which must be specified.

allowed: string

Default:

outfile Name of output CASA image.

allowed: string

Default:

order New zero-based axes order.

allowed: any Default: variant

Returns

bool

Example

PARAMETER SUMMARY

imagename Name of the input image

outfile Name of output CASA image. Must be specified.

order Output axes mapping

This task reorders (transposes) the axes in the input image to the specified order. The associated pixel values and coordinate system are transposed.

The order parameter describes the mapping of the input axes to the output axes. It can be one of three types: a non-negative integer, a string, or a list of

strings. If a string or non-negative integer, it should contain zero-based digits describing the new order of the input axes. It must contain the same number of (unique) digits as the number of input axes. For example, specifying order="1032" or order=1032 for a four axes image maps input axes 1, 0, 3, 2 to output axes 0, 1, 2, 3. In the case of order being a nonnegative integer and the zeroth axis in the input being mapped to zeroth axis in the output, the zeroth digit is implicitly understood to be 0 so that to transpose an image where one would use a string order="0321", one could equivalently specify an int order=321. IMPORTANT: When specifying a non-negative integer and mapping the zeroth axis of the input to the zeroth axis of the output, do *not* explicitly specify the leading 0; eg, specify order=321 rather than order=0321. Python interprets an integer with a leading 0 as an octal number.

Because of ambiguity for axes numbers greater than nine, using string or integer order specifications cannot handle images containing more than 10 axes.

The order parameter can also be specified as a list of strings which uniquely match, ignoring case, the first characters of the image axis names (ia.coordsys().names()). So to reorder an image with right ascension, declination, and frequency axes, one could specify order=["d", "f", "r"] or equivalently ["decl", "frequ", "right a"]. Note that specifying "ra" for the right ascension axis will result in an error because "ra" does not match the first two characters of "right ascension".

Axes can be simultaneously inverted in cases where order is a string or an array of strings by specifying negative signs in front of the axis/axes to be inverted. So, in a 4-D image, order="-10-3-2" maps input axes 1, 0, 3, 2 to output axes 0, 1, 2, 3 and reverses the direction and values of input axes 1, 3, and 2. EXAMPLE:

```
# Swap the stokes and spectral axes in an RA-Dec-Stokes-Frequency image
imagename = "myim.im"
outfile = "outim.im"
order = "0132"
imtrans()

# or

outfile = "myim_2.im"
order = 132
imtrans()

# or

outfile = "myim_3.im"
order = ["r", "d", "f", "s"]
imtrans()
```

or

```
utfile = "myim_4.im"
order = ["rig", "declin", "frequ", "stok"]
imtrans()
```

imval-task.html

0.1.61 imval

Requires:

 $\label{eq:synopsis} \textbf{Synopsis}$ Get the data value(s) and/or mask value in an image.

Arguments

Outputs

blc Bottom-left corner of the bounding box that encloses the

region being examined..

allowed: any

Default: variant

trc top-right corner of the bounding box that encloses the

region being examined. allowed: any

Default: variant

axes A listing of the axis index numbers and the data stored

along that axis. allowed: any

Default: variant

unit The units the data values are stored and displayed in.

allowed: any Default: variant

data The mask values found at the give point(s).

allowed: any
Default: variant

mask The mask values found at the give point(s).

allowed: any Default: variant

Inputs

imagename Name of the input image

allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any Default: variant

box Rectangular region(s) to select in direction plane. See

"help par.box" for details. Default is to use the entire

direction plane. allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Planes specified must be contiguous. Default is to use

all Stokes planes. allowed: string

Default:

Returns

void

Example

The data point(s) to be retrieved are those found in the specified region, which may be:

- 1. A region file or text string (see help par.region), with the following caveat:
 - * If the specified region is complex (eg, a union or intersection of multiple region in this set is used.
 - * If the region is not rectangular, then the rectangular region that circumscribe specified region (ie the bounding box) is used to retrieve values, since the rearrays must be rectangular. The resulting mask values in this case are the resulting the image mask values with the specified region mask values, eg if a pixel falls outside the specified region but within the bounding box, its mask value will be false even if its image mask value is true.
- 2. A region specified by a set of rectangular pixel coordinates, the channel ranges and/or the Stokes.

```
For directed output, run as myoutput = imval()
```

```
Example: box='10,10,50,50'

box = '10,10,30,30,35,35,50,50' (two boxes)
```

stokes='I,Q'

General procedure:

1. Specify inputs, then

- 2. myoutput = imval()
 or specify inputs directly in calling sequence to task
 myoutput = imsval(imagename='image.im', etc)
- 3. myoutput['KEYS'] will contain the result associated with any of the keys given below

KEYS CURRENTLY AVAILABLE

blc - absolute PIXEL coordinate of the bottom left corner of the bounding box surrounding the selected region

trc - the absolute PIXEL coordinate of the top right corner of the bounding box surrOunding the selected region

axes - List the data stored in each axis of the data block.

unit - unit of the returned data values.

data - data value(s) found in the given region

mask - mask value(s) found in the given region. See important note above regarding returned mask values for non-rectangular regions.

NOTE: The data returned is in the same order as it is internally stored, typically RA, DEC, spectral, stokes. Also both the data and mask values are returned as Python Numpy arrays, for more information on how to manipulate them see

http://numpy.scipy.org/#array_interface

```
Additional Examples
```

- # Select and report on two box regions
- # box 1, bottom-left coord is 2,3 and top-right coord is 14,15
- # Select the same two box regions but only channels 4 and 5
 imval('myImage', box='2,3,14,15;30,31,42,43', chan='4~5')
- # Select all channels greater the 20 as well as channel 0.
 - # Then the mean and standard deviation are printed
 - # Note that the data returned is a Python numpy array which
 - # has built in operations such as min, max, and means as
 - # demonstrated here.

results = imval('myImage', chans='>20;0')
 inval_data=results['data']

```
mask=results['mask']
# holds the absolute coordinates of the associated pixels in imval_data
coords = results['coords']
print "Data max: ", imval_data.max(), " mean is ", imval_data.mean()
swapped_data=imval_data.swapaxes(0,2)
swapped_mask=mask.swapaxes(0,2)
print "Data values for 21st channel: \n", swapped_data[0]
print "Mask values for 21st channel: \n", swapped_mask[0]
```

imview-task.html

0.1.62 imview

Requires:

Synopsis

View an image

Description

The imview task will display images in raster, contour, vector or marker form. Images can be blinked, and movies are available for spectral-line image cubes. Executing the imview task will bring up a display panel window, which can be resized. If no data file was specified, a Load Data window will also appear. Click on the desired data file and choose the display type; the rendered data should appear on the display panel.

A Data Display Options window will also appear. It has drop-down subsections for related options, most of which are self-explanatory. The state of the imview task – loaded data and related display options – can be saved in a 'restore' file for later use. You can provide the restore filename on the command line or select it from the Load Data window.

Arguments

Inputs

raster

(Optional) Raster filename (string) or complete raster config dictionary. The allowed dictionary keys are file (string), scaling (numeric), range (2 element numeric vector), colormap (string), and colorwedge (bool).

allowed: any Default: variant

contour

(Optional) Contour filename (string) or complete contour config dictionary. The allowed dictionary keys are file (string), levels (numeric vector), unit (float), and base (float).

allowed: any Default: variant

zoom

(Optional) zoom can specify intermental zoom (integer), zoom region read from a file (string) or dictionary specifying the zoom region. The dictionary can have two forms. It can be either a simple region specified with blc (2 element vector) and trc (2 element vector) [along with an optional coord key ("pixel" or "world"; pixel is the default) or a complete region rectangle e.g. loaded with "rg.fromfiletorecord()". The dictionary can also contain a channel (integer) field which indicates which channel should be displayed.

allowed: any Default: variant 1

(Optional) this can either be a three element vector (string) where each element describes what should be found on each of the x, y, and z axes or a dictionary containing fields "x", "y" and "z" (string).

allowed: any Default: variant

out

axes

(Optional) Output filename or complete output config dictionary. If a string is passed, the file extension is used to determine the output type (jpg, pdf, eps, ps, png, xbm, xpm, or ppm). If a dictionary is passed, it can contain the fields, file (string), scale (float), dpi (int), or orient (landscape or portrait). The scale field is used for the bitmap formats (i.e. not ps or pdf) and the dpi parameter is used for scalable formats (pdf or ps).

allowed: any Default: variant

Returns

void

Example

The imview task provides access to a subset of all of the configuration options for loading and configuring the display of images in the casaviewer. This interface will evolve and eventually provide access to nearly all of the image options available in the casaviewer.

To simply create a casaviewer to set up interactively, you can use:

```
imview
```

To open a particular image:

```
imview "ngc5921.clean.image"
```

to open an image and overlay a contour:

imview "ngc5921.clean.image", "ngc5921.clean.image"

or equivalently:

```
imview( raster="ngc5921.clean.image", contour="ngc5921.clean.image" )
```

to output an image:

```
imview( raster="ngc5921.clean.image", out="ngc5921-01.png" )
```

There are five optional parameters for imview -- raster, contour, zoom, axes, and out. Each of these parameters can take a few different forms and are treated as python dictionaries:

```
(dict)
                   file (string)
                                      => file to load
                    levels (float*N)
                                     => relative levels
                    base (numeric)
                                      => zero in relative levels
                                      => one in the relative levels
                    unit (numeric)
        -- (int)
                    integral zoom level
zoom
           (string) region file to load as the zoom region
           (dict)
                   blc (numeric*2)
                                     => bottom left corner
                    trc (numeric*2) => top right corner
                    coord (string)
                                     => pixel or world
                    channel (int)
                                     => chanel to display
           (dict)
                    <region record> => record loaded
                                         e.g. rg.fromfiletorecord()
        -- (string*3) demension to display on the x, y, and z axes
axes
           (dict)
                                      => dimension for x-axes
                      Х
                                      => dimension for y-axes
                      У
                                      => dimension for z-axes
                      z
        -- (string) file with a supported extension
out
                    [jpg, pdf, eps, ps, png, xbm, xpm, ppm]
            (dict)
                      file (string) => filename
                      format (string) => valid ext (filename ext overrides)
                      scale (numeric) => scale for non-eps, non-ps output
                      dpi (numeric) => dpi for eps or ps output
                      orient (string) => portrait or landscape
        Examples:
1) A subset (zoom) of a raster image. Note the notation of curly brackets:
    imview(raster="ngc5921.clean.image", out="ngc5921-02.png",
           zoom={'channel': 10, 'blc': [113,109], 'trc': [141,136]} )
2) An overlay of a raster image, ngc5921.clean.image, with a
contour map of the same image ngc5921.clean.image. Data ranges
are selected, as well as the colormap and the scaling cycles
of the raster image. Contours are autogenerated and The x-axis
will be Declination. The image is written out to a file named
        myout.png in the png format.
imview(raster={'file': 'ngc5921.clean.image',
               'range': [-0.01,0.03],
               'colormap': 'Hot Metal 2',
               'scaling': -1},
       contour={'file': 'ngc5921.clean.image'},
       axes={'x':'Declination'} ,
       zoom={'channel': 7, 'blc': [75,75], 'trc': [175,175],
```

```
'coord': 'pixel'},
       out='myout.png')
3) As example (2) but with an integral zoom level and no output to a file
imview(raster={'file': 'ngc5921.clean.image',
               'range': [-0.01,0.03],
               'colormap': 'Hot Metal 2'},
       contour={'file': 'ngc5921.clean.image'},
       axes={'x':'Declination'} ,
       zoom=2)
4) Now, the contour levels are explicitely given, a region file is used
to define the zoom area
imview(raster={'file': 'ngc5921.clean.image',
               'range': [-0.01,0.03],
               'colormap': 'Hot Metal 2'},
       contour={'file': 'ngc5921.clean.image',
                'levels': [-0.2, 0.2, 0.25, 0.3, 0.35, 0.4, 0.6, 0.8] },
       zoom='myregion.rgn')
specifying "zoom={'file': 'myregion.rgn', 'channel': 10}" would result
in the same level of zoom and would display channel number 10 from
the cube.
```

in it weights-task. html

0.1.63initweights

Requires:

 ${\bf Synopsis}\\ {\bf Initializes \ weight \ information \ in \ the \ MS}$

Arguments

Inputs			
vis	Name of input visibility file (MS)		
	allowed: string		
	Default:		
wtmode	Initialization mode		
	allowed: string		
	Default: nyq		
tsystable	Tsys calibration table to apply on the fly		
	allowed: string		
	Default:		
gainfield	Select a subset of calibrators from Tsys table		
	allowed: string		
	Default:		
interp	Interpolation type in time[,freq]. default==linear,linear		
	allowed: string		
	Default:		
spwmap	Spectral windows combinations to form for gaintables(s)		
	allowed: intArray		
	Default:		
dowtsp	Initialize the WEIGHT_SPECTRUM column.		
	allowed: bool		
	Default: False		

Returns

void

Example

This task provides for initialization of the weight information in the MS. For ALMA interferometry and EVLA data, it should not generally be necessary to use this task, as the weight information should have been initialized properly at fill time (v4.2.2 and later).

Several initialization modes are supported via the wtmode parameter.

If wtmode='nyq' (the default), SIGMA and WEIGHT will be initialized according to bandwidth and integration time. This is the theoretically correct mode for raw normalized visibilities. (e.g., ALMA). For the EVLA, this is correct if switched-power and bandpass calibration will later be applied.

If wtmode='sigma', WEIGHT will be initialized according to the existing SIGMA column.

If mode='weight', WEIGHT_SPECTRUM will be initialized according to the existing WEIGHT column; dowtspec=T must be specified in this case.

If wtmode='ones', SIGMA and WEIGHT will be initialized with 1.0, globally. This is a traditional means of initializing weight information, and is adequate when the integration time and bandwidth are uniform. It is not recommended for modern instruments (ALMA, EVLA), where variety in observational setups is common, and properly initialized and calibrated weights will be used for imaging sensitivity estimates.

There are two EXPERIMENTAL modes, wtmode='tsys' and 'tinttsys'. In the modes, SIGMA and WEIGHT will be initialized according to Tsys, bandwidth, and integration time (used only in 'tinttsys'), i.e.,

tsys : weight=bw/Tsys^2
tinttsys: weight=bw*t_int/Tsys^2

These modes use Tsys values to calculate weight as is done in Tsys calibration. Tsys values are taken from a tsys calibration table given as tsystable. Selection of gain field (gainfield), interpolation method (interp), and spectral window mapping (spwmap) are supported, too.

Available types of interpolation are,

Time: 'nearest', 'linear', the variation of those with 'perobs',
 e.g., 'linearperobs' (enforce obsId boundaries in interpolation)
Freq: 'nearest', 'linear', 'cubic', 'spline', and the variation
 of those with 'flag', e.g., 'linearflag' (with

channelized flag).

See the help of applycal for details of interpolations. Note if the weight in an MS is initialized with these modes and Tsys calibration table is applied with calwt=True after that, the weight would be contaminated by being devided by square of Tsys twice.

!!! USERS ARE ADVICED TO USE THESE EXPERIMENTAL MODES WITH CARE !!!

For the above wtmodes, if dowtsp=T (or if the WEIGHT_SPECTRUM column already exists), the WEIGHT_SPECTRUM column will be initialized (uniformly in channel in wtmode='nyq', 'sigma', 'weight', and 'ones'), in a manner consistent with the disposition of the WEIGHT column. If the WEIGHT_SPECTRUM column does not exist, dowtsp=T will force its creation. Use of the WEIGHT_SPECTRUM column is only meaningful for ALMA data which will be calibrated with channelized Tsys information, or if the weights will become channelized after calibration, e.g., via averaging over time- and channel-dependent flagging. (A task for channel-dependent weight estimation from the data itself is also currently under development).

In non-channelized modes (wtmode='nyq', 'sigma', 'weight', and 'ones') or when dowtsp=F, SIGMA_SPECTRUM column will be removed from MS. On the other hand, SIGMA_SPECTRUM column is added and initialized in channelized modes (wtmode='tsys' and 'tinttsys') if dowtsp=T or WEIGHT_SPECTRUM already column exists.

Two additional modes are available for managing the spectral weight info columns; these should be used with extreme care: If wtmode='delwtsp', the WEIGHT_SPECTRUM column will be deleted (if it exists). If wtmode='delsigsp', the SIGMA_SPECTRUM column will be deleted (if it exists). Note that creation of SIGMA_SPECTRUM is not supported via this method.

Note that this task does not support any prior selection. Intialization of the weight information must currently be done globally or not at all. This is to maintain consistency.

listcal-task.html

0.1.64 listcal

Requires:

Synopsis

List antenna gain solutions

Description

This task lists antenna gain solutions in tabular form. The table is organized as follows. Solutions are output by 1) Spectral window, 2) Antenna, 3) Time, 4) Channel, 5) and Polarization; where the inner-most loop is over polarization.

The listcal output table contains two table headers. The top-level header is printed each time the spectral window changes. This header lists the spectral window ID (SpwID), the date of observation (Date), the calibration table name (CalTable), and the measurement set name (MS name).

A lower-level header is printed when the top-level header is printed, when the antenna names change, and every 'pagerows' of output. The lower-level header columns are described here:

Column Name Description — — — — Ant Antenna name (contains sub-columns: Amp, Phs, F) Time Visibility timestamp corresponding to gain solution Field Field name Chn Channel number Amp Complex solution amplitude Phs Complex solution phase F Flag

Elements of the "F" column contain an 'F' when the datum is flagged, and ' ' (whitespace) when the datum is not flagged.

Presently, the polarization mode names (for example: R, L) are not given, but the ordering of the polarization modes (left-to-right) is equivalent to the order output by task listobs (see "Feeds" in listobs output).

Input Parameters:

vis Name of input visibility file default: none; example: vis='ngc5921.ms' caltable Name of input calibration table default: none; example: caltable='ngc5921.gcal'

field Select data based on field ID(s) or name(s) default: "== ξ all; example: field='1' field='0~2' field ids inclusive from 0 to 2 field='3C*' all field names starting with 3C

antenna Select calibration data based on antenna default: "-iall; example: antenna='5' antenna='5,6' antenna index 5 and 6 solutions antenna='VA05','VA06' VLA antenna 5 and 6

spw Select spectral window, channel to list default: " -; All spws and channels; spw='2:34' spectral window 2, channel 34 will only list one spw, one channel at a time

listfile write output to disk; will not overwrite default: " $-\xi$ write to screen pagerows rows per page of listing default: 50; 0 $-\xi$ do not paginate

Arguments

Inputs			
vis	Name of input visibility file		
	allowed: string		
	Default:		
caltable	Input calibration table to list		
	allowed: string		
	Default:		
field	Field name or index; "==>all		
	allowed: string		
	Default:		
antenna	Antenna name or index; "==>all; antenna='3'		
	allowed: string		
	Default:		
spw	Spectral window and channel: "==>all; spw='5:0~10'		
	allowed: string		
	Default:		
listfile	Disk file to write output: "==>to terminal		
	allowed: string		
	Default:		
pagerows	Rows per page		
	allowed: int		
	Default: 50		

Returns

void

Example

This task lists antenna gain solutions in tabular form. The table

is organized as follows. Solutions are output by

- 1) Spectral window,
- 2) Antenna,
- 3) Time,
- 4) Channel,
- 5) and Polarization;

where the inner-most loop is over polarization.

The listcal output table contains two table headers. The top-level header is printed each time the spectral window changes. This header lists the spectral window ID (SpwID), the date of observation (Date), the calibration table name (CalTable), and the measurement set name (MS name).

A lower-level header is printed when the top-level header is printed, when the antenna names change, and every 'pagerows' of output.

The lower-level header columns are described here:

Column Name	Description
Ant	Antenna name (contains sub-columns: Amp, Phs, F)
Time	Visibility timestamp corresponding to gain solution
Field	Field name
Chn	Channel number
Amp	Complex solution amplitude
Phs	Complex solution phase
F	Flag

Elements of the ''F'' column contain an 'F' when the datum is flagged, and ' ' (whitespace) when the datum is not flagged.

Presently, the polarization mode names (for example: R, L) are not given, but the ordering of the polrization modes (left-to-right) is equivalent to the order output by task listobs (see ''Feeds'' in listobs output).

Input Parameters:

```
vis Name of input visibility file
    default: none; example: vis='ngc5921.ms'

caltable Name of input calibration table
    default: none; example: caltable='ngc5921.gcal'

field Select data based on field ID(s) or name(s)
    default: ''==>all; example: field='1'
    field='0~2' field ids inclusive from 0 to 2
```

```
antenna='5,6' antenna index 5 and 6 solutions
           antenna='VA05','VA06' VLA antenna 5 and 6
           Select spectral window(s), channel(s) to list
spw
           default: '' --> All spws and channels;
           spw='2:34' spectral window 2, channel 34;
           spw='1:5,3~5:7~9' spectral window 1, channel
           5 and spectral windows 3 thru 5, channels
           7 thru 9.
listfile
           write output to disk; will not overwrite
           default: '' --> write to screen
pagerows
           rows per page of listing
           default: 50; 0 --> do not paginate
Example:
# Get path to CASA home dir
pathname=os.environ.get('CASAPATH').split()[0]
# Select uv-data (FITS) file
fitsdata=pathname+'/data/demo/NGC5921.fits'
# MS name; write to current directory
msdata='NGC5921.ms'
# import FITS data to MS
importuvfits(fitsfile=fitsdata, vis=msdata)
# Create model data for flux calibrator
setjy(vis=msdata)
# Calibration table name
caldata=msdata+'.bcal'
# Bandpass calibration
bandpass(vis=msdata, caltable=caldata)
# List a subset of calibration factors
listcal(vis=msdata, caltable=caldata, field='N5921_2, 0, 1',
       antenna='1,2,5;10~14', spw='0:1,0:22~25', pagerows=0)
Example Output:
SpwID = 0, Date = 1995/04/13, CalTable = NGC5921.ms.bcal (B Jones), MS name = /users/jcross
------
                           \mid Ant = 1
                                                      | Ant = 2
                        Chn | Amp Phs F Amp Phs F Amp
                                                                              Phs F|
Time
        Field
```

field='3C*' all field names starting with 3C

Select calibration data based on antenna name

default: ''-->all; example: antenna='5';

antenna

```
7.9 0.117
09:21:46.0 1331+30500002_0
                       1|0.165
                                            21.3 0.168
                                                       98.8 0.161 -116.8
10:05:27.9 1445+09900002_0
                                            20.0
                                                 0.266 102.3
                                                              0.250 -116.1
                       1|0.260
                               10.3
                                     0.185
10:09:05.3
               N5921_2 1|0.047
                               54.2
                                     0.030
                                            50.7 0.057 -64.6
                                                              0.041
                                                                    36.5
                       \mid Ant = 11
                                                 | Ant = 12
Time
       Field
                    Chn | Amp Phs F Amp Phs F Amp
                                                                   Phs Fl
09:21:46.0 1331+30500002_0 1|0.156 -112.6
                                     0.128
                                           -5.5 0.156 -178.4 0.169 -146.2
10:05:27.9 1445+09900002_0
                       1|0.243 -110.6
                                     0.199
                                           -5.7
                                                 0.251 - 175.4
                                                              0.272 -146.9
10:09:05.3 N5921_2 1|0.054 47.1
                                     0.056 105.5
                                                 0.042 -84.9
                                                              0.043 -18.9
SpwID = 0, Date = 1995/04/13, CalTable = NGC5921.ms.bcal (B Jones), MS name = /users/jcross
                        | Ant = 1
                                                 | Ant = 2
                                Phs F
                                            Phs F| Amp
                                                         Phs F
Time
        Field
                      Chn | Amp
                                                                     Phs F
                                       Amp
                                                               Amp
-----|----|----|---|---|
                                                  -----|
09:21:46.0 1331+30500002_0 22|0.319
                                4.6 0.323
                                            -6.8
                                                 0.311 109.6 0.315 -109.0
09:21:46.0 1331+30500002_0
                                     0.323
                                           -6.8
                                                 0.309
                                                       109.7
                                                              0.315 -108.8
                      23 | 0.318
                                4.4
                                                       109.8 0.316 -108.6
09:21:46.0 1331+30500002_0 24|0.318
                                4.2
                                     0.323 -6.6 0.309
                                     0.323 -6.6 0.308
09:21:46.0 1331+30500002_0 25|0.319
                                4.3
                                                       109.5 0.315 -108.4
                                7.0
                                     0.508 -7.9
                                                       112.2 0.499 -108.5
10:05:27.9 1445+09900002_0 22|0.502
                                                 0.483
10:05:27.9 1445+09900002_0 23|0.498
                                7.2 0.509
                                           -8.2 0.489 112.6 0.502 -108.8
10:05:27.9 1445+09900002_0 24|0.496 6.3 0.506
                                          -7.1 0.487 111.9 0.502 -108.3
10:05:27.9 1445+09900002_0 25|0.489 6.3
                                     0.512
                                           -8.2
                                                 0.483 113.0 0.498 -108.7
         N5921_2 22|0.089 53.9
                                            38.8
                                                       -84.0 0.148
10:09:05.3
                                     0.084
                                                 0.135
                                                                    54.9
                                                 0.117 -80.7
10:09:05.3
               N5921_2 23|0.068 50.4
                                     0.073
                                           31.5
                                                              0.150
                                                                    50.5
                                           45.1
10:09:05.3
              N5921_2 24|0.068
                               51.4
                                     0.080
                                                 0.125 -89.0 0.146
                                                                    47.3
10:09:05.3
              N5921_2 25|0.060 45.8
                                     0.060
                                            42.5
                                                0.124 -85.4
                                                              0.146
                                                                    47.8
                        | Ant = 11
                                                 | Ant = 12
                     Chn | Amp Phs F
                                           Phs F| Amp
Time
       Field
                                       Amp
                                                         Phs F
                                                               Amp
                                                                    Phs F
09:21:46.0 1331+30500002_0 22|0.302 -99.8
                                     0.301 -10.5 0.341 169.8
                                                            0.350 - 137.6
09:21:46.0 1331+30500002_0 23|0.301 -99.9
                                     0.302 - 10.6
                                                 0.341
                                                       169.7
                                                              0.349 -138.0
09:21:46.0 1331+30500002_0 24|0.300 -100.0
                                     0.301 -10.9
                                                 0.342
                                                       169.6 0.348 -138.4
09:21:46.0 1331+30500002_0 25|0.301 -100.1
                                     0.300 -11.0
                                                 0.339
                                                       169.9 0.347 -138.5
10:05:27.9 1445+09900002_0 22|0.478 -97.3
                                     0.482
                                           -9.7
                                                 0.535
                                                       171.3 0.544 -138.1
10:05:27.9 1445+09900002_0 23|0.481 -97.4
                                     0.479 -10.4
                                                 0.531
                                                       171.4 0.549 -138.9
10:05:27.9 1445+09900002_0 24|0.482 -97.6
                                     0.484 -10.1
                                                 0.532 172.7 0.544 -139.3
10:05:27.9 1445+09900002_0 25|0.479 -98.4
                                     0.484 -10.1
                                                 0.534 172.4 0.553 -139.0
               N5921_2 22|0.127
                                     0.142 128.9
                                                 0.090 -94.4
                                                              0.090 -48.5
                              44.8
10:09:05.3
               N5921_2 23|0.135 43.1
                                                 0.087 -89.3 0.103 -38.2
10:09:05.3
                                     0.132 126.0
              N5921_2 24|0.135 49.4
                                                 0.092 -95.9 0.084 -42.7
10:09:05.3
                                     0.137 136.1
10:09:05.3
              N5921_2 25|0.144 49.8
                                     0.119 130.0
                                                 0.086 -96.5
                                                              0.074 - 42.8
```

Listed 120 antenna solutions.

list history-task.html

0.1.65 listhistory

Requires:

Synopsis

List the processing history of a dataset:

Description

List the processing history of a dataset: The list of all task processing steps will be given in the logger.

Arguments

Inputs	
vis	Name of input visibility file (MS)
	allowed: string
	Default:

Returns

void

Example

```
The list of all task processing steps in a visibility data set are listed in the logger.
```

listfits-task.html

0.1.66 listfits

Requires:

Synopsis

List the HDU and typical data rows of a fits file:

Description

List the HDU and typical data rows of a fits file: The list will be given in the logger.

Arguments

Inputs			
fitsfile	Name of in	Name of input fits file	
	allowed:	string	
	Default:		

Returns

void

Example

The HDU and typical data rows in a fits file are listed in the logger.

listobs-task.html

0.1.67 listobs

Requires:

Synopsis

List the summary of a data set in the logger or in a file

Description

List the summary information of a data set in the logger or in a file, based on a data selection. Only rows can be selected and printed. No in-row selection is possible (channel or correlation).

Lists the following properties of a measurement set: scan list, field list, spectral window list with correlators, antenna locations, ms table information.

Arguments

Inputs

vis Name of input visibility file (MS)

allowed: string

Default:

selectdata Data selection parameters

allowed: bool

Default: True

spw spectral-window/frequency/channel

allowed: any Default: variant

field Field names or field index numbers: "==>all,

 $\begin{array}{ll} {\rm field}{=}{}'0{\sim}2{,}3{\rm C}286{'}\\ {\rm allowed:} & {\rm any}\\ {\rm Default:} & {\rm variant} \end{array}$

antenna antenna/baselines: "==>all, antenna ='3,VA04'

allowed: any Default: variant

uvrange uv range: "==>all; uvrange ='0 \sim 100klambda', default

units=meters allowed: any Default: variant

time range: "==>all,timerange='09:14:0 \sim 09:54:0'

allowed: any Default: variant

correlation Select data based on correlation

allowed: any Default: variant

scan numbers: "==>all

allowed: any Default: variant

intent Select data based on observation intent: "==>all

allowed: any Default: variant

feed multi-feed numbers: Not yet implemented

allowed: any Default: variant

array (sub)array numbers: "==>all

allowed: any Default: yaggiant

observation Select data based on observation ID: "==>all

allowed: any
Default: variant

verbose

allowed: bool Default: True

Returns

void

Example

```
List the summary information of a data set in the logger or in a file, based on
a data selection. Only rows can be selected and printed. No in-row selection is
possible (channel or correlation). Refer to the task listvis to list visibilites.
Lists the following properties of a measurement set:
scan list, field list, spectral window list with
correlators, antenna locations, ms table information.
Keyword arguments:
vis -- Name of input visibility file
        default: none. example: vis='ngc5921.ms'
selectdata -- Select a subset of data for flagging
             default: False
             options: True, False
             The summary listing will only apply to the specified selection.
       antenna -- Select data based on baseline
             default: '' (all); example: antenna='5&6' baseline 5-6
             antenna='5\&6;7\&8' #baseline 5-6 and 7-8
             antenna='5' # all cross-correlation baselines between antenna 5 and all
                           antennas
             antenna='5,6' # all baselines with antennas 5 and 6
             antenna='1&&1' \mbox{\#} only the auto-correlation baselines for antenna 1
             antenna='1&&*' # cross and auto-correlation baselines between antenna 1
                                      and all other available antennas
             antenna='1~7&&&' # only the auto-correlation baselines for antennas in
       spw -- Select data based on spectral window and channels
             default: '' (all); example: spw='1'
             spw='<2' #spectral windows less than 2
             spw='>1' #spectral windows greater than 1
       correlation -- Correlation types
             default: '' (all);
             example: correlation='RR LL'
```

field -- Select data based on field id(s) or name(s)
 default: '' (all); example: field='1'

```
field='0~2' # field ids inclusive from 0 to 2
             field='3C*' # all field names starting with 3C
       uvrange -- Select data within uvrange (default units meters)
             default: '' (all); example:
             uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lamgda
             uvrange='>4klamda';uvranges greater than 4 kilo-lambda
             uvrange='0~1000km'; uvrange in kilometers
       timerange -- Select data based on time range:
             default = '' (all); example,
             timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
             Note: YYYY/MM/DD can be dropped as needed:
             timerange='09:14:0~09:54:0' # this time range
             timerange='09:44:00' # data within one integration of time
             timerange='>10:24:00' # data after this time
             timerange='09:44:00+00:13:00' #data 13 minutes after time
       scan -- Select data based on scan number
             default: '' (all); example: scan='>3'
       intent -- Select data based on observation intent
             default: '' (all); example: intent='*CAL*,*BAND*'
       feed -- Selection based on the feed - NOT IMPLEMENTED YET
       array -- Selection based on the antenna array
       observation -- Selection based on the observation ID
             default: '' (all); example: observation='1' or observation=1
verbose -- level of detail
      verbose=True: (default); scan and antenna lists
      verbose=False: less information
listfile -- name of disk file to write output.
```

listunfl -- List unflagged row counts? If true, it can have significant negative per

cachesize -- maximum size of the memory cache in megabytes in which data structures of stored. For very large datasets this can be increased for possibly better this is only experiemental for now, and increasing the value of this particles. Depending on its (LACK OF) usefulness, it may be removed in the large teacher.

The 'Int (s)' column is the average of the MS's INTERVAL column for each scan, so in a time-averaged MS 'Int' = 9.83s more likely means 5 10s integrations and 1 9s integration (timebin) than 6 9.83s integrations.

default: None. Example: listfile='list.txt'

DESCRIPTION OF ALGORITHM TO CALCULATE THE NUMBER OF UNFLAGGED ROWS

The number of unflagged rows are only computed if listunfl=True. Computing these quantition have a negative performance impact, especially for large datasets.

The number of unflagged rows (the nUnflRows columns in the scans and fields portions of calculated by summing the fractional unflagged bandwidth for each row (and hence why the rows, in general, is not an integer). Thus a row which has half of its total bandwidth flagged contributes 0.5 rows to the unflagged row count. A row with 20 of

homogeneous width contributes 20/32 = 0.625 rows to the unflagged row count. A row with in the FLAG_ROW column is not counted in the number of unflagged rows.

listpartition-task.html

0.1.68 listpartition

Requires:

Synopsis

List the summary of a multi-MS data set in the logger or in a file

Description

Lists the following properties of a multi-measurement set: sub-MS name, scan list, spw list, list of number of channels per spw, number of rows for all scans.

Arguments

Inputs			
vis	Name of multi-MS or normal MS.		
	allowed: string		
	Default:		
createdict	Create and return a dictionary with sub-MS information		
	allowed: bool		
	Default: False		
listfile	Name of ASCII file to save output: "==>to terminal		
	allowed: string		
	Default:		

Returns

void

Example

A multi-measurement set (MMS) is an MS that has been split into sub-MSs. An MMS contains a reference MS in the top directory and the sub-MSs are located in a directory called SUBMSS inside the MMS directory.

Example of a MS that was partitioned in the 'scan' axis using the task partition:

```
> ls ngc5921.mms
```

ANTENNA	FLAG_CMD	POLARIZATION	SPECTRAL_WINDOW	table.dat
DATA_DESCRIPTION	HISTORY	PROCESSOR	STATE	table.info
FEED	OBSERVATION	SORTED_TABLE	SUBMSS	WEATHER
FIELD	POINTING	SOURCE	SYSCAL	

> ls ngc5921.mms/SUBMSS/

```
ngc5921.0000.ms/ ngc5921.0002.ms/ ngc5921.0004.ms/ ngc5921.0006.ms/ ngc5921.0001.ms/ ngc5921.0003.ms/ ngc5921.0005.ms/
```

The task lists the following properties of a multi-MS or MS: sub-MS name, scan, spw list, list of number of channels per spw, number of rows for each scan and the size in disk. Example of logger output:

Sub-MS	Scan	Spw	Nchan	Nrows	Size
ngc5921.0000.ms	1	[0]	[63]	4509	11M
ngc5921.0001.ms	2	[0]	[63]	1890	6.4M
ngc5921.0002.ms	3	[0]	[63]	6048	13M
ngc5921.0003.ms	4	[0]	[63]	756	4.9M
ngc5921.0004.ms	5	[0]	[63]	1134	6.4M
ngc5921.0005.ms	6	[0]	[63]	6804	15M
ngc5921.0006.ms	7	[0]	[63]	1512	6.4M

```
----- Detailed description of keyword arguments -----
vis -- Name of multi-MS or normal MS.
default: ''.
example: vis='pScan.mms'
```

createdict -- Create and return a dictionary containing scan summaries of each sub-MS.

default: False

If set to True, the returned dictionary will contain information from ms.getscansummary() and ms.getspectralwindowinfo(), with the addition of an index as the top key and the sub-MS name. Example:

listsdm-task.html

0.1.69 listsdm

Requires:

Synopsis

Lists observation information present in an SDM directory.

Description

Given an SDM directory, this task will print observation information to the logger and return a dictionary keyed by scan.

Arguments

Inputs			
sdm	Name of in	put SDM directory	
	allowed:	string	
	Default:		

Returns

void

Example

The listsdm task reads SDM XML tables, processes the observation information contained therein, and prints this information to the CASA log. It will also return a dictionary keyed on scan number. The dictionary contains the following information:

```
'baseband' list of baseband name(s)
'chanwidth' list of channel widths (Hz)
'end' observation end time (UTC)
```

'field' field ID
'intent' scan intent(s)
'nchan' list of number of channels
'nsubs' number of subscans

'reffreq' list of reference frequencies (Hz)
'source' source name
'spws' list of spectral windows
'start' observation start time (UTC) 'timerange' start time - end time range (UTC)

Example:

myscans = listsdm(sdm='AS1039_sb1382796_2_000.55368.51883247685')

Prints information about the requested SDM to the CASA logger and returns a dictionary with scan information in 'myscans'.

Keyword argument:

```
sdm -- Name of input SDM directory.
       example: sdm='AG836_sb1377811_1.55345.300883159725'
```

listvis-task.html

0.1.70 listvis

Requires:

Synopsis

List measurement set visibilities.

Description

This task lists measurement set visibility data under a number of input selection conditions. The measurement set data columns that can be listed are: the raw data, float_data, corrected data, model data, and residual (corrected - model) data.

The output table format is dynamic. Field, Spectral Window, and Channel columns are not displayed if the column contents are uniform. For example, if "spw = '1" is specified, the spw column will not be displayed. When a column is not displayed, a message is sent to the logger and terminal indicating that the column values are uniform and listing the uniform value.

Table column descriptions:

COLUMN NAME DESCRIPTION — — — — Date/Time Time stamp of data sample (YYMMDD/HH:MM:SS UT) Intrf Interferometer baseline (antenna names) UVDist uv-distance (units of wavelength) Fld Field ID (if more than 1) SpW Spectral Window ID (if more than 1) Chn Channel number (if more than 1) (Correlated Correlated polarizations (eg: RR, LL, XY) polarization) Sub-columns are: Amp, Phs, Wt, F Amp Visibility amplitude Phs Visibility phase (deg) Wt Weight of visibility measurement F Flag: 'F' = flagged datum; ' ' = unflagged UVW UVW coordinates (meters) Input Parameters: vis Name of input visibility file default: none; example: vis='ngc5921.ms'

options List options: default = 'ap' Not yet implemented for suboptions datacolumn Visibility file data column: default = 'data': options are data, float_data, corrected, model, residual (corrected-model)

field Select data based on field id(s) or name(s) default: "==iall; example: field='1' field='0 \sim 2' field ids inclusive from 0 to 2 field='3C*' all field names starting with 3C

spw Select spectral window, channel to list default: '0:0' –; spw=0, chan=0 spw='2:34' spectral window 2, channel 34

selectdata Toggle the following 7 selection parameters. default: False; example: selectdata=True If false, the following parameters are reset to default values.

```
antenna Select calibration data based on antenna default: "-¿all; examples:
antenna = '5,6'; antenna index 5 and 6 solutions antenna = '05,06'; antenna
names '05' and '06 solutions
timerange Select time range to list default: "-¿all; examples:
timerange='10:37:50.1'; list data for this sampling interval
timerange=';10:37:25'; list data before 10:37:25
correlation Select polarization correlations to list default: "-¿all; examples:
correlation='RR LL'; list RR and LL correlations correlation='XX XY'; list
XX and XY correlations
scan Select scans to list default: "-jall; examples: scan='2'; list scan 2
scan=';2'; list scan numbers greater than 2
feed (not yet implemented)
array (not yet implemented)
observation Select by observation ID.
uvrange Select baseline lengths to list. default: "-į, all; examples:
uvrange='¡5klambda'; less than 5 kilo-wavelengths Caution: Input units
default to meters. Listed units are always wavelengths.
average (not yet implemented)
showflags (not yet implemented)
pagerows rows per page of listing default: 50; 0 -¿ do not paginate
listfile write output to disk; will not overwrite default: " -i, write to screen
listfile = 'solutions.txt'
async Run asynchronously default = False; do not run asychronously
```

Arguments

Inputs vis Name of input visibility file allowed: string Default: options List options: ap only allowed: string Default: ap datacolumn Column to list: data, float_data, corrected, model, residual allowed: string Default: data field Field names or index to be listed: "==>all allowed: string Default: Spectral window:channels: "==>all, spw='1:5~57' spw allowed: string Default: selectdata Other data selection parameters allowed: bool Default: False Antenna/baselines: "==>all, antenna = '3' antenna allowed: string Default: timerange Time range: "==>all allowed: string Default: Correlations: "==>all, correlation = 'RR RL' correlation allowed: string Default: Scan numbers scan allowed: string Default: feed Multi-feed numbers (Not yet implemented) allowed: string Default: Array numbers (Not yet implemented) array allowed: string Default: observation Select by observation ID(s) allowed: any Default: variant uv range: "==>all; not yet implemented uvrange allowed: string Default: Averaging mode: "==>none (Not yet implemented) average allowed: string Default: 333 showflags Show flagged data (Not yet implemented) allowed: bool Default: False Rows per page pagerows

allowed:

Default:

Output file allowed:

listfile

int

50

string

Returns

void

Example

This task lists measurement set visibility data under a number of input selection conditions. The measurement set data columns that can be listed are: the raw data, float_data, corrected data, model data, and residual (corrected - model) data.

The output table format is dynamic. Field, Spectral Window, and Channel columns are not displayed if the column contents are uniform. For example, if "spw = '1'" is specified, the spw column will not be displayed. When a column is not displayed, a message is sent to the logger and terminal indicating that the column values are uniform and listing the uniform value.

Table column descriptions:

COLUMN	NAME	DESCRIPTION

Date/Time Time stamp of data sample (YYMMDD/HH:MM:SS UT)

Intrf Interferometer baseline (antenna names)

UVDist uv-distance (units of wavelength)

Fld Field ID (if more than 1)

SpW Spectral Window ID (if more than 1)
Chn Channel number (if more than 1)

(Correlated Correlated polarizations (eg: RR, LL, XY)

polarization) Sub-columns are: Amp, Phs, Wt, F

Amp Visibility amplitude
Phs Visibility phase (deg)

Wt Weight of visibility measurement

F Flag: 'F' = flagged datum; ' ' = unflagged

UVW coordinates (meters)

Input Parameters:

vis Name of input visibility file

default: none; example: vis='ngc5921.ms'

options List options: default = 'ap'

```
Not yet implemented for suboptions
datacolumn Visibility file data column:
            default = 'data': options are
            data, float_data, corrected, model, residual (corrected-model)
field
            Select data based on field id(s) or name(s)
            default: ''==>all; example: field='1'
            field='0~2' field ids inclusive from 0 to 2
            field='3C*' all field names starting with 3C
            Select spectral window, channel to list
spw
            default: '0:0' --> spw=0, chan=0
            spw='2:34' spectral window 2, channel 34
selectdata Toggle the following 7 selection parameters.
            default: False; example: selectdata=True
            If false, the following parameters are reset
            to default values.
                  Select calibration data based on antenna
      antenna
                  default: ''-->all; examples:
                  antenna = '5,6'; antenna index 5 and 6 solutions
                  antenna = '05,06'; antenna names '05' and '06 solutions
      timerange
                  Select time range to list
                  default: ''-->all; examples:
                  timerange='10:37:50.1'; list data for this sampling interval
                  timerange='<10:37:25'; list data before 10:37:25
      correlation Select polarization correlations to list
                  default: ''-->all; examples:
                  correlation='RR LL'; list RR and LL correlations
                  correlation='XX XY'; list XX and XY correlations
      scan
                  Select scans to list
                  default: ''-->all; examples:
                  scan='2'; list scan 2
                  scan='>2'; list scan numbers greater than 2
      feed
                  (not yet implemented)
      array
                  (not yet implemented)
```

example: observation='0' (select obsID 0)

uvrange Select baseline lengths to list.

default: ''--> all; examples:

uvrange='<5klambda'; less than 5 kilo-wavelengths</pre>

Caution: Input units default to meters. Listed units are always wavelengths.

average (not yet implemented)

showflags (not yet implemented)

pagerows rows per page of listing

default: 50; 0 --> do not paginate

listfile write output to disk; will not overwrite

default: '' --> write to screen
listfile = 'solutions.txt'

async Run asynchronously

default = False; do not run asychronously

makemask-task.html

0.1.71 makemask

Requires:

Synopsis

Makes and manipulates image masks

Description

Construct masks based on various criteria, convert between mask-types, and generate a mask for clean $\,$

Arguments

Inputs modeMask method (list, copy,expand,delete,setdefaultmask) allowed: string Default: list inpimage Name of input image. allowed: any Default: variant inpmask $\operatorname{mask}(s)$ to be processed: image $\operatorname{masks}, T/F$ internal masks(Need to include parent image names), regions (for copy mode) allowed: any Default: variant output Name of output mask (imagename or imagename:internal_maskname) allowed: string Default: overwrite overwrite output if exists? allowed: bool Default: False inpfreqs List of chans/freqs (in inpmask) to read masks from allowed: any Default: variant outfreqs List of chans/freqs (in output) on which to expand the maskallowed: any Default: variant

Returns

void

Example

Modes:

list : list internal masks in inpimage to the \log

copy: Copy/merge masks and regrid if necessary to a new or existing mask

 $\ensuremath{\mathsf{expand}}$: Expand a mask from one range of freqs to another range

delete : delete an internal mask from an image (if the deleted mask was a default mask,

the task chooses the first one in the remaining internal mask list (as appears

in the log when do listing with mode='list')

setdefaultmask : set a specified internal mask as a default internal mask

In all cases (for output mask is expected), if the output image has a different coordinate a result of input and processing, the mask will be re-gridded to the output coordinate system.

Parameter Descriptions and rules:

inpimage: Name of input image to use as a reference for the output coordinates (if output of Also used as a reference image when regions are specified in inpmask for copy most if output is a new image specified with an internal T/F mask, the pixel values is are copied to the output image and the regions specified in inpmask are merged (specified) and treated as a valid region therefore will be UNMASKED in output. default: none (must specify for list, copy, expand modes)

Expandable parameters for mode='copy','expand','delete' and 'setdefaultmask':

inpmask : Name(s) of input mask(s)

default: none

To specify an image (zero/non-zero) mask, just give a image name (e.g. myimage1.im. To specify an internal (T/F) mask, you must give a parent image name and the internseparated by a colon. (e.g. myimage1.im:mask0). The internal mask names can be found the makemask task in mode='list'.

(expand mode)

'myimage:mask0' : use(true/false) internal mask

'myimage' : use the inpimage values to make a mask (zero/non-zero).

Non-zero values are normalized to one in the process.

(copy mode)

Specify the image mask(s), T/F mask(s), and region(s) to be merged in a list of strange The regions can be specified directly in the CASA region format or in the text file the regions.

(delete and setdefaultmask mode)

Specify the internal mask with the format, image:mask

output : Name of output image.

default: none

- *The resultant mask is written as an image (zero/one) mask if the output is a plain
- *The resultant mask is written as an internal (T/F) mask if the output name is the The created mask is set as a default internal mask.
- *To re-grid a mask to a different coordinate system,

give an image with the target coordinate system in inpimage. Or make a copy an image with the target coordinate system and specified the name of the copy in output.

- If output is specified as a plain image, if it exists, it will regrid the mask to the new coordinate system and modify output (if overwrite=True).
- If output is specified as an image with an internal mask, if the internal mask exists it will regrid the mask to the new coordinate system and modify the internal mask on
- If output does not exist, it will only copy inpimage.
- If output == inpimage, do not regrid. Only modify in-place.
- *** Please note that the term 'mask' is used in the image analysis and clean tasks in operate. In the image analysis, the masked region in general a region to be excluded to clean's input mask defines the region to be used as a clean box/region.

 In the makewask task, since the most common use case of output image mask is to use

In the makemask task, since the most common use case of output image mask is to use an input mask in clean, when it converts an internal mask to the image mask, the 'masked' region (where the pixels are masked and have the Boolean values 'False of the internal mask is translated to the pixels with value of 0 in output image mask

overwrite : overwrite the mask specified in output? (see also the output rules above) default: False

* Note that for a cube mask, overwrite=True generally overwrites in the specific so any pre-existed masks in other channels will be remain untouched.

Additional expandable parameters for mode='expand':

inpfreqs : input channel/frequency/velocity range

Specify channels in a list of integers. for frequency/velocity, a range is specified in a string with '~', e.g. '1.5MHz'1.6MHz', '-8km/s~-14km,

(for the cube with ascending frequencies)

default: [] - all channels

* Note that the range in frequency or velocity needs to be specified as the sar as in the template cube specified in inpimage. E.g., if a template cube has defrequencies, then the range will be, for example, '1.6MHz' 1.5MHz' or '-14km/s'-4

outfreqs : output channel/frequency/velocity range

Specify same way as inpfreqs default: [] - all channels

Usage	${\tt examples}$:	
-------	------------------	---	--

- (1) (list mode):
 makemask(mode='list', inpimage='mymask.im')
 it prints out a list of the internal mask(s) exist in mymask.im to the log
- (2) (copy mode):

 Regrid a Boolean mask from one coordinate system to another and save as Boolean mask in the output image.

makemask(mode='copy', inpimage='oldmask.im', inpmask='oldmask.im:mask0', output='newmas

(3) (copy mode):

will be masked.

will be masked.

Same as (1), but save as integer mask in the output image.

makemask(mode='copy', inpimage='oldmask.im', inpmask='oldmask.im:mask0', output='newmask')

- * maskO is translated so that pixels in oldmask.im that appears as 'masked' in the view has the pixel mask value = 'False' when extracted in imval, are to have pixel value the output image, newmask.im.
- (4) (copy mode):
 Convert a Boolean(true/false) mask to an integer(one/zero) mask in the same image
 makemask(mode='copy', inpimage='oldmask.im', inpmask='oldmask.im:mask0', output='', over
- (5) (copy mode):
 Convert an integer(one/zero) mask to a Boolean(true/false) mask in the same image
 makemask(mode='copy', inpimage='oldmask.im', inpmask='oldmask.im', output='oldmask.im:
- (6) (copy mode): Copy a CRTF mask defined in mybox.txt to a Boolean(true/false) mask in a new image makemask(mode='copy', inpimage='image1.im', inpmask='mybox.txt', output='image2.im:mask The pixel values of image1.im will be copied to image2.im and the region outside mybox
- (7) (copy mode):
 Apply a region defined in a CRTF file to mask part of an image
 makemask(mode='copy', inpimage='image1.im', inpmask='myregion.crtf', output='image1.im
 The region is copied as a T/F mask (mask0) inside the image, image1.im. The region outs

(8) (copy mode):

Merge a (one/zero) mask and T/F masks, using the input coordinate-sys of inpimage and saving in a new output file. Remember, if the image specified in output already exist a has a different coordinate system from inpimage, the mask will be regridded to it. All masks to be merged are specified in a list in inpmask.

The name of internal masks must be given in the format, 'parent_image_name:internal_masks shown the example below.

In the example below, image1.im (the 1/0 mask), the internal masks, mask0 from image1.: and mask1 from image2.im, and a region (on image1.im as defined in inpimage) are comb: The output, newmask.im is a new mask name which has not

yet exist so image specified in inpimage, image1.im's coordinates are used as a target image coordinates. If image1.im and image2.im has different coordinates, image2.im:masl regridded before it is combined to the other two masks.

(9) (expand mode):

Expand a (one/zero) mask from continuum imaging to use as an input mask image for spectral line imaging. Use an existing spectral line clean image as a template by specified in inpimage.

The inpfreqs is left out as it uses a default (=[], means all channels).

(10) (expand mode):

Expand a Boolean mask from one range of channels to another range in the same image.

(11) (expand mode):

Expand a Boolean mask from a range of channels in the input image to another range of channels in a different image with a different spectral-coordinate system. Save the mask as ones/zeros so that it can be used as an input mask in the clean task. As the inpimage is used as a template for the CoordinateSystem of the output cube, it a prerequisite to have the cube image (a dirty image, etc). In this particular example it is assumed that bigmask.im is a working copy made from the cube image of a previous

```
execution. It is used as an input template and the resultant mask is overwritten to the
    Specify the infreqs and outfreqs in frequency (assuming here bigmask.im has frequencies
    makemask(mode='expand', inpimage='bigmask.im', inpmask='smallmask.im:mask0',
              inpfreqs='1.5MHz"1.6MHz', outfreqs='1.2MHz"1.8MHz', output='bigmask.im', over
    or to specify the ranges in velocities,
    makemask(mode='expand', inpimage='bigmask.im', inpmask='smallmask.im:mask0',
              inpfreqs=4.0km/s~0.5km/s', outfreqs='6.5km/s~-2.4km/s', output='bigmask.im', o
(12) (delete mode)
```

Delete an internal mask from an image.

makemask(mode='delete', inpmask='newmask.im:mask0')

(13) (setdefaultmask mode)

Set an internal mask as a default internal mask.

makemask(mode='setdefaultmask', inpmask='newmask.im:mask1')

mosaic-task.html

0.1.72 mosaic

Requires:

Synopsis

Create a multi-field deconvolved image with selected algorithm

Description

Form images from visibilities. Handles continuum and spectral line cubes.

Arguments

Inputs

gain

vis name of input visibility file

allowed: string

Default:

imagename Pre-name of output images

allowed: string

Default:

mode Type of selection (mfs, channel, velocity, frequency)

allowed: string Default: mfs

alg Algorithm to use (clark, hogbom, multiscale)

allowed: string
Default: clark

imsize Image size in pixels (nx,ny), symmetric for single value

allowed: intArray Default: 256256

cell arcsec The image cell size in arcseconds [x,y].

allowed: doubleArrayarcsec

Default: 1.01.0

phasecenter Field Identififier or direction of the image phase center

allowed: any Default: variant

stokes Stokes params to image

(I,IV,QU,IQUV,RR,LL,XX,YY,RRLL,XXYY)

allowed: string Default: I

niter Maximum number of iterations

allowed: int
Default: 500
Loop gain for cleaning

allowed: double Default: 0.1

threshold Flux level to stop cleaning (unit mJy assumed)

allowed: double Default: 0.0

mask Set of mask images used in cleaning

allowed: stringArray

Default:

cleanbox clean box regions or file name or 'interactive'

allowed: any
Default: variant

nchan Number of channels in output image

allowed: int
Default: 1
Start channel 45

start Start channel 45

allowed: any Default: variant 0

width Channel width (value > 1 indicates channel averaging)

allowed: any Default: variant 1

field Field Name

allowed: any
Default: variant

Returns

void

Example

Two types of point-source deconvolution, as well as multi-scale deconvolution, are available. A continuum image (mfs) is produced by gridding together all spectral data. Individual channels or groups of channels can also be images and then placed in an output image cube.

The cleaning regions can be specified by an input mask image, from a file containing rectangular regions, or interactively as the deconvolution progresses.

The mosaic task only uses the "corrected" datacolumn which is made from the "data" data column using applycal with the appropriate calibration tables. Many Stokes combinations are available.

```
Keyword arguments:
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
imagename -- Pre-name of output images:
        default: none; example: imagename='m2'
        output images are:
          m2.image; cleaned and restored image
          m2.flux; relative sky sensitivity over field
          m2.model; image of clean components
          m2.residual; image of residuals
          m2.interactive.mask; image containing clean regions
mode -- Frequency Specification:
NOTE: See examples below:
        default: 'mfs'
          mode = 'mfs' means produce one image from all specified data.
          mode = 'channel'; Use with nchan, start, width to specify
                  output image cube. See examples below
          mode = 'velocity', means channels are specified in velocity.
  mode = 'frequency', means channels are specified in frequency.
   >>> mode expandable parameters (for modes other than 'mfs')
```

```
Start, width are given in units of channels, frequency or velocity
             as indicated by mode, but only channel is complete.
          nchan -- Number of channels (planes) in output image
            default: 1; example: nchan=3
          start -- Start input channel (relative-0)
            default=0; example: start=5
          width -- Output channel width (>1 indicates channel averaging)
            default=1; example: width=4
      examples:
          spw = '0,1'; mode = 'mfs'
            will produce one image made from all channels in spw 0 and 1
          spw='0:5^28^2'; mode = 'mfs'
             will produce one image made with channels (5,7,9,\ldots,25,27)
          spw = '0'; mode = 'channel': nchan=3; start=5; width=4
             will produce an image with 3 output planes
             plane 1 contains data from channels (5+6+7+8)
             plane 2 contains data from channels (9+10+11+12)
            plane 3 contains data from channels (13+14+15+16)
          spw = '0:0~63^3'; mode=chann; nchan=21; start = 0; width = 1
             will produce an image with 20 output planes
             Plane 1 contains data from channel 0
            Plane 2 contains date from channel 2
            Plane 21 contains data from channel 61
          spw = '0:0^40^2; mode = 'channel'; nchan = 3; start = 5; width = 4
             will produce an image with three output planes
            plane 1 contains channels (5,7)
            plane 2 contains channels (13,15)
            plane 3 contains channels (21,23)
  alg -- Algorithm to use (expandable):
          default: 'clark': Options: 'clark', 'hogbom', 'multiscale', 'entropy'
          'hogbom' Cleans from the images only. Only inner quarter
  of image is cleaned
          'clark' Cleans from gridded us data. Only inner quarter of
  image is cleaned
          'multiscale' cleans with several resolutions using hobgom clean
                Currently much slower than single resolution. For extended
sources, try single resolution with interactive and
          'entropy' Maximum entropy algorithm is still experimental
and not recommended for general use
   >>> multiscale expandable parameter
          scales -- in pixel numbers; the size of component to deconvolve
                default = [0,3,10]
                 recommended sizes are 0 (point), 3 (points per clean beam), and
                  10 (about a factor of three lower resolution)
          negcomponent' -- Stop component search when the largest
        scale has found this number of negative components; -1 means
```

```
continue component search even if the largest component is
      negative.
              default: 2; example: negcomponent=-1
  >>> entropy (MEM) expandable parameters (experimental)
sigma -- Target image sigma
              default: '0.001Jy'; example: sigma='0.1Jy'
        targetflux -- Target flux for final image
              default: '1.0Jy'; example: targetflux='200Jy'
        constrainflux -- Constrain image to match target flux;
              otherwise, targetflux is used to initialize model only.
                   default: False; example: constrainflux=True
        prior -- Name of MEM prior images
              default: ['']; example: prior='source_mem.image'
imsize -- Image pixel size (x,y)
        default = [256,256]; example: imsize=[350,350]
        imsize = 500 is equivalent to [500,500]
cell -- Cell size (x,y)
        default= none;
        example: cell=['0.5arcsec,'0.5arcsec'] or
        cell=['1arcmin', '1arcmin']
        cell = 'larcsec' is equivalent to ['larcsec', 'larcsec']
NOTE:cell = '2' makes default cell size of 2 radians!
phasecenter -- direction measure or fieldid for the mosaic center
        default: 0 (imply field=0 as center); example: phasecenter=6
        or phasecenter='J2000 19h30m00 -40d00m00'
stokes -- Stokes parameters to image
        default='I'; example: stokes='IQUV';
        Options: 'I', 'IV', QU', 'IQUV', 'RR', 'LL', 'XX', 'YY', 'RRLL', 'XXYY'
niter -- Maximum number iterations, set to zero for no CLEANing
        default: 500; example: niter=500
gain -- Loop gain for CLEANing
        default: 0.1; example: gain=0.5
threshold -- Flux level at which to stop CLEANing (units=mJy)
        default: 0.0; example: threshold=0.0
mask -- Name of mask image used for CLEANing
        default ', means no mask;
          example: mask='orion.mask'.
It is useful to use a mask from a previous interactive mosaic
session for a new execution. The mask image shape
        must be the same as the new mosaic.
cleanbox -- Cleaning region:
        default: [] defaults to inner quarter of image
        Three specification types:
        (a) 'interactive' allows the user to build the cleaning
             mask interactively using the viewer. The viewer will
             appear every npercycle interation, but modify as needed
```

```
The final interactive maks is saved in the file imagename_interactive.mask.

(b) Explicit pixel ranges
```

```
example: cleanbox=[110,110,150,145]
             clean region with blc=110,100; trc=150,145 (pixel values)
             Only one clean region can be given this way.
         (c) Filename with pixel values with ascii format:
             <fieldindex blc-x blc-y trc-x trc-y> on each line
             1 45 66 123 124
             2 23 100 300 340
   >>> 'interactive' expandable parameter
         npercycle -- this is the number of iterations between each clean
 to update mask interactively. Set to about niter/5, can also
        be changed interactively.
 field -- Select fields in mosaic. Use field id(s) or field name(s).
            ['go listobs' to obtain the list id's or names]
        default: ''=all fields
        If field string is a non-negative integer, it is assumed to
            be a field index otherwise, it is assumed to be a field name
       field='0~2'; field ids 0,1,2
        field='0,4,5~7'; field ids 0,4,5,6,7
       field='3C286,3C295'; field named 3C286 and 3C295
       field = '3,4C*'; field id 3, all names starting with 4C
 spw -- Select spectral window/channels
NOTE: This selects the data passed as the INPUT to mode
        default: ''=all spectral windows and channels
          spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
          spw='<2'; spectral windows less than 2 (i.e. 0,1)
          spw='0:5~61'; spw 0, channels 5 to 61
          spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
          spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
          spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
          spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
 timerange -- Time range:
         default = '' (all); examples,
         selectime = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
         Note: if YYYY/MM/DD is missing date defaults to first day
   in data set
         timerange='09:14:0~09:54:0' picks 40 min on first day
         timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
         timerange='09:44:00' data within one integration of time
         timerange='>10:24:00' data after this time
 restfreq -- Specify rest frequency to use for image
         default=',
 Occasionally it is necessary to set this (for example some VLA
```

```
spectral line data). For example for
        NH_3 (1,1) put restfreq='23.694496GHz'
sdimage -- Input Single Dish image to use for model
        default='' (no image); example: sdimage='n4826_12mchan.im'
modelimage -- Name of output(/input) model image
        default='' (none=imagename.model); modelimage='orion.model'
        Note: This specifies the output model if a single dish
        image is input or the output model name from the imaging
weighting -- Weighting to apply to visibilities:
        default='natural'; example: weighting='uniform';
        Options: 'natural', 'uniform', 'briggs', 'radial', 'superuniform'
   >>> Weighting expandable parameters
        For weighting='briggs'
          rmode -- Robustness mode (see help mosaic)
            default='norm'; example='abs';
            Options: 'norm', 'abs', 'none'
          robust -- Brigg's robustness parameter
            default=0.0; example: robust=0.5;
            Options: -2.0 to 2.0; -2 (uniform)/+2 (natural)
                -- noise parameter to use for rmode='abs' in
          noise
    briggs weighting
            example noise='1.0mJy'
        For superuniform/briggs weighting
            npixels -- number of pixels to determine uv-cell size
    for weight calculation
            example npixels=7
mosweight -- Individually weight the fields of the mosaic
        default: False; example: mosweight=True
        This can be useful if some of your fields are more
        sensitive than others (i.e. due to time spent on-source);
        this parameter will give more weight to higher sensitivity
        fields in the overlap regions.
ftmachine -- Gridding method for the image;
        Options: ft (standard interferometric gridding), sd
(standard single dish) both (ft and sd as appropriate),
mosaic (gridding use PB as convolution function)
        default: 'mosaic'; example: ftmachine='ft'
cyclefactor -- Change the threshold at which the deconvolution cycle will
        stop, degrid and subtract from the visibilities. For poor PSFs,
        reconcile often (cyclefactor=4 or 5); For good PSFs, use
        cyclefactor 1.5 to 2.0.
        default: 1.5; example: cyclefactor=4
        cycle threshold = cyclefactor * max sidelobe * max residual
cyclespeedup -- Cycle threshold doubles in this number of iterations
        default: -1; example: cyclespeedup=500
scaletype -- Controls scaling of pixels in the image plane.
```

```
default='SAULT'; example: scaletype='PBCOR'
    Options: 'PBCOR','SAULT'
    'SAULT' scale makes an output image where the noise is constant
    across the whole mosaic. However, the image is NOT
    corrected for the PB pattern, and therefore is not "flux
    correct". Division of the SAULT image_name.image image
    by the image_name.flux image will produce a "flux correct image".
    The 'PBCOR' option uses the SAULT scaling scheme for
    deconvolution, but when interactively cleaning shows the
    primary beam corrected image; the final PBCOR image is "flux
    correct"

minpb -- Minimum PB level to use
    default=0.1; example: minpb=0.01
async -- Run asynchronously
    default = False; do not run asychronously
```

msview-task.html

0.1.73 msview

Requires:

Synopsis

View a visibility data set

Description

The msview task will display measurements in raster form. Many display and editing options are available.

Executing the msview task will bring up a display panel window, which can be resized. If no data file was specified, a Load Data window will also appear. Click on the desired measurement set, and the rendered data should appear on the display panel.

A Data Display Options window will also appear. It has drop-down subsections for related options, most of which are self-explanatory. The state of the msview task – loaded data and related display options – can be saved in a 'restore' file for later use. You can provide the restore filename on the command line or select it from the Load Data window. See the cookbook for more details on using the msview task.

Arguments

Inputs infile (Optional) Name of file to visualize. allowed: string Default: displaytype (Optional) Type of visual rendering (raster, contour, vector or marker). lel if an lel expression is given for infile (advanced). allowed: string Default: raster channel (Optional) access a specific channel in the image cube allowed: int Default: 0 (Optional) zoom in/out by increments zoom allowed: Default: outfile (Optional) name of the output file to generate allowed: string Default: outscale (Optional) amount to scale output bitmap formats (non-PS, non-PDF) allowed: double Default: 1.0 (Optional) output DPI for PS/PDF outdpi allowed: int Default: outformat (Optional) format of the output e.g. jpg or pdf (this is overridden by the output files extension allowed: string Default: jpg

outlandscape (Optional) should the output mode be landscape (PS or

PDF)

allowed: bool Default: False

gui (Optional) Display the panel in a GUI.

allowed: bool Default: True

Returns

void

Example

```
examples of usage:
msview
msview "mymeasurementset.ms"
msview "myrestorefile.rstr"
Keyword arguments:
infile -- Name of file to visualize
default: ''
example: infile='my.ms'
If no infile is specified the Load Data window
will appear for selecting data.
displaytype -- (optional): method of rendering data
visually (raster, contour, vector or marker).
You can also set this parameter to 'lel' and
provide an lel expression for infile (advanced).
default: 'raster'
Note: there is no longer a filetype parameter; typing of
data files is now done automatically.
        example: msview infile='my.ms'
obsolete: msview infile='my.ms', filetype='ms'
```

0.1.74 mstransform

Requires:

Synopsis

Split the MS, combine/separate/regrid spws and do channel and time averaging

Description

The task mstransform can do the same functionalities available in cvel, partition, hanningsmooth and split without the need to read and write the output to disk multiple times. The main features of this task are:

* take an input MS or Multi-MS (MMS) * ability to create an output MS or MMS * spw combination and separation * channel averaging taking flags and weights into account * time averaging taking flags and weights into account * reference frame transformation * Hanning smoothing

All these transformations will be applied on the fly without any writing to disk to optimize I/O. The user can ask to create a Multi-MS in parallel using CASA's cluster infrastructure using the parameter createmms. See MPIInterface for more information on the cluster infrastructure.

This task is implemented in a modular way to preserve the functionalities available in the replaced tasks. One can choose which functionality to apply or apply all of them by setting the corresponding parameters to True. Note that there is an order in which the transformations are applied to the data that makes logical sense on the point of view of the data analysis.

This task can create a multi-MS as the output. General selection parameters are included, and one or all of the various data columns (DATA, LAG_DATA and/or FLOAT_DATA, and possibly MODEL_DATA and/or

CORRECTED_DATA) can be selected. It can also be used to create a normal MS, split-based on the given data selection parameters.

The mstransform task creates a Multi-MS in parallel, using the CASA MPI framework. The user should start CASA as follows in order to run it in parallel.

- 1) Start CASA on a single node with 8 engines. The first engine will be used as the MPIClient, where the user will see the CASA prompt. All other engines will be used as MPIServers and will process the data in parallel. mpicasa -n 8 casa -nogui -log2term mstransform(.....)
- 2) Running on a group of nodes in a cluster. mpicasa -hostfile user_hostfile casa mstransform(.....)

where user_hostfile contains the names of the nodes and the number of engines to use in each one of them. Example: pc001234a, slots=5 pc001234b, slots=4 If CASA is started without mpicasa, it is still possible to create an MMS, but the processing will be done in sequential.

The resulting WEIGHT_SPECTRUM produced by mstransform is in the statistical sense correct for the simple cases of channel average and time average, but not for the general re-gridding case, in which the error propagation formulas applicable for WEIGHT_SPECTRUM are yet to be defined. Currently, as in cvel and in the imager, WEIGHT_SPECTRUM is transformed in the same way as the other data columns. Notice that this is not formally correct from the statistical point of view, but is a good approximation at this stage.

NOTE: the input/output in mstransform have a one-to-one relation. input MS – output MS input MMS – output MMS unless the user sets the parameter createmms to True to create the following:

input MS – output MMS

Arguments

Inputs

vis Name of input Measurement set or Multi-MS.

allowed: string

Default:

outputvis Name of output Measurement Set or Multi-MS.

allowed: string

Default:

createmms Create a multi-MS output from an input MS.

allowed: bool Default: False

separationaxis Axis to do parallelization

across(scan,spw,auto,baseline).

allowed: string Default: auto

numsubms The number of Sub-MSs to create (auto or any number)

allowed: any

Default: variant auto

tileshape List with 1 or 3 elements giving the tile shape of the disk

data columns.

allowed: intArray

Default: 0

field Select field using ID(s) or name(s).

allowed: any
Default: variant

spw Select spectral window/channels.

allowed: any Default: variant

scan Select data by scan numbers.

allowed: any
Default: variant

antenna Select data based on antenna/baseline.

allowed: any
Default: variant

correlation: " ==> all, correlation='XX,YY'.

allowed: any Default: variant

timerange Select data by time range.

allowed: any Default: variant

intent Select data by scan intent.

allowed: any
Defa**yy** variant

array Select (sub)array(s) by array ID number.

allowed: any Default: variant

uvrange Select data by baseline length.

allowed: any Default: variant

Example

```
Detailed description of keyword arguments:
--- Input/Output parameters ---
   vis -- Name of input visibility file
        default: ''; example: vis='ngc5921.ms'
    outputvis -- Name of output visibility file or Multi-MS
       default: ''; example: outputvis='ngc5921.mms'
    createmms -- Create an output Multi-MS from an input MS.
       default: False
       This parameter only has effect if set to True, when it will try
       to create an output Multi-MS from an input MS. The one-to-one
       relation of input/output in mstransform is:
          input MS -- output MS
          input MMS -- output MMS
       by setting createmms=True, the following is possible:
          input MS -- output MMS
       NOTE: See information on processing input Multi-MS at the end of this help section.
        separationaxis -- Axis to do parallelization across.
            default: 'auto'
            options: 'scan', 'spw', 'auto', 'baseline'
            * The 'auto' option will partition per scan/spw to obtain optimal load balancing
            following criteria:
            1 - Maximize the scan/spw/field distribution across sub-MSs
            2 - Generate sub-MSs with similar size
```

- * The 'scan' or 'spw' axes will partition the MS into scan or spw. The individuation to be balanced with respect to the number of rows.
- * The 'baseline' axis is mostly useful for Single-Dish data. This axis will part based on the available baselines. If the user wants only auto-correlations, us antenna selection such as antenna='*&&&' together with this separation axis. I if numsubms='auto', partition will try to create as many subMSs as the number servers in the cluster. If the user wants to have one subMS for each baseline

```
numsubms -- The number of sub-MSs to create.
            default: 'auto'
            Options: any integer number (example: numsubms=4)
               The default 'auto' is to partition using the number of available servers in
               If the task is unable to determine the number of running servers, or the user
              using mpicasa, numsubms will use 8 as the default.
   tileshape -- List with 1 or 3 elements describing the tile shape that will be used
                to save the columns to disk. (list)
        default: [0]
        options: [0] or [1] or [int,int,int]. When list has only one element, it should
                 be either 0 or 1. When the list has three elements, they should be the
                 number of correlations, channels, rows.
--- Data selection parameters ---
    field -- Select field using field id(s) or field name(s).
             [run listobs to obtain the list iof d's or names]
        default: ''=all fields If field string is a non-negative
           integer, it is assumed to be a field index
           otherwise, it is assumed to be a field name
          field='0^2'; field ids 0,1,2
          field='0,4,5~7'; field ids 0,4,5,6,7
          field='3C286,3C295'; fields named 3C286 and 3C295
          field = '3,4C*'; field id 3, all names starting with 4C
    spw -- Select spectral window/channels
        default: ''=all spectral windows and channels
           spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
           spw='<2'; spectral windows less than 2 (i.e. 0,1)
           spw='0:5~61'; spw 0, channels 5 to 61
           spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
           spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
           spw = '*:3~64' channels 3 through 64 for all sp id's
                   spw = ':3^64' will NOT work.
               NOTE: mstransform does not support multiple channel ranges per
                     spectral window (';').
    scan -- Scan number range
       default: ''=all
    antenna -- Select data based on antenna/baseline
```

parameter to a number higher than the number of baselines to achieve this.

```
Non-negative integers are assumed to be antenna indices, and
        anything else is taken as an antenna name.
    examples:
        antenna='5&6': baseline between antenna index 5 and index 6.
        antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8': baselines 5-6 and 7-8
        antenna='5': all baselines with antenna 5
        antenna='5,6,10': all baselines including antennas 5, 6, or 10
        antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                               10. (cross-correlations only. Use &&
                               to include autocorrelations, and &&&
                               to get only autocorrelations.)
        antenna='!ea03,ea12,ea17': all baselines except those that
                                   include EVLA antennas ea03, ea12, or
                                   ea17.
correlation -- Correlation types or expression.
    default: '' (all correlations)
    example: correlation='XX,YY'
timerange -- Select data based on time range:
    default: '' (all); examples,
       timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date, timerange defaults to the
      first day in the dataset
      timerange='09:14:0~09:54:0' picks 40 min on first day
      timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
       timerange='09:44:00' data within one integration of time
      timerange='>10:24:00' data after this time
array -- (Sub)array number range
    default: ''=all
uvrange -- Select data within uvrange (default units meters)
    default: ''=all; example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
        uvrange='0~1000km'; uvrange in kilometers
observation -- Select by observation ID(s)
   default: ''=all
feed -- Selection based on the feed - NOT IMPLEMENTED YET
```

default: '' (all)

default: ''=all

datacolumn -- Which data column to use for processing (case-insensitive).
 default: 'corrected'; example: datacolumn='data'

options: 'data', 'model', 'corrected', 'all', 'float_data', 'lag_data', 'float_data,data', 'lag_data,data'.

NOTE: 'all' = whichever of the above that are present. If the requested column does not exist, the task will exit with an error.

When datacolumn is set to either one of the values 'model', 'all', 'data, model, corrected', a sub-parameter realmodelcol will be enabled. See description below.

realmodelcol -- Make real a virtual MODEL column. If set to True, a real MODEL_DATA column will be added to the output MS based on the existing SOURCE_I column.

default: False

keepflags -- Keep completely flagged rows in the output or drop them. This has no effect on partially flagged rows. All of the channels and correlations of a row must be flagged for it to be droppable, and a row must be well defined to be keepable.

IMPORTANT: Regardless of this parameter, flagged data is never included in channel averaging. On the other hand, partially flagged rows will always be included in time averaging. The average value of the flagged data for averages containing ONLY flagged data in the relevan output channel will be written to the output with the corresponding flag set to True, while only unflagged data is used on averages where there is some unflagged data with the flag set to False.

default: True (keep completely flagged rows in the output)

usewtspectrum -- Create a WEIGHT_SPECTRUM column in the output MS. When set to True, a WEIGHT_SPECTRUM column will be created using the input WEIGHT column such that each channel in the WEIGHT_SPECTRUM will get WEIGHT/nChannels default: False

--- SPW combination parameters --- combinespws -- Combine the input spws into a new output spw.

default: False

NOTE: Whenever the data to be combined has different EXPOSURE values in the spectral windows, mstransform will use the WEIGHT_SPECTRUM for the combination. If WEIGHT_SPECTRUM is not available, it will use the values from the WEIGHT column. Each output channel is calculated using the following equation:

outputChannel_j = SUM(inputChannel_i*contributionFraction_i*inputWeightSpectrum_i)

SUM(contributionFraction_i*inputWeightSpectrum_i)

--- Channel averaging parameters ---

chanaverage -- Average data across channels. Partially flagged data is not be included unless all data contributing to a given output channel is flagged. In the mstransform calculates the average of all flagged data, and writes it to with the corresponding flag set to true. If present, WEIGHT_SPECTRUM/SIGN are used together with the channelized flags (FLAG), to compute a weight (using WEIGHT_SPECTRUM for CORRECTED_DATA and SIGMA_SPECTRUM for DATA).

default: False

chanbin -- Bin width for channel average in number of input channels.

If a list is given, each bin applies to one of the selected SPWs.

default: 1 => no channel averaging.

options: (int) or [int]

example: chanbin=[2,3] => average 2 channels of 1st selected

spectral window and 3 in the second one.

NOTE: WEIGHT_SPECTRUM/SIGMA_SPECTRUM will be used (if present) in addition to the flags to compute a weighted average. The calculations is done as follows:

- 1) When WEIGHT_SPECTRUM/SIGMA_SPECTRUM are not present: Avg = SUM(Chan_i*Flag_i)/SUM(Flag_i)
- --- Hanning smoothing parameters --hanning -- Hanning smooth frequency channel data to remove Gibbs ringing.
 default: False
- --- Regrid parameters --- regridms -- Transform channel labels and visibilities to a different spectral reference

Notice that u, v, w data is not transformed.

default: False

mode -- Regridding mode.

default: 'channel'; produces equidistant grid based on first selected channel. options: 'velocity', 'frequency', 'channel_b'.

When set to velocity or frequency, it means that the channels must be specified in the respective units. When set to channel_b it means an alternative 'channel mode that does not force an equidistant grid. It is faster.

nchan -- Number of channels in the output spw (int). default: -1

start -- First channel to use in the output spw (depends on the mode)
 default: 0 --> when mode='channel'

When mode='channel', 'start' means the first channel in the input spw to use when creating the output spw. When mode='frequency', 'start' means the lowest frequency of the output spw. If this information is not available, leave it blank and mstransform will calculate it.

width -- Width of input channels that are used to create an output channel.
 default: 1

Note that mstransform will only shift spws with channel widths of the same sign in a single operation. If you are regridding spws with mixed positive and negative channel widths, you should run this task separated for each group of spws. You can verify the channel widths for your MS using listobs for example, and looking at the SPW table, column ChanWid.

nspw -- Number of output spws to create in the output MS/MMS (int).
 default: 1 --> it means, do not separate the spws.

One can regrid the MS or not and further separate the output into a given number of spws. Internally, the framework will combine the selected spws before separating them so that channel gaps and overlaps are taken into account. This parameter will create a regular grid of spws in the output MS. If nchan is set, it will refer to the number of output channels in each of the separated spws.

interpolation -- Spectral interpolation method.

default: 'linear'

options: 'nearest', 'cubic', 'spline', 'fftshift'

```
phasecenter -- Direction measure or fieldid. To be used in mosaics to indicate
             the center direction to be used in the spectral coordinate transformation.
          default: '' (first selected field)
          options: FIELD_ID (int) or center coordinate measure (str).
          example: phasecenter=6 or phasecenter='J2000 19h30m00 -40d00m00'
      restfreq -- Specify rest frequency to use for output.
          default: ''; occasionally it is necessary to set this.
          example1 for some VLA spectral line data.
          example2 for NH_3 (1,1) put restfreq='23.694496GHz'.
      outframe -- Output reference frame (case-insensitive).
          default: ''; it will keep the input reference frame.
          options: 'LSRK', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB', 'GEO', 'TOPO'.
      veltype -- Definition of velocity (as used in mode).
          default: 'radio'
-- Time averaging parameters ---
  timeaverage -- Average data across time. Partially flagged data is not be included in tl
                 unless all data contributing to a given output channel is flagged. In the
                 mstransform calculates the average of all flagged data, and writes it to
                 with the corresponding flag set to true. If keepflags=False, the fully fi
                 is not be written to the output MS. If present, WEIGHT_SPECTRUM/SIGMA_SPI
                 are used together with the channelized flags (FLAG), to compute a weighter
                  (using WEIGHT_SPECTRUM for CORRECTED_DATA and SIGMA_SPECTRUM for DATA). (
                 WEIGHT/SIGMA are used instead to average together data from different in
      default: False
      timebin -- Bin width for time average in seconds.
          default: '0s'
      timespan -- Let the timebin span across scan, state or both.
                  State is equivalent to sub-scans. One scan may have several
                  state ids. For ALMA MSs, the sub-scans are limited to about
                  30s duration each. In these cases, the task will automatically
                  add state to the timespan parameter. To see the number of states
                  in an MS, use the msmd tool. See help msmd.
          default: '' (separate time bins by both of the above)
          options: 'scan', 'state', 'state, scan'
          examples:
          timespan = 'scan'; can be useful when the scan number
```

goes up with each integration as in many WSRT MSs.
timespan = ['scan', 'state']: disregard scan and state
 numbers when time averaging.
timespan = 'state,scan'; same as above.

--- On-the-fly calibration parameters --docallib -- Enable on-the-fly (OTF) calibration as in task applycal
default: False

callib -- Path to calibration library file, which is a ascii file containing the parameters to correct the data as task in task applycal, namely gaintable/gainfield/interp/spwmap/calwt. In a Cal Library file, each row expresses the calibration apply instructions for a particular caltable and (optionally) a specific selection of data in the MS to which it is to be applied.

default: '' (there is no default callib file)

examples:

caltable='cal.G' tinterp='linear' calwt=True

-> Arrange a caltable called cal.G to be applied (with no detailed selection) to all MS data with linear interpolation in time, and with the weights also calibrated.

caltable='cal.G' tinterp='linear' fldmap='nearest' spwmap=[0,1,1,3] calwt=True caltable='cal.B' finterp='linear' fldmap='3' spwmap=[0,0,0,0] calwt=False

-> In this case, solutions from cal.G will be selected based on directional proximity ('nearest') for each MS field via the fldmap parameter, and spw 2 will be calibrated by spw 1 solutions. For cal.B, solutions from field id 3 will be used exclusively, with spw 0 calibrating all MS spws.

----- Multi-MS Processing and Heuristics -----

** Input Multi-MS (MMS) **

Task mstransform will process an input MMS in parallel whenever possible. Each sub-MS of the MMS will be processed in a separate engine and the results will be post-processed at end to create an output MMS. The output MMS will have the same separationaxis of the input MMS, which will be written to the table.info file inside the MMS directory.

Naturally, some transformations available in mstransform require more care when the user first partition the MS. If one wants to do a combination of spws by setting the parameter combinespws = True in mstransform, the input MMS needs to contain all the selected spws in each of the sub-MSs or the processing will fail. For this, one may set separationaxis to scan or use the default auto with a proper numsubms set so that each state MMS is self-contained with all the necessary spws for the combination.

The task will check if the sub-MSs contain all the selected spws when combinespws=True and if not, it will issue a warning and process the input MMS as a monolithic MS. In the case, the separation axis of the output MMS will be set to scan, regardless of what the axis was.

A similar case happens when the separation axis of the input MMS is per scan and the use asks to do time averaging with time spanning across scans. If the individual sub-MSs are self-contained of the necessary scans and the duration of the scans is shorter than the timebin, the spanning will not be possible. In this case, the task will process the input a monolithic MS and will set the axis of the output MMS to spw.

It is important that the user sets the separation axis correctly when first partitioning See the table below for when it is possible to process the input MMS in parallel or not mstransform.

input MMS axis	combinespws=True	nspw > 1	timeaverage=True,	timespan='scan'
scan	YES	YES	NO	
spw	NO	NO	YES	
auto	MAYBE	MAYBE	MAYBE	

----- EXAMPLES -----

More documentation on mstransform can be found here: http://www.eso.org/~scastro/ALMA/casa/MST/MSTransformDocs/MSTransformDocs.html

- 1) Split out a single channel.
 mstransform(vis='ctb80-vsm.ms', outputvis='mychn.ms', datacolumn='data', spw='0:25')
- 2) Only combine the selected spws into a single output spw.
 mstransform(vis='Four_ants.ms', outputvis='myspw.ms', combinespws=True, spw='0~3')
- 3) Combine two spws and regrid one field, using two input channels to make one output.

- 4) Combine 24 spws and regrid in frequency mode to create 21 output channels. Change the phase center.
 - mstransform(vis='g19_d2usb_targets_line.ms', outputvis='test2.ms', datacolumn='DATA', combinespws=True, regridms=True, mode='frequency', nchan=21, start='229587.0 width='1600kHz', phasecenter="J2000 18h25m56.09 -12d04m28.20")
- 6) Change the reference frame and apply Hanning smoothing after combining all spws.

 mstransform(vis='g19_d2usb_targets_line.ms', outputvis='test4.ms', datacolumn='DATA',

 combinespws=True, regridms=True, mode="channel", outframe="BARY",

 phasecenter="J2000 18h25m56.09 -12d04m28.20", hanning = True)
- 7) Apply time averaging using a bin of 30 seconds on the default CORRECTED column. mstransform(vis='g19_d2usb_targets_line.ms', outputvis='test5.ms', timeaverage=True, timebin='30s')
- 8) Apply OTF calibration to ng5921 using a calibration library mstransform(vis='ngc5921.ms', outputvis='ngc5921_calibrated.ms',docallib=True, callib='unittest/mstransform/ngc5921_regression/ngc5921_callib.txt')

msuvbin-task.html

0.1.75 msuvbin

Requires:

Synopsis

grid the visibility data onto a defined uniform grid (in the form of an ms); multiple MS's can be done onto the same grid

Description

msuvbin is a uv gridding task. The use is for large volumes of data (from multiple epochs) that needs to be imaged into one image. One way of proceeding is to image the epochs and average them after wards. Rather than doing this averaging the visibilities on a common uv grid has several convenience advantages like easily doing the proper weighted averaging and imaging. If an output grid already exists and a second ms is gridded on the grid then the output grid parameters is ignored but the existant grid is used.

Inputs
vis

Name of input visibility file (MS)
allowed: string

Default:

field Field selection of input ms

allowed: string

Default:

spw Spw selection

allowed: string

Default:

taql TaQl string for data selection

allowed: string

Default:

outvis name of output uvgrid

allowed: string

Default:

phasecenter phase center of uv grid

allowed: string

Default:

nx Number of pixels of grid along the x-axis

allowed: int Default: 1000

ny Number of pixels of grid along the y-axis

allowed: int Default: 1000

cell pixel cell size defined in sky dimension

allowed: string
Default: larcsec

ncorr number of correlations to store in grid

allowed: int Default: 1

nchan Number of spectral channels in grid

allowed: int Default: 1

fstart Frequency of first spectral channel

allowed: string Default: 1GHz spectral channel width

fstep spectral channel width allowed: string

allowed: string
Default: 1kHz

wproject Do wprojection correction while gridding

allowed: bool Default: False

memfrac Limit how much of memory to use

allowed: double Default: 0.5

Returns

void

Example

Keyword arguments:

```
vis -- Name of input visibility file
              default: none; example: vis='ngc5921.ms'
       field -- Field name list
               default: '' ==> all
               field = '1328+307' specifies source '1328+307'
               field = '4' specified field with index 4
       spw -- Spw selection
               default: spw = '' (all spw)
       spw='2'
       taql --TaQl expression for data selection (see http://www.astron.nl/casacore/trunk/o
               default taql=''
       Example select all data where U > 1 \text{ m} in the ms
       taql='UVW[0] > 1'
       outvis -- name of output grid
               default: '' The user has to give something here
       phasecenter -- phasecenter of the grid
               default= ''
                phasecenter='J2000 18h03m04 -20d00m45.1'
      nx -- number of pixels along the x axis of the grid
               default: 1000
       nx = 1200
      ny -- number of pixels along the y axis of the grid
               default: 1000
       ny=1200
       cell -- cellsize of the grid (given in sky units)
               default: 'larcsec'
               cell='0.1arcsec'
ncorr -- number of correlation/polarization plane in uv grid (allowed 1, 2, 4)
               default: 1
               ncorr=4
        nchan -- number of spectral channel
       default: 1
```

nchan=2000

fstart -- frequency of the first channel

default: '1GHz'; User has to give something useful here

fstep -- spectral channel width

default: '1kHz'

wproject -- do wprojection correction while gridding

default: False
wproject=True

memfrac -- control how much of computer's memory is available for gridding

default=0.5
memfrac=0.9

old hanning smooth-task.html

0.1.76 oldhanningsmooth

Requires:

Synopsis

Hanning smooth frequency channel data to remove Gibbs ringing

Description

THISTASKISDEPRECATEDITWILLBEREMOVED SOON

This function Hanning smoothes the frequency channels with a weighted running average. The weights are 0.5 for the central channel and 0.25 for each of the two adjacent channels. The first and last channels are flagged. Inclusion of a flagged value in an average causes that data value to be flagged. If an 'outputvis' filename is given, the task will copy the input file to the output file name first, including all columns that are present in the input MS. After that step it will smooth the column(s) as requested in the 'datacolumn' parameter. Alternatively, if no 'outputvis' is specified, oldhanningsmooth will work directly on the input visibility file. If the 'CORRECTED' data column is requested for an MS that does not contain this column, it will be filled from the 'DATA' column and then smoothed.

WARNING: by default, all visibility columns will be smoothed. This will modify the DATA column of the output MS in order to make sure that later gaincal will work on the smoothed data, e.g. as part of self-cal.

Inputs			
vis	Name of input visibility file (MS)		
	allowed: string		
	Default:		
datacolumn	the name of the MS column into which to write the		
	smoothed data		
	allowed: string		
	Default: all		
outputvis	name of the output visibility file (MS)		
	allowed: string		
	Default:		

Returns

void

Example

oldsplit-task.html

0.1.77 oldsplit

Requires:

Synopsis

Create a visibility subset from an existing visibility set

Description

THISTASKISDEPRECATEDITWILLBEREMOVED SOON

Oldsplit is the general purpose program to make a new data set that is a subset or averaged form of an existing data set. General selection parameters are included, and one or all of the various data columns (DATA, LAG_DATA and/or FLOAT_DATA, and possibly MODEL_DATA and/or CORRECTED_DATA) can be selected.

Oldsplit is often used after the initial calibration of the data to make a smaller measurement set with only the data that will be used in further flagging, imaging and/or self-calibration. Oldsplit can average over frequency (channels) and time (integrations).

Inputs

vis Name of input measurement set

allowed: string

Default:

outputvis Name of output measurement set

allowed: string

Default:

datacolumn Which data column(s) to Oldsplit out

allowed: string

Default: corrected

field Select field using ID(s) or name(s)

allowed: any
Default: variant

spw Select spectral window/channels

allowed: any Default: variant

width Number of channels to average to form one output chan-

nel

allowed: any Default: variant 1

antenna Select data based on antenna/baseline

allowed: any Default: variant

timebin Bin width for time averaging

allowed: string
Default: 0s

timerange Select data by time range

allowed: string

Default:

scan Select data by scan numbers

allowed: string

Default:

intent Select data by scan intents

allowed: string

Default:

array Select (sub)array(s) by array ID number

allowed: string

Default:

uvrange Select data by baseline length

allowed: string

Default:

correlation Select correlations

allowed: any Default: variant

375

observation Select by observation $\mathrm{ID}(\mathbf{s})$

allowed: any Default: variant

combine Let time bins span changes in scan and/or state

allowed: any Default: variant

Example

```
Keyword arguments:
vis -- Name of input visibility file
       default: none; example: vis='ngc5921.ms'
outputvis -- Name of output visibility file
        default: none; example: outputvis='ngc5921_src.ms'
datacolumn -- Which data column to split out
       default='corrected'; example: datacolumn='data'
       Options: 'data', 'model', 'corrected', 'all',
        'float_data', 'lag_data', 'float_data,data', and
        'lag_data,data'.
       N.B.: 'all' = whichever of the above that are present.
        Otherwise the selected column will go to DATA (or
       FLOAT_DATA) in the output.
       Splitting with the default datacolumn='corrected'
       before clean is normally required for self-calibration!
--- Data Selection (see help par.selectdata for more detailed
    information)
field -- Select field using field id(s) or field name(s).
          [run listobs to obtain the list id's or names]
       default: ''=all fields If field string is a non-negative
       integer, it is assumed to be a field index
       otherwise, it is assumed to be a field name
       field='0~2'; field ids 0,1,2
      field='0,4,5~7'; field ids 0,4,5,6,7
       field='3C286,3C295'; fields named 3C286 and 3C295
      field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
       default: ''=all spectral windows and channels
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw = '*:3~64' channels 3 through 64 for all sp id's
               spw = ':3^64' will NOT work.
       Oldsplit does not support multiple channel ranges per spectral
       window (';') because it is not clear whether to keep the ranges
       in the original spectral window or make a new spectral window
```

```
for each additional range.
width -- Defines the number of channel to average to form the one
         output channel.
 default: '1' => no channel averaging
 example: width=[2,3] => average 2 channels of 1st
          spectral window selected and 3 in the second one.
        antenna -- Select data based on antenna/baseline
               default: '' (all)
                Non-negative integers are assumed to be antenna indices, and
                anything else is taken as an antenna name.
                Examples:
                antenna='5&6': baseline between antenna index 5 and index 6.
                antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
                antenna='5\&6;7\&8': baselines 5-6 and 7-8
                antenna='5': all baselines with antenna 5
                antenna='5,6,10': all baselines including antennas 5, 6, or 10
                antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                                       10. (cross-correlations only. Use &&
                                       to include autocorrelations, and &&&
                                       to get only autocorrelations.)
                antenna='!ea03,ea12,ea17': all baselines except those that
                                           include EVLA antennas ea03, ea12, or
                                           ea17.
        timebin -- Interval width for time averaging.
                   default: '0s' or '-1s' (no averaging)
                   example: timebin='30s'
                            '10' means '10s'
        timerange -- Select data based on time range:
               default = '' (all); examples,
               timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
               Note: if YYYY/MM/DD is missing date, timerange defaults to the
               first day in the dataset
               timerange='09:14:0~09:54:0' picks 40 min on first day
               timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
               on next day
               timerange='09:44:00' data within one integration of time
               timerange='>10:24:00' data after this time
        array -- (Sub)array number range
            default: ''=all
uvrange -- Select data within uvrange (default units meters)
            default: ''=all; example:
            uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
            uvrange='>4klambda';uvranges greater than 4 kilo-lambda
            uvrange='0~1000km'; uvrange in kilometers
```

scan -- Scan number range

default: ''=all

intent -- Select by scan intent (state). Case sensitive.

default: '' = all

Examples:

intent = 'CALIBRATE_ATMOSPHERE_REFERENCE'

intent = 'calibrate_atmosphere_reference'.upper() # same as above
Select states that include one or both of CALIBRATE_WVR.REFERENCE
or OBSERVE_TARGET_ON_SOURCE.

intent = 'CALIBRATE_WVR.REFERENCE, OBSERVE_TARGET_ON_SOURCE'

correlation -- Select correlations, e.g. 'rr, ll' or ['XY', 'YX']. default '' (all).

goes up with each integration, as in many WSRT MSes.

combine = 'state,scan': Same as above.

keepflags -- If practical, keep completely flagged rows instead of dropping them. This has absolutely no effect on averaging calculations, or partially flagged rows. All of the channels and correlations of a row must be flagged for it to be droppable, and a row must be well defined to be keepable. The latter condition means that this option has no effect on time averaging - in that case fully flagged rows are automatically omitted. Regardless of this parameter, flagged data is never included in averaging calculations.

The only time keepflags matters is if

1. the input MS has some completely flagged rows

2. time averaging is not being done.

Then, if keepflags is False, the completely flagged rows will be omitted from the output MS. Otherwise, they will be included (subject to the selection parameters).

keepmms -- If true and the input is a multi-MS, make the output one, too.

Otherwise, the output will be a normal MS without partitioning.

(experimental)

Default: False

plotants-task.html

0.1.78 plotants

Requires:

Synopsis

Plot the antenna distribution in the local reference frame:

Description

The location of the antennas in the MS will be plotted with X-toward local east; Y-toward local north.

Arguments

Inputs			
vis	Name of input visibility file (MS)		
	allowed: string		
	Default:		
figfile	Save the plotted figure to this file		
	allowed: string		
	Default:		

Returns

void

Example

Plot the antenna distribution in the local reference frame:

The location of the antennas in the MS will be plotted with X-toward local east; Y-toward local north.

Keyword arguments:
vis -- Name of input visibility file.

default: none. example: vis='ngc5921.ms'

The name of each antenna (egs. vla=antenna number) is shown next to its respective location.

- DO NOT use the buttons on the Mark Region line. These are not implemented yet and might abort CASA.
- You can zoom in by pressing the magnifier button (bottom, third from left) and making a rectangular region with the mouse. Press the home button (left most button) to remove zoom.
- A hard-copy of this plot can be obtained by pressing the button on the right at the bottom of the display. This produces a png format file.

plotbandpass-task.html

0.1.79 plotbandpass

Requires:

Synopsis

Makes detailed plots of Tsys and bandpass solutions.

Description

Developed at the NAASC, this is a generic task to display CASA Tsys and bandpass solution tables with options to overlay them in various combinations, and/or with an atmospheric transmission or sky temperature model. It works with both the 'new' (casa 3.4) and 'old' calibration table formats, and allows for mixed mode spws (e.g. TDM and FDM for ALMA). It uses the new msmd tool to access the information about an ms. This task is still being developed as new ALMA observing modes are commissioned. So if you encounter problems, please report them.

Inputs caltable Input table name, either a ban-

Input table name, either a bandpass solution or a Tsys

solution

allowed: string

Default:

antenna A comma-delimited string list of antennas (either names

or integer indices) for which to display solutions. Default

= all antennas. allowed: any Default: variant

field A comma-delimited string list of fields (either names or

integer indices) for which to display solutions. Default

= all fields.

allowed: any Default: variant

spw A comma-delimited string list of spws for which to dis-

play solutions. Default = all spws.

allowed: any Default: variant

yaxis The quantity to plot on the y-axis ("amp", "phase",

"both", "tsys", append "db" for dB).

allowed: string
Default: amp

xaxis The quantity to plot on the x-axis ("chan" or "freq").

allowed: string
Default: chan

figfile The name of the plot file to produce.

allowed: string

Default:

plotrange The axes limits to use [x0,x1,y0,y1].

allowed: doubleArray
Default: 0.0.0.0

caltable2 A second cal table, of type BPOLY or B, to overlay on

a B table

allowed: string

Default:

overlay Show multiple solutions in same frame in different colors

(time, antenna, spw, baseband, or time, antenna)

allowed: string

Default:

showflagged Show the values of the solution, even if flagged

allowed: bool Default: False

timeranges Show only these timeranges, the first timerange being 0

383 allowed: string

Default:

buildpdf If True, assemble all the pngs into a pdf

allowed: bool
Default: False

caltable3 A third cal table, of type BPOLY, to overlay on the first

two tables

allowed: string

Default:

Returns

variant

Example

This task returns void unless the channeldiff option is selected, in which case it returns a dictionary containing the statistics of the solutions, keyed by the antenna name, followed by the spw, timerange, polarization, and finally 'amp' and/or 'phase' depending on the yaxis selection.

Keyword arguments:

```
antenna: must be either an ID (int or string or list), or a single antenna name or list
basebands: show only spws from the specified baseband or list of basebands (default: ''=[]:
buildpdf: True/False, if True and figfile is set, assemble pngs into a pdf
caltable: a bandpass table, of type B or BPOLY
caltable2: a second cal table, of type BPOLY or B, to overlay on a B table
caltable3: a third cal table, of type BPOLY, to overlay on the first two
channeldiff: set to value > 0 to plot derivatives of amplitude, the value is also used as
chanrange: set xrange (e.g. "5~100") over which to autoscale y-axis for xaxis='freq'
chanrangeSetXrange: if True, then chanrange also sets the xrange to display
convert: full path for convert command (in case it's not found)
density: dpi to use in creating PNGs and PDFs (default=108)
edge: the number of edge channels to ignore in finding outliers (for channeldiff>0)
field: must be an ID, source name, or list thereof; can use trailing *: 'J*'
figfile: the base_name of the png files to save: base_name.antX.spwY.png
figfileSequential: naming scheme, False: name by spw/antenna (default)
                   True: figfile.1.png, figfile.2.png, etc.
gs: full path for ghostscript command (in case it's not found)
interactive: if False, then figfile will run to completion automatically
lo1: specify the LO1 setting (in GHz) for the observation
overlay: 'antenna', 'time', 'spw', or 'baseband', make 1 plot with different items in colors
markersize: size of points (default=3)
```

```
ms: name of the ms for this table, in case it does not match the string in the caltable
parentms: name of the parent ms, in case the ms has been previously split
pdftk: full path for pdftk command (in case it's not found)
phase: the y-axis limits to use for phase plots when yaxis='both'
platformingSigma: declare platforming if the amplitude derivative exceeds this many times
platformingThreshold: if platformingSigma=0, then declare platforming if the amplitude
                      derivative exceeds this percentage of the median
plotrange: define axis limits: [x0,x1,y0,y1] where 0,0 means auto
poln: polarizations to plot (e.g. 'XX', 'YY', 'RR', 'LL' or '' for both)
pwv: define the pwv to use for the showatm option: 'auto' or value in mm
resample: channel expansion factor to use when computing MAD of derivative (for channeldif:
scans: show only solutions for the specified scans (int, list, or string)
showatm: compute and overlay the atmospheric transmission curve (on B or Tsys solutions)
showatmfield: use first observation of this fieldID or name
showatmPoints: draw atmospheric curve with points instead of a line
showBasebandNumber: put the BBC_NO in the title of each plot
showfdm: when showing TDM spws with xaxis='freq', draw locations of FDM spws
showflagged: show the values of data, even if flagged
showimage: also show the atmospheric curve for the image sideband (in black)
showtsky: compute and overlay the sky temperature curve instead of transmission
showlines: draw lines connecting the data (default=T for amp, F for phase)
showpoints: draw points for the data (default=F for amp, T for phase)
solutionTimeThresholdSeconds: consider 2 solutions simultaneous if within this interval (de
spw: must be single ID or list or range (e.g. 0~4, not the original ID)
subplot: 11..81,22,32 or 42 for RowsxColumns (default=22), any 3rd digit is ignored
timeranges: show only these timeranges, the first timerange being 0
xaxis: 'chan' or 'freq'
yaxis: 'amp', 'tsys', 'phase', or 'both' amp+phase == 'ap'. Append 'db' for dB
zoom: 'intersect' will zoom to overlap region of caltable with caltable2
```

plotcal-task.html

0.1.80 plotcal

Requires:

Synopsis

An all-purpose plotter for calibration results

Description

An all-purpose plotter for calibration results. The values for all calibration solutions (G, T, GSPLINE, B, BPOLY, D) can be displayed for a variety of polarization combinations and calibrations. The solutions may be iterated through antennas/spw/fields during one execution.

Inputs caltable Name of input calibration table allowed: string Default: Value xaxis toplot along (time,chan,freq, Х axis antenna, antenna1, antenna2, scan, amp,phase,real,imag,snr, tsys,delay,spgain) allowed: string Default: yaxis Value to plot along y axis (amp,phase,real,imag,snr, antenna,antenna1,antenna2,scan, tsys,delay,spgain,tec) allowed: string Default: poln Antenna polarization to plot (RL,R,L,XY,X,Y,/) allowed: string Default: field field names or index of calibrators: "==>all allowed: string Default: antenna/baselines: "==>all, antenna = '3,VA04' antenna allowed: string Default: spectral window:channels: "==>all, spw='1:5~57' spw allowed: string Default: time range: "==>all timerange allowed: string Default: subplot Panel number on display screen (yxn) allowed: int Default: 111 Overplot solutions on existing display overplot allowed: bool Default: False clearpanel Specify if old plots are cleared or not (ignore) allowed: string Default: Auto iteration Iterate plots on antenna, time, spw, field allowed: string Default: plotrange plot axes ranges: [xmin,xmax,ymin,ymax] allowed: doubleArray Default: If true, show flagged solutions showflags allowed: bool Default: False plotsymbol pylab plot symbol allowed: stging Default: O plotcolor initial plotting color allowed: string Default: blue

Size of plotted marks

Font size for labels

double

5.0

allowed:

Default:

markersize

fontsize

Returns

void

Example

The values for all calibration solutions (G, T, GSPLINE, B, BPOLY, D, M) can be displayed for a variety of polarization combinations and calibrations. The plot solutions may be iterated through antennas/spw/fields during one execution and many frames can be obtained in each plot.

The plotter permits zooming, listing and flagging of solutions, although the results of flagged solutions are not yet available.

The plotter permits zooming, listing and flagging of solutions, although the implications of flagged solutions are not yet made. See some hints at the end of this description.

```
Keyword arguments:
caltable -- Name of input calibration table
default: none; example: caltable='ngc5921.gcal'
        The type of calibration table is determined automatically.
xaxis -- Value to plot on the x axis
Options: 'time', 'scan', 'chan', 'freq', 'antenna', 'amp', 'phase', 'real', 'imag', 'snr'
Default: cal type dependent, usually 'time'
yaxis -- Value to plot on the y-axis
Options: 'amp','phase','real','imag','snr','antenna','tsys','delay','spgain'
Default: cal type dependent, usually 'amp'
poln -- Polarization (or combination) to plot
        default: '' (RL); all polarizations
Options: '' = ('RL'), 'R', 'L', 'XY', 'X', 'Y',
               '/' --> form complex poln ratio
             (amp ratio and phase difference)
field -- Select field using field id(s) or field name(s).
                  ['go listobs' to obtain the fieldt id's or names]
               default: ''=all fields
               If field string is a non-negative integer, it is assumed a
       field index, otherwise it is assumed a field name
               field='0~2'; field ids 0,1,2
               field='0,4,5~7'; field ids 0,4,5,6,7
```

```
field='3C286,3C295'; field named 3C286 and 3C295
               field = '3,4C*'; field id 3, all names starting with 4C
antenna -- Antenna selection (baseline syntax ignored)
               default: '' (all);
               example: antenna='1,3~5' means antenna
                  indices 1,3,4,5.
spw -- Select spectral window (channel syntax ignored, except for D)
               default: ''=all spectral windows
               spw='0~2,4'; spectral windows 0,1,2,4
               spw='<2'; spectral windows less than 2
timerange -- Time selection
                  default: '' (all)
  example: timerange='1995/04/13/09:15:00~1995/04/13/09:25:00'
--- Plot Options ---
subplot -- Panel number on the display screen
               default: 111 (full screen display);
               examples:
               if iteration = 'antenna'; subplot=321 then
                  a plot frame will contain the first 6 antennas, in three
                  rows and two columns. Follow instructions on screen to
                  cycle through the frames
               if iteration = ''; then one frame can be filled with many
                  plots in a piecemeal fashion; for example
                  antenna='0'; subplot=221; plotcal()
                  antenna='1'; subplot=222; plotcal()
                  antenna='2'; subplot=223; plotcal()
                  antenna='3'; subplot=224; plotcal()
overplot -- Overplot these values on current plot (if possible)
               default: False;
          True (overplotting) can be done ONLY IF iteration=''
clearpanel -- Ignore this parameter.
                  Clear nothing on the plot window, automatically
          clear plotting area, clear the current plot area, or
          clear the whole plot panel.
       options: None, Auto, Current, All (None and Auto not supported)
       default: Auto
       example: clearpanel='Current'
iteration -- Create a sequence of plots, iterating over antenna, time,
                 field, and/or spw
               default: '' --> create in all in one plot
       example: iteration='antenna' --> create a sequence of
                separate plots separated by antenna. Flagging cannot
                be done in iteration mode.
plotrange -- Control the x and y ranges of the plot, as a list of
                 values, e.g., [xmin,xmax,ymin,ymax]
```

```
default=[] --> plot will self-scale
 Note: time plotting ranges are cumbersome to use.
                       Use the zoom option
showflags -- If true, only flagged solutions will be plotted
        default: false --> only show unflagged solutions
plotsymbol -- pylab plot symbol. See cookbook for details
                   default: '.': large points
                   ',' = small points (see markersize)
                   '-' = connect points by line
                   colors are cycled automatically for multi-function plots
plotcolor -- Initial color to use on each plot
                 default: 'blue'
markersize -- Control the size of plot symbols
                  default: 5.0 --> a nice size for symbols
fontsize -- Control the font size of title (axes labels will be
          80% of this size)
                  default: 10.0
showgui -- Whether or not to display the plotting GUI
          default: True; example showgui=False
        figfile -- File name to save the plotted figure to.
          default: ''; example figfile=myPlot.png
        Hints on using plotxy (see section 3.4 in cookbook)
        Useful Buttons at bottom left:
              5th--magnifying glass. Click on this,
                       left mouse button rectangle drag will zoom
                       right mose button rectangle drag will unzoom a certain amount
              1st--restore original magnification
        Useful regions just above:
              Quit will terminate plotter
              Next will go to next plot as specified by iteration
              To locate, you must click 'Mark Region' first
                 then make appropriate region(s)
                 then click locate to list points on logger
                 DO NOT USE Flag, Unflag at the present time.
```

plotms-task.html

0.1.81 plotms

Requires:

Synopsis

A plotter/interactive flagger for visibility data.

Description

Task for plotting and interacting with visibility data. Limited support for caltable plotting is also included as of CASA v4.1.

A variety of axes choices (including data column) along with MS selection and averaging options are provided for data selection. Flag extension parameters are also available for flagging operations in the plotter.

All of the provided parameters can also be set using the GUI once the application has been launched. Additional and more specific operations are available through the GUI and/or through the plotms tool (pm).

Most basic functions (plotting, iteration, locate, flagging) will work for most CalTables. Parameterized CalTables (delays, antpos, gaincurve, opacity), will, at best, currently just plot the simple parameters contained in the table, not the effective amplitudes or phases sampled at observing times, frequencies etc. BPOLY and GSPLINE tables are not yet supported. Features currently unsupported for CalTables include Averaging, Transformations (velocity conversions, etc.), and some details of selection (channel and polarization selection are not yet enabled) and axes choices (geometry options are not yet enabled). In the plotms gui, many options irrelevant for CalTables are not yet hidden when interacting with a CalTable, and such settings will be ignored (when benign) or cause an error message.

Inputs

vis input MS (or CalTable) (blank for none)

allowed: string

Default:

gridrows Number of subplot rows (default 1).

allowed: int Default: 1

gridcols Number of subplot columns (default 1).

allowed: int Default: 1

rowindex Row location of the plot (0-based, default 0)

allowed: in Default: 0

colindex Column location of the plot (0-based, default 0)

allowed: int Default: 0

plotindex Index to address a subplot (0-based, default 0)

allowed: int Default: 0

xaxis plot x-axis (blank for default/current)

allowed: string

Default:

xdatacolumn data column to use for x-axis (blank for default/current)

allowed: string

Default:

yaxis plot y-axis (blank for default/current)

allowed: any Default: variant

ydatacolumn data column to use for y-axis (blank for default/current)

allowed: any Default: variant

yaxislocation whether to use a left or right y-axis for the data (blank

for default)

allowed: any Default: variant

selectdata data selection parameters

allowed: bool Default: True

field field names or field index numbers (blank for all)

allowed: string

Default:

spw spectral windows:channels (blank for all)

allowed: string

Default:

timerange time range (blank for all)

allowed: string

Default:

uvrange uv range (blank for all)

allowed: string

Default:

antenna antenna/baselines (blank for all)

allowed: string

Default:

Returns

void

Example

Task for plotting and interacting with visibility data. Limited support for caltable plotting is also included as of CASA v4.1.

A variety of axes choices (including data column) along with MS selection and averaging options are provided for data selection. Flag extension parameters are also available for flagging operations in the plotter.

All of the provided parameters can also be set using the GUI once the application has been launched. Additional and more specific operations are available through the GUI and/or through the plotms tool (pm).

Most basic functions (plotting, iteration, locate, flagging) will work for most CalTables. Parameterized CalTables (delays, antpos, gaincurve, opacity), will, at best, currently just plot the simple parameters contained in the table, not the effective amplitudes or phases sampled at observing times, frequencies etc. BPOLY and GSPLINE tables are not yet supported. Features currently unsupported for CalTables include Averaging, Transformations (velocity conversions, etc.), and some details of selection (channel and polarization selection are not yet enabled) and axes choices (geometry options are not yet enabled). In the plotms gui, many options irrelevant for CalTables are not yet hidden when interacting with a CalTable, and such settings will be ignored (when benign) or cause an error message.

```
rowindex -- Row location of the subplot (0-based).
                default: 0
colindex -- Column location of the subplot (0-based).
                default: 0
plotindex -- Index to address a subplot (0-based).
default: 0
xaxis, yaxis -- what to plot on the two axes
                default: '' (defaults are xaxis='time',
                             yaxis='amp' on first execution;
                             thereafter the most recent
                             settings are used)
          valid options (=indicates valid synonyms):
           MS Ids and other meta info:
             'scan'
                      (number)
             'field'
                      (index)
             'time',
             'interval'='timeint'='timeinterval'='time_interval'
             'spw'
                      (index)
             'chan'='channel'
                                 (index)
             'freq'='frequency' (GHz)
             'vel'='velocity'
                                (km/s)
             'corr'='correlation' (index)
             'ant1'='antenna1'
                               (index)
                                 (index)
             'ant2'='antenna2'
             'baseline' (a baseline index)
                   (absoute row Id from the MS)
             'observation' (index)
                           (index)
             'intent'
                           (index)
             'feed1'
             'feed2'
                           (index)
           Visibility values, flags:
             'amp'='amplitude'
             'phase' (deg)
             'real'
             'imag'='imaginary'
             'wt'='weight' (unchannelized)
             'wtsp'='weightspectrum'
             'flag'
             'flagrow'
           Observational geometry:
             'uvdist' (meters)
             'uvwave'='uvdistl'='uvdist_l' (wavelengths, per channel)
             'u' (meters)
             'v' (meters)
             'w' (meters)
             'uwave' ('u' in wavelengths, per channel)
```

```
'vwave' ('v' in wavelengths, per channel)
             'wwave' ('w' in wavelengths, per channel)
             'azimuth' (at array reference; degrees)
             'elevation' (at array reference; degrees)
             'hourang'='hourangle' (at array reference; hours)
             'parang'='parangle'='parallacticangle' (at array reference; degrees)
           Antenna-based (only works vs. data Ids):
             'ant'='antenna'
             'ant-azimuth'
             'ant-elevation'
             'ant-parang'='ant-parangle'
           Calibration:
             'gainamp'='gamp'
             'gainphase'='gphase'
             'gainreal'='greal'
             'gainimag'='gimag'
             'delay'='del'
             'opacity'='opac'
             'swpower'='swp'='switchedpower'
 >>> xaxis, yaxis expandable parameters
   xdatacolumn,
   ydatacolumn -- which data column to use for Visibility values:
                    default: '' ('data' on first execuation;
                                 thereafter the most recent
                                 setting is used)
                    valid options: 'data'
                                                (observed)
                                    'corrected'='corr'
                                    'model'
                                    'residual' (aliases 'corrected-model')
                                    'corrected-model'
                                    'data-model'
                                    'float'
selectdata -- data selection parameters flag
             default: True (reveals data selection parameters
                              described below)
             Consult listobs output for data selection values,
              and see help par.selectdata for more detailed
              information on syntax; also, visit
             http://casa.nrao.edu/other_doc.shtml and click
              on "Measurement Set selection syntax" for more
             tips on using data selection parameters in CASA)
 >>> selectdata expandable parameters:
```

```
field -- Select field using field id(s) or field name(s).
        default: ''=all fields
        If field string is a non-negative integer, it is assumed a
          field index, otherwise, it is assumed a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5^{\sim}7'; field ids 0,4,5,6,7
        field='3C286,3C295'; field named 3C286 and 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
         type 'help par.selection' for more examples.
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61, INCLUSIVE
       spw='*:5~61'; all spw with channels 5 to 61
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                 NOTE ';' to separate channel selections
timerange -- Select data based on time range:
        default = '' (all); examples,
        timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
        Note: if YYYY/MM/DD is missing date defaults to first day in data set
        timerange='09:14:0~09:54:0' picks 40 min on first day
        timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on NEXT day
        timerange='09:44:00' pick data within one integration of time
        timerange='>10:24:00' data after this time
uvrange -- Select data within uvrange (default units meters)
        default: '' (all); example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo lambda
antenna -- Select data based on antenna/baseline
        default: '' (all, including auto-correlations, if present)
        If antenna string is a non-negative integer, it is assumed an
          antenna index, otherwise, it is assumed as an antenna name
        antenna='5&6'; baseline between antenna index 5 and index 6.
        antenna='!ea02'; exclude EVLA antenna 2.
        antenna='ea13;!ea22'; EVLA antenna 13, excluding antenna 22.
        antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8'; baselines with indices 5-6 and 7-8
        antenna='5'; all baselines with antenna index 5
        antenna='05'; all baselines with antenna number 05 (VLA old name)
        antenna='5,6,10'; all baselines with antennas 5,6,10 index numbers
        NB: For explicit selections, use a single ampersand (&) to
```

```
select only cross-correlations among the specified antennas,
         double ampersands (&&) to select cross- and
         auto-correlations among the specified antennas, and
         triple ampersands (&&&) to select only
         auto-correlations. E.g.:
         antenna='*&'; selects all cross-correlation baseline
                        (excludes all auto-correlations)
         antenna='*&&&'; selects all auto-correlation baselines
                          (excludes all cross-correlations)
         antenna='1&&1,2,3'; selects baselines 1-1 (auto), 1-2,1-3 (cross)
         antenna='VA05&&&'; selects the VA05 autocorrelation
         See the link noted above for more information.
 scan -- Scan numbers or ranges.
         default: '' (all scans)
         scan='1,2,6,43'; scans 1, 2, 6, and 43
         scan='3~14'; scans 3 through 14, inclusive
 correlation -- Select by correlation
                default: '' (all correlations)
                 options: 'RR', 'RL', 'LR', 'LL', 'XX', 'XY', 'YX', 'YY',
                           or any comma-separated combination; use
                           basis (R/L or X/Y) appropriate to the MS)
 array -- Select the array id
          default: '' (all array ids)
 observation -- Select by observation ID(s).
                 default: ''-->all;
                 observation='0' (select obsID 0)
 intent -- Select observing intent
           default: '' (no selection by intent)
           intent='*BANDPASS*' (selects data labelled with
               BANDPASS intent)
 feed -- Select by feed IDs
         default: '' (all feeds)
         feed='1~2'
 msselect -- Optional TaQL data selection
averagedata -- data averaging parameters flag
                              (reveals expandable parameters
              default: True
                                described below)
 >>> averagedata expandable parameters
   avgchannel -- average over channel? either blank for none, or a value
                  in channels.
                  default: '' (no channel averaging).
   avgtime -- average over time? either blank for none, or a value in
              seconds.
              default: '' (no time averaging).
   avgscan -- average over scans? only valid if time averaging is turned
```

```
on.
               default: False.
    avgfield -- average over fields? only valid if time averaging is
                turned on.
                default: False.
    avgbaseline -- average over selected baselines; mutually
                   exclusive with avgantenna.
                   default: False. (no averaging over baseline)
    avgantenna -- form per-antenna averages; mutually exclusive with
                  avgbaseline.
                  default: False.
                                    (no per-antenna averaging)
    avgspw -- average over selected spectral windows?
              default: False. (no average of spectral windows)
    scalar -- scalar averaging?
              default: False (i.e., do vector averaging)
transform -- apply various transformations on data for plotting
             default: False.
  >>> transform expandable parameters
    freqframe -- the coordinate frame in which to render frequency and velocity axes
             default: '' (unspecified: will use frame in which data were taken)
             options: TOPO, GEO, BARY, LSRK, LSRD
    restfreq -- the rest frequency to use in velocity conversions (MHz)
             default: '' (use spw central frequency and show relative velocity)
             example: '22235.08MHz'
    veldef -- the velocity definition to use
             default: 'RADIO'
             options: 'RADIO','OPT','TRUE'
    shift -- adjust phase according to a phase center shift [dx,dy] (arcsec)
             NB: the phase shift in plotms is an approximate transformation
             default: [0,0] (no shift)
extendflag -- have flagging extend to other data points?
              default: False.
  >>> extendflag expandable parameters
    extcorr -- extend flags based on correlation?
               default: False.
    extchannel -- extend flags based on channel?
iteraxis -- axis upon which iterate plots (one plot per page, for now)
            default: '' (no iteration)
            options: 'scan', 'field', 'spw', 'baseline', 'antenna', 'time', ''
  >>> iteraxis expandable parameters
   xselfscale -- If true, iterated plots should share a common x-axis label per column
    yselfscale -- If true, iterated plots should share a common y-axis label per row.
                  default: false, which will scale all plots globally
```

```
xsharedaxis -- If true, iterated plots should share a common x-axis (must also set
       default: false, each plot will have its own x-axis.
    ysharedaxis -- If true, iterated plots should share a common y-axis (must also set
       default: false, each plot will have its own y-axis.
customsymbol -- If true, use a custom symbol for drawing unflagged points
                default: False
  >>> customsymbol expandable parameters
    symbolshape -- If true, use a custom shape to draw unflagged symbols
                   default: 'autoscaling' (ignores symbolsize)
                   options: 'autoscaling', 'circle', 'square', 'diamond', 'pixel', 'nos
    symbolsize -- size of the unflagged symbols in pixels
                 default: 2
    symbolcolor -- color to use for unflagged symbols; can be a RGB hex code or a color
                   default: '0000ff'
                   example: 'purple'
    symbolfill -- type of fill to use for unflagged symbols
                  default: 'fill'
                  options: 'fill', 'mesh1', 'mesh2', 'mesh3', 'nofill'
    symboloutline -- If true, outline unflagged symbols in black
coloraxis -- axis upon which to colorize the plotted points
            options (= indicates synonyms):
                'scan', 'field', 'spw', 'antenna1'='ant1', 'antenna2'='ant2',
                'baseline', 'channel'='chan', 'corr'='correlation', 'time',
                'observation', 'intent'
            default: '' (use a single color for all points)
customflaggedsymbol -- If true, use a custom symbol for drawing flagged points
                       default: False
  >>> customflaggedsymbol expandable parameters
    symbolshape -- If true, use a custom shape to draw flagged symbols
                   default: 'nosymbol'
                   options: 'autoscaling', 'circle', 'square', 'diamond', 'pixel', 'nos
    symbolsize -- size of the flagged symbols in pixels
                 default: 2
    symbolcolor -- color to use for flagged symbols; can be a RGB hex code or a color na
                   default: '0000ff'
                   example: 'purple'
    symbolfill -- type of fill to use for flagged symbols
                  default: 'fill'
                  options: 'fill', 'mesh1', 'mesh2', 'mesh3', 'nofill'
    symboloutline -- If true, outline flagged symbols in black
plotrange -- manual plot axis ranges: [xmin,xmax,ymin,ymax]
             Does not affect data selection.
```

```
default: []; both axes will be autoscaled according
             to the ranges found in the selected data
             If xmin=xmax (or ymin=ymax) then that axis will
             be autoscaled, e.g.:
             [0,0,-2.0,14.0]; autoscale the xaxis, and use
                              ymin=-2.0, ymax=14.0
title -- title along top of plot (called "canvas" in some places)
xlabel -- text to label horizontal axis, with formatting using '%%'
ylabel -- text to label horizontal axis, with formatting using '%%'
showmajorgrid -- show major grid lines (horiz and vert.)
              default: False
  >>> showmajorgrid expandable parameters
    majorwidth -- line width in pixels of major grid lines
    majorstyle -- major grid line style: solid dash dot none
    majorcolor -- color in hex code of major grid lines
showminorgrid -- show minor grid lines (horiz and vert.)
              default: False
  >>> showminorgrid expandable parameters
    minorwidth -- line width in pixels of minor grid lines
    minorstyle -- minor grid line style: solid dash dot none
    minorcolor -- color in hex code of minor grid lines
plotfile -- name of plot file to save automatically
            default: '' (i.e., draw an interactive plot in the gui)
  >>> plotfile expandable parameters
    expformat -- export format type; if 'txt' is used an ASCII dump of the plotted point
                 default: '' (plotfile extension will be used)
                 options: 'jpg', 'png', 'ps', 'pdf', 'txt'
    exprange -- pages to export for iteration plots
     default:
     options: 'current', 'all'
    highres -- use high resolution in exported plot
               default: False (use screen resolution)
    dpi -- DPI of exported plot
           default: -1 (not set)
    width -- width of exported plot
            default: -1 (not set)
    height -- height of exported plot
             default: -1 (not set)
    overwrite -- overwrite plot file if it already exists
                 default: False
```

callib -- calibration library string, list of strings, or filename
 default: ''

showgui - Whether or not to display the plotting GUI default: True $\,$

plotuv-task.html

plotuv 0.1.82

Requires:

Synopsis
Plot the baseline distribution

Description

Plots the selected baselines of vis one field at a time, in kilowavelengths.

vis Name of input visibility file (MS)

allowed: string

Default:

field Select field using ID(s) or name(s)

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: any Default: variant

spw Select spectral window/channels

allowed: any Default: variant

observation Select by observation ID(s)

allowed: any Default: variant

array Select (sub)array(s) by array ID number

allowed: any Default: variant

maxnpts Maximum number of points per plot.

allowed: int Default: 100000

colors a list of matplotlib color codes

allowed: stringArray
Default: r y g b

symb A matplotlib plot symbol code

allowed: string

Default:

ncycles How many times to cycle through colors per plot.

allowed: int Default: 1

figfile Save the plotted figure(s) using this name

allowed: string

Default:

Returns

bool

Example

Plots the uv coverage of vis in klambda. ncycles of colors will be allocated to representative wavelengths. Keyword arguments: vis -- Name of input visibility file default: none; example: vis='ngc5921.ms' --- Data Selection (see help par.selectdata for more detailed information) field -- Select field using field id(s) or field name(s). [run listobs to obtain the list IDs or names] default: ''=all fields. If field is a non-negative integer, it is assumed to be a field index. Otherwise, it is assumed to be a field name field='0~2'; field ids 0,1,2 field='0,4,5 $^{\sim}$ 7'; field ids 0,4,5,6,7 field='3C286,3C295'; fields named 3C286 and 3C295 field = '3,4C*'; field id 3, all names starting with 4C antenna -- Select data based on antenna/baseline default: '' (all) Non-negative integers are assumed to be antenna indices, and anything else is taken as an antenna name. Examples: antenna='5&6': baseline between antenna index 5 and index 6. antenna='VA05&VA06': baseline between VLA antenna 5 and 6. antenna='5&6;7&8': baselines 5-6 and 7-8 antenna='5': all baselines with antenna 5 antenna='5,6,10': all baselines including antennas 5, 6, or 10 antenna='5,6,10&': all baselines with *only* antennas 5, 6, or 10. (cross-correlations only. Use && to include autocorrelations, and &&& to get only autocorrelations.) antenna='!ea03,ea12,ea17': all baselines except those that include EVLA antennas ea03, ea12, or ea17. spw -- Select spectral windows. Channel selection is ignored for now. default: ''=all spectral windows spw='0~2,4'; spectral windows 0,1,2,4 spw='<2'; spectral windows less than 2 (i.e. 0,1) spw='0'; spw 0

Example: if figfile is 'test.png', and field is '1,2,4', the plots

figfile -- If not '', save the plots using names based on figfile.

will be saved to test_fld1.png, test_fld2.png,

and test_fld4.png.

default: '' (Do not save)

plotweather-task.html

0.1.83 plotweather

Requires:

Synopsis

Plot elements of the weather table; estimate opacity.

Arguments

Inputs vis MS name

allowed: string

Default:

seasonal_weight weight of the seasonal model

allowed: double Default: 0.5

doPlot set this to True to create a plot

allowed: bool

Default: True

plotName (Optional) the name of the plot file

allowed: string

Default:

Example

Generates opacity estimates from both the weather data and a seasonal model; intended for VI By default the returned opacity is the mean of these predictions, but this can be adjusted to

These methods and models are described in detail in EVLA Memo 143, VLA Test Memo 232, VLA Se

Saves the plot to the following default file: MS name + .plotweather.png Custom plot filenames must end in one of: .png, .pdf, .ps, .eps or .svg

If run as a function, will return the mean zenith opacity per spectral window.

The wind direction is defined as the direction where the wind is coming from. The wind direction is thus in the opposite side of the arrow, with north at the top and counterclockwise through west, south, and east.

```
Written by Josh Marvil, revised 02/06/12
example:
myTau = plotweather(vis='myMS.ms',seasonal_weight=0.5, doPlot=True)
```

partition-task.html

0.1.84 partition

Requires:

Synopsis

Task to produce Multi-MSs using parallelism

Description

Partition is a task to create a Multi-MS out of an MS. General selection parameters are included, and one or all of the various data columns (DATA, LAG_DATA and/or FLOAT_DATA, and possibly MODEL_DATA and/or CORRECTED_DATA) can be selected.

The partition task creates a Multi-MS in parallel, using the CASA MPI framework. The user should start CASA as follows in order to run it in parallel.

- 1) Start CASA on a single node with 8 engines. The first engine will be used as the MPIClient, where the user will see the CASA prompt. All other engines will be used as MPIServers and will process the data in parallel. mpicasa -n 8 casa -nogui -log2term partition(.....)
- 2) Running on a group of nodes in a cluster. mpicasa -hostfile user_hostfile casa partition(.....)

where user_hostfile contains the names of the nodes and the number of engines to use in each one of them. Example: pc001234a, slots=5 pc001234b, slots=4 If CASA is started without mpicasa, it is still possible to create an MMS, but the processing will be done in sequential.

A multi-MS is structured to have a reference MS on the top directory and a sub-directory called SUBMSS, which contain each partitioned sub-MS. The reference MS contains links to the sub-tables of the first sub-MS. The other sub-MSs contain a copy of the sub-tables each. A multi-MS looks like this in disk.

ls ngc5921.mms ANTENNA FLAG_CMD POLARIZATION SPECTRAL_WINDOW table.dat DATA_DESCRIPTION HISTORY PROCESSOR STATE table.info FEED OBSERVATION SORTED_TABLE SUBMSS WEATHER FIELD POINTING SOURCE SYSCAL ls ngc5921.mms/SUBMSS/ngc5921.0000.ms/ngc5921.0002.ms/ngc5921.0004.ms/ngc5921.0006.ms/ngc5921.0001.ms/ngc5921.0003.ms/ngc5921.0005.ms/

Inside casapy, one can use the task list partition to list the information from a multi-MS. When partition processes an MMS in parallel, each sub-MS is processed independently in an engine. The log messages of the engines are identified by the string MPIServer-#, where # gives the number of the engine running that process. When the task runs sequentially, it shows the MPIClient text in the origin of the log messages or does not show anything.

vis Name of input measurement set

allowed: string

Default:

outputvis Name of output measurement set

allowed: string

Default:

createmms Should this create a multi-MS output

allowed: bool Default: True

separationaxis Axis to do parallelization across(scan, spw, baseline,

auto)

allowed: string
Default: auto

numsubms The number of SubMSs to create (auto or any number)

allowed: any

Default: variant auto

flagbackup Create a backup of the FLAG column in the MMS.

allowed: bool Default: True

datacolumn Which data column(s) to process.

allowed: string Default: all

field Select field using ID(s) or name(s).

allowed: any Default: variant

spw Select spectral window/channels.

allowed: any
Default: variant

scan Select data by scan numbers.

allowed: any Default: variant

antenna Select data based on antenna/baseline.

allowed: any Default: variant

correlation: " ==> all, correlation='XX,YY'.

allowed: any Default: variant

timerange Select data by time range.

allowed: any Default: variant

intent Select data by g can intent.

allowed: any Default: variant

array Select (sub)array(s) by array ID number.

allowed: any Default: variant

uvrange Select data by baseline length.

Example

---- Detailed description of keyword arguments ----

```
vis -- Name of input visibility file
    default: none; example: vis='ngc5921.ms'
outputvis -- Name of output visibility file
    default: none; example: outputvis='ngc5921.mms'
createmms -- Create a multi-MS as the output.
    default: True
    If False, it will work like the split task and create a
    normal MS, split according to the given data selection parameters.
    Note that, when this parameter is set to False, a cluster
    will not be used.
    separationaxis -- Axis to do parallelization across.
        default: 'auto'
        Options: 'scan', 'spw', 'baseline', 'auto'
        * The 'auto' option will partition per scan/spw to obtain optimal load balancing
         following criteria:
           1 - Maximize the scan/spw/field distribution across sub-MSs
           2 - Generate sub-MSs with similar size
        * The 'scan' or 'spw' axes will partition the MS into scan or spw. The individua
        not be balanced with respect to the number of rows.
        * The 'baseline' axis is mostly useful for Single-Dish data. This axis will part
          based on the available baselines. If the user wants only auto-correlations, us
          antenna selection such as antenna='*&&&' together with this separation axis. I
          if numsubms='auto', partition will try to create as many submSs as the number
          servers in the cluster. If the user wants to have one subMS for each baseline
          parameter to a number higher than the number of baselines to achieve this.
    numsubms -- The number of sub-MSs to create.
        default: 'auto'
```

The default 'auto' is to partition using the number of available servers in

Options: any integer number (example: numsubms=4)

If the task is unable to determine the number of running servers, or the user using mpicasa, numsubms will use 8 as the default.

Example: Launch CASA with 5 engines, where 4 of them will be used to create engine is used as the MPIClient.

mpicasa -n 5 casa --nogui --log2term
CASA> partition('uid__A1', outputvis='test.mms')

flagbackup -- Make a backup of the FLAG column of the output MMS. When the
MMS is created, the .flagversions of the input MS are not transferred
therefore it is necessary to re-create it for the new MMS. Note
that multiple backups from the input MS will not be preserved. This
will create a single backup of all the flags present in the input
MS at the time the MMS is created.

default: True

N.B.: 'all' = whichever of the above that are present.

---- Data selection parameters (see help par.selectdata for more detailed information)

field -- Select field using field id(s) or field name(s).
 [run listobs to obtain the list iof d's or names]
 default: ''=all fields If field string is a non-negative
 integer, it is assumed to be a field index
 otherwise, it is assumed to be a field name
 field='0^2'; field ids 0,1,2
 field='0,4,5~7'; field ids 0,4,5,6,7
 field='3C286,3C295'; fields named 3C286 and 3C295
 field = '3,4C*'; field id 3, all names starting with 4C

spw -- Select spectral window/channels
 default: ''=all spectral windows and channels
 spw='0^2,4'; spectral windows 0,1,2,4 (all channels)
 spw='<2'; spectral windows less than 2 (i.e. 0,1)
 spw='0:5^61'; spw 0, channels 5 to 61
 spw='0,10,3:3^45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
 spw='0^2:2^6'; spw 0,1,2 with channels 2 through 6 in each.
 spw = '*:3^64' channels 3 through 64 for all sp id's
 spw = ':3^64' will NOT work.</pre>

```
spw = '*:0;60~63' channel 0 and channels 60 to 63 for all IFs
              ';' needed to separate different channel ranges in one spw
       spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
       spw='0:0~10,1:20~30,2:1;2;4'; spw 0, channels 0-10,
                spw 1, channels 20-30, and spw 2, channels, 1, 2 and 4
antenna -- Select data based on antenna/baseline
    default: '' (all)
        Non-negative integers are assumed to be antenna indices, and
        anything else is taken as an antenna name.
        Examples:
        antenna='5&6': baseline between antenna index 5 and index 6.
        antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8': baselines 5-6 and 7-8
        antenna='5': all baselines with antenna 5
        antenna='5,6,10': all baselines including antennas 5, 6, or 10
        antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                               10. (cross-correlations only. Use &&
                               to include autocorrelations, and &&&
                               to get only autocorrelations.)
        antenna='!ea03,ea12,ea17': all baselines except those that
                                   include EVLA antennas ea03, ea12, or
                                   ea17.
timerange -- Select data based on time range:
    default = '' (all); examples,
       timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date, timerange defaults to the
      first day in the dataset
      timerange='09:14:0~09:54:0' picks 40 min on first day
      timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
       on next day
      timerange='09:44:00' data within one integration of time
       timerange='>10:24:00' data after this time
array -- (Sub)array number range
   default: ''=all
uvrange -- Select data within uvrange (default units meters)
    default: ''=all; example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
        uvrange='0~1000km'; uvrange in kilometers
scan -- Scan number range
```

default: ''=all

observation -- Select by observation ${\tt ID}({\tt s})$

default: ''=all

----- EXAMPLES -----

- 1) Create a Multi-MS of some spws, partitioned per spw. The MS contains 16 spws. partition('uid001.ms', outpuvis='source.mms', spw='1,3~10', separationaxis='spw')
- 2) Create a Multi-MS but select only the first channels of all spws. Do not back up the FLACCOLUMN.

partition('uid0001.ms', outputvis='fechans.mms', spw='*:1~10', flagbackup=False)

- 3) Create a Multi-MS using both separation axes. partition('uid0001.ms', outputvis='myuid.mms', createmms=True, separationaxis='auto')
- 4) Create a single-dish Multi-MS using the baseline axis only for the auto-correlations. partition('uid0001.ms', outputvis='myuid.mms', createmms=True, separationaxis='baseline

polcal-task.html

0.1.85 polcal

Requires:

Synopsis

Determine instrumental polarization calibrations

Description

The complex instrumental polarization factors (D-terms) for each antenna/spwid are determined from the data for the specified calibrator sources. Previous calibrations can be applied on the fly.

vis Name of input visibility file

> allowed: string

Default:

caltable Name of output gain calibration table

> allowed: string

Default:

field Select field using field id(s) or field name(s)

> allowed: string

Default:

Select spectral window/channels spw

> allowed: string

Default:

intent Select observing intent

> allowed: string

Default:

selectdata Other data selection parameters

> allowed: bool Default: True

Select data based on time range timerange

> allowed: string

Default:

uvrange Select data within uvrange (default units meters)

> allowed: any Default: variant

antenna Select data based on antenna/baseline

> allowed: string

Default:

Scan number range scan

> allowed: string

Default:

observation Select by observation ID(s)

> allowed: any Default: variant

msselect Optional complex data selection (ignore for now)

> allowed: string

Default:

Solution interval

solint

allowed: any

Default: variant inf

combine Data axes which to combine for solve (obs, scan, spw,

and/or field)

allowed: string Default: obs, scan

Pre-averaging interval (sec) preavg

> allowed: 44 quble Default: 300.0

refant Reference antenna name(s)

> allowed: string

Default:

minblperant Minimum baselines _per antenna_ required for solve

> allowed: int Default:

minsnr Reject solutions below this SNR

Example

The instrumental polarization factors (D-terms), the calibrator polarization, and the R-L polarization angle can be determined using polcal. The solutions can be obtained for each antenna/spwid and even individual channels, if desired. Previous calibrations of the total intensity data should be applied on the fly when running polcal, since polcal uses the 'data' column, not the 'corrected' column.

After calibrating the gain, bandpass, and (if relevant, for channelized data) cross-hand delay, the simplest way to calibrate the polarization data is:

- a) Run polcal with poltype = 'D+QU' on the main 'calibrator' source. The D terms and polarization (QU) of the calibrator will be determined. Relatively good parallactic angle coverage is needed.
- b) If there is little parallactic angle coverage, place the known polarization of the main calibrator (or 0) using setjy with the appropriate fluxdensity. Then run polcal with poltype = 'D'. Run plotcal with xaxis = 'real'; yaxis = 'imag' to view solutions. It is best to use an unpolarized calibrator in this instance; large systematic offsets from zero indicate significant source polarization that will bias the polarization calibration. A mechanism to constrain this bias will be made available in the near future.
- c) To determine R-L polarization angle, use setjy to put the fluxdensity of the polarization calibrator [I,Q,U,0.0] in the model column. For resolved sources put in values associated with an appropriate u-v range. Polarized models are not yet available for the major polarization standard sources, so very resolved polarized sources should not be used.
- d) Run polcal with poltype = 'X' and include polarization standard. Make sure to include all previous calibrations, especially the D results. Run plotxy with correlation = 'RL LR' and make sure polarization angles are as expected.
- e) Run applycal with all calibration table, include the D and X tables. Make sure that parang = T
- NOTE: For very high dynamic range, use poltype='Df' or 'Df+QU' to determine D terms for each channel. Similarly, poltype='Xf' can be used to determine a channel-dependent R-L phase "bandpass".
- NOTE: Rather than use setjy in b and c above, the new smodel parameter may be used in polcal to specify a simple

```
point source Stokes model.
```

```
Keyword arguments:
vis -- Name of input visibility file
        default: none; example: vis='ngc5921.ms'
caltable -- Name of output gain calibration table
        default: none; example: caltable='ngc5921.dcal'
--- Data Selection (see help par.selectdata for more detailed information)
field -- Select field using field id(s) or field name(s).
           [run listobs to obtain the list id's or names]
        default: ''=all fields.
            Most likely, the main calibrator source should be picked.
        If field string is a non-negative integer, it is assumed a field index
          otherwise, it is assumed a field name
        field='0~2'; field ids 0,1,2
        field='0,4,5~7'; field ids 0,4,5,6,7
        field='3C286,3C295'; field named 3C286 adn 3C295
        field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
        type 'help par.selection' for more examples.
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61, INCLUSIVE
       spw='*:5~61'; all spw with channels 5 to 62
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw='0:0~10;15~60'; spectral window 0 with channels 0-10,15-60
                 NOTE ';' to separate channel selections
       spw='0:0~10^2,1:20~30^5'; spw 0, channels 0,2,4,6,8,10,
             spw 1, channels 20,25,30
intent -- Select observing intent
          default: '' (no selection by intent)
          intent='*BANDPASS*' (selects data labelled with
                                BANDPASS intent)
selectdata -- Other data selection parameters
        default: True
timerange -- Select data based on time range:
        default = '' (all); examples,
        timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
        Note: if YYYY/MM/DD is missing dat defaults to first day in data set
        timerange='09:14:0~09:54:0' picks 40 min on first day
        timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr 30min on next day
        timerange='09:44:00' data within one integration of time
        timerange='>10:24:00' data after this time
```

```
uvrange -- Select data within uvrange (default units meters)
        default: '' (all); example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
antenna -- Select data based on antenna/baseline
        default: '' (all)
        If antenna string is a non-negative integer, it is assumed an antenna index
          otherwise, it is assumed as an antenna name
        antenna='5&6'; baseline between antenna index 5 and index 6.
        antenna='VA05&VA06'; baseline between VLA antenna 5 and 6.
        antenna='5\&6;7\&8'; baseline 5-6 and 7-8
        antenna='5'; all baselines with antenna index 5
        antenna='05'; all baselines with antenna name 05, i.e. VLA ant 5
        antenna='5,6,10'; all baselines with antennas 5, 6 and 10
scan -- Scan number range
observation -- Observation ID(s).
               default: '' = all
               example: '0~2,4'
msselect -- Optional complex data selection (ignore for now)
--- Solution parameters
poltype -- Type of instrumental polarization solution
        'D+QU' (or 'Df+QU') solve also for apparent source polarization (channelized
           Need relatively good parallactic angle coverage for this
        'D' (or 'Df') solve only for instrumental polarization (channelized). The
           I, Q, U flux density of the source can be placed in the model column using
           setjy. Use for poor parallactic angle coverage.
        'X' (or 'Xf') = solve only for position angle correction (channelized).
           The source must have its I, Q, U flux density in the model column
           or specified in smodel. If the source is resolved, use a limited
           uvrange that is appropriate.
        'D+X' (or 'Df+X') = solve also for position angle offset (channelized D) as
           well as the D-term. Not normally done.
        default: 'D+QU'
        The solution used the traditional linear approximation. Non-linearized option
            will be avaible soon.
smodel -- Point source Stokes parameters for source model (experimental)
        default: [] (use MODEL_DATA column)
        examples: [1,0,0,0] (I=1, unpolarized)
                  [5.2,0.2,0.3,0.0] (I=5.2, Q=0.2, U=0.3, V=0.0)
solint -- Solution interval (units optional)
        default: 'inf' ("infinite, up to boundaries controlled by combine);
        Options: 'inf' ("infinite), 'int' (per integration), any float
                 or integer value with or without units
        examples: solint='1min'; solint='60s', solint=60 --> 1 minute
                  solint='0s'; solint=0; solint='int' --> per integration
```

solint-'-1s'; solint='inf' --> ~infinite, up to boundaries enforced by combine combine -- Data axes to combine for solving default: 'obs,scan' --> solutions will break at field and spw boundaries but may extend over multiple obs and scans (per field and spw) up to solint. Options: '', 'obs', 'scan', 'spw', field', or any comma-separated combination in a single string example: combine='scan,spw' --> extend solutions over scan boundaries (up to the solint), and combine spws for solving preavg -- Pre-averaging interval (sec) default=300 Interval to apply parallactic angle. refant -- Reference antenna name default: '' => refant = '0' example: refant='13' (antenna with index 13) refant='VA04' (VLA antenna #4) refant='EA02,EA23,EA13' (EVLA antenna EA02, use EA23 and EA13 as alternates if/when EA02 drops out) Use 'go listobs' for antenna listing. USE SAME REFERENCE ANTENNA AS USED FOR I CALIBRATION. minblperant -- Minimum number of baselines required per antenna for each solve Antennas with fewer baaselines are excluded from solutions. Amplitude solutions with fewer than 4 baselines, and phase solutions with fewer than 3 baselines are only trivially constrained, and are no better than baseline-based solutions. default: 4 example: minblperant=10 => Antennas participating on 10 or more baselines are included in the solve minsnr -- Reject solutions below this SNR default: 3.0 append -- Append solutions to the (existing) table. Appended solutions must be derived from the same MS as the existing caltable, and solution spws must have the same meta-info (according to spw selection and solint) or be non-overlapping. default: False; overwrite existing table or make new table --- Other calibrations to apply on the fly before determining polcal solution docallib -- Control means of specifying the caltables: default: False ==> Use gaintable,gainfield,interp,spwmap,calwt If True, specify a file containing cal library in callib callib -- If docallib=True, specify a file containing cal library directives

```
gaintable -- Gain calibration table(s) to apply
         default: '' (none); BUT I CALIBRATION TABLES SHOULD GENERALLY BE INCLUDED
         examples: gaintable='ngc5921.gcal'
                   gaintable=['ngc5921.ampcal', 'ngc5921.phcal']
gainfield -- Select a subset of calibrators from gaintable(s)
         default:'' ==> all sources in table;
         'nearest' ==> nearest (on sky) available field in table
         otherwise, same syntax as field
         example: gainfield='0~3'
                  gainfield=['0~3','4~6'] means use field 0 through 3
                    from first gain file, field 4 through 6 for second.
interp -- Interpolation type (in time[,freq]) to use for each gaintable.
          When frequency interpolation is relevant (B, Df, Xf),
          separate time-dependent and freq-dependent interp
          types with a comma (freq _after_ the comma).
         Specifications for frequency are ignored when the
          calibration table has no channel-dependence.
         Time-dependent interp options ending in 'PD' enable a
          "phase delay" correction per spw for non-channel-dependent
          calibration types.
         For multi-obsId datasets, 'perobs' can be appended to
          the time-dependent interpolation specification to
          enforce obsId boundaries when interpolating in time.
          default: '' --> 'linear, linear' for all gaintable(s)
          example: interp='nearest'
                                     (in time, freq-dep will be
                                       linear, if relevant)
                   interp='linear,cubic' (linear in time, cubic
                                           in freq)
                   interp='linearperobs, spline' (linear in time
                                                 per obsId,
                                                 spline in freq)
                   interp=',spline'
                                     (spline in freq; linear in
                                      time by default)
                   interp=['nearest,spline','linear'] (for multiple gaintables)
          Options: Time: 'nearest', 'linear'
                   Freq: 'nearest', 'linear', 'cubic', 'spline'
spwmap -- Spectral windows combinations to form for gaintable(s)
         default: [] (apply solutions from each spw to that spw only)
          Example: spwmap=[0,0,1,1] means apply the caltable solutions
                    from spw = 0 to the spw 0,1 and spw 1 to spw 2,3.
                    spwmap=[[0,0,1,1],[0,1,0,1]]
async -- Run asynchronously
        default = False; do not run asychronously
```

predictcomp-task.html

0.1.86 predictcomp

Requires:

Synopsis

Make a component list for a known calibrator

Description

Writes a component list named clist to disk and returns a dict of 'clist': clist, 'objname': objname, 'standard': standard, 'epoch': epoch, 'freqs': pl.array of frequencies, in GHz, 'antennalist': a simdata type configuration file, 'amps': pl.array of predicted visibility amplitudes, in Jy, 'savedfig': False or, if made, the filename of a plot. or False on error.

objname Object name

allowed: string

Default:

standard Flux density standard

allowed: string

Default: Butler-JPL-Horizons 2010

epoch Epoch

allowed: string

Default:

minfreq Minimum frequency

allowed: string

Default:

maxfreq Maximum frequency

allowed: string

Default:

nfreqs Number of frequencies

allowed: int Default: 2

prefix Prefix for the component list directory name.

allowed: string

Default:

antennalist Plot for this configuration

allowed: string

Default:

showplot Plot S vs —u— to the screen?

allowed: bool Default: False

savefig Save a plot of S vs —u— to this filename

allowed: string

Default:

symb A matplotlib plot symbol code

allowed: string

Default:

include0amp Force the amplitude axis to start at 0?

allowed: bool Default: False

include0bl Force the baseline axis to start at 0?

allowed: bool
Default: False

blunit unit of the baseline axis

allowed: string

Default:

showbl0flux Print the zero baseline flux?

allowed: bool Default: False

Returns

record

Example

```
Writes a component list to disk and returns a dict of
 {'clist': filename of the component list,
  'objname': objname,
  'angdiam': angular diameter in radians (if used in clist),
  'standard': standard,
  'epoch': epoch,
  'freqs': pl.array of frequencies, in GHz,
  'antennalist': pl.array of baseline lengths, in m,
  'amps': pl.array of predicted visibility amplitudes, in Jy,
  'savedfig': False or, if made, the filename of a plot.}
 or False on error.
 objname: An object supported by standard.
 standard: A standard for calculating flux densities, as in setjy.
           Default: 'Butler-JPL-Horizons 2010'
 epoch: The epoch to use for the calculations.
                                                 Irrelevant for
        extrasolar standards. (Uses UTC)
Examples: '2011-12-31/5:34:12', '2011-12-31-5:34:12'
 minfreq: The minimum frequency to use.
          Example: '342.0GHz'
 maxfreq: The maximum frequency to use.
          Default: minfreq
          Example: '346.0GHz'
          Example: '', anything <= 0, or None: use minfreq.
nfreqs: The number of frequencies to use.
          Default: 1 if minfreq == maxfreq,
                   2 otherwise.
 prefix: The component list will be saved to
           prefix + 'spw0_<objname>_<minfreq><epoch>.cl'
         Default: ''
 Example: "Bands3to7_"
                  (which could produce 'Bands3to7_spw0_Uranus_100GHz55877d.cl',
   depending on the other parameters)
 antennalist: 'Observe' and plot the visibility amplitudes for this
              antenna configuration. The file should be in a format usable
              by simdata. The search path is:
```

```
.:casa['dirs']['data'] + '/alma/simmos/'
         Default: '' (None, just make clist.)
 Example: 'alma.cycle0.extended.cfg'
Subparameters of antennalist:
showplot: Whether or not to show a plot of S vs. |u| on screen.
          Subparameter of antennalist.
          Default: Necessarily False if antennalist is not specified.
                   True otherwise.
savefig: Filename for saving a plot of S vs. |u|.
         Subparameter of antennalist.
         Default: False (necessarily if antennalist is not specified)
         Examples: ''
                               (do not save the plot)
                   'myplot.png' (save to myplot.png)
symb: One of matplotlib's codes for plot symbols: .:,o^v<>s+xDd234hH|_
      Default: '.'
includeOamp: Force the amplitude axis to start at 0?
             Default: False
includeObl: Force the baseline axis to start at O?
           Default: False
blunit: unit of the baseline axis ('' or 'klambda')
       Default: ''=use a unit in the data
showbl0flux: Print the zero baseline flux?
            Default: False
```

impv-task.html

0.1.87 impv

Requires:

Synopsis

Construct a position-velocity image by choosing two points in the direction plane.

imagename Name of the input image

allowed: string

Default:

outfile Output image name. If empty, no image is written.

allowed: string

Default:

mode If "coords", use start and end values. If "length", use

center, length, and pa values.

allowed: string
Default: coords

start The starting pixel in the direction plane (array of two

values).

allowed: any Default: variant

end The ending pixel in the direction plane (array of two

values).

allowed: any Default: variant

center The center point in the direction plane (array of two

values). If specified, length and pa must also be specified

and neither of start nor end may be specified.

allowed: any Default: variant

length The length of the segment in the direction plane. If spec-

ified, center and pa must also be specified and neither

of start nor end may be specified.

allowed: any
Default: variant

The position angle of the segment in the direction plane,

measured from north through east. If specified, center and length must also be specified and neither of start

nor end may be specified.

allowed: any Default: variant

width Width of slice for averaging pixels perpendicular to the

slice. Must be an odd positive integer or valid quantity.

See help for details. allowed: any Default: variant 1

unit Unit for the offset axis in the resulting image. Must be

a unit of angular measure.

allowed: stying
Default: arcsec

overwrite Overwrite the output if it exists?

allowed: bool Default: False

region Region selection. Default is entire image. No selection

is permitted in the direction plane. See help par.region.

allowed: any
Default: variant ""

Returns

image

Example

PARAMETER SUMMARY

imagename Name of the input (CASA, FITS, MIRIAD) image outfile Name of output CASA image. Must be specified.

mode Indicates which sets of parameters to use for defining the slice. mode="code"

start and end parameters. mode="length" means use center, length, and pa pa

the slice.

The starting pixel in the direction plane (array of two values), such as [start

Used iff mode="coords".

end The ending pixel in the direction plane (array of two values), such as [200]

Used iff mode="coords".

The center of the slice in the direction plane (array of two values), such center

Used iff mode="length".

length The length of the slice in the direction plane. May be specified as a sing

> case it is interpreted as the number of pixels, or as a valid quantity which the direction axes units (eg "40arcsec", {"value": 40, "unit": "arcsec"}).

Used iff mode="length".

Position angle of the slice, measured from the direction of positive latit pa

(eg north through east in an equatorial coordinate system). Must be express

quantity (eg "40deg", {"value": 40, "unit": "deg"}).

Used iff mode="length".

width Width of slice for averaging pixels perpendicular to the slice which must I

valid quantity. The averaging using this value occurs after the image has I

An integer value is interpreted as the number of pixels to average.

A value of 1 means no averaging. A value of 3 means average one pixel on ea

side of the slice and the pixel on the slice. A value of 5 means average 2 on each side of the slice and the pixel on the slice, etc. If a quantity (

is specified, the equivalent number of pixels is calculated, and if necessation to the next odd integer.

unit Allows the user to set the unit for the angular offset axis. Must be a uni-

If output file is specified, this parameter controls if an already existing overwrite

same name can be overwritten. If true, the user is not prompted, the file

if it exists is automatically overwritten.

Region specification. See help par.region. Default is to not use a region. region

the entire direction plane must be specified. If specified do not specify

chans Optional contiguous frequency channel number specification. Default is all

If specified, do not specify region. See "help par.chans" for examples.

stokes Contiguous stokes planes specification. If specified, do not specify region mask Mask to use. See help par.mask. Default is none.

stretch Stretch the input mask if necessary and possible. Only used if a mask is sp

See help par.stretch.

Create a position-velocity image. The way the slice is specified is controlled by the mode mode="coords", start end end are used to specified the points between which a slice is taken coordinate. If mode="length" center, pa (position angle), and length are used to specify the extent of the resulting image will be that provided by the region specification or the entire the input image if no region is specified. One may not specify a region in direction space; specifying the slice as described previously. The parameters start and end may be specified element arrays of numerical values, in which case these values will be interpreted as pixel image. Alternatively, they may be expressed as arrays of two strings each representing the can either represent quantities (eg ["40.5deg", "0.5rad") or be sexigesimal format (eg ["14] ["14:20:20.5s", "-30.45.25.4"]). In addition, they may be expressed as a single string contag latitude-like values and optionally a reference frame value, eg "J2000 14:20:20.5s -30.45.29 be specified in the same way. The length parameter may be specified as a single numerical va interpreted as the length in pixels, or a valid quantity, in which case it must have units direction axes units. The pa (position angle) parameter must be specified as a valid quanti-The position angle is interpreted in the usual astronomical sense; eg measured from north tl coordinate system. The slice in this case starts at the specified position angle and ends or the specified center. Thus pa="45deg" means start at a point at a pa of 45 degrees relative end at a point at a pa of 215 degrees relative to the center. Either start/end or center/pa, if a parameter from one of these sets is specified, a parameter from the other set may not l case, the end points of the segment must fail within the input image, and they both must be edge of the input image to facilite rotation (see below).

One may specify a width, which represents the number of pixels centered along and perpendict to the direction slice that are used for averaging along the slice. The width may be specificase it must be positive and odd. Alternatively, it may be specified as a valid quantity structure quantity record (eg qa.quantity("4arcsec"). In this case, units must be conformant to the dangular units) and the specified quantity will be rounded up, if necessary, to the next high of pixels. The default value of 1 represents no averaging.

A value of 3 means average one pixel on each side of the slice and the pixel on the slice. Note that this width is applied to pixels in the image after it has been rotated (see below of the algorithm used).

One may specify the unit for the angular offset axis.

Internally, the image is first rotated, padding if necessary to include relevant pixels that be excluded by the rotation operation, so that the slice is horizontal, with the starting pending pixel. Then, the pixels within the specified width of the slice are averaged and the written and/or returned. The output image has a linear coordinate in place of the direction input image, and the corresponding axis represents angular offset with the center pixel have

The equivalent coordinate system, with a (usually) rotated direction coordinate (eg, RA and

```
to the output image as a table record. It can be retrieved using the table tool as shown in
# create a pv image with the position axis running from ra, dec pixel positions of [45, 50]
# in the input image
impv(imagename="my_spectral_cube.im", outfile="mypv.im", start=[45,50], end=[100,120])
# analyze the pv image, such as get statistics
pvstats = imstat("mypv.im")
#
# get the alternate coordinate system information
tb.open("mypv.im")
alternate_csys_record = tb.getkeyword("misc")["secondary_coordinates"]
tb.done()
```

 ${\it rmfit-task.html}$

0.1.88 rmfit

Requires:

Synopsis
Calculate rotation measure.

Inputs imagename Name(s) of the input image(s). Must be specified. allowed: any Default: variant Output rotation measure image name. If not specified, rmno image is written. allowed: string Default: Output rotation measure error image name. If not specrmerrified, no image is written. allowed: string Default: pa0 Output position angle (degrees) at zero wavelength image name. If not specified, no image is written. allowed: string Default: pa0err Output position angle (degrees) at zero wavelength error image name. If not specified, no image is written. allowed: string Default: nturns Output number of turns image name. If not specified, no image is written. allowed: string Default: chisq Output reduced chi squared image name. If not specified, no image is written. allowed: string Default: Estimate of the thermal noise. A value less than 0 means sigma auto estimate. allowed: double Default: -1 Foreground rotation measure in rad/m/m to subtract. rmfg allowed: double Default: rmmax Maximum rotation measure in rad/m/m for which to solve. IMPORTANT TO SPECIFY.

in solution determination.

double

double

1e30

432

Maximum input position angle error in degrees to allow

0.0

allowed:

Default:

allowed:

Default:

maxpaerr

Returns

bool

Example

PARAMETER SUMMARY

imagename	Name(s) of the input image(s).
rm	Output rotation measure image name. If not specified, no image is written.
rmerr	Output rotation measure error image name. If not specified, no image is wr
pa0	Output position angle (degrees) at zero wavelength image name. If not spec
pa0err	Output position angle (degrees) at zero wavelength error image name. If not
nturns	Output number of turns image name. If not specified, no image is written.
chisq	Output reduced chi squared image name. If not specified, no image is writte
sigma	Estimate of the thermal noise. A value less than 0 means auto estimate.

rmfg Foreground rotation measure in rad/m/m to subtract.

rmmax Maximum rotation measure in rad/m/m for which to solve. IMPORTANT TO SPECI

This task generates the rotation measure image from stokes Q and U measurements at several different frequencies. You are required to specify the name of at least one image with a per axis containing stokes Q and U planes and with a frequency axis containing more than two pix frequencies do not have to be equally spaced (ie the frequency coordinate can be a tabular of the summary of the position angle images for you. You may also specify multiple image name case these images will first be concatenated along the spectral axis using ia.imageconcat() are that for all images, the axis order must be the same and the number of pixels along each be identical, except for the spectral axis which may differ in length between images. The spectral contiguous from one image to another.

See also the fourierrotationmeasure function for a new Fourier-based approach.

Rotation measure algorithms that work robustly are few. The main problem is in trying to account for the \$n- \pi\$ ambiguity (see Leahy et al, Astronomy \& Astrophysics, 156, 234 or Killeen et al; http://www.atnf.csiro.au/\verb+~+nkilleen/rm.ps).

The algorithm that this task uses is that of Leahy et al. in see Appendix A.1. But as in all these algorithms, the basic process is that for each spatial pixel, the position angle vs frequency data is fit to determine the rotation measure and the position angle at zero wavelength (and associated errors). An image containing the number of \$n- \pi\$ turns that were added to the data at each spatial pixel and for which the best fit was found can be written. The reduced chi-squared image for the fits can

also be written.

Note that no assessment of curvature (i.e. deviation from the simple linear position angle - \$\lambda^2\$ functional form) is made.

Any combination of output images can be written.

The parameter sigma gives the thermal noise in Stokes $\mathbb Q$ and $\mathbb U$. By default it is determined automatically using the image data. But if it proves to be inaccurate (maybe not many signal-free pixels), it may be specified. This is used for calculating the error in the position angles (via propagation of Gaussian errors).

The argument maxpaerr specifies the maximum allowable error in the position angle that is acceptable. The default is an infinite value. From the standard propagation of errors, the error in the linearly polarized position angle is determined from the Stokes Q and U images (at each directional pixel for each frequency). If the position angle error for any pixel exceeds the specified value, the position angle at that pixel is omitted from the fit. The process generates an error for the fit and this is used to compute the errors in the output images.

Note that maxpaerr is not used to mask pixels in the output images.

The argument rmfg is used to specify a foreground RM value. For example, you may know the mean RM in some direction out of the Galaxy, then including this can improve the algorithm by reducing ambiguity.

The parameter rmmax specifies the maximum absolute RM value that should be solved for. This quite an important parameter. If you leave it at the default, zero, no ambiguity handling will be used. So some apriori information should be supplied; this is the basic problem with rotation measure algorithms.

EXAMPLES

- # Calculate the rotation measure for a single polarization image rmfit(imagename="mypol.im", rm="myrm.im", rmmax=50.0)
- # calculate the rotation measure using a set of polarization images from # different spectral windows or bands.

rmfit(imagename=["pol1.im", "pol2.im", "pol3.im", rm="myrm2.im", rmmax=50.0)

 ${\it rmtables-task.html}$

0.1.89 rmtables

Requires:

Synopsis

Remove tables cleanly, use this instead of rm -rf $\,$

Description

This task removes tables if they are not being currently accessed via the casapy process. Note: if you have multiple sessions running bad things could happen if you remove a table being accessed by another process.

Arguments

Inputs			
tablenames	Name of the tables		
	allowed:	$\operatorname{stringArray}$	
	Default:		

Example

```
Removes tables cleanly. Arguments may contain \ast or ?. Ranges [] are support but not \tilde{\ } expansion.
```

sdaverage-task.html

0.1.90 sdaverage

Requires:

Synopsis

ASAP SD task: averaging and smoothing of spectra

Description

Task sdaverage performs averaging in time/polarization and smoothing of the single-dish spectra. When timeaverage=True, spectra are averaged in time. Spectra within each scan ID are averaged when scanaverage=True. When polaverage=True, spectra are averaged in polarization and time (Note time averaging with polaverage=True would be discarded in future). See examples in below for details of time/polarization average. When kernel is specified (!="), each spectrum is smoothed by convolving the kernel after averaging of spectra.

If you give multiple IFs (spectral windows) in spw, then your scantable will have multiple IFs by default. Averaging of multi-resolution (multi-IFs) spectra can be achieved by setting a sub-parameter in timeaverage, averageall = True. It handles multi-IFs by merging IFs which have overlaps in frequency coverages and assigning new IFs in the output spectra.

Set plotlevel $\not = 1$ to plot spectrum before and after smoothing, and verify=True to interactively select whether or not accept smoothing results. NOTE, so far, there is no mechanism to verify averaging of spectra in time and/or polarization.

Arguments

Inputs infile name of input SD dataset allowed: string Default: select an antenna name or ID, e.g. 'PM03' (only effective antenna for MS input) allowed: any Default: variant 0 field select data by field IDs and names, e.g. '3C2*' ("=all) allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: select data by polarization IDs, e.g. '0,1' ("=all) pol allowed: string Default: average spectra over time [True, False] (see examples in timeaverage help) allowed: bool Default: False tweight weighting for time averaging allowed: string Default: tintsys scanaverage average spectra within a scan number [True, False] (see examples in help) allowed: bool Default: False averageall set True only when averaging spectra with different spectral resolutions allowed: bool False Default: polaverage average spectra over polarizations [True, False] allowed: bool Default: False pweight weighting for polarization averaging allowed: string Default: tsys kernel type of spectral smoothing kernel ("=no smoothing) allowed: string Default: kwidth width of smoothing kernel in channels allowed: int Default: **4**38 chanwidth width of regridded channels allowed: string Default: verify interactively verify the results of smoothing for each

spectrum. [not available for kernel="regrid"]

plot and summarize results (0=none). See description

bool

False

allowed:

Default:

plotlevel

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
       this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)
       NOTE this task only supports IF ID selction and ignores channel
       selection.
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
timeaverage -- average spectra over time
        options: (bool) True, False
        default: False
    >>>timeaverage expandable parameter
        tweight -- weighting for time averaging
                options: 'var' (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
```

```
'tint' (integration time weighted)
                         'tintsys' (Tint/Tsys**2)
                         'median' (median averaging)
                default: 'tintsys'
        scanaverage -- average spectra within a scan number
                       when True, spectra are NOT averaged over
                       different scan numbers.
                options: (bool) True, False
                default: False
        averageall -- average multi-resolution spectra
                       spectra are averaged by referring
                       their frequency coverage
                 default: False
polaverage -- average spectra over polarizations
        options: (bool) True, False
        default: False
    >>>polaverage expandable parameter
        pweight -- weighting for polarization averaging
                options: 'var' (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
                default: 'tsys'
kernel -- type of spectral smoothing kernel
        options: '', 'hanning', 'gaussian', 'boxcar', 'regrid'
        default: '' (no smoothing)
    >>>kernel expandable parameter
        kwidth -- width of spectral smoothing kernel
                options: (int) in channels
                default: 5
        example: 5 or 10 seem to be popular for boxcar
                 ignored for hanning (fixed at 5 chans)
                         (0 will turn off gaussian or boxcar)
        chanwidth -- channel width of regridded spectra
         default: '5' (in channels)
         example: '500MHz', '0.2km/s'
        verify -- interactively verify the results of smoothing for each
                  spectrum. When verify = True, for each input spectrum,
                  spectra before and after the operation are displayed
                  in a plot window. At the prompt there are four choices
                  of action: 'Y' (accept the operation and continue to
                  the next input spectrum), 'N' (reject the operation
                  and continue to the next input spectrum), 'A' (accept
                  the current operation and continue non-interactively),
```

```
and 'R' (reject the current operation and exit from
                  Note that when the operation is rejected by 'N' or 'R',
                  no smoothing is done to the spectrum/spectra.
                options: (bool) True, False
                default: False
outfile -- name of output file
        default: '' (<infile>_sm)
outform -- output file format
        options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'
        default: 'ASAP'
        NOTE the ASAP format is easiest for further sd
        processing; use MS2 for CASA imaging.
        If ASCII, then will append some stuff to
        the outfile name
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
plotlevel -- control for plotting and summary of smoothing results
        options: (int) 0, 1, 2, and their negative counterparts
default: 0 (no plotting)
example: plotlevel=1; plot spectra before and after smoothing
                 plotlevel=2; additionally list data before and after operation.
                 plotlevel<0 as abs(plotlevel), e.g.</pre>
                 -1 => hardcopy of final plot (will be named
                 <outfile>_smspec.eps)
```

AVERAGING OF SPECTRA

Task sdaverage has two modes of averaging spectra, i.e., time and polarization average.

When timeaverage=True, spectra are averaged over time for each IF (spectral window), polarization, and beam, independently. Note that, by default (scanaverage=False), timeaverage=True averages spectra irrespective of scan IDs.

It is possible to average spectra separately for each scan ID by setting a sub-parameter scanaverage=True.

For example, the combination of parameters: scan='0~2', timeaverage=True, and

 ${\tt scanaverage=False: averages \ spectra \ in \ scan \ ID \ 0 \ through \ 2 \ all \ together}$

to a spectrum,

scanaverage=True : averages spectra per scan ID and end up with three spectra from scan 0, 1, and 2.

When polaverage=True, spectra are averaged over polarization for each IF (spectral window) and beam. Note that, so far, time averaging is automatically switched on when polaverage is set to True. This behavior is not desirable and will be discarded in future.

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs. sdbaseline-task.html

0.1.91 sdbaseline

Requires:

Synopsis

Fit/subtract a spectral baseline

Description

Task sdbaseline performs baseline fitting/removal for single-dish spectra. The fit parameters, terms and rms of base-line are saved to an ascii file, 'joutfile; blparam.txt'.

Arguments

Inputs

scan

infile name of input SD dataset

allowed: string

Default:

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any Default: variant 0

fluxunit units of the flux ("=current)

allowed: string

Default:

telescope parameters of telescope for flux conversion (see examples

in help)

allowed: any Default: variant

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

restfreq the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see

examples in help)
allowed: any
Default: variant

frame frequency reference frame ("=current)

allowed: string

Default:

doppler doppler convention ("=current). Effective only when

spw selection is in velocity unit.

allowed: string

Default:

timerange select data by time range, e.g. '09:14:0 \sim 09:54:0' ("=all)

(see examples in help) allowed: string

Default:

select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: string

Default:

tau the zenith atmospheric optical depth for correction

allowed: double Default: 4440.0

maskmode mode of setting additional channel masks

allowed: string

Default:

thresh S/N threshold for linefinder

allowed: double Default: 5.0

avg_limit channel averaging for broad lines

allowed: int

Returns

void

Example

```
Keyword arguments
_____
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap. eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
```

```
spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
    >>> spw expandable parameter
        restfreq -- the rest frequency
                    available type includes float, int, string, list of float,
                    list of int, list of string, and list of dictionary. the
                    default unit of restfreq in case of float, int, or string
                    without unit is Hz. string input can be a value only
                    (treated as Hz) or a value followed by unit for which 'GHz',
                    'MHz', 'kHz', and 'Hz' are available.
                    a list can be used to set different rest frequencies for
                    each IF. the length of list input must be number of IFs.
                    dictionary input should be a pair of line name and
                    frequency with keys of 'name' and 'value', respectively.
                    values in the dictionary input follows the same manner as
                    as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
        frame -- frequency reference frame
               options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
                default: '' (keep current frame in data)
        doppler -- doppler convention (effective only when spw is in
                   velocity unit)
                options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
                default: '' (keep current doppler setting in data)
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss'
                 Note: YYYY/MM/DD can be dropped as needed:
                 timerange='09:14:00~09:54:00' # this time range
                 timerange='09:44:00' # data within one integration of time
                 timerange='>10:24:00' # data after this time
                 timerange='09:44:00+00:13:00' #data 13 minutes after time
       this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
```

spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all

default: '' (use all polarizations)

example: pol='0,1' (polarization IDs 0,1)

this selection is in addition to the other selections to data

tau -- the zenith atmospheric optical depth for correction

default: 0.0 (no correction)

maskmode -- mode of setting additional channel masks

options: 'auto', 'list', or 'interact'

default: 'auto'

example: maskmode='auto' runs linefinder to detect line regions to be excluded from fitting. this mode requires three expandable parameters: thresh, avg_limit, and edge.

USE WITH CARE! May need to tweak the expandable parameters. maskmode='list' uses the given masklist only: no additional masks applied.

maskmode='interact' allows users to manually modify the mask regions by dragging mouse on the spectrum plotter GUI. use LEFT or RIGHT button to add or delete regions, respectively.

>>> maskmode expandable parameters

thresh -- S/N threshold for linefinder. a single channel S/N ratio above which the channel is considered to be a detection.

default: 4

edge -- channels to drop at beginning and end of spectrum

 ${\tt default:}\ {\tt 0}$

example: edge=[1000] drops 1000 channels at beginning AND end. edge=[1000,500] drops 1000 from beginning and 500 from end.

Note: For bad baselines threshold should be increased, and avg_limit decreased (or even switched off completely by setting this parameter to 1) to avoid detecting baseline undulations instead of real lines.

blfunc -- baseline model function

options: 'poly', 'chebyshev', 'cspline', or 'sinusoid'

default: 'poly'

example: blfunc='poly' uses a single polynomial line of any order which should be given as an expandable parameter 'order' to fit baseline.

blfunc='chebyshev' uses Chebyshev polynomials.

blfunc='cspline' uses a cubic spline function, a piecewise cubic polynomial having C2-continuity (i.e., the second derivative is continuous at the joining points).

```
blfunc='sinusoid' uses a combination of sinusoidal curves.
    >>> blfunc expandable parameters
        order -- order of baseline model function
                options: (int) (<0 turns off baseline fitting)
                default: 5
                example: typically in range 2-9 (higher values
                         seem to be needed for GBT)
        npiece -- number of the element polynomials of cubic spline curve
                options: (int) (<0 turns off baseline fitting)
                default: 2
        applyfft -- automatically set wave numbers of sinusoidal functions
                    for fitting by applying some method like FFT.
                options: (bool) True, False
                default: True
        fftmethod -- method to be used when applyfft=True. Now only
                     'fft' is available and it is the default.
        fftthresh -- threshold to select wave numbers to be used for
                     sinusoidal fitting. both (float) and (str) accepted.
                     given a float value, the unit is set to sigma.
                     for string values, allowed formats include:
                     'xsigma' or 'x' (= x-sigma level. e.g., '3sigma'), or
                     'topx' (= the x strongest ones, e.g. 'top5').
                default is 3.0 (unit: sigma).
        addwn -- additional wave number(s) of sinusoids to be used
                 for fitting.
                 (list) and (int) are accepted to specify every
                 wave numbers. also (str) can be used in case
                 you need to specify wave numbers in a certain range.
                 default: [0] (i.e., constant is subtracted at least)
                 example: 0
                          [0,1,2]
                          'a-b' (= a, a+1, a+2, ..., b-1, b),
                          ^{\prime}<a^{\prime} (= 0,1,...,a-2,a-1),
                          '>=a' (= a, a+1, ... up to the maximum wave
                                   number corresponding to the Nyquist
                                   frequency for the case of FFT).
        rejwn -- wave number(s) of sinusoid NOT to be used for fitting.
                 can be set just as addwn but has higher priority:
                 wave numbers which are specified both in addwn
                 and rejwn will NOT be used.
                 default: []
        clipthresh -- clipping threshold for iterative fitting
                 default: 3
        clipniter -- maximum iteration number for iterative fitting
                 default: 0 (no iteration, i.e., no clipping)
verify -- interactively verify the results of operation for each spectrum.
```

When verify = True, for each input spectrum, spectra before and after the operation are displayed in a plot window. At the prompt there are four choices of action: 'Y' (accept the operation and continue to the next input spectrum), 'N' (reject the operation and continue to the next input spectrum), 'A' (accept the current operation and continue non-interactively), and 'R' (reject the current operation and exit from operation). Note that when the operation is rejected by 'N' or 'R', no operation is done to the spectrum/spectra. options: (bool) True, False default: False NOTE: Currently available only when blfunc='poly' verbose -- output fitting results to logger. if False, the fitting results including coefficients, residual rms, etc., are not output to the CASA logger, while the processing speed gets faster. options: (bool) True, False default: True bloutput -- output fitting results to a text file. if False, the fitting results including coefficients, residual rms, etc., are not output to a text file (<outfile>_blparam.txt), while the processing speed gets faster. options: (bool) True, False default: True blformat -- format of the logger output and text file specified with bloutput options: '', 'csv' default: '' (same as in the past, easy to read but huge) showprogress -- show progress status for large data options: (bool) True, False default: True >>> showprogress expandable parameter minnrow -- minimum number of input spectra to show progress status default: 1000 outfile -- name of output file default: '' (<infile>_bs) outform -- output file format options: 'ASAP', 'MS2', 'ASCII', 'SDFITS' default: 'ASAP' NOTE the ASAP format is easiest for further sd processing; use MS2 for CASA imaging. If ASCII, then will append some stuff to the outfile name overwrite -- overwrite the output file if already exists options: (bool) True, False

NOTE this parameter is ignored when outform='ASCII'

default: False

plotlevel -- control for plotting of results.

2 (more)

<0 (hardcopy) as abs(plotlevel), e.g.</pre>

-1 => hardcopy of final plot (will be named

<outfile>_bspec.eps)

DESCRIPTION

Task sdbaseline performs baseline fitting/removal for single-dish spectra. The fit parameters, terms and rms of baseline are saved to an ascii file, '<outfile>_blparam.txt' if bloutput is True.

BASELINE MODEL FUNCTION

The list of available model functions are shown above (see Keyword arguments section). In general 'cspline' or 'chebyshev' are recommended since they are more stable than others. 'poly' will work for lower order but will be unstable for higher order fitting. 'sinusoid' is kind of special mode that will be useful for the data that clearly shows standing wave in the spectral baseline.

SIGMA CLIPPING (ITERATIVE FITTING)

In general least square fitting is strongly affected by an extreme data so that the resulting fit makes worse. Sigma clipping is an iterative baseline fitting with data clipping based on a certain threshold. Threshold is set as a certain factor times rms of the resulting (baseline subtracted) spectra. If sigma clipping is on, baseline fit/removal is performed several times. After each baseline subtraction, the data whose absolute value is above threshold are detected and those data are excluded from the next round of fitting. By using sigma clipping, extreme data are excluded from the fit so that resulting fit is more robust.

The user is able to control a multiplication factor using parameter clipthresh for clipping threshold based on rms. Actual threshold for sigma clipping will be (clipthresh) x (rms of spectra). Also, the user can specify number of maximum iteration to the parameter clipniter.

In general, sigma clipping will lower the performance since it increases number of fits per spectra. However, it is strongly recommended to turn on sigma clipping unless you are sure that the data is free from any kind of extreme values that may affect the fit.

FLUX UNIT CONVERSION

The task is able to convert flux unit between K and Jy. To do that, fluxunit and its subparameter telescopeparam must be properly set. The fluxunit should be 'Jy' or 'K' depending on what unit input data is and what unit you want to convert. If given fluxunit is different from the unit of input data, unit conversion is performed. The telescopeparam is used to specify conversion factor. There are three ways to specify telescopeparam: 1) set Jy/K conversion factor, 2) set telescope diameter, D, and aperture efficiency, eta, separately, and 3) 'FIX' mode (only change the unit without converting spectral data). If you give telescopeparam as a list, then if the list has a single float it is assumed to be the gain in Jy/K (case 1), if two or more elements they are assumed to be telescope diameter (m) and aperture efficiency respectively (case 2).

See the above parameter description as well as note on 'FIX' mode below for details.

There are two special cases that don't need telescopeparam for unit conversion. Telescope name is obtained from the data.

- 1) ASAP (sd tool) recognizes the conversion factor (actually D and eta) for the "AT" telescopes, namely ATNF MOPRA telescope, until 2004.
- 2) The task does know D and eta for GBT telescope.

If you wish to change the fluxunit, by leaving the sub-parameter telescopeparam unset (telescopeparam=''), it will use internal telescope parameters for flux conversion for the data from AT telescopes and it will use an approximate aperture efficiency conversion for the GBT data.

Note that sdbaseline assumes that the fluxunit is set correctly in the data already. If not, then set telescopeparam='FIX' and it will set the default units to fluxunit without conversion. Note also that, if the data in infile is an ms from GBT and the default flux unit is missing, this task automatically fixes the default fluxunit to 'K' before the conversion.

WARNING

For the GBT raw SDFITS format data as input:

SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs.

sdbaseline 2-task.html

0.1.92sdbaseline2

Requires:

Synopsis Fit/subtract a spectral baseline

Description

Task sdbaseline2 performs baseline fitting/removal for single-dish spectra.

Arguments

Inputs infile name of input SD dataset allowed: string Default: select an antenna name or ID, e.g. 'PM03' (only effective antenna for MS input) allowed: any Default: variant 0 select data by row IDs, e.g. '3,5,7' ("=all) row allowed: string Default: field select data by field IDs and names, e.g. '3C2*' ("=all) allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: restfreq the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see examples in help) allowed: any Default: variant frame frequency reference frame ("=current) allowed: string Default: doppler convention ("=current). Effective only when doppler spw selection is in velocity unit. allowed: string Default: select data by time range, e.g. $`09:14:0\sim09:54:0'$ ("=all) timerange (see examples in help) allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: select data by polarization IDs, e.g. '0,1' ("=all) pol allowed: string Default: blmode baselining mode ('subtract' or 'apply') allowed: string Default: subtract blparam per spectrum fit parameters allowed: any Default: variant bltable name of baseline 4.3 ple allowed: string Default:

> allowed: bool Default: False

allowed:

Default:

name of output file (See a WARNING in help)

string

overwrite the output file if already exists

outfile

overwrite

Returns

void

Example

```
Keyword arguments
_____
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                 spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
   >>> spw expandable parameter
        restfreq -- the rest frequency
                    available type includes float, int, string, list of float,
                    list of int, list of string, and list of dictionary. the
                    default unit of restfreq in case of float, int, or string
                    without unit is Hz. string input can be a value only
                    (treated as Hz) or a value followed by unit for which 'GHz',
                    'MHz', 'kHz', and 'Hz' are available.
                    a list can be used to set different rest frequencies for
                    each IF. the length of list input must be number of IFs.
                    dictionary input should be a pair of line name and
                    frequency with keys of 'name' and 'value', respectively.
                    values in the dictionary input follows the same manner as
```

```
as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
        frame -- frequency reference frame
                options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
                default: '' (keep current frame in data)
        doppler -- doppler convention (effective only when spw is in
                   velocity unit)
                options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
                default: '' (keep current doppler setting in data)
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss'
                 Note: YYYY/MM/DD can be dropped as needed:
                 timerange='09:14:00~09:54:00' # this time range
                 timerange='09:44:00' # data within one integration of time
                 timerange='>10:24:00' # data after this time
                 timerange='09:44:00+00:13:00' #data 13 minutes after time
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
blmode -- 'subtract' or 'apply'
        default: 'subtract'
    >>> blmode expandable parameter
        blparam -- per spectrum fit parameters. it must be a list of
                   dictionary. Each dictionary corresponds to each
                   spectrum and must contain the following keys and values:
                     'row': row number,
                     'blfunc': function name. available ones include
                               'poly', 'chebyshev', 'cspline' and 'sinusoid',
                     'order': maximum order of polynomial. needed when
                              blfunc='poly' or 'chebyshev',
                     'npiece': number or piecewise polynomial.
                               needed when blfunc='cspline' and
                     'nwave': a list of sinusoidal wave numbers.
                              needed when blfunc='sinusoid'.
                example: [{'row':0,'blfunc':'poly','order':5},
```

----DESCRIPTION

Task sdbaseline2 performs baseline fitting/removal for single-dish spectra.

BASELINE MODEL FUNCTION

The list of available model functions are shown above (see Keyword arguments section). In general 'cspline' or 'chebyshev' are recommended since they are more stable than others. 'poly' will work for lower order but will be unstable for higher order fitting. 'sinusoid' is kind of special mode that will be useful for the data that clearly shows standing wave in the spectral baseline.

SIGMA CLIPPING (ITERATIVE FITTING)

In general least square fitting is strongly affected by an extreme data so that the resulting fit makes worse. Sigma clipping is an iterative baseline fitting with data clipping based on a certain threshold. Threshold is set as a certain factor times rms of the resulting (baseline subtracted) spectra. If sigma clipping is on, baseline fit/removal is performed several times. After each baseline subtraction, the data whose absolute value is above threshold are detected and those data are excluded from the next round of fitting. By using sigma clipping, extreme data are excluded from the fit so that resulting fit is more robust.

The user is able to control a multiplication factor using parameter clipthresh for clipping threshold based on rms. Actual threshold for sigma clipping will be (clipthresh) x (rms of spectra). Also, the user can specify number of maximum iteration to the parameter clipniter.

In general, sigma clipping will lower the performance since it increases

number of fits per spectra. However, it is strongly recommended to turn on sigma clipping unless you are sure that the data is free from any kind of extreme values that may affect the fit.

sdcal-task.html

0.1.93 sdcal

Requires:

Synopsis

ASAP SD calibration task

Description

Task sdcal performs calibration for single-dish spectra. The parameter, calmode, defines calibration mode. The available calibration modes are 'ps' (for position switching with explicit reference scans), 'otfraster' (for raster OTF scan without explicit reference scans), 'otf' (for non-raster OTF scan without explicit reference scans, e.g, Lissajous, double circle), 'fs' (for frequency switching), 'nod' (beam switching), and 'quotient' (for position switching scans by ATNF telescopes). The task selects appropriate calbiration equation based on the value of calmode and telescope with which the data is taken. See below for details of calibration equation adopted in this task. By setting calmode='none', one can run sdcal on already calibrated data for atmospheric optical depth correction.

Arguments

Inputs infile name of input SD dataset allowed: string Default: select an antenna name or ID, e.g, 'PM03' (only effective antenna for MS input) allowed: any Default: variant 0 fluxunit units of the flux ("=current) allowed: string Default: parameters of telescope for flux conversion (see examples telescopeparam in help) allowed: any Default: variant select data by field IDs and names, e.g. '3C2*' ("=all) field allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: select data by scan numbers, e.g., '21 \sim 23' (" = all) scan allowed: string Default: select data by polarization IDs, e.g, '0,1' (" = all) pol allowed: string Default: calmode SD calibration mode allowed: string Default: fraction fraction of the OFF data to mark as OFF spectra, e.g., '10%' allowed: anv Default: variant 10% noff number of the OFF data to mark (-1) = use fraction instead of number) allowed: int Default: -1 width width of the pixel for edge detection allowed: double Default: 0.5 elongated the observed area is elongated in one direction allowed: bool Default: False markonly do calibration (False) or just mark OFF (True) allowed: 460 bool

= no correction)
allowed: double
Default: 0.0

plotpointings

tau

Default:

allowed:

Default:

False

bool

False

plot pointing direction for ON and OFF

the zenith atmospheric optical depth for correction (0.

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
antenna -- select an antenna name or ID
        default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap.eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)
       NOTE this task only supports IF ID selction and ignores channel
       selection.
        default: '' (use all IFs and channels)
```

example: spw='3,5,7' (IF IDs 3,5,7; all channels) spw='<2' (IF IDs less than 2, i.e., 0,1; all channels) spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all this selection is in addition to the other selections to data scan -- select data by scan numbers default: '' (use all scans) example: scan='21~23' (scan IDs 21,22,23) this selection is in addition to the other selections to data pol -- select data by polarization IDs default: '' (use all polarizations) example: pol='0,1' (polarization IDs 0,1) this selection is in addition to the other selections to data calmode -- calibration mode options: 'ps', 'nod', 'otf', 'otfraster', 'fs', 'quotient', 'none' default: 'ps' example: choose mode 'none' if you have already calibrated and want to correct for atmospheric opacity defined by tau. >>> calmode expandable parameter fraction -- edge marker parameter of 'otf' and 'otfraster'. Specify a number of OFF integrations (at each side of the raster rows in 'otfraster' mode) as a fraction of total number of integrations. In 'otfraster' mode, number of integrations to be marked as OFF, n_off, is determined by the following formula, n_off = floor(fraction * n), where n is number of integrations per raster row. Note that n_off from both sides will be marked as OFF so that twice of specified fraction will be marked at most. For example, if you specify fraction='10%', resultant fraction of OFF integrations will be 20% at In 'otf' mode, n_off is given by, n_off = floor(fraction * n), where n is number of total integrations. n_off is used as criterion of iterative marking process. Therefore, resulting total number of

OFFs will be larger than n_off. In practice,

fraction is a geometrical fraction of edge region. Thus, if integrations are concentrated on edge region (e.g. some of Lissajous patterns), then resulting n_off may be unexpectedly large.

default: '10%'

options: '20%' in string style or float value less than 1.0 (e.g. 0.15).

'auto' is available only for 'otfraster'.

noff -- edge marking parameter for 'otfraster'.

It is used to specify a number of OFF scans near edge directly. Value of noff comes before setting by fraction. Note that n_off from both sides will be marked as OFF so that twice of specified noff will be marked at most.

default: -1 (use fraction)

options: any positive integer

width -- edge marking parameter for 'otf'.

Pixel width with respect to a median spatial separation between neighboring two data in time.

Default will be fine in most cases.

default: 0.5

options: float value

elongated -- edge marking parameter for 'otf'.

Set True only if observed area is elongeted in one direction.

options: (bool) True, False

default: False

options: (bool) True, False

default: False

plotpointings -- load plotter and plot pointing directions of

ON and OFF scans.

options: (bool) True, False

default: False

verify -- interactively verify the results of calibration.

When verify = True, for the first six on-source spectra (at max), spectra before and after the calibration are displayed in a plot window. At the prompt there are two choices of action: 'Y' (accept the operation for whole dataset), 'N' (reject the operation and finish task).

```
Note that when the operation is rejected by 'N',
          no operation is done to the spectrum/spectra.
        options: (bool) True, False
        default: False
outfile -- name of output file
        default: '' (<infile>_cal)
outform -- output file format
        options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'
        default: 'ASAP'
        NOTE the ASAP format is easiest for further sd
        processing; use MS2 for CASA imaging.
        If ASCII, then will append some stuff to
        the outfile name
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
plotlevel -- control for plotting of results
        options: (int) 0, 1, 2, and their negative counterparts
        default: 0 (no plotting)
        example: plotlevel=1; plot calibrated spectra
                 plotlevel=2; additionally list data before and after operation.
                 plotlevel<0 as abs(plotlevel), e.g.</pre>
                 -1 => hardcopy of final plot (will be named
                 <outfile>_calspec.eps)
```

DESCRIPTION:

HOW TO CHOOSE CALMODE

For position switching calibration, the user should choose appropriate calibration mode depending on the data. Use case for each mode is as follows:

'ps': position switch (including OTF) with explicit reference (OFF) scans

'otf': non-raster OTF scan without explicit OFFs (e.g. Lissajous, double circle, etc.) intends to calibrate fast scan data 'otfraster': raster OTF scan without explicit OFFs

So, if the data contains explicit reference scans, 'ps' should be used. Otherwise, 'otfraster' and 'otf' are appropriate for raster OTF and non-raster OTF, respectively. In 'otf' and 'otfraster' modes, the task first try to find several integrations near edge as OFF scans, then the

data are calibrated using those OFFs. If the observing pattern is raster, you should use the 'otfraster' mode to calibrate data. Otherwise, the 'otf' mode should be used. For detail about edge marking, see inline help of sd.edgemarker module and its methods.

Those modes are designed for OTF observations without explicit OFF scans. However, these modes should work even if explicit reference scans exist. In this case, explicit reference scans will be ignored and scans near edges detected by edge marker will be used as reference.

Except for how to choose OFFs, the procedure to derive calibrated spectra is common for the above three modes. Selected (or preset) OFF integrations are separated by its continuity in time domain, averaged in each segment, then interpolated to timestamps for ON integrations. Effectively, it means that OFF integrations are averaged by each OFF scans for 'ps' mode, averaged by either ends of each raster row for 'otfraster' mode, averaged by each temporal segments of detected edges for 'otf' mode. The formula for calibrated spectrum is

Tsys * (ON - OFF) / OFF.

The 'fs' mode is for frequency switch calibration. Currently, only GBT frequency switch data is supported.

The 'quotient' mode is special mode for "AT" telescopes, namely ANNF MOPRA. It assumes that observing sequence looks like "target, reference, target, reference,..." and it derives calibrated spectrum by applying the above formula to the pair of "target" and "reference" in order. Reference spectra are not averaged in this mode.

FLUX UNIT CONVERSION

The task is able to convert flux unit between K and Jy. To do that, fluxunit and its subparameter telescopeparam must be properly set. The fluxunit should be 'Jy' or 'K' depending on what unit input data is and what unit you want to convert. If given fluxunit is different from the unit of input data, unit conversion is performed. The telescopeparam is used to specify conversion factor. There are three ways to specify telescopeparam: 1) set Jy/K conversion factor, 2) set telescope diameter, D, and aperture efficiency, eta, separately, and 3) 'FIX' mode (only change the unit without converting spectral data). If you give telescopeparam as a list, then if the list has a single float it is assumed to be the gain in Jy/K (case 1), if two or more elements they are assumed to be telescope diameter (m) and aperture efficiency respectively (case 2).

See the above parameter description as well as note on 'FIX' mode below for details.

There are two special cases that don't need telescopeparam for unit conversion. Telescope name is obtained from the data.

- 1) ASAP (sd tool) recognizes the conversion factor (actually D and eta) for the "AT" telescopes, namely ATNF MOPRA telescope, until 2004.
- 2) The task does know D and eta for GBT telescope.

If you wish to change the fluxunit, by leaving the sub-parameter telescopeparam unset (telescopeparam=''), it will use internal telescope parameters for flux conversion for the data from AT telescopes and it will use an approximate aperture efficiency conversion for the GBT data.

Note that sdcal assumes that the fluxunit is set correctly in the data already. If not, then set telescopeparam='FIX' and it will set the default units to fluxunit without conversion.

Note also that, if the data in infile is an ms from GBT and the default flux unit is missing, this task automatically fixes the default fluxunit to 'K' before the conversion.

WARNING

For the GBT raw SDFITS format data as input:

SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs.

sdcal2-task.html

0.1.94 sdcal2

Requires:

Synopsis

ASAP SD calibration task

without explicit OFFs

Description

Task sdcal2 is an implementation of a calibration scheme like as interferometry, i.e., generate caltables and apply them. Available calibration modes are 'ps', 'otf', 'otfraster', and 'tsys'. Those modes generates caltables for sky or Tsys calibration. Those caltables can be applied to the data by using calmode 'apply'.

The above three calibration modes, 'ps', 'otf', and 'otfraster', generate sky calibration tables. The user should choose appropriate calibration mode depending on the data. Use case for each mode is as follows: 'ps': position switch (including OTF) with explicit reference (OFF) spectra 'otf': non-raster OTF scan without explicit OFFs (e.g. Lissajous, double circle, etc.) intends to calibrate fast scan data 'otfraster': raster OTF scan

So, if the data contains explicit reference spectra, 'ps' should be used. Otherwise, 'otfraster' and 'otf' are appropriate for raster OTF and non-raster OTF, respectively. In 'otf' and 'otfraster' modes, the task first try to find several integrations near edge as OFF spectra, then the data are calibrated using those OFFs. If the observing pattern is raster, you should use the 'otfraster' mode to calibrate data. Otherwise, the 'otf' mode should be used. For detail about edge marking, see inline help of sd.edgemarker module and its methods. Those modes are designed for OTF observations without explicit OFF spectra. However, these modes should work even if explicit reference spectra exist. In this case, these spectra will be ignored and spectra near edges detected by edge marker will be used as reference.

Except for how to choose OFFs, the procedure to derive calibrated spectra is common for the above three modes. Selected (or preset) OFF integrations are separated by its continuity in time domain, averaged in each segment, then interpolated to timestamps for ON integrations. Effectively, it means that OFF integrations are averaged by each OFF spectrum for 'ps' mode, averaged by either ends of each raster row for 'otfraster' mode, averaged by each temporal segments of detected edges for 'otf' mode. The formula for calibrated spectrum is

Tsys * (ON - OFF) / OFF.

Inputs infile name of input SD dataset (must be in scantable format) allowed: string Default: calmode SD calibration mode string allowed: Default: psfraction fraction of the OFF data to mark allowed: any Default: variant 10%noff number of the OFF data to mark allowed: int Default: -1 width width of the pixel for edge detection allowed: double Default: 0.5whether observed area is elongated in one direction or elongated not allowed: bool Default: False Whether Tsys is averaged in spectral axis or not tsysavg allowed: bool Default: False list of IF IDs (spectral windows) and their channel tsysspw ranges of averaging for Tsys calibration. allowed: string Default: applytable (List of) sky and/or tsys tables allowed: any Default: variant Interpolation type in time[,freq]. Valid options are interp "nearest", "linear", "cspline", or any numeric string that indicates an order of polynomial interpolation. You can specify interpolation type for time and frequency separately by joining two of the above options by comma (e.g., "linear,cspline"). allowed: string Default: A dictionary indicating IFNO combinations to apply spwmap Tsys calibration to target. The key should be IFNO for Tsys calibration and its associated value must be a list of science IFNOs to be applied. allowed: any Default: variant field select data by field IDs and names, e.g. ' $3C2^*$ ' (" = all) allowed: string Default: select data by IF IDs (spectral windows), e.g., '3,5,7' (" spw = all

Default:
pol select data by polarization IDs, e.g, '0,1' (" = all)

string

string

select data by scan numbers, e.g. '21~23' ("=all)

allowed:

Default:

allowed:

scan

Returns

void

Example

```
Keyword arguments:
infile -- Name of input SD dataset
calmode -- Calibration mode. If you want to generate calibration table
           or apply existing calibration tables, set calmode to simple
           string. On the other hand, if you want to calibrate data
           on-the-fly, you have to set calmode to a composite calmode
           string separated by comma. So far, sky calibration has three
           types, 'ps', 'otf', and 'otfraster'. If observation is
           configured to observe reference position, calmode must be
           'ps'. Otherwise, 'otf' or 'otfraster' should be used
           depending on observing pattern. If observing pattern is
           raster scan, calmode must be 'otfraster' while 'otf' must
           be used when observing pattern is non-raster
           (e.g., Lissajous).
        options: 'ps','otf','otfraster','tsys','apply'
        default: 'ps'
        example: Here is an example for composite calmode.
                 'ps,apply' (do sky cal and apply)
                 'ps,tsys,apply' (do sky and Tsys cal and apply)
   >>> calmode expandable parameter
        fraction -- Edge marker parameter of 'otf' and 'otfraster'.
                    Specify a number of OFF integrations (at each
                    side of the raster rows in 'otfraster' mode)
                    as a fraction of total number of integrations.
                    In 'otfraster' mode, number of integrations
                    to be marked as OFF, n_off, is determined by
                    the following formula,
                        n_off = floor(fraction * n),
                    where n is number of integrations per raster
                    row. Note that n_off from both sides will be
                    marked as OFF so that twice of specified
                    fraction will be marked at most. For example,
                    if you specify fraction='10%', resultant
```

most.

fraction of OFF integrations will be 20% at

In 'otf' mode, n_off is given by,
 n_off = floor(fraction * n),

where n is number of total integrations. n_off is used as criterion of iterative marking process. Therefore, resulting total number of OFFs will be larger than n_off. In practice, fraction is a geometrical fraction of edge region. Thus, if integrations are concentrated on edge region (e.g. some of Lissajous patterns), then resulting n_off may be unexpectedly large.

default: '10%'

options: '20%' in string style or float value less than 1.0 (e.g. 0.15).

'auto' is available only for 'otfraster'.

noff -- Edge marking parameter for 'otfraster'.
 It is used to specify a number of OFF spectra near
 edge directly. Value of noff comes before setting
 by fraction. Note that n_off from both sides will
 be marked as OFF so that twice of specified noff
 will be marked at most.

default: -1 (use fraction)
options: any positive integer

width -- Edge marking parameter for 'otf'.

Pixel width with respect to a median spatial separation between neighboring two data in time.

Default will be fine in most cases.

default: 0.5

options: float value

elongated -- Edge marking parameter for 'otf'.

Set True only if observed area is elongated in one direction.

default: False

tsysavg -- Whether Tsys is averaged in spectral axis or not.

default: False

options: (bool) True, False

tsysspw -- list of IF IDs (spectral windows) and their channel ranges of averaging for Tsys calibration.

It does no effect if you don't want to do Tsys calibration. the user is able to specify channel range for averaging (effective if tsysavg is True).

default: '' (auto-detect tsys spws)

example: tsysspw='3,5,7' (IF IDs 3,5,7; all channels) tsysspw='<2' (IF IDs less than 2; all channels)

```
applytable -- List of sky/Tsys calibration tables you want to
                      apply.
                default: ''
        interp -- Interpolation method in time and frequency axis.
                  Set comma separated method strings if you want
                  to use different interpolation in time and
                  frequency.
                options: 'linear', 'cspline', 'nearest',
                         any numeric string indicating an order
                         of polynomial.
                default: '' (linear in time and frequency)
                example: 'linear,cspline' (linear in time, cubic
                                           spline in frequency)
                         'linear,3' (linear in time, third order
                                     polynomial in frequency)
                         'nearest' (nearest in time and frequency)
        spwmap -- Dictionary defining transfer of Tsys calibration.
                  Key must be IFNO for Tsys and its value must be
                  a list of IFNOs for science target.
                default: {}
                example: {1: [5,6], 3: [7,8]}
                         Tsys in IFN01 is transferred to IFN05, 6
                         while Tsys in IFNO3 is to IFNO7, 8.
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)
        NOTE this task only supports IF ID selction and ignores channel
        selection.
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
```

tsysspw='1:0~100' (IF ID1; between channels 0 and 100)

outfile -- Name of output file

NOTE if you omit, behavior of the task depends on calmode. If calmode includes 'apply', then omitting outfile indicates that infile is overwritten by the calibrated data. In this case, you have to set overwrite to True. If calmode doesn't include 'apply', omitting outfile indicates that the task will use default outfile name based on infile and predefined suffix ('_sky' for sky, '_tsys' for Tsys).

overwrite -- overwrite the output file if already exists

options: (bool) True, False

default: False

NOTE this parameter is ignored when outform='ASCII'

DESCRIPTION:

Task sdcal2 is an implementation of a calibration scheme like as interferometry, i.e., generate caltables and apply them. Available calibration modes are 'ps', 'otf', 'otfraster', and 'tsys'. Those modes generates caltables for sky or Tsys calibration. Those caltables can be applied to the data by using calmode 'apply'.

The above three calibration modes, 'ps', 'otf', and 'otfraster', generate sky calibration tables. The user should choose appropriate calibration mode depending on the data. Use case for each mode is as follows:

'ps': position switch (including OTF) with explicit reference (OFF) spectra 'otf': non-raster OTF scan without explicit OFFs (e.g. Lissajous, double circle, etc.) intends to calibrate fast scan data 'otfraster': raster OTF scan without explicit OFFs

So, if the data contains explicit reference spectra, 'ps' should be used. Otherwise, 'otfraster' and 'otf' are appropriate for raster OTF and non-raster OTF, respectively. In 'otf' and 'otfraster' modes, the task first try to find several integrations near edge as OFF spectra, then the data are calibrated using those OFFs. If the observing pattern is raster, you should use the 'otfraster' mode to calibrate data. Otherwise, the 'otf' mode should be used. For detail about edge marking, see inline help of sd.edgemarker module and its methods. Those modes are designed for OTF observations without

explicit OFF spectra. However, these modes should work even if explicit reference spectra exist. In this case, these spectra will be ignored and spectra near edges detected by edge marker will be used as reference.

Except for how to choose OFFs, the procedure to derive calibrated spectra is common for the above three modes. Selected (or preset) OFF integrations are separated by its continuity in time domain, averaged in each segment, then interpolated to timestamps for ON integrations. Effectively, it means that OFF integrations are averaged by each OFF spectrum for 'ps' mode, averaged by either ends of each raster row for 'otfraster' mode, averaged by each temporal segments of detected edges for 'otf' mode. The formula for calibrated spectrum is

Tsys * (ON - OFF) / OFF.

ps

You can calibrate data on-the-fly like sdcal task by setting calmode to a composite calmode string separated by comma. For example, calmode='ps,apply' means doing sky calibration and apply it on-the-fly. In this case, caltable is generated as a temporary plain table and will be deleted at the end. Allowed calibration modes in this task is as follows:

```
generate sky caltable using 'ps' mode
otf
    generate sky caltable using 'otf' mode
    generate sky caltable using 'otfraster' mode
tsys
    generate tsys caltable
apply
    apply caltables specified by applytable parameter
ps,apply
    generate temporary sky caltable using 'ps' mode and
    apply it. also apply caltables specified by applytable
ps, tsys, apply
    generate temporary sky caltable using 'ps' mode as well
    as temporary tsys caltable, and apply them.
otf,apply
    generate temporary sky caltable using 'otf' mode and
    apply it. also apply caltables specified by applytable
otf, tsys, apply
    generate temporary sky caltable using 'otf' mode as well
```

```
as temporary tsys caltable, and apply them.

otfraster,apply
generate temporary sky caltable using 'otfraster' mode
and apply it. also apply caltables specified by applytable

otfraster,tsys,apply
generate temporary sky caltable using 'otfraster' mode
as well as temporary tsys caltable, and apply them.
```

There are several control parameters for sky/Tsys calibration and application of caltables. See the above parameter description.

In ALMA, Tsys measurement is usually done using different spectral setup from spectral windows for science target. In this case, sdcal2 transfers Tsys values to science spectral windows in the application stage. To do that, the user has to give a list of spectral windows for Tsys measurement as well as mapping between spectral windows for Tsys measurement and scicence target. These can be specified by parameters 'tsysspw' and 'spwmap', which are defined as subparameters of 'calmode'. For example, suppose that Tsys measurements for science windows 17, 19, 21, and 23 are done in spw 9, 11, 13, and 15, respectively. In this case, tsysspw and spwmap should be specified as follows:

```
tsysspw = '9,11,13,15'
spwmap = {9:[17],11:[19],13:[21],15:[23]}
```

Below is an example of full specification of task parameters for calmode of 'ps,tsys,apply':

```
default(sdcal2)
infile = 'foo.asap'
calmode = 'ps,tsys,apply'
spw = ''
tsysspw = '9,11,13,15'
spwmap = {9:[17],11:[19],13:[21],15:[23]}
outfile = 'bar.asap'
sdcal2()
```

Note that, in contrast to applycal task, spwmap must be a dictionary with Tsys spectral window as key and a list of corresponding science spectral window as value. Note also that the parameter 'spw' should not be used to specify a list of spectral windows for Tsys measurement. It is intended to select data to be calibrated so that the list should contain spectral windows for both science target and Tsys measurement. The task will fail if you use 'spw' instead of 'tsysspw'.

For Tsys calibration, the user is able to choose whether Tsys is

averaged in spectral axis or not. If tsysavg is False (default), resulting Tsys is spectral value. On the other hand, when tsysavg is True, Tsys is averaged in spectral axis before output. The channel range for averaging is whole channels by default. If channel range is specified by tsysspw string, it is used for averaging. The user can specify channel range with ms selection syntax. For example,

tsysspw = '1:0~100'

specifies spw 1 for Tsys calibration and channel range between channel 0 and 100 for averaging. You can specify more than one ranges per spw.

tsysspw = '1:0~100;200~400'

In this case, selected ranges are between 0 and 100 plus 200 and 400. Note that even if multiple ranges are selected, the task average whole ranges together and output single averaged value. You can specify multiple spws by separating comma.

tsysspw = '1:0~100,3:400~500'

Note that specified channel range is ignored if tsysavg is False.

sdcoadd-task.html

0.1.95 sdcoadd

Requires:

Synopsis

Coadd multiple scantables into one

Description

Task sdcoadd performs co-add multiple single dish spectral data given by a list of spectral data file names in any of the following formats, ASAP, MS2,SDFITS, and ASCII. The units of line flux, the units of spectral axis, frame, and doppler are assumed to be those of the first one in the infiles. The task tries to combine spws according to a tolerance value specified by the parameter freqtol. Default tolerance is '0Hz', which means spws are combined only when spectral setup are the same. Note that, except for first data in the infiles, spw is ignored if there are no corresponding spectral data in the main table.

Inputs infiles list of names of input SD dataset

stringArray

allowed: Default:

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input) allowed: any

Default: variant 0

freqtol Frequency shift tolerance for considering data as the

same spwid

allowed: any Default: variant

outfile name of output file (See a WARNING in help)

allowed: string

Default:

outform output file format (See a WARNING in help)

allowed: string Default: ASAP

overwrite overwrite the output file if already exists (See a WARN-

ING in help)

allowed: bool Default: False

Returns

void

Example

```
Keyword arguments
------
infiles -- list of names of input SD dataset
antenna -- select an antenna name or ID
    default: 0
    example: 'PMO3'
    NOTE this parameter is effective only for MS input
freqtol -- Frequency shift tolerance for considering data to be in the same
    spwid. The number of channels must also be the same.
    default: '' == 0 Hz (combine spwid only when frequencies are the same)
    example: freqtol='10MHz' will not combine spwid unless they are
```

within 10 MHz.

Note: This option is useful to combine spectral windows with very slight frequency differences caused by Doppler tracking, for example.

outfile -- name of output file

default: '' (<infile>_coadd)

outform -- format of output file

options: 'ASCII', 'SDFITS', 'MS', 'ASAP'

default: 'ASAP'

example: the ASAP format is easiest for further sd processing; use MS for CASA imaging.

If ASCII, then will append some stuff to

the outfile name

overwrite -- overwrite the output file if already exists

options: (bool) True, False

default: False

NOTE this parameter is ignored when outform='ASCII'

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs. sdfit-task.html

0.1.96 sdfit

Requires:

Synopsis

Fit a spectral line

Description

Task sdfit is a basic line-fitter for single-dish spectra. It assumes that the spectra have been calibrated in sdcal or sdreduce.

Outputs

xstat RETURN ONLY: a Python dictionary of line statistics

allowed: any

Default: variant

Inputs

fluxunit

scan

infile name of input SD dataset

allowed: string

Default:

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any

Default: variant 0

units of the flux ("=current)

allowed: string

Default:

telescope for flux conversion (see examples

in help)

allowed: any Default: variant

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

restfreq the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see

examples in help)
allowed: any
Default: variant

frame frequency reference frame ("=current)

allowed: string

Default:

doppler doppler convention ("=current). Effective only when

spw selection is in velocity unit.

allowed: string

Default:

select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: string

Default:

timeaverage average spectra over time (see examples in help)

allowed: bool Default: 481 False

tweight weighting for time averaging

allowed: string
Default: tintsys

scanaverage average spectra within a scan number (see examples in

help)

allowed: bool Default: False

polaverage average spectra over polarizations

Returns

variant

Example

```
Keyword arguments
_____
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap. eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
```

```
spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
    >>> spw expandable parameter
        restfreq -- the rest frequency
                    available type includes float, int, string, list of float,
                    list of int, list of string, and list of dictionary. the
                    default unit of restfreq in case of float, int, or string
                    without unit is Hz. string input can be a value only
                    (treated as Hz) or a value followed by unit for which 'GHz',
                    'MHz', 'kHz', and 'Hz' are available.
                    a list can be used to set different rest frequencies for
                    each IF. the length of list input must be number of IFs.
                    dictionary input should be a pair of line name and
                    frequency with keys of 'name' and 'value', respectively.
                    values in the dictionary input follows the same manner as
                    as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
        frame -- frequency reference frame
                options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
                default: '' (keep current frame in data)
        doppler -- doppler convention (effective only when spw is in
                   velocity unit)
                options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
                default: '' (keep current doppler setting in data)
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
fitfunc -- function for fitting
        options: 'gauss' (Gaussian), 'lorentz' (Lorentzian)
        default: 'gauss'
fitmode -- mode for fitting
        options: 'auto', 'list', or 'interact'
        default: 'auto'
```

spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all

>>> fitmode expandable parameters

thresh -- S/N threshold for linefinder. a single channel S/N ratio above which the channel is considered to be a detection. default: 5

default: 4

default: 0.2

edge -- channels to drop at beginning and end of spectrum

default: 0

example: edge=[1000] drops 1000 channels at beginning AND end.
 edge=[1000,500] drops 1000 from beginning and 500
 from end

Note: For bad baselines threshold should be increased, and avg_limit decreased (or even switched off completely by setting this parameter to 1) to avoid detecting baseline undulations instead of real lines.

nfit -- list of number of gaussian/lorentzian lines to fit in in maskline region (ignored when fitmode='auto')

default: 0 (no fitting)

nfit=[1,1] for single lines in each of two regions, etc.

outfile -- name of output file

default: no output fit file

example: 'mysd.fit'

overwrite -- overwrite the output file if already exists options: (bool) True, False

default: False

plotlevel -- control for plotting of results

options: 0, 1, 2

default: 0 (no plotting)

example: plotlevel=0 no plotting
 plotlevel=1 plots fit

plotlevel=2 plots fit and residual
no hardcopy available for fitter

WARNING: be careful plotting OTF data with lots of fields

Returns

a Python dictionary of line statistics keys: 'peak', 'cent', 'fwhm', 'nfit'

example: each value is a list of lists with one list of 2 entries [fitvalue,error] per component.
e.g. xstat['peak']=[[234.9, 4.8],[234.2, 5.3]]
for 2 components.

DESCRIPTION

Task sdfit is a basic line-fitter for single-dish spectra. It assumes that the spectra have been calibrated in sdcal or sdreduce.

Furthermore, it assumes that any selection of scans, IFs, polarizations, and time and channel averaging/smoothing has also already been done (in other sd tasks) as there are no controls for these. Note that you can use sdsave to do selection, writing out a new scantable.

Note that multiple scans, IFs, and polarizations can in principle be handled, but we recommend that you use scan, field, spw, and pol to give a single selection for each fit.

Currently, you can choose Gaussian or Lorentzian profile as a fitting model.

For complicated spectra, sdfit does not do a good job of "auto-guessing" the starting model for the fit. We recommend you use sd.fitter in the toolkit which has more options, such as fixing components in the fit and supplying starting guesses by hand.

FITMODE

As described in the parameter description section, sdfit implements three fitting mode, 'auto', 'list', and 'interact'. Only difference between these modes are a method to set initial guess for line fitting. In 'auto' mode, initial guess is automatically set by executing line finder. On the other hand, 'list' and 'interact' allow to set initial guess manually. In these modes, only controllable parameter for the guess is range of the line region and number of lines per region. In 'list' mode, the user must give line region via spw parameter by using ms selection syntax while number of lines per region can be specified via nfit parameter. For example,

spw = '17:1500~2500'
nfit = [1]

will set line region between channels 1500 and 2500 for spw 17, and indicate that there is only one line in this region. Specifying single region with multiple line is also possible but is not recommended. In 'interact' mode, spectral data to be fitted will be displayed with pre-defined line region specified by spw parameter. The user is able to customize line region interactively.

FLUX UNIT CONVERSION

The task is able to convert flux unit between K and Jy. To do that, fluxunit and its subparameter telescopeparam must be properly set. The fluxunit should be 'Jy' or 'K' depending on what unit input data is and what unit you want to convert. If given fluxunit is different from the unit of input data, unit conversion is performed. The telescopeparam is used to specify conversion factor. There are three ways to specify telescopeparam: 1) set Jy/K conversion factor, 2) set telescope diameter, D, and aperture efficiency, eta, separately, and 3) 'FIX' mode (only change the unit without converting spectral data). If you give telescopeparam as a list, then if the list has a single float it is assumed to be the gain in Jy/K (case 1), if two or more elements they are assumed to be telescope diameter (m) and aperture efficiency respectively (case 2).

See the above parameter description as well as note on 'FIX' mode below for details.

There are two special cases that don't need telescopeparam for unit conversion. Telescope name is obtained from the data.

- 1) ASAP (sd tool) recognizes the conversion factor (actually D and eta) for the "AT" telescopes, namely ATNF MOPRA telescope, until 2004.
- 2) The task does know D and eta for GBT telescope.

If you wish to change the fluxunit, by leaving the sub-parameter telescopeparam unset (telescopeparam=''), it will use internal telescope parameters for flux conversion for the data from AT telescopes and it will use an approximate aperture efficiency conversion for the GBT data.

Note that sdcal assumes that the fluxunit is set correctly in the data already. If not, then set telescopeparam='FIX' and it will set the default units to fluxunit without conversion.

Note also that, if the data in infile is an ms from GBT and the default flux unit is missing, this task automatically fixes the default fluxunit to 'K' before the conversion.

AVERAGING OF SPECTRA

Task sdfit has two averaging modes, i.e., time and polarization average.

When timeaverage=True, spectra are averaged over time for each IF (spectral window), polarization, and beam, independently. Note that, by default (scanaverage=False), timeaverage=True averages spectra irrespective of scan IDs.

It is possible to average spectra separately for each scan ID by setting a sub-parameter scanaverage=True.

For example, the combination of parameters: scan='0~2', timeaverage=True, and scanaverage=False: averages spectra in scan ID 0 through 2 all together to a spectrum,

scanaverage=True : averages spectra per scan ID and end up with three spectra from scan 0, 1, and 2.

When polaverage=True, spectra are averaged over polarization for each IF (spectral window) and beam. Note that, so far, time averaging is automatically switched on when polaverage is set to True. This behavior is not desirable and will be discarded in future.

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet,

so that there may be unknown bugs.

sdflag-task.html

0.1.97 sdflag

Requires:

Synopsis

ASAP SD spectral spectral/row flagging task

Description

Task sdflag performs either interactive or non-interactive channel/row based flagging on spectra.

Currently, there are three ways of non-interactive flagging available: (1) channel or row based flagging by selecting spectra by field, lists of scan numbers, IF numbers, and polarization idices in mode='manual', (2) channel based flagging by specifying a range of spectral values in mode='clip', and (3) row based flagging by specifying a list of row numbers in mode='rowid'. Note this is an EXPERT mode since it might not be straight forward for general users to select data by row IDs in scantable.

In mode='manual', the channel based flagging are invoked when spw parameter contains channel range selection. Otherwise, the whole channels are flagged for the selected spectra. Note channel range selection by spw parameter has effect only in mode='manual'.

Interactive flagging is available when mode='interactive'. The available ways of interactive flagging include: (1) row based flagging by selecting 'panel' and (2) channel based flagging by selecting 'region's of channels on Flag plotter. See the cookbook for details of how to select channel regions and spectra on the plotter.

NOTE the task sdflag only modifies flag information, FLAGROW and FLAGTRA, in the input scantable. This task keeps all records in input dataset. Data selection parameters are used for selecting data to modify flag information.

If plotlevel =1, the task asks you if you really apply the flags before it is actually written to the data with a plot indicating flagged regions.

WARNING for overwrite option: Be sure 'outform' is the same as data format of input file when you overwrite it. The default value of the option 'overwrite' is True in this task, thereby the current dataset (infile) is overwritten unless a different file name is set to outfile. There is a known issue in overwriting infile. If 'outform' differs to the data format of infile, the data is overwritten with the

new data format (specified by 'outform') and the data in the original format

will be lost.

Inputs infile name of input SD dataset allowed: string Default: select an antenna name or ID, e.g, 'PM03' (only effective antenna for MS input) allowed: any Default: variant 0 mode mode of data selection and flag operation allowed: string Default: manual unflag selected data (False: flag, True: unflag) unflag allowed: bool Default: False field select data by field IDs and names, e.g. '3C2*' (" = all) allowed: Default: spw select data by IF IDs (spectral windows), e.g., '3,5,7' (" = allallowed: string Default: select data by time range, e.g., '09:14:0 \sim 09:54:0' (" = timerange all) (see examples in help) allowed: string Default: select data by scan numbers, e.g., '21 \sim 23' (" = all) scan allowed: string Default: pol select data by polarization IDs, e.g., 0.1' (" = all) allowed: string Default: select data by beam IDs, e.g, '0,1' (" = all) beam allowed: string Default: restfreq the rest frequency, '1.41GHz' (default unit: Hz). Effective only when spw selection is in velocity unit. (see examples in help) allowed: any Default: variant frequency reference frame ("=current) Effective only frame when spw selection is in velocity or frequency unit. allowed: string Default: doppler doppler convention ("=current). Effective only when spw selection is in velocity unit. allowed: string Default: 490 range of data that will NOT be flagged clipminmax allowed: any Default: variant

clip outside the range, or within it

any

show flagged data (in gray) on plots

variant True

allowed:

Default:

clipoutside

showflagged

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
mode -- type of flag operation
        options: (str) 'manual', 'clip', 'interactive', 'rowid'
        default: 'manual'
     >>> common data selection parameters for all modes except mode='rowid'
        field -- select data by field IDs and names
                default: '' (use all fields)
                example: field='3C2*' (all names starting with 3C2)
                         field='0,4,5~7' (field IDs 0,4,5,6,7)
                         field='0,3C273' (field ID 0 or field named 3C273)
                this selection is in addition to the other selections to data
        spw -- select data by IF IDs (spectral windows)/channels
                NOTE channel range selection is valid only in mode='manual'
                default: '' (use all IFs and channels)
                example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                         spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                         spw='115GHz' (IF IDs with the center frequencies in range 30-45GHz
                         spw='0:5~61' (IF ID 0; channels 5 to 61)
                         spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                         spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3
                         spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 as
                this selection is in addition to the other selections to data
        timerange -- select data by time range
                default: '' (use all)
                example: timerange = 'YYYY/MM/DD/hh:mm:ss"YYYY/MM/DD/hh:mm:ss'
                         Note: YYYY/MM/DD can be dropped as needed:
                         timerange='09:14:00~09:54:00' # this time range
                         timerange='09:44:00' # data within one integration of time
                         timerange='>10:24:00' # data after this time
                         timerange='09:44:00+00:13:00' #data 13 minutes after time
                this selection is in addition to the other selections to data
```

```
scan -- select data by scan numbers
           default: '' (use all scans)
           example: scan='21~23' (scan IDs 21,22,23)
           this selection is in addition to the other selections to data
   pol -- select data by polarization IDs
           default: '' (use all polarizations)
           example: pol='0,1' (polarization IDs 0,1)
           this selection is in addition to the other selections to data
   beam -- select data by beam IDs
           default: '' (use all beams)
           example: beam='0,1' (beam IDs 0,1)
           this selection is in addition to the other selections to data
>>> common data parameters for all modes except mode='interactive'
   unflag -- flag or unflag
           default: False (flag selected data)
           options: (bool) True, False
>>> mode='manual' expandable parameters
   restfreq -- the rest frequency (effective only when spw selection is in
               velocity unit.)
               available type includes float, int, string, list of float,
               list of int, list of string, and list of dictionary. the
               default unit of restfreq in case of float, int, or string
               without unit is Hz. string input can be a value only
               (treated as Hz) or a value followed by unit for which 'GHz',
               'MHz', 'kHz', and 'Hz' are available.
               a list can be used to set different rest frequencies for
               each IF. the length of list input must be number of IFs.
               dictionary input should be a pair of line name and
               frequency with keys of 'name' and 'value', respectively.
               values in the dictionary input follows the same manner as
               as for single float or string input.
           example: 345.796
                    '1420MHz'
                    [345.8, 347.0, 356.7]
                    ['345.8MHz', '347.0MHz', '356.7MHz']
                    [{'name':'CO','value':345}]
   frame -- frequency reference frame (effective only when spw selection is in
            velocity or frequency unit.)
           options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
           default: '' (keep current frame in data)
   doppler -- doppler convention (effective only when spw is in
              velocity unit)
           options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
           default: '' (keep current doppler setting in data)
```

```
>>> mode='clip' expandable parameters
        clipminmax -- range of data that will NOT be flagged
                default: [] (means no clip operation)
                example: [0.0, 1.5]
        clipoutside -- clip OUTSIDE the range ?
                options: (bool)True,False
                default: True
                example: clipoutside=False means flag data WITHIN the range.
     >>> mode='interactive' expandable parameters
        showflagged -- show flagged data on plots
                options: (bool) True, False
                default: False
     >>> mode='rowid' expandable parameters
        row -- select data by row IDs to apply flag/unflag in the input scannable
                Note, this parameter is effective only when one or more row
                IDs are given explicitly
                default: '' (means no selection)
                example: '200~300,400~500' (rows 200 to 300 and 400 to 500)
outfile -- name of output file
        default: ''
        Note: by default (outfile=''), actual output file name is set as follows:
              (1) if overwrite=True (default), infile (input) will be overwritten.
              WARNING: If the formats of input and ouput files are different,
                       this causes complete loss of input file.
              (2) if overwrite=False, outfile will be <infile>_f.
outform -- output file format
        options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'
        default: 'ASAP'
        NOTE the ASAP format is easiest for further sd
        processing; use MS2 for CASA imaging.
        If ASCII, then will append some stuff to
        the outfile name
        WARNING: Be sure outform is same as the input file format when you
                 overwrite the input file by overwrite=True and outfile='' (default).
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: True
        WARNING: input file is overwritten if overwrite=True and outfile='' (default).
                 This causes the complete loss of input file if the formats of
                 input and ouput files are different.
plotlevel -- control for plotting of results
        options: (int) 0, 1, 2, and their negative counterparts
        default: 0 (no plotting)
        example: plotlevel=1; plot spectra and flagged channels before and after
                         current operation. asked if you accept the flag for each
                         spw. also, the first spectrum after the operation is plotted.
```

plotlevel=2; additionally list scantable before and after operation.
plotlevel<0 as abs(plotlevel), e.g.
-1 => hardcopy of final plot (will be named
<outfile>_flag.eps)

sdflagmanager-task.html

0.1.98 sdflagmanager

Requires:

Synopsis

ASAP SD task to manipulate flag version files

Description

Task sdflagmanager enables users to save the current flag information (both channel and row flags) in the given SD dataset out to a separate 'flag version file'. In the current implementation, sdflagmanager calls flagmanager internally, so these flag version files are copies of the flag columns for a measurement set actually. They can be restored to the data set to obtain a previous flag version. Users can also list, delete and rename flag version files using sdflagmanager. It is wise to save a flagversion at the beginning or after serious editing.

Inputs		
infile	name of input SD dataset (ASAP scantable)	
	allowed:	string
	Default:	
mode	operation mode	
	allowed:	string
	Default:	list
versionname	Flag version name	
	allowed:	string
	Default:	
oldname	Flag version to rename	
	allowed:	string
	Default:	
comment	Short description of a versionname	
	allowed:	string
	Default:	
merge	Merge option	: replace will save or over-write the flags
	allowed:	string
	Default:	replace

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
        default: ''
        example: infile='ngc5921.asap'
mode -- Flag version operation
        default: 'list'; to list existing flagtables
                           to copy flag columns of infile to a flag file
                 'restore' to place the specified flag file into infile
                 \mbox{'delete'} to delete the specified flag file
                 'rename' to rename the specified flag file
   >>> mode expandable parameters
        versionname -- Flag version name
                default: none; example: versionname='original_data'
                No imbedded blanks in the versionname
        comment -- Short description of a versionname, when mode is 'save'
                   or 'rename'
                default: ''
                example: comment='Clip above 1.85'
                         comment = versionname
        oldname -- When mode='rename', the flag file to rename
        merge -- merge operation
                options: 'or', 'and', but not recommended for now.
```

sdgrid-task.html

0.1.99 sdgrid

Requires:

Synopsis SD gridding task

Description

Task sdgrid performs spatial gridding according to the user specification of spatial grid, convolution function, etc. For grid configuration, the task supplements necessary information by referring input data if any of gridding parameter ('npix', 'cell', or 'center') is not specified by the user. If 'center' is default value (empty string), central position of the grid will be set to the center of observed area, i.e. x=0.5*(xmax+xmin), y=0.5*(ymax+ymin). If either 'cell' or 'npix' is set, unspecified one will be calculated from the others. In that case, total extent of the grid will be set to cover all observed position. If neither 'cell' nor 'npix' is set, cell size will be set to 1.0 arcmin and number of pixel will be calculated based on that cell size. Currently, only J2000 frame is supported.

Inputs infiles a list of names of input SD datasets allowed: any variant "" Default: select an antenna name or ID, e.g. 'PM03' (only effective antenna for MS input) allowed: any Default: variant -1 select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: -1 scan select data by scan numbers, e.g. '21~23' ("=all) allowed: Default: pol select data by polarization IDs, e.g. '0,1' ("=all) allowed: string Default: gridfunction gridding function for imaging allowed: string Default: BOX truncate of convolution kernel convsupport allowed: int Default: -1 truncate truncation radius of convolution kernel allowed: any Default: variant -1gwidth HWHM for gaussian allowed: any Default: variant -1 jwidth c-parameter for jinc function allowed: any Default: variant -1 weight weight type allowed: string Default: UNIFORM clipminmax clip minimum and maximum values during gridding allowed: bool Default: False outfile name of output file allowed: string Default: overwrite overwrite the output file if already exists [True, False] bool allowed: False Default: number of pixels in x and y, symmetric for single value npix allowed: any

center Image center

cell

allowed: any Default: variant

493 griant -1

x and y cell size. default unit arcsec

variant

any

Default:

allowed:

Default:

Returns

void

Example

```
Keyword arguments:
infiles -- a list of names of input SD datasets. in case input is a
           single dataset, its name can be given as a string.
        example: 'testimage.asap'
                 ['testimage1.asap','testimage2.asap']
antenna -- select an antenna name or ID
        default: -1
        example: 'PM03'
        NOTE this parameter is effective only for MS input
spw -- select data by IF IDs (spectral windows)
       NOTE this task only supports IF ID selction and ignores channel
       selection.
        default: '-1' (only process IFNO in the first row)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
gridfunction -- gridding function
        options: 'BOX' (Box-car), 'SF' (Spheroidal),
                 'GAUSS' (Gaussian), 'PB' (Primary-beam)
                 'GJINC' (Gaussian*Jinc)
        default: 'BOX'
        example: 'SF'
    >>> gridfunction expandable parameter:
        convsupport -- convolution support for 'SF'
                default: -1 (use default for each gridfunction)
                example: 3
        truncate -- truncattion radius of convolution kernel.
                    effective only for 'GAUSS' and 'GJINC'.
```

```
default: '-1' (use default for each gridfunction)
                example: 3, '20arcsec', '3pixel'
        gwidth -- HWHM for gaussian. Effective only for
                  'GAUSS' and 'GJINC'.
                default: '-1' (use default for each gridfunction)
                example: 3, '20arcsec', '3pixel'
        jwidth -- Width of jinc function. Effective only for
                  'GJINC'.
                default: '-1' (use default for each gridfunction)
                example: 3, '20arcsec', '3pixel'
weight -- weight type (both lower-case and upper-case are acceptable)
        options: 'UNIFORM',
                 'TSYS' (1/Tsys**2 weighted)
                 'TINT' (integration time weighted)
                 'TINTSYS' (Tint/Tsys**2)
        default: 'UNIFORM'
clipminmax -- do min/max cliping if True
        default: False
outfile -- name of output file
        default: '' (outfile will be set to infile[0]+'.grid')
        example: 'mydata.asap.grid'
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
npix -- x and y image size in pixels, symmetric for single value
        default: -1 (automatically calculated from cell size and
                     the data)
        example: npix=200 (equivalent to [200,200])
cell -- x and y cell size. default unit arcsec
        default: '' (automatically calculated from npix if it is
                     set, otherwise '1.0arcmin')
        example: cell=['0.2arcmin, 0.2arcmin']
                 cell='0.2arcmin' (equivalent to example above)
                 cell=12.0 (interpreted as '12.0arcsec'='0.2arcmin')
center -- grid center
        default: '' (automatically calculated from the data)
        example: 'J2000 13h44m00 -17d02m00'
                 ['05:34:48.2', '-05.22.17.7'] (in J2000 frame)
                 [1.46, -0.09] (interpreted as radian in J2000 frame)
plot -- Plot result or not
        default: False (not plot)
        example: if True, result will be plotted
```

DESCRIPTION:

The sdgrid task performs spatial gridding according to the user specification of spatial grid, convolution function, etc.

For grid configuration, the task supplements necessary information by referring input data if any of gridding parameter ('npix', 'cell', or 'center') is not specified by the user. If 'center' is default value (empty string), central position of the grid will be set to the center of observed area, i.e. x=0.5*(xmax+xmin), y=0.5*(ymax+ymin). If either 'cell' or 'npix' is set, unspecified one will be calculated from the others. In that case, total extent of the grid will be set to cover all observed position. If neither 'cell' nor 'npix' is set, cell size will be set to 1.0 arcmin and number of pixel will be calculated based on that cell size.

Currently, only J2000 frame is supported.

The parameter gridfunction sets gridding function for imaging. Currently, the task supports 'BOX' (Box-car), 'SF' (Prolate Spheroidal Wave Function), 'GAUSS' (Gaussian), 'GJINC' (Gaussian* Jinc), where $\text{Jinc}(x) = J_1(\text{pi*x/c})/(\text{pi*x/c})$ with a first order Bessel function J_1 , and 'PB' (Primary Beam, not implemented yet). For 'PB', correct antenna informations should be included in input file.

There are four subparameters for gridfunction: convsupport, truncate, gwidth, and jwidth. The convsupport is an integer specifying cut-off radius for 'SF' in units of pixel. By default (convsupport=-1), the cut-off radius is set to 3 pixels. The truncate is a cut-off radius for 'GAUSS' or 'GJINC'. It accepts integer, float, and string values of numeric plus unit. Allowed units are angular units such as 'deg', 'arcmin', 'arcsec', and 'pixel'. Default unit is 'pixel' so that string without unit or numerical values (integer or float) will be interpreted as radius in pixel. Default value for truncate, which is used when negative radius is set, is 3*HWHM for 'GAUSS' and radius at first null for 'GJINC'. The gwidth is the HWHM of gaussian for 'GAUSS' and 'GJINC'. Default value is sqrt(log(2)) pixel for 'GAUSS' and 2.52*sqrt(log(2)) pixel for 'GJINC'. The jwidth specifies width of the jinc function (parameter 'c' in the definition above). Default is 1.55 pixel. Both gwidth jwidth allows integer, float, or string of numeric plus unit. Default values for gwidth and jwidth are taken from Mangum et al. (2007). Formula for 'GAUSS' and 'GJINC' are taken from Table 1 in the paper, and are written as below using gwidth and jwidth:

GAUSS: exp[-(|r|/gwidth)**2]

GJINC: $J_1(pi*|r|/jwidth)/(pi*|r|/jwidth) * exp[-(|r|/gwidth)^2]$

Boolean parameter 'plot' controls whether gridded result is plotted or not. If True, color map of gridded data will be shown. Pixel center and observed position are overlayed as blue dot and red dot, respectively. Currently, channel averaged value will be plotted.

Reference: Mangum, et al. 2007, A&A, 474, 679-687

sdimaging-task.html

0.1.100 sdimaging

Requires:

Synopsis

SD task: imaging for total power and spectral data

Description

Task sdimaging creates an image from input single-dish data sets. The input can be either total power and spectral data. Currently, this task directly accesses the Measurement Set data because of the data access efficiency. So it differs from other single-dish tasks that mostly operate on the ASAP scantable data format.

The coordinate of output image is defined by four axes, i.e., two spatial axes, frequency and polarization axes. By default, spatial coordinate of image is defined so that the all pointing directions in POINTING tables of input data sets are covered with the cell size, 1/3 of FWHM of primary beam of antennas in the first MS. Therefore, it is often easiest to leave spatial definitions at the default values. It is also possible to define spatial axes of the image by specifying the image center direction (phasecenter), number of image pixel (imsize) and size of the pixel (cell). The frequency coordinate of image is defined by three parameters, the number of channels (nchan), the channel id/frequency/velocity of the first channel (start), and channel width (width). There are three modes available to define unit of start and width, i.e., 'channel' (use channel indices), 'frequency' (use frequency unit, e.g., 'GHz'), and 'velocity' (use velocity unit, e.g., 'km/s'). By default, nchan, start, and width are defined so that all selected spectral windows are covered with the channel width equal to separation of first two channels selected. Finally, polarizations of image is defined by stokes parameter or polarization. For example, stokes='XXYY' produces an image cube with each plane contains the image of one of the polarizations, while stokes='I' produces a 'total intensity' or Stokes I image.

The task also supports various grid function (convolution kernel) to weight spectra. See description below for details of gridfunction available.

Inputs infiles a list of names of input SD Measurementsets (only MS is allowed for this task) allowed: stringArray Default: outfile name of output image allowed: string Default: overwrite overwrite the output file if already exists [True, False] allowed: bool Default: False field select data by field IDs and names, e.g. '3C2*' ("=all) allowed: any Default: variant select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: any Default: variant select data by antenna names or IDs, e.g, 'PM03' (" = antenna all antennas) allowed: any Default: variant select data by scan numbers, e.g. '21~23' ("=all) scan allowed: any Default: variant intent select data by observational intent, e.g. '*ON_SOURCE*' ("=all) allowed: any Default: variant mode spectral gridding type allowed: string Default: channel nchan number of channels (planes) in output image (-1=all) allowed: int Default: -1 start of output spectral dimension, e.g. '0', '110GHz', start $'-20 \mathrm{km/s}'$ allowed: any Default: variant 0width width of output spectral channels allowed: any Default: variant 1 veltype velocity definition allowed: string Default: radio

velocity frame of output image ("=current frame or

LSRK for multiple-MS inputs)

string

gridfunction gridding function for imaging (see description in help) allowed: string

allowed:

Default:

outframe

Returns

void

Example

```
Keyword arguments:
infiles -- a list of names of input SD Measurementsets
        example: 'm100.PM01.ms'
                 ['m100.PM01.ms', 'm100.PM03.ms']; multiple MSes
outfile -- name of output image
        default: ''
        example: 'mySDimage.im'
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False (do NOT overwrite)
        example: if True, existing file will be overwritten
field -- select data by field IDs and names
                If field string is a non-negative integer, it is assumed to
                be a field index otherwise, it is assumed to be a
                field name
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 3 or filed named 3C273)
                 For multiple MS input, a list of field strings can be used:
                 field = ['0^2', '0^4'] (field ids 0-2 for the first MS and 0-4
                         for the second)
                 field = '0~2' (field ids 0-2 for all input MSes)
        this selection is in addition to the other selections to data
spw -- select data by spectral window IDs/channels
       NOTE: channels de-selected here will contain all zeros if
       selected by the parameter mode subparameters.
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                 spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
                 For multiple MS input, a list of spw strings can be used:
                 spw=['0','0~3'] (spw ids 0 for the first MS and 0-3 for the second)
```

```
spw='0~3' (spw ids 0-3 for all input MSes)
        this selection is in addition to the other selections to data
antenna -- select data by antenna names or IDs
           If antenna string is a non-negative integer, it is
           assumed to be an antenna index, otherwise, it is
           considered an antenna name.
        default: '' (all baselines, i.e. all antenna in case of auto data)
        example: antenna='PM03'
                 For multiple MS input, a list of antenna strings can be used:
                 antenna=['5','6'] (antenna id5 for the first MS and 6 for the second)
                 antenna='5' (antenna index 5 for all input MSes)
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
                 For multiple MS input, a list of scan strings can be used:
                 scan=['0~100','10~200'] (scan ids 0-100 for the first MS
                 and 10-200 for the second)
                 scan='0~100 (scan ids 0-100 for all input MSes)
        this selection is in addition to the other selections to data
intent -- select data by observational intent, also referred to as 'scan intent'
        default: '' (use all scan intents)
        example: intent='*0N_SOURCE*' (any valid scan-intent expression accepted by the MSSource example:
                 For multiple MS input, a list of scan-intent expressions can be used:
                 intent=['ON_SOURCE', 'CALIBRATE_BANDPASS'] (scan intent ON_SOURCE for the f:
                 and CALIBRATE_BANDPASS for the second)
        this selection is in addition to the other selections to data
mode -- spectral gridding type
        options: 'channel', 'velocity', 'frequency'
        default: 'channel'
    >>> mode expandable parameters
       nchan -- Total number of channels in the output image.
           default: -1; Automatically selects enough channels to cover
                    data selected by 'spw' consistent with 'start' and 'width'.
                    It is often easiest to leave nchan at the default value.
           example: nchan=100
       start -- First channel, velocity, or frequency.
                For mode='channel'; This selects the channel index number
                from the MS (0 based) that you want to correspond to the
                first channel of the output cube. The output cube will be
                in frequency space with the first channel having the
                frequency of the MS channel selected by start. start=0
                refers to the first channel in the first selected spw, even
                if that channel is de-selected in the spw parameter.
                Channels de-selected by the spw parameter will be filled with
```

zeros if included by the start parameter. For example,

```
spw=3~8:3~100 and start=2 will produce a cube that starts on
                the third channel (recall 0 based) of spw index 3, and the
                first channel will be blank.
           default: '' (the first input channel of first input spw)
           example: start=100 (mode='channel')
                    start='22.3GHz' (mode='frequency')
                    start='5.0km/s' (mode='velocity')
       width -- Output channel width
               For mode='channel', default=1; width>1 indicates channel averaging
               example: width=4.
               For mode= 'velocity' or 'frequency', default=''; width of
               first input channel, or more precisely, the difference
               in frequencies between the first two selected channels.
               -- For example if channels 1 and 3 are selected with spw,
                then the default width will be the difference between their
                frequencies, and not the width of channel 1.
               -- Similarly, if the selected data has uneven channel-spacing,
                 the default width will be picked from the first two selected
                 channels. In this case, please specify the desired width.
               When specifying the width, one must give units
               examples: width='1.0km/s', or width='24.2kHz'.
               Setting width>0 gives channels of increasing frequency for
               mode='frequency', and increasing velocity for mode='velocity'.
       veltype -- Velocity reference frame of output image
           Options: 'radio','optical','true','relativistic'
           default: 'radio'
outframe -- velocity reference frame of output image
        Options: '','LSRK','LSRD','BARY','GEO','TOPO','GALACTO',
                 'LGROUP', 'CMB'
        default: ''; same as input data or 'LSRK' for multiple-MS inputs
        example: frame='bary' for Barycentric frame
gridfunction -- gridding function for imaging
        options: 'BOX' (Box-car), 'SF' (Spheroidal),
                 'PB' (Primary-beam), 'GAUSS' (Gaussian),
                 'GJINC' (Gaussian*Jinc)
        default: 'BOX'
        example: 'SF'
    >>> gridfunction expandable parameter:
       convsupport -- convolution support for 'SF'
           default: -1 (use default for each gridfunction)
           example: 3
       truncate -- truncattion radius of convolution kernel.
                   effective only for 'GAUSS' and 'GJINC'.
           default: '-1' (use default for each gridfunction)
           example: 3, '20arcsec', '3pixel'
       gwidth -- HWHM for gaussian. Effective only for
```

```
'GAUSS' and 'GJINC'.
           default: '-1' (use default for each gridfunction)
           example: 3, '20arcsec', '3pixel'
       jwidth -- Width of jinc function. Effective only for
                 'GJINC'.
           default: '-1' (use default for each gridfunction)
           example: 3, '20arcsec', '3pixel'
imsize -- x and y image size in pixels, symmetric for single value
        default: [] (=cover all pointings in MS)
        example: imsize=200 (equivalent to [200,200])
cell -- x and y cell size. default unit arcmin
        default: '' (= 1/3 of FWHM of primary beam)
        example: cell=['0.2arcmin, 0.2arcmin']
                 cell='0.2arcmin' (equivalent to example above)
phasecenter -- image phase center: direction measure or field ID
        default: '' (= the center of pointing directions in
                     POINTING table of infiles)
        example: 6 (field id), 'J2000 13h44m00 -17d02m00',
                 'AZEL -123d48m29 15d41m41'
ephemsrcname -- ephemeris source name for moving source (solar sytem objects)
        default: '' (none)
        if the source name in the data matches one of the solar system
        objects known by CASA, the imaging realigns the data by
        correcting shifts of the source during observation,
        so that the source appears to be fixed in the image.
        examples: 'MERCURY', 'VENUS', 'MARS', 'JUPITER', 'SATURN',
                  'URANUS', 'NEPUTUNE', 'PLUTO', 'SUN', 'MOON'
pointingcolumn -- pointing data column to use
        option: 'direction', 'target', 'pointing_offset', 'source_offset', encoder'
        default: 'direction'
restfreq -- specify rest frequency to use for output image
        default: '' (refer input data)
        example: 1.0e11, '100GHz'
stokes -- stokes parameters or polarization types to image
        default: '' (use all polarizations)
        example: 'XX'
minweight -- Minimum weight ratio to the median of weight used in
             weight correction and weight based masking
        default: 0.1
        example: minweight = 0.
Gridding Kernel
_____
```

The parameter gridfunction sets gridding function (convolution kernel)

for imaging. Currently, the task supports 'BOX' (Box-car), 'SF' (Prolate Spheroidal Wave Function), 'GAUSS' (Gaussian), 'GJINC' (Gaussian*Jinc), where $Jinc(x) = J_1(pi*x/c)/(pi*x/c)$ with a first order Bessel function J_1, and 'PB' (Primary Beam). For 'PB', correct antenna informations should be included in input file.

There are four subparameters for gridfunction: convsupport, truncate, gwidth, and jwidth. The convsupport is an integer specifying cut-off radius for 'SF' in units of pixel. By default (convsupport=-1), the cut-off radius is set to 3 pixels. The truncate is a cut-off radius for 'GAUSS' or 'GJINC'. It accepts integer, float, and string values of numeric plus unit. Allowed units are angular units such as 'deg', 'arcmin', 'arcsec', and 'pixel'. Default unit is 'pixel' so that string without unit or numerical values (integer or float) will be interpreted as radius in pixel. Default value for truncate, which is used when negative radius is set, is 3*HWHM for 'GAUSS' and radius at first null for 'GJINC'. The gwidth is the HWHM of gaussian for 'GAUSS' and 'GJINC'. Default value is sqrt(log(2)) pixel for 'GAUSS' and 2.52*sqrt(log(2)) pixel for 'GJINC'. The jwidth specifies width of the jinc function (parameter 'c' in the definition above). Default is 1.55 pixel. Both gwidth jwidth allows integer, float, or string of numeric plus unit. Default values for gwidth and jwidth are taken from Mangum et al. (2007). Formula for 'GAUSS' and 'GJINC' are taken from Table 1 in the paper, and are written as below using gwidth and jwidth:

GAUSS: exp[-log(2)*(|r|/gwidth)**2]

GJINC: J_1(pi*|r|/jwidth)/(pi*|r|/jwidth) * $\exp[-\log(2)*(|r|/gwidth)^2]$

Reference: Mangum, et al. 2007, A&A, 474, 679-687

Mask in Output Image

The parameter minweight defines a threshold of weight values to mask. The pixels in outfile whose weight is smaller than minweight*median(weight) are masked out. The task also creates a weight image with the name outfile.weight.

sdimprocess-task.html

0.1.101 sdimprocess

Requires:

Synopsis

Task for single-dish image processing

Description

Task sdimprocess is used to remove a scanning noise that appears as a striped noise pattern along the scan direction in a raster scan data. By default, the scanning noise is removed by using the FFT-based 'Basket-Weaving' method (Emerson & Grave 1988) that requires multiple images that observed exactly the same area with different scanning direction. If only one image is available, the 'Pressed-out' method (Sofue & Reich 1979) can be used to remove the scanning effect.

Arguments

Inputs infiles list of name of input SD images (FITS or CASA image) allowed: any Default: variant " mode image processing mode allowed: string Default: numpoly order of polynomial fit for Pressed-out method allowed: int Default: beam size for Pressed-out method beamsize allowed: double variant 0.0 Default: smoothsize size of smoothing beam for Pressed-out method allowed: any Default: variant 2.0direction scan direction of each image in unit of degree allowed: any Default: variant masklistmask width for Basket-Weaving (on percentage) allowed: any Default: variant 1.0 tmaxmaximum threshold value for processing allowed: double Default: 0.0 minimum threshold value for processing tminallowed: double Default: 0.0outfile name of output file allowed: string Default: overwrite the output file if already exists overwrite

Returns

void

Example

bool

False

allowed:

Default:

```
Keyword arguments
infiles -- name or list of names of input SD (FITS or CASA) image(s)
mode -- image processing mode
        options: 'basket' (FFT-based Basket-Weaving),
                 'press' (Pressed-out method)
        default: 'basket'
    >>>mode expandable parameter
        direction -- scan direction of each input image in unit of degree
                default: []
                example: direction=[0.0, 90.0] means that the first image
                         has scan direction along longitude axis while the
                         second image is along latitude axis.
        masklist -- mask width for Basket-Weaving on percentage
                default: 1.0 (1.0% of map size)
        numpoly -- order of polynomial fit in Presssed-out method
                default: 2
        beamsize -- beam size for Pressed-out method
                default: 0.0
                example: beamsize=10.0 is interpreted as '10arcsec'.
                         beamsize='1arcmin' specifies beam size as
                         quantity.
        smoothsize -- smoothing beam size in Pressed-out method.
                      if numeric value is given, it is interpreted in unit
                      of beam size specified by the parameter beamsize
                default: 2.0
                example: smoothsize=2.0 means that smoothing beam size is
                         2.0 * beamsize.
                         smoothsize='larcmin' sets smoothsize directly.
tmax -- maximum threshold value for processing
        default: 0.0 (no threshold in maximum)
        example: 10.0 (mask data larger value than 10.0)
tmin -- minimum threshold value for processing
        default: 0.0 (no threshold in minimum)
        example: -10.0 (mask data smaller value than -10.0)
outfile -- name of output file. output file is in CASA image format.
        default: '' (use default name 'sdimprocess.out.im')
        example: 'output.im'
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
DESCRIPTION
```

512

Task sdimprocess is used to remove a scanning noise that appears as a striped noise pattern along the scan direction in a raster scan data.

By default, the scanning noise is removed by using the FFT-based 'Basket-Weaving' method (Emerson & Grave 1988) that requires multiple images that observed exactly the same area with different scanning direction. If only one image is available, the 'Pressed-out' method (Sofue & Reich 1979) can be used to remove the scanning effect.

For 'Basket-Weaving', scanning directions must have at least two different values. Normally, the scanning direction should be specified for each input image. Otherwise, specified scanning directions will be used iteratively. The masklist is a width of masking region in the Fourier plane. It is specified as a fraction (percentage) of the image size.

For 'Pressed-out', the scanning direction must be unique. There are two ways to specify a size of smoothing beam used for process. One is to specify smoothing size directly. To do this, smoothsize should be specified as string that consists of a numerical value and an unit (e.g. '10.0arcsec'). A value of beamsize will be ignored in this case. Another way to specify smoothing size is to set an observed beam size and indicate smoothing size as a scale factor of the observed beam size. In this case, the beamsize is interpreted as the observed beam size, and the smoothsize is the scale factor. If the beamsize is provided as float value, its unit is assumed to 'arcsec'. It is also possible to set the beamsize as string consisting of the numerical value and the unit. The smoothsize must be float value.

The infiles only allows an image data (CASA or FITS), and not does not work with MS or Scantable. The direction is an angle with respect to the horizontal direction, and its unit is degree. Any value may be interpreted properly, but the value ranging from 0.0 to 180.0 will be secure. The tmax and the tmin is used to specify a threshold that defines a range of spectral values used for processing. The data point that has the value larger than tmax or smaller than tmin will be excluded from the processing. The default (0.0) is no threshold. The outfile specifies an output CASA image name. If the outfile is empty, the default name ('sdimprocess.out.im') will be used.

sdlist-task.html

0.1.102 sdlist

Requires:

Synopsis

list summary of single dish data

Description

Task sdlist lists the scan summary of the dataset after importing as a scantable into ASAP. It will optionally output this summary as file.

Arguments

Inputs	
infile	name of input SD dataset
	allowed: string
	Default:
antenna	select an antenna name or ID, e.g. 'PM03' (only effective
	for MS input)
	allowed: any
	Default: variant 0
outfile	name of output file (ASCII) for summary list
	allowed: string
	Default:
overwrite	overwrite the output file if already exists [True, False]
	allowed: bool
	Default: False

Returns

void

Example

Keyword arguments

infile -- name of input SD dataset

default: none - must input file name

example: 'mysd.asap'

See sdcal for allowed formats.

antenna -- select an antenna name or id (only effective for MS input)

default: 0
example: 'PM03'

NOTE this parameter is effective only for MS input

outfile -- name of output file for summary list

default: '' (no output file)
example: 'mysd_summary.txt'

overwrite -- overwrite the output file if already exists

options: (bool) True, False

default: False

DESCRIPTION

Task sdlist lists the scan summary of the dataset after importing as a scantable into ASAP. It will optionally output this summary as file.

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs.

sdmath-task.html

0.1.103 sdmath

Requires:

Synopsis

ASAP SD task for simple arithmetic of spectra

Description

Task sdmath execute a simple arithmetic (i.e., subtraction, addition, multiplication, and division) expression for single dish spectra. The spectral data file can be any of the formats supported by ASAP (scantable, MS, rpfits, and SDFITS). In the expression, these file names should be put inside of single or double quotes.

You can use variables in the expression. If you want to use, you must define varnames dictionary. Name of variables should be simple, e.g. V0, V1, etc., to avoid unexpected error. Keys of varnames must be name of variables that you used in the expression, and their values will be substituted for variables in the expression. Allowed type for the value is numerical values, one- or two-dimensional lists (Python list or numpy.ndarray), and filename strings that indicate spectral data or ASCII text, which is space-separated list of numerical values consisting of adequate number of rows and columns. In case you give a list of file names in infiles, they are automatically referred to as IN0, IN1, etc. in expr and you can not use IN0, IN1, etc. as variable names in varnames.

Arguments

Inputs

infiles a list of names of input SD datasets

allowed: stringArray

Default:

expr mathematical expression using spectra

allowed: string

Default:

varnames dictionary of variables and their values used in expr

allowed: any Default: variant

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any
Default: variant 0

fluxunit units of the flux ("=current)

allowed: string

Default:

telescopeparam parameters of telescope for flux conversion (see examples

in help)

allowed: any Default: variant

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

scan select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: string

Default:

outfile name of output file (must be specified)

allowed: string

Default:

outform output file format (See a WARNING in help)

allowed: string

Default: ASAP

overwrite overwrite the output file if already exists [True, False]

allowed: bool Default: False

Returns

void

Example

```
Keyword arguments:
infiles -- a list of names of input SD datasets
        The file names will automatically replace the phrases
        INO, IN1, ... in expr parameter.
expr -- mathematical expression using scantables
varnames -- a python dictionary of variables in expr and their values.
        Keys must be coincide with variables used in expr.
        Values are substituted in each value in expr.
antenna -- select an antenna name or ID
        default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
         telescopeparam -- parameters of telescope for flux conversion
                 options: (str) name or (list) list of gain info
                 default: '' (none set)
                 example: if telescopeparam='', it tries to get the telescope
                          name from the data.
                          Full antenna parameters (diameter, ap.eff.) known
                          to ASAP are
                          'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                          'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                          to 'K' first then convert to a new fluxunit.
                          telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                          telescopeparam=[0.743] gain in Jy/K
                          telescopeparam='FIX' to change default fluxunit
                          see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
```

```
spw -- select data by IF IDs (spectral windows)
       NOTE this task only supports IF ID selction and ignores channel
       selection.
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
outfile -- name of output file
        default: '' (must be specified)
outform -- output file format
        options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'
        default: 'ASAP'
        NOTE the ASAP format is easiest for further sd
        processing; use MS2 for CASA imaging.
        If ASCII, then will append some stuff to
        the outfile name
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
```

DESCRIPTION:

Task sdmath execute a simple arithmetic (i.e., subtraction, addition, multiplication, and division) expression for single dish spectra. The spectral data file can be any of the formats supported by ASAP (scantable, MS, rpfits, and SDFITS). In the expression, these file names should be put inside of single or double quotes.

You can use variables in the expression. If you want to use, you must define varnames dictionary. Name of variables should be simple, e.g. VO, V1, etc., to avoid unexpected error. Keys of varnames must be name of variables that you used in the expression, and their values will be substituted for variables in the expression. Allowed type for the value is numerical values, one- or two-dimensional lists (Python list or numpy.ndarray), and filename strings that indicate

spectral data or ASCII text, which is space-separated list of numerical values consisting of adequate number of rows and columns. In case you give a list of file names in infiles, they are automatically referred to as INO, IN1, etc. in expr and you can not use INO, IN1, etc. as variable names in varnames.

The fluxunit can be set, otherwise, the current settings of the first spectral data in the expression are used. Other selections (e.g. scan No, . IF, Pol) also apply to all the spectral data in the expression, so if any of the data does not contains selection, the task will produce no output.

WARNING for the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs.

```
Example:
# do on-off/off calculation
expr='("orion_on_data.asap"-"orion_off_data.asap")/"orion_off_data.asap"
outfile='orion_cal.asap'
sdmath()
# do on-off/off calculation (using infiles)
infiles = ["orion_on_data.asap", "orion_off_data.asap"]
expr='(INO-IN1)/IN1'
outfile='orion_cal.asap'
sdmath()
# do on-off/off calculation using varnames
varnames={} (this can be skipped if you executed inp(sdmath) or
             default(sdmath).)
varnames['V0']="orion_on_data.asap"
varnames['V1']="orion_off_data.asap"
varnames['V2']=1.0
expr='V0/V1-V2'
outfile='orion_cal.asap'
sdmath()
# do on-off/off calculation using varnames (in pythonic way)
sdmath(varnames={'V0':'orion_on_data.asap','V1':'orion_off_data.asap',
        'V2':1.0}, expr='V0/V1-V2', outfile='orion_cal.asap')
# interpretation of ASCII file value for varnames
```

If the contents of input ASCII file is shown as,

0.5 0.3 0.2 1.0 0.2 0.9

it is interpreted as a list [[0.5, 0.3, 0.2],[1.0, 0.2, 0.9]].

sdplot-task.html

0.1.104 sdplot

Requires:

Synopsis

ASAP SD plotting task

Description

Task sdplot displays single-dish spectra, total power, or pointing direction of input data. It assumes that the spectra have been calibrated. It does allow selection of scans, spectral windows, polarizations, and some time and channel averaging/smoothing options also, but does not write out this data. This task adds an additional toolbar to Matplotlib plotter. See the cookbook for details of its capability.

Arguments

Inputs

infile name of input SD dataset

allowed: string

Default:

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any Default: varia

Default: variant 0 fluxunit units of the flux ("=current)

allowed: string

Default:

telescope parameters of telescope for flux conversion (see examples

in help)

allowed: any Default: variant

specunit units for spectral axis

allowed: string

Default:

restfreq rest frequency (default unit: Hz)

allowed: any Default: variant

frame frequency reference frame ("=current)

allowed: string

Default:

doppler doppler convention ("=current). Effective only when

spw selection is in velocity unit

allowed: string

Default:

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

scan select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: string

Default:

beam select data by beam IDs, e.g. '0,1' ("=all)

allowed: string

Default:

rastermode mode of raster selection ['row', 'raster']

 $\begin{array}{ll} \text{allowed:} & 523 \, \text{string} \\ \text{Default:} & \text{row} \end{array}$

raster select data by raster scan row or map iteration e.g. '0~2'

("=all)

allowed: string

Default:

timeaverage average spectra over time [True, False] (see examples in

help)

allowed: bool

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
antenna -- select an antenna name or ID
        default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
   >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap. eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
specunit -- units for spectral axis
        options: (str) 'channel', 'km/s', 'GHz', 'MHz', 'kHz', 'Hz'
        default: '' (=current)
        example: this will be the units for masklist
    >>> specunit expandable parameter
        restfreq -- the rest frequency
                available type includes float, int, string, list of float,
                list of int, list of string, and list of dictionary. the
                default unit of restfreq in case of float, int, or string
                without unit is Hz. string input can be a value only
                (treated as Hz) or a value followed by unit for which 'GHz',
                'MHz', 'kHz', and 'Hz' are available.
```

```
a list can be used to set different rest frequencies for
                each IF. the length of list input must be number of IFs.
                dictionary input should be a pair of line name and
                frequency with keys of 'name' and 'value', respectively.
                values in the dictionary input follows the same manner as
                as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
frame -- frequency reference frame
        options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
        default: '' (keep current frame in data)
doppler -- doppler convention (effective only when spw is in
           velocity unit)
        options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
        default: '' (keep current doppler setting in data)
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)
       NOTE this task only supports IF ID selction and ignores channel
       selection.
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
beam -- select data by beam IDs
        default: '' (use all beams)
        example: beam='0,1' (beam IDs 0,1)
        this selection is in addition to the other selections to data
rastermode -- mode of raster selection
        options: 'row', 'raster'
```

```
default: 'row'
   >>> rasterrow expandable parameter
        raster -- select data by raster scan row or map iteration
        default: '' (use all data)
        example: raster='0~2'
timeaverage -- average spectra over time
        options: (bool) True, False
        default: False
    >>>timeaverage expandable parameter
        tweight -- weighting for time averaging
                options: 'var'
                                  (1/var(spec) weighted)
                         'tsys'
                                  (1/Tsys**2 weighted)
                         'tint'
                                  (integration time weighted)
                         'tintsys' (Tint/Tsys**2)
                         'median' (median averaging)
                default: 'tintsys'
        scanaverage -- average spectra within a scan number
                       when True, spectra are NOT averaged over
                       different scan numbers.
                options: (bool) True, False
                default: False
polaverage -- average spectra over polarizations
        options: (bool) True, False
        default: False
    >>>polaverage expandable parameter
        pweight -- weighting for polarization average
                options: 'var' (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
                default: 'tsys'
kernel -- type of spectral smoothing
        options: 'hanning', 'gaussian', 'boxcar', 'none'
        default: '' (= no smoothing)
    >>>kernel expandable parameter
        kwidth -- width of spectral smoothing kernel
                options: (int) in channels
                default: 5
                example: 5 or 10 seem to be popular for boxcar
                         ignored for hanning (fixed at 5 chans)
                         (0 will turn off gaussian or boxcar)
plottype -- type of plot
        options: 'spectra', 'totalpower', 'pointing', 'azel', 'grid'
        default: 'spectra'
    >>> plottype expandable parameters
        stack -- code for stacking on single plot for spectral plotting
                options: 'p','b','i','t','s','r' or
                         'pol', 'beam', 'if', 'time', 'scan', 'row'
```

```
default: 'p'
        example: maximum of 16 stacked spectra
                 stack by pol, beam, if, time, scan
       Note stack selection is ignored when panel='r'.
       Note behavior of stack='t' depends on plottype:
           * stack by time in plottype='spectra'
           * stack by source type in plottype='totalpower' and 'pointing'
panel -- code for splitting into multiple panels for spectral plotting
        options: 'p','b','i','t','s','r' or
                 'pol', 'beam', 'if', 'time', 'scan', 'row'
        default: 'i'
        example: maximum of 16 panels
                 panel by pol, beam, if, time, scan
       Note panel selection is ignored when stack='r'.
flrange -- range for flux axis of plot for spectral plotting
        options: (list) [min,max]
       default: [] (full range)
        example: flrange=[-0.1,2.0] if 'K'
                 assumes current fluxunit
sprange -- range for spectral axis of plot
       options: (list) [min,max]
       default: [] (full range)
       example: sprange=[42.1,42.5] if 'GHz'
                 assumes current specunit
linecat -- control for line catalog plotting for spectral plotting
       options: (str) 'all', 'none' or by molecule
       default: 'none' (no lines plotted)
        example: linecat='SiO' for SiO lines
                 linecat='*OH' for alcohols
                 uses sprange to limit catalog
        WARNING: specunit must be in frequency (*Hz)
                 to plot from the line catalog!
                 and must be 'GHz' or 'MHz' to use
                 sprange to limit catalog
linedop -- doppler offset for line catalog plotting (spectral plotting)
        options: (float) doppler velocity (km/s)
       default: 0.0
       example: linedop=-30.0
center -- the central direction of gridding
       default: '' (map center)
       example: 'J2000 19h30m00 -40d00m00'
       Note currently only supports 'J2000' as direction frame
cell -- x and y cell size of gridding
       default: [] (map extent devided by # of subplots in x and y)
        example: cell=['1.0arcmin','1.0arcmin']
                 cell='1.0arcmin' (equivalent to the example above)
```

```
subplot -- number of subplots (row and column) on a page
                NOTICE plotter will slow down when a large number is specified
                default: -1 (auto. for plottype='spectra', 1x1 for plottype='grid')
                example: 23 (2 rows by 3 columns)
        colormap -- the colours to be used for plot lines.
                default: None
                example: colormap="green red black cyan magenta" (html standard)
                         colormap="g r k c m" (abbreviation)
                         colormap="#008000 #00FFFF #FF0090" (RGB tuple)
                         The plotter will cycle through these colours
                         when lines are overlaid (stacking mode).
        linestyles -- the linestyles to be used for plot lines.
                default: None
                example: linestyles="line dashed dotted dashdot dashdotdot dashdotdot".
                         The plotter will cycle through these linestyles
                         when lines are overlaid (stacking mode).
                WARNING: Linestyles can be specified only one color has been set.
        linewidth -- width of plotted lines.
                default: 1
                example: linewidth=1 (integer)
                         linewidth=0.75 (double)
        histogram -- plot histogram
                options: (bool) True, False
                default: False
        scanpattern -- plot additional lines on the plot to indicate scan patterns
                       when plottype='pointing'
                options: (bool) True, False
                default: False
header -- print header information on the plot
        options: (bool) True, False
        default: True
        The header information is printed only on the logger when
        plottype = 'azel' and 'pointing'.
    >>> header expandable parameter
        headsize -- header font size
                options: (int)
                default: 9
plotstyle -- customise plot settings
        options: (bool) True, False
        default: False
   >>> plotstyle expandable parameter
        margin -- a list of subplot margins in figure coordinate (0-1),
                  i.e., fraction of the figure width or height.
                  The order of elements should be:
                  [left, bottom, right, top, horizontal space btw panels,
```

Note default number of subplots is 1 x 1 in plottype='grid'.

```
vertical space btw panels]
                example: margin = [0.125, 0.1, 0.9, 0.9, 0.2, 0.2]
        legendloc -- legend location on the axes (0-10)
                options: (integer) 0 -10
                         see help of "sd.plotter.set_legend" for
                         the detail of location. Note that 0 ('best')
                         is very slow.
                default: 1 ('upper right')
outfile -- file name for hardcopy output
        options: (str) filename.eps,.ps,.png
        default: '' (no hardcopy)
        example: 'specplot.eps', 'specplot.png'
        Note this autodetects the format from the suffix (.eps,.ps,.png).
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
```

DESCRIPTION:

Task sdplot displays single-dish spectra, total power, or pointing direction of input data. It assumes that the spectra have been calibrated. It does allow selection of scans, IFs, polarizations, and some time and channel averaging/smoothing options also, but does not write out this data.

This task adds an additional toolbar to Matplotlib plotter. See the cookbook for details of its capability.

*** Data selection ***

This task allows data selection via field name, scan, IF, polarization and beam IDs. Selection of field allows pattern matching using asterisk, e.g., 'FLS3a*'. Selection of scans, IFs, polarizations, and beams, is possible by a CASA type selection syntax using a string of comma separated numbers with operaters, i.e., '~', '>', and '<'. For example, the following selection scan = "<3,7~9,15" is to select scan IDs 0, 1, 2, 7, 8, 9, and 15.

AVERAGING OF SPECTRA

Task sdplot has two averaging modes, i.e., time and polarization average.

When timeaverage=True, spectra are averaged over time for each IF (spectral window), polarization, and beam, independently. Note that, by default (scanaverage=False), timeaverage=True averages spectra irrespective of scan IDs.

It is possible to average spectra separately for each scan ID by setting a sub-parameter scanaverage=True.

For example, the combination of parameters: scan='0~2', timeaverage=True, and scanaverage=False: averages spectra in scan ID 0 through 2 all together to a spectrum,

scanaverage=True : averages spectra per scan ID and end up with three spectra from scan 0, 1, and 2.

When polaverage=True, spectra are averaged over polarization for each IF (spectral window) and beam. Note that, so far, time averaging is automatically switched on when polaverage is set to True. This behavior is not desirable and will be discarded in future.

*** available plottypes ***

* plottype = 'spectra' plots single dish spectra. Multiple scans, IFs, polarizations, and beams can be handles through stacking and panelling.

This task uses the JPL line catalog as supplied by ASAP. If you wish to use a different catalog, or have it plot the line IDs from top or bottom (rather than alternating), then you will need to explore the sd toolkit also.

* plottype = 'grid' plots spectra based on their pointing direction. The spectra are gridded by direction before plotting.

Multiple IFs and polarizations are not handled in this mode. Only the first IF and polarization is gridded and plotted if data includes multiple IDs after selections are applied. Hence, over plotting is not available

Currently most of the parameters are ignored in the following modes.

- * plottype='totalpower' is used to plot the total power data. and only plot option is amplitude versus data row number.
- * plottype='azel' plots azimuth and elevation tracks of the source.
- * plottype='pointing' plots antenna poinitings.

*** control of plot lines in 'spectra' and 'grid' plottype ***
Note that colormap and linestyles cannot be controlled at a time.
The 'linestyles' is ignored if both of them are specified.
Some plot options, like changing titles, legends, fonts, and the like are not supported in this task. You should use sd.plotter from the ASAP toolkit directly for this.

ASAP recognizes the data of the "AT" telescopes, but currently does not know about the GBT or any other telescope. This task does know about GBT. Telescope name is obtained from the data. If you wish to change the fluxunit (see below), and telescopeparam='', for the AT telescopes it will use internal telescope parameters for flux conversion. For GBT, it will use an approximate aperture efficiency conversion. If you give telescopeparam a list, then if the list has a single float it is assumed to be the gain in Jy/K, if two or more elements they are assumed to be telescope diameter (m) and aperture efficiency respectively.

WARNING: be careful plotting otf data with lots of fields!

WARNING for the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs. sdreduce-task.html

0.1.105 sdreduce

Requires:

Synopsis

ASAP SD task: do sdcal, sdaverage, and sdbaseline in one task

Description

Task sdreduce performs data selection, calibration, spectral averaging and/or baseline fitting for single-dish spectra. This task internally calls the tasks, sdcal, sdaverage, and sdbaseline and it can be used to run all the three steps in one task execution. This task has better performance than invoking the three tasks separately because it runs all three steps without writing intermediate data to disk.

It is possible to skip arbitrary operations by setting calmode = 'none' (for calibration), average=False (for time and polarization averaging), kernel = 'none' (for smoothing), and/or blfunc='none' (for baseline fitting). Please take a look at descriptions of tasks, sdcal, sdaverage, and sdbalseline, for more information.

Arguments

Inputs infile name of input SD dataset allowed: string Default: select an antenna name or ID, e.g. 'PM03' (only effective antenna for MS input) allowed: any Default: variant 0 fluxunit units of the flux ("=current) allowed: string Default: parameters of telescope for flux conversion (see descriptelescopeparam tion in help of sdcal) allowed: Default: select data by field IDs and names, e.g. '3C2*' ("=all) field allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see restfreq examples in help) allowed: any Default: variant frequency reference frame ("=current) frame allowed: string Default: doppler doppler convention ("=current). Effective only when spw selection is in velocity unit. allowed: string Default: timerange select data by time range, e.g. $'09:14:0\sim09:54:0'$ ("=all) (see examples in help of sdcal) allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: pol select data by polarization IDs, e.g. '0,1' ("=all) allowed: string Default: calmodeSD calibration mode ('none' = skip calibration) allowed: string Default: none fraction fraction of the OFF data to mark as OFF spectra, e.g., '10%'

Default: width width of the pixel for edge detection

instead of number)

allowed:

Default:

allowed:

noff

any

int

-1

variant 10%

number of the OFF data to mark (-1) = use fraction

Returns

void

Example

```
Keyword arguments:
infile -- name of input SD dataset
antenna -- select an antenna name or ID
        default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
   >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap. eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
       NOTE channel range selections are interpreted as mask regions to
       INCLUDE in BASELINE fit, and ignored in the other operations.
       when maskmode is 'auto' or 'interact', the channel mask
       will be applied first before fitting as base mask
```

```
example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                 spw='0:5~61' (IF ID 0; channels 5 to 61)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
   >>> spw expandable parameters
        restfreq -- the rest frequency
                    available type includes float, int, string, list of float,
                    list of int, list of string, and list of dictionary. the
                    default unit of restfreq in case of float, int, or string
                    without unit is Hz. string input can be a value only
                    (treated as Hz) or a value followed by unit for which 'GHz',
                    'MHz', 'kHz', and 'Hz' are available.
                    a list can be used to set different rest frequencies for
                    each IF. the length of list input must be number of IFs.
                    dictionary input should be a pair of line name and
                    frequency with keys of 'name' and 'value', respectively.
                    values in the dictionary input follows the same manner as
                    as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
        frame -- frequency reference frame
                options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
                default: '' (keep current frame in data)
        doppler -- doppler convention (effective only when spw is in
                   velocity unit)
                options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
                default: '' (keep current doppler setting in data)
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
                 Note: YYYY/MM/DD can be dropped as needed:
                 timerange='09:14:00~09:54:00' # this time range
                 timerange='09:44:00' # data within one integration of time
                 timerange='>10:24:00' # data after this time
                 timerange='09:44:00+00:13:00' #data 13 minutes after time
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
```

default: '' (use all IFs and channels)

default: '' (use all scans)

example: scan='21~23' (scan IDs 21,22,23)

this selection is in addition to the other selections to data

pol -- select data by polarization IDs

default: '' (use all polarizations)

example: pol='0,1' (polarization IDs 0,1)

this selection is in addition to the other selections to data

calmode -- calibration mode

options: 'ps', 'nod', 'otf', 'otfraster',

'fs', 'quotient', 'none'

default: 'none'

example: choose mode 'none' if you have already calibrated

and want to correct for atmospheric opacity defined by tau, subtract baseline or average/smooth spectra.

>>> calmode expandable parameter

fraction -- edge marker parameter of 'otf' and 'otfraster'.

Specify a number of OFF integrations (at each side of the raster rows in 'otfraster' mode) as a fraction of total number of integrations.

In 'otfraster' mode, number of integrations to be marked as OFF, n_off, is determined by the following formula,

n_off = floor(fraction * n),

where n is number of integrations per raster row. Note that $n_{\rm o}$ ff from both sides will be marked as OFF so that twice of specified fraction will be marked at most. For example, if you specify fraction='10%', resultant fraction of OFF integrations will be 20% at most.

In 'otf' mode, n_off is given by,

n_off = floor(fraction * n),

where n is number of total integrations. n_off is used as criterion of iterative marking process. Therefore, resulting total number of OFFs will be larger than n_off. In practice, fraction is a geometrical fraction of edge region. Thus, if integrations are concentrated on edge region (e.g. some of Lissajous patterns), then resulting n_off may be unexpectedly large.

options: '20%' in string style or float value less than 1.0 (e.g. 0.15). 'auto' is available only for 'otfraster'. noff -- edge marking parameter for 'otfraster'. It is used to specify a number of OFF scans near edge directly. Value of noff comes before setting by fraction. Note that n_off from both sides will be marked as OFF so that twice of specified noff will be marked at most. default: -1 (use fraction) options: any positive integer width -- edge marking parameter for 'otf'. Pixel width with respect to a median spatial separation between neighboring two data in time. Default will be fine in most cases. default: 0.5 options: float value elongated -- edge marking parameter for 'otf'. Set True only if observed area is elongeted in one direction. options: (bool) True, False default: False markonly -- set True if you want to save data just after edge marking (i.e. uncalibrated data) to see how OFF scans are defined. options: (bool) True, False default: False plotpointings -- load plotter and plot pointing directions of ON and OFF scans. options: (bool) True, False default: False tau -- the zenith atmospheric optical depth for correction default: 0.0 (no correction) average -- averaging on spectral data options: (bool) True, False default: False >>>average expandable parameter timeaverage -- average spectra over time options: (bool) True, False default: False example: if True, this happens after calibration tweight -- weighting for time averaging (effective only when timeaverage=True)

default: '10%'

```
options: 'var'
                                 (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
                         'tint' (integration time weighted)
                         'tintsys' (Tint/Tsys**2)
                         'median' ( median averaging)
                default: 'tintsys'
        scanaverage -- average spectra within a scan number (effective
                       only when timeaverage=True)
                       when True, spectra are NOT averaged over
                       different scan numbers.
                options: (bool) True, False
                default: False
        averageall -- average multi-resolution spectra (effective only
                      when timeaverage=True)
                      spectra are averaged by referring their frequency
                      coverage
                 default: False
        polaverage -- average spectra over polarizations
                options: (bool) True, False
                default: False
        pweight -- weighting for polarization averaging (effective only
                   when polaverage=True)
                options: 'var' (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
                default: 'tsys'
kernel -- type of spectral smoothing kernel
        options: 'none', 'hanning', 'gaussian', 'boxcar', 'regrid', ''(='none')
        default: 'none' (no smoothing)
   >>>kernel expandable parameter
        kwidth -- width of spectral smoothing kernel
                options: (int) in channels
                default: 5
        example: 5 or 10 seem to be popular for boxcar
                 ignored for hanning (fixed at 5 chans)
                         (0 will turn off gaussian or boxcar)
        chanwidth -- channel width of regridded spectra
        default: '5' (in channels)
         example: '500MHz', '0.2km/s'
maskmode -- mode of setting additional channel masks
        options: 'auto', 'list', or 'interact'
        default: 'auto'
        example: maskmode='auto' runs linefinder to detect line regions
                 to be excluded from fitting. this mode requires three
```

expandable parameters: thresh, avg_limit, and edge.
USE WITH CARE! May need to tweak the expandable parameters.
maskmode='list' uses the given masklist only: no additional
masks applied.

maskmode='interact' allows users to manually modify the mask regions by dragging mouse on the spectrum plotter GUI. use LEFT or RIGHT button to add or delete regions, respectively.

>>> maskmode expandable parameters

thresh -- S/N threshold for linefinder. a single channel S/N ratio above which the channel is considered to be a detection. default: 5

default: 4

edge -- channels to drop at beginning and end of spectrum

default: 0

example: edge=[1000] drops 1000 channels at beginning AND end. edge=[1000,500] drops 1000 from beginning and 500 from end.

Note: For bad baselines threshold should be increased, and avg_limit decreased (or even switched off completely by setting this parameter to 1) to avoid detecting baseline undulations instead of real lines.

blfunc -- baseline model function

options: 'poly', 'chebyshev', 'cspline', or 'sinusoid'

default: 'none' (no baseline fit)

example: blfunc='poly' uses a single polynomial line of any order which should be given as an expandable parameter 'order' to fit baseline.

blfunc='chebyshev' uses Chebyshev polynomials.

blfunc='cspline' uses a cubic spline function, a piecewise cubic polynomial having C2-continuity (i.e., the second derivative is continuous at the joining points).

blfunc='sinusoid' uses a combination of sinusoidal curves.

>>> blfunc expandable parameters

order -- order of baseline model function

options: (int) (<0 turns off baseline fitting)</pre>

default: 5

example: typically in range 2-9 (higher values seem to be needed for GBT)

```
for fitting by applying some method like FFT.
                options: (bool) True, False
                default: True
        fftmethod -- method to be used when applyfft=True. Now only
                     'fft' is available and it is the default.
        fftthresh -- threshold to select wave numbers to be used for
                     sinusoidal fitting. both (float) and (str) accepted.
                     given a float value, the unit is set to sigma.
                     for string values, allowed formats include:
                     'xsigma' or 'x' (= x-sigma level. e.g., '3sigma'), or
                     'topx' (= the x strongest ones, e.g. 'top5').
                default is 3.0 (unit: sigma).
        addwn -- additional wave number(s) of sinusoids to be used
                 for fitting.
                 (list) and (int) are accepted to specify every
                 wave numbers. also (str) can be used in case
                 you need to specify wave numbers in a certain range.
                 default: [0] (i.e., constant is subtracted at least)
                 example: 0
                          [0,1,2]
                          'a-b' (= a, a+1, a+2, ..., b-1, b),
                          '<a' (= 0,1,...,a-2,a-1),
                          '>=a' (= a, a+1, ... up to the maximum wave
                                   number corresponding to the Nyquist
                                   frequency for the case of FFT).
        rejwn -- wave number(s) of sinusoid NOT to be used for fitting.
                 can be set just as addwn but has higher priority:
                 wave numbers which are specified both in addwn
                 and rejwn will NOT be used.
                 default: []
        clipthresh -- clipping threshold for iterative fitting
                 default: 3
        clipniter -- maximum iteration number for iterative fitting
                 default: 0 (no iteration, i.e., no clipping)
verifycal -- interactively verify the results of calibration
          See description of verify parameter in the task, sdcal,
          for details.
        options: (bool) True, False
        default: False
verifysm -- interactively verify the results of smoothing for each
            spectrum.
          See description of verify parameter in the task, sdaverage,
          for details.
```

applyfft -- automatically set wave numbers of sinusoidal functions

default: 2

```
options: (bool) True, False
        default: False
        Note: verification is not yet available for kernel='regrid'
verifybl -- interactively verify the results of baseline fitting for
            each spectrum.
          See description of verify parameter in the task, sdbaseline,
          for details.
        options: (bool) True, False
        default: False
        NOTE: Currently available only when blfunc='poly'
verbosebl -- output fitting results to logger. If False, the fitting results
             including coefficients, residual rms, etc., are not output to
             the CASA logger, while the processing speed gets faster.
        options: (bool) True, False
        default: True
bloutput -- output fitting results to a text file. if False, the fitting
            results including coefficients, residual rms, etc., are not
            output to a text file (<outfile>_blparam.txt), while
            the processing speed gets faster.
        options: (bool) True, False
        default: True
blformat -- format of the logger output and text file specified with bloutput
        options: '', 'csv'
        default: '' (same as in the past, easy to read but huge)
showprogress -- show progress status for large data
        options: (bool) True, False
        default: True
    >>> showprogress expandable parameter
        minnrow -- minimum number of input spectra to show progress status
                 default: 1000
outfile -- name of output file
        default: '' (<infile>_cal)
outform -- output file format
        options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'
        default: 'ASAP'
        NOTE the ASAP format is easiest for further sd
        processing; use MS2 for CASA imaging.
        If ASCII, then will append some stuff to
        the outfile name
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
plotlevel -- control for plotting and summary of results
        options: (int) 0, 1, 2, and their negative counterparts
```

default: 0 (no plotting)

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs. sdsave-task.html

0.1.106 sdsave

Requires:

Synopsis

Save the sd spectra in various format

Description

Task sdsave writes the single dish data to a disk file in specified format (ASAP, MS2, SDFITS, ASCII). It is possible to save the subset of the data by selecting field names, spw ids, time ranges, scan numbers, and polarization ids. The ASAP (scantable) format is recommended for further analysis using Sd tool or tasks except imaging. For further imaging using imager or sdimaging, save the data to the Measurement Set (MS2).

Arguments

Inputs

infile name of input SD dataset

allowed: string

Default:

split output file by antenna (only effective for MS input)

allowed: bool

Default: False

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any

Default: variant 0

getpt fill DIRECTION column properly (True), or reuse

POINTING table in original MS (False) (only effective

for MS input)

allowed: bool Default: True

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

timerange select data by time range, e.g. '09:14:0~09:54:0' ("=all)

(see examples in help) allowed: string

Default:

scan select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: string

Default:

beam select data by beam IDs, e.g. '0,1' ("=all)

allowed: string

Default:

restfreq the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see

examples in help)
allowed: any
Default: variant

outfile name of output file (See a WARNING in help)

allowed: string

Default:

outform output file format (See a WARNING in help)

allowed: string
Default: ASAP

fillweight fill the WEIGHT5and SIGMA columns for output MS

allowed: bool
Default: False

overwrite overwrite the output file if already exists

allowed: bool Default: False

Returns

void

Example

```
Keyword arguments
_____
infile -- name of input SD dataset
splitant -- split output file by antenna. this parameter is only
            effective for MS input.
        options: (bool) True, False
        default: False
    >>>splitant expandable parameter
        antenna -- select an antenna name or ID. this parameter is
                   effective only for MS input.
                default: 0
                example: antenna=0 specifies antenna by id
                         antenna='PM03' specifies antenna by name
getpt -- fill DIRECTION column properly (True), or reuse POINTING
        table in original MS (False). this parameter is only
         effective for MS input.
    options: (bool) True, False
    default: True
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                 spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
timerange -- select data by time range
        default: '' (use all)
```

```
example: timerange = 'YYYY/MM/DD/hh:mm:ss"YYYY/MM/DD/hh:mm:ss'
                 Note: YYYY/MM/DD can be dropped as needed:
                 timerange='09:14:00~09:54:00' # this time range
                 timerange='09:44:00' # data within one integration of time
                 timerange='>10:24:00' # data after this time
                 timerange='09:44:00+00:13:00' #data 13 minutes after time
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
beam -- select data by beam IDs
        default: '' (use all beams)
        example: beam='0,1' (beam IDs 0,1)
        this selection is in addition to the other selections to data
restfreq -- the rest frequency
            available type includes float, int, string, list of float,
            list of int, list of string, and list of dictionary. the
            default unit of restfreq in case of float, int, or string
            without unit is Hz. string input can be a value only
            (treated as Hz) or a value followed by unit for which 'GHz',
            'MHz', 'kHz', and 'Hz' are available.
            a list can be used to set different rest frequencies for
            each IF. the length of list input must be number of IFs.
            dictionary input should be a pair of line name and
            frequency with keys of 'name' and 'value', respectively.
            values in the dictionary input follows the same manner as
            as for single float or string input.
        example: 345.796
                 '1420MHz'
                 [345.8, 347.0, 356.7]
                 ['345.8MHz', '347.0MHz', '356.7MHz']
                 [{'name':'CO','value':345}]
outfile -- name of output file
        default: '' ((<infile>_saved)
        NOTE actual output file name(s) will be modified if splitant
        is True as antenna names are to be included. If outfile has a
        suffix '.asap' or '.ASAP', antenna name will be inserted before
        the suffix like 'out.antName.asap', otherwise, antenna name
        will be simply appended to outfile like 'out.sdfits.antName'.
outform -- output file format
```

options: 'ASAP', 'MS2', 'ASCII', 'SDFITS'

default: 'ASAP'

NOTE the ASAP format is easiest for further sd

processing; use MS2 for CASA imaging. If ASCII, then will append some stuff to

the outfile name

fillweight -- fill WEIGHT and SIGMA column for output MS

default: True

options: True, False

DESCRIPTION

Task sdsave writes the single dish data to a disk file in specified format (ASAP, MS2, SDFITS, ASCII). It is possible to save the subset of the data by selecting field names, spw ids, time ranges, scan numbers, and polarization ids. The ASAP (scantable) format is recommended for further analysis using Sd tool or tasks except imaging. For further imaging using imager or sdimaging, save the data to the Measurement Set (MS2).

Note that setting getpt=False needs a lot of attention. If you set getpt=False, the task retrieves pointing direction from MS's FIELD table, which might not be correct for single dish observation, instead to check MS's POINTING table, which is the default behavior of the task (getpt=True). To compensate this, absolute path to MS's POINTING table is stored, and it will be used for POINTING table when the data is converted back to MS format. In general, getpt=False is faster especially for large data. However, MS created from Scantable cannot have correct POINTING table if original MS's POINTING table doesn't exist. Such situation will happen when original MS is removed or renamed, or imported Scantable is moved to other computer alone.

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs.

sdscale-task.html

0.1.107 sdscale

Requires:

Synopsis

Scale the sd spectra

Description

Task sdscale performs scaling of single-dish spectra by scaling factor given by parameter named factor. By setting scaletsys = True, associated Tsys is also scaled.

Arguments

Inputs	
infile	name of input SD dataset
	allowed: string
	Default:
antenna	select an antenna name or ID, e.g. 'PM03' (only effective
	for MS input)
	allowed: any
	Default: variant 0
factor	scaling factor (float or float list)
	allowed: any
	Default: variant 1.0
scaletsys	scaling of associated Tsys
	allowed: bool
	Default: True
outfile	name of output file (See a WARNING in help)
	allowed: string
	Default:
overwrite	overwrite the output file if already exists
	allowed: bool
	Default: False
verbose	Print verbose log output
	allowed: bool
	Default: True

Returns

void

Example

```
-----
Keyword arguments
-----
infile -- name of input SD dataset
antenna -- select an antenna name or ID
       default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
factor -- scaling factor. float, one- or two-dimensional float list,
          or filename storing scaling factor are acceptable
       default: 1.0 (no scaling)
       example: see description below
scaletsys -- scaling of associated Tsys
         options: (bool) True, False
         default: True
outfile -- name of output file
        default: outfile='' (<infile>_scaled<factor>)
        example: 'scaled.asap'
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
verbose -- Print verbose log messages. If True, Tsys values before
           (and after) scaling are printed to logger.
          options: (bool) True, False
          default: True
DESCRIPTION
Task sdscale performs scaling of single-dish spectra.
Associated Tsys is also scaled if scaletsys is True.
Tsys informations are written in the casalogger and they are
automatically stored in 'casapy.log'.
The infile can be any of ASAP, MS, SDFITS, or RPFITS format.
If outfile name is given or outfile=''(default), the scaled data
```

is written to a new file with the same format as the input data

(Note: in case of the RPFITS format input data, it will be written to SDFITS format).

The scaling factor, factor, accepts both scalar type and list type value. The list must be one or two dimensional. If factor is one dimensional, its length must coincide with a number of spectral channel. If factor is two dimensional, its shape must be (n, 1) or (n, m), where n is a number of spectrum, while m is a number of channel for each spectrum. In addition, the factor can be an ASCII filename that stores a space-separated list of scaling factor consisting of adequate number of rows and columns. For example, if the contents of input ASCII file is shown as,

0.5 0.3 0.2 1.0 0.2 0.9

it is interpreted as a list [[0.5, 0.3, 0.2],[1.0, 0.2, 0.9]].

WARNING

For the GBT raw SDFITS format data as input: SDtasks are able to handle GBT raw SDFITS format data since the data filler is available. However, the functionality is not well tested yet, so that there may be unknown bugs. sdstat-task.html

0.1.108 sdstat

Requires:

Synopsis

list statistics of spectral

Description

Task sdstat computes basic statistics for each of single-dish spectrum. This task returns a Python dictionary of statistics. The return value contains the maximum and minimum intensity and their channels ('max', 'max_abscissa', 'min', and 'min_abscissa'), RMS ('rms'), mean ('mean'), sum ('sum'), median ('median'), standard deviation ('stddev'), total intensity ('totint'), and equivalent width ('eqw'). If you do have multiple scantable rows, then the return values will be lists.

It is possible to select channel regions to calculate spectra either non-interactively by spw parameter or interactively on a plotter by setting interactive=True.

If one of averaging parameters is set True, the spectra are averaged before calculating the statistics.

Arguments

Outputs

xstat RETURN ONLY: a Python dictionary of line statistics

allowed: any

Default: variant

Inputs

infile name of input SD dataset

allowed: string

Default:

antenna select an antenna name or ID, e.g. 'PM03' (only effective

for MS input)

allowed: any

Default: variant 0

fluxunit units of the flux ("=current)

allowed: string Default:

telescopeparam

parameters of telescope for flux conversion (see examples

in help)

allowed: any Default: variant

field select data by field IDs and names, e.g. '3C2*' ("=all)

allowed: string

Default:

spw select data by IF IDs (spectral windows), e.g. '3,5,7'

("=all)

allowed: string

Default:

restfreq the rest frequency, e.g. '1.41GHz' (default unit: Hz) (see

examples in help)
allowed: any
Default: variant

frame frequency reference frame ("=current)

allowed: string

Default:

doppler doppler convention ("=current). Effective only when

spw selection is in velocity unit.

allowed: string

Default:

timerange select data by time range, e.g. '09:14:0~09:54:0' ("=all)

(see examples in help) allowed: string

Default:

scan select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

pol select data by polarization IDs, e.g. '0,1' ("=all)

allowed: 552 string

Default:

beam select data by beam IDs, e.g. '0,1' ("=all)

allowed: string

Default:

timeaverage average spectra over time [True, False] (see examples in

help)

allowed: bool Default: False

Returns

void

Example

How to use return values

---xstat = sdstat();
print "rms = ",xstat['rms']

these can be used for testing in scripts or for regression

'max_abscissa' and 'min_abscissa' refer to the channel of max and min intensity.

'totint' is the integrated intensity (sum*channel).

'eqw' is equivalent width (totint/mag) where mag is either max or min depending on which has greater magnitude.

Note that 'max_abscissa', 'min_abscissa', 'totint' and 'eqw' are quantities (python dictionaries with keys, 'unit' and 'value').

AVERAGING OF SPECTRA

Task sdstat has two averaging modes, i.e., time and polarization average.

When timeaverage=True, spectra are averaged over time for each IF (spectral window), polarization, and beam, independently. Note that, by default (scanaverage=False), timeaverage=True averages spectra irrespective of scan IDs.

It is possible to average spectra separately for each scan ID by setting a sub-parameter scanaverage=True.

For example, the combination of parameters: scan='0~2', timeaverage=True, and scanaverage=False: averages spectra in scan ID 0 through 2 all together to a spectrum,

scanaverage=True : averages spectra per scan ID and end up with three spectra from scan 0, 1, and 2.

When polaverage=True, spectra are averaged over polarization for each IF (spectral window) and beam. Note that, so far, time averaging is automatically switched on when polaverage is set to True. This behavior is not desirable and will be discarded in future.

FLUX UNIT CONVERSION

respectively (case 2).

The task is able to convert flux unit between K and Jy. To do that, fluxunit and its subparameter telescopeparam must be properly set. The fluxunit should be 'Jy' or 'K' depending on what unit input data is and what unit you want to convert. If given fluxunit is different from the unit of input data, unit conversion is performed. The telescopeparam is used to specify conversion factor. There are three ways to specify telescopeparam: 1) set Jy/K conversion factor, 2) set telescope diameter, D, and aperture efficiency, eta, separately, and 3) 'FIX' mode (only change the unit without converting spectral data). If you give telescopeparam as a list, then if the list has a single float it is assumed to be the gain in Jy/K (case 1), if two or more elements

See the above parameter description as well as note on 'FIX' mode below for details.

they are assumed to be telescope diameter (m) and aperture efficiency

There are two special cases that don't need telescopeparam for unit conversion. Telescope name is obtained from the data.

- 1) ASAP (sd tool) recognizes the conversion factor (actually D and eta) for the "AT" telescopes, namely ATNF MOPRA telescope, until 2004.
- 2) The task does know D and eta for GBT telescope.

If you wish to change the fluxunit, by leaving the sub-parameter telescopeparam unset (telescopeparam=''), it will use internal telescope parameters for flux conversion for the data from AT telescopes and it will use an approximate aperture efficiency conversion for the GBT data.

Note that xxx assumes that the fluxunit is set correctly in the data already. If not, then set telescopeparam='FIX' and it will set the default units to fluxunit without conversion.

Note also that, if the data in infile is an ms from GBT and the default flux unit is missing, this task automatically fixes the default fluxunit to 'K' before the conversion.

Keyword arguments

infile -- name of input SD dataset

default: none - must input file name

example: 'mysd.asap'

See sdcal for allowed formats.

antenna -- select an antenna name or ID

```
default: 0
        example: 'PM03'
        NOTE this parameter is effective only for MS input
fluxunit -- units for line flux
        options: 'K', 'Jy', ''
        default: '' (keep current fluxunit in data)
        WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
        telescopeparam -- parameters of telescope for flux conversion
                options: (str) name or (list) list of gain info
                default: '' (none set)
                example: if telescopeparam='', it tries to get the telescope
                         name from the data.
                         Full antenna parameters (diameter, ap.eff.) known
                         to ASAP are
                         'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
                         'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
                         to 'K' first then convert to a new fluxunit.
                         telescopeparam=[104.9,0.43] diameter(m), ap.eff.
                         telescopeparam=[0.743] gain in Jy/K
                         telescopeparam='FIX' to change default fluxunit
                         see description below
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
        default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                 spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                 spw='0:5~61' (IF ID 0; channels 5 to 61)
                 spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                 spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                 spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
        this selection is in addition to the other selections to data
    >>> spw expandable parameter
        restfreq -- the rest frequency
                    available type includes float, int, string, list of float,
                    list of int, list of string, and list of dictionary. the
                    default unit of restfreq in case of float, int, or string
                    without unit is Hz. string input can be a value only
```

(treated as Hz) or a value followed by unit for which 'GHz',

```
'MHz', 'kHz', and 'Hz' are available.
                    a list can be used to set different rest frequencies for
                    each IF. the length of list input must be number of IFs.
                    dictionary input should be a pair of line name and
                    frequency with keys of 'name' and 'value', respectively.
                    values in the dictionary input follows the same manner as
                    as for single float or string input.
                example: 345.796
                         '1420MHz'
                         [345.8, 347.0, 356.7]
                         ['345.8MHz', '347.0MHz', '356.7MHz']
                         [{'name':'CO','value':345}]
        frame -- frequency reference frame
                options: 'LSRK', 'TOPO', 'LSRD', 'BARY', 'GALACTO', 'LGROUP', 'CMB'
                default: '' (keep current frame in data)
        doppler -- doppler convention (effective only when spw is in
                   velocity unit)
                options: 'RADIO', 'OPTICAL', 'Z', 'BETA', or 'GAMMA'
                default: '' (keep current doppler setting in data)
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
                 Note: YYYY/MM/DD can be dropped as needed:
                 timerange='09:14:00~09:54:00' # this time range
                 timerange='09:44:00' # data within one integration of time
                 timerange='>10:24:00' # data after this time
                 timerange='09:44:00+00:13:00' #data 13 minutes after time
        this selection is in addition to the other selections to data
scan -- select data by scan numbers
        default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
beam -- select data by beam IDs
        default: '' (use all beams)
        example: beam='0,1' (beam IDs 0,1)
        this selection is in addition to the other selections to data
timeaverage -- average spectra over time
        options: (bool) True, False
        default: False
    >>> timeaverage expandable parameter
        tweight -- weighting for time averaging
                options: 'var' (1/var(spec) weighted)
```

```
'tsys' (1/Tsys**2 weighted)
                         'tint' (integration time weighted)
                         'tintsys' (Tint/Tsys**2)
                         'median' ( median averaging)
                default: 'tintsys'
        scanaverage -- average spectra within a scan number
                       when True, spectra are NOT averaged over
                       different scan numbers.
                options: (bool) True, False
                default: False
polaverage -- average spectra over polarizations
        options: (bool) True, False
        default: False
    >>> polaverage expandable parameter
        pweight -- weighting for polarization averaging
                options: 'var' (1/var(spec) weighted)
                         'tsys' (1/Tsys**2 weighted)
                default: 'tsys'
interactive -- determines interactive masking
        options: (bool) True, False
        default: False
        example: interactive=True allows adding and deleting mask
                 regions by drawing rectangles on the plot with mouse.
                 Draw a rectangle with LEFT-mouse to ADD the region to
                 the mask and with RIGHT-mouse to DELETE the region.
outfile -- name of output file (ASCII) to save statistics
        default: '' (no output statistics file)
        example: 'stat.txt'
format -- format string to print statistic values
        default: '3.3f'
overwrite -- overwrite the statistics file if already exists
        options: (bool) True, False
        default: False
        Returns: a Python dictionary of line statistics
           keys: 'rms','stddev','max','min','max_abscissa',
                 'min_abscissa', 'sum', 'median', 'mean', 'totint', 'eqw'
_____
WARNING
For the GBT raw SDFITS format data as input:
SDtasks are able to handle GBT raw SDFITS format data since the
```

data filler is available. However, the functionality is not well

tested yet, so that there may be unknown bugs.

setjy-task.html

0.1.109 setjy

Requires:

Synopsis

Fills the model column with the visibilities of a calibrator

Description

This task places the model visibility amp and phase associated with a specified clean components image into the model column of the data set. The flux density (I,Q,U,V) for a point source calibrator can be entered explicitly. Models are available for 3C48, 3C138, and 3C286 between 1.4 and 43 GHz. 3C147 is available above 13 GHz. These models are scaled to the precise frequency of the data. Only I models are presently available. The location of the models is system dependent: At the AOC, the models are in the directory::/usr/lib/casapy/data/nrao/VLA/CalModels/ 3C286_L.im (egs)

setjy need only be run on the calibrator sources with a known flux density and/or model.

For Solar System Objects, model determination was updated and it is available via the 'Butler-JPL-Horizons 2012' standard.

Currently they are modeled as uniform temperature disks based on their ephemeris at the time of observation (note that this may oversimplify objects, in particular asteroids). Specify the name of the object in the 'field' parameter.

Arguments

Outputs

fluxd Dictionary containing flux densities and their errors.

allowed: any

Default: variant

Inputs

reffreq

vis Name of input visibility file

allowed: string

Default:

field Field name(s)

allowed: string

Default:

spw Spectral window identifier (list)

allowed: string

Default:

selectdata Other data selection parameters

allowed: bool Default: False

timerange Time range to operate on (for usescratch=T)

allowed: any Default: variant

scan Scan number range (for usescaratch=T)

allowed: any Default: variant

intent Observation intent

allowed: string

Default:

observation Observation ID range (for usescratch=T)

allowed: any
Default: variant

scalebychan scale the flux density on a per channel basis or else on a

per spw basis

allowed: bool
Default: True

standard Flux density standard allowed: string

Default: Perley-Butler 2013

model File location for field model

allowed: string

Default:

modimage File location for field model

allowed: string

Default:

list models List the available modimages for VLA calibrators or Tb

models for Solar System objects

allowed: 5600l Default: False

fluxdensity Specified flux density [I,Q,U,V]; (-1 will lookup values)

allowed: any
Default: variant -1

spix Spectral index (including higher terms) of I fluxdensity

allowed: any

Default: variant 0.0
Reference frequency for spix

Returns

void

Example

The task sets the model visibility amp and phase of a specified source (generally a calibrator). The simplest way is to enter the flux density (I,Q,U,V) explicitly, but this is valid only for a point source.

For an extended source, the clean model (image.model) can be specified and the model visibilities associated with this clean model is placed in the visibility model column.

Models are available for 3C48, 3C138, 3C286 between 1.4 and 43 GHz. 3C147 is available above 4 GHz. These models are scaled to the precise frequency of the data. Only I models are presently available.

The location of the models is system dependent: At the AOC and CV, the models are in the directory::/usr/lib/casapy/data/nrao/VLA/CalModels or /usr/lib64/casapy/data/nrao/VLA/CalModels (depending on whether 32 or 64 bit CASA was installed on the machine being used). In general (using Python), the stock models should be in casa['dirs']['data'] + '/nrao/VLA/CalModels' setjy also looks for models in the current directory before trying casa['dirs']['data'] + '/nrao/VLA/CalModels'.

setjy need only be run on the calibrator sources with a known flux density and/or model.

Solar System Objects are supported via the 'Butler-JPL-Horizons 2012' standard. This uses new brightness temperature models and a new flux calculation code that replace the 'Butler-JPL-Horizons 2010' standard. The older 'Butler-JPL-Horizons 2010' standard is still available for comparison. Users may want to use predictcomp task to see the differences. Currently they are modeled as uniform temperature disks based on their ephemerides at the time of observation (note that this may oversimplify objects, in particular asteroids). The object name is obtained from the 'field' parameter. Recognized objects are listed below, under 'standard'.

With standard='manual', flux densities and spectral index can be manually specified. As in the previous CASA versions, if fluxdensity[0] (Stokes I) is < 0, the default standard will be used to calculate flux density as a function of frequency.

```
The calculated flux densities are reported in the logger but also will be
returned as a dictionary if you run as,
fluxds = setjy(vis='ngc5921.ms', ...).
The dictionary have the structure,
     {field name, {spw Id: {'fluxd': [I,Q,U,V] (flux densities in Jy)}}}
and the description is also in fluxds['format'].
Keyword arguments:
vis -- Name of input visibility file
        default: none. example: vis='ngc5921.ms'
field -- Select field using field id(s) or field name(s).
       default: ''=all fields, but run setjy one field at a time.
          [run listobs to obtain the list id's or names of calibrators]
       If field is a non-negative integer, it is assumed to be a field
       index. Otherwise, it is taken to be a field name (case sensitive
       - it must match the name as listed by listobs).
       field='0~2'; field ids 0,1,2
       field='0,4,5~7'; field ids 0,4,5,6,7
       field='3C286,3C295'; field named 3C286 and 3C295
       field = '3,4C*'; field id 3, all names starting with 4C
spw -- Spectral window selection string.
       default: '' = all spectral windows
       Note that setjy only selects by spectral window, and ignores
       channel selections. Fine-grained control could be achieved using
       (and possibly constructing) a cube for modimage.
selectdata -- Other parameters for selecting part(s) of the MS
```

selectdata -- Uther parameters for selecting part(s) of the MS
to operate on.
(Currently all time-oriented and most likely only of

(Currently all time-oriented and most likely only of interest when using a Solar System object as a calibrator.) default: False

>>> selectdata=True expandable parameters

See help par.selectdata for more on these.

Note: for usescratch=False, timerange, scan, and observation are ignored (i.e. time-specific virtual model is not possible.).

timerange -- Select data based on time range (when usescratch=T):
 default: '' (all); examples,
 timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'

```
day in data set
                  timerange='09:14:0~09:54:0' picks 40 min on first day
                  timerange='25:00:00~27:30:00' picks 1 hr to 3 hr
    30min on NEXT day
                  timerange='09:44:00' pick data within one integration
            of time
                  timerange='>10:24:00' data after this time
                  For multiple MS input, a list of timerange strings can be
                  used:
                  timerange=['09:14:0~09:54:0','>10:24:00']
                  timerange='09:14:0~09:54:0''; apply the same timerange for
                                                all input MSes
              scan -- Scan number range (when usescratch=T).
                  default: '' (all)
                  example: scan='1~5'
                  For multiple MS input, a list of scan strings can be used:
                  scan=['0~100','10~200']
                  scan='0~100; scan ids 0-100 for all input MSes
                  Check 'go listobs' to insure the scan numbers are in order.
              observation -- Observation ID range (when usescratch=T).
                  default: '' (all)
                  example: observation='1~5'
              intent -- observation intent.
                  default: '' (all)
                  example: using wildcard characters,
                           intent="*CALIBRATE_AMPLI*"
                           will match field(s) contains CALIBRATE_AMPLI in a list of inten-
                  WARNING: If a source with a specific field id has scans that can be dist:
                           with intent selection, one should set usescatch=True. Otherwise
                           model of the source may be cleared and overwritten even if the ]
                           not selected by intent.
   scalebychan -- This determines whether the fluxdensity set in the model is
           calculated on a per channel basis. If False then it only one
           fluxdensity value is calculated per spw. (Either way, all channels
           in spw are modified.) It is effectively True if fluxdensity[0] >
           0.0.
           default: True
   standard -- Flux density standard, used if fluxdensity[0] < 0.0
           default: 'Perley-Butler 2013'; example: standard='Baars'
           Options: 'Baars',
                    'Perley 90',
```

Note: if YYYY/MM/DD is missing date defaults to first

```
'Perley-Taylor 95',
'Perley-Taylor 99',
'Perley-Butler 2010',
'Perley-Butler 2013',
'Scaife-Heald 2012',
'Butler-JPL-Horizons 2010',
'Butler-JPL-Horizons 2012',
'manual'
'fluxscale'
```

All but the last two are for extragalactic calibrators, and the final two are for Solar System objects. Note that Scaife-Heald 2012 is for the low frequencies (mostly valid for the frequency range, 30-300MHz).

Extragalactic calibrators:

Following source names and their common aliases are recognized. The last column shows which standards support for each source. Note that the task does not do exact matching of the name (also case insensitive) and it recognizes as long as the field name contains the string listed below (e.g. 'PKS 1934-638' works). For 3C Name, a space or an underscore between 3C and the number (e.g. '3C 286' and '3C_286') also works. If the matching by the field name fails, the task tries to match by its position to the known calibrator list stored in the data directory ("/data/nrao/VLA/standards/fluxscalibrator.data).

3C Name B1950 Name J2000 Name Alt. J2000 Name standards*

```
3C48
                                                 1,2,3,4,5,6,7
3C123 0433+295 0437+296 J0437+2940

      3C138
      0518+165
      0521+166
      J0521+1638

      3C147
      0538+498
      0542+498
      J0542+4951

      3C196
      0809+483
      0813+482
      J0813+4813

                                               1,2,3,4,5,6
                                              1,2,3,4,5,6
                                               1,2,7
3C286 1328+307 1331+305 J1331+3030
                                               1,2,3,4,5,6,7
3C295 1409+524 1411+522 J1411+5212
                                                 1,2,3,4,5,6,7
        1934-638
                               J1939-6342
                                                 1,3,4,5,6
3C380 1828+487 1829+487 J1829+4845
_____
```

* supported in: 1 - Perley-Butler 2010, 2 - Perley-Butler 2013 (ref. Perley and Butler 2013, ApJS 204, 19), 3 - Perley-Taylor 99, 4 - Perley-Taylor 95, 5 - Perley 90, 6 - Baars, 7 - Scaife-Heald 2012

Solar system objects:

The 'Butler-JPL-Horizons 2012' standard is recommended over 'Butler-JPL-Horizons 2010' as the former uses updated models.

Recognized Solar System objects (for 'Butler-JPL-Horizons 2012') are:

Planets: Venus, Mars, Jupiter, Uranus, Neptune

Moons: Jupiter: Io, Europa, Ganymede, Callisto

Saturn: Titan

Asteroids: Ceres, Pallas**, Vesta**, Juno**

- * Venus: model for ~300MHz to 350GHz, no atmospheric lines (CO,H2O,HDO, etc)
- * Mars: tabulated as a function of time and frequency (30 1000GHz) based on Rudy et al (1988), no atmospheric lines (CO, H2O, H2O2, HDO, etc)
- * Jupiter: model for 30-1020GHz, does not include synchrotron emission
- * Uranus: model for 60-1800GHz, contains no rings or synchrotron.
- * Neptune: model for 2-2000GHz, the broad CO absorption line is included, but contains no rings or synchrotron.
- * Titan: model for 53.3-1024.1GHz, include many spectral lines
- ** not recommended (The temperature is not yet adjusted for varying distance from the Sun. The model data can be scaled after running setjy, but it is an involved process.)

The 'field' parameter must match the case of the field name(s) in vis (as shown by listobs).

Flux density calculation with Solar System objects depends on ephemerides. The setjy task looks for the data in

os.getenv('CASAPATH').split()[0] + '/data/ephemerides/JPL-Horizons'.

If no ephemeris for the right object at the right time is present, the calculation will fail. Ask the helpdesk to make an ephemeris. The very adventurous and well versed in python can try it using CASA's recipes.ephemerides package:

import recipes.ephemerides as eph

help eph

CASA comes with ephemerides for several more objects, but they are intended for use with me.framecomet(), and are not (yet) suitable flux density calibrators. It is up to the observer to pick a good flux density calibrator (bright, spherical and featureless, on a circular orbit, in the right part of the sky, and not too resolved). Even some of the objects listed above may prove to require more sophisticated flux density models than are currently implemented in CASA. For many objects running casalog.filter('INFO1') before running setjy will send more

information to the logger. The cookbook also has an appendix with descriptions of the models used by setjy (both extragalactic and Solar System).

>>> standard="Perley-Butler 2010" or "Perley-Butler 2013 expandable parameter model -- Model image (I only) for setting the model visibilities.

- \ast Previously, this parameter is called 'modimage', now modimage \ast
- * is deprecated. The setjy still accepts modimage but will be *
- * removed in future releases. Please use the parameter, 'model' *
- * instead.

The model can be a cube, and its channels do not have to exactly match those of vis. It is recommended to use modimage for sources that are resolved by the observation, but the Butler-JPL-Horizons standard supplies a basic model of what several Solar System objects look like. default: '': do not use a model image.

Each field must be done separately when using a model image.

Both the amplitude and phase are calculated. At the AOC or CV, the models are located in casa['dirs']['data'] + '/nrao/VLA/CalModels/', e.g. /usr/lib/casapy/data/nrao/VLA/CalModels/3C286_L.im lib64

If model does not start with '/', setjy will look for a match in '.', './CalModels', and any CalModels directories within the casa['dirs']['data'] tree (excluding certain branches).

Note that model should be deconvolved, i.e. a set of clean components instead of an image that has been convolved with a clean beam.

```
interpolation -- method for interpolation ('nearest', 'linear', 'cubic',
                or 'spline') in time for the time variable sources (3C48,3C138,3C147).
                This parameter is ignored for other non-variable sources in the standard.
                default: 'nearest'
       >>> standard="Butler-JPL-Horizons 2012" expandable parameter
            useephemdir -- If True: use the direction from the ephemeris table for
                the solar system object.
                default: False -use the direction information in the MS(i.e. Field table)
       >>> standard="manual" expandable parameters
    fluxdensity -- Specified flux density [I,Q,U,V] in Jy
default: -1, uses [1,0,0,0] flux density for unrecognized sources,
and standard flux densities for ones recognized by the default
                standard (Perley-Butler 2010).
setjy will try to use the standard if fluxdensity is not
positive.
Only one flux density can be specified at a time. The phases are
set to zero.
example
         fluxdensity=-1 will use the default standard for recognized
          calibrators (like 3C286, 3C147 and 3C48) and insert 1.0
                          for selected fields with unrecognized sources.
example field = '1'; fluxdensity=[3.2,0,0,0] will put in
  a flux density of I=3.2 for field='1'
        At present (June 2000), this is the only method to insert a
polarized flux density model.
example: fluxdensity=[2.63,0.21,-0.33,0.02]
          will put in I,Q,U,V flux densities of 2.63,0.21,-0.33,
  and 0.02, respectively, in the model column.
    spix -- Spectral index for I flux density (a float or a list of float values):
       where S = fluxdensity * (freq/reffreq)**(spix[0]+spix[1]*log(freq/reffreq)+..)
Default: [] =>0.0 (no effect)
Only used if fluxdensity is being used.
N.B.: If fluxdensity is positive, and spix is nonzero, then reffreq
     must be set too! (See below)
It is applied in the same way to all polarizations, and does
not account for Faraday rotation or depolarization.
```

>>> standard="Perley-Butler 2013" expandable parameter

Example: [-0.7, -0.15] for alpha and a curvature term

reffreq -- The reference frequency for spix, given with units. Default: '1GHz'; this is only here to prevent division by 0! N.B.: If the flux density is being scaled by spectral index, then reffreq must be set to whatever reference frequency is correct for the given fluxdensity and spix. It cannot be determined from vis. On the other hand, if spix is 0, then any positive frequency can be used (and ignored).

Examples: '86.0GHz', '4.65e9Hz'

Default: []

Example: [0.2, -0.01] (= [c0, c1])

polangle -- Coefficients of the frequency-dependent linear polarization angle (pol. angle = 0.5*arctan(U/Q) = d0 + d1*((freq-reffreq)/reffreq) + d2When Q and U flux densities are given fluxdensity, d0 is determined these flux densities and the entry for d0 in polangle is ignored. On fluxdensity can be set to 0.0 and then polindex[0] and polangle[0] at reffreq.

Default: []

Example: [0.57, 0.2] (=[d0,d1])

rotmeas -- rotation measure (in rad/m^2)

>>> standard="fluxscale" expandable parameters

fluxdict -- Output dictionary from fluxscale

Using the flexibly results, the flux density, spectral index,
and reference frequency are extracted and set to fluxdensity,
spix, and reffreq parameters, respectively.

The field and spw selections can be used to specify subset of
the fluxdict to be used to set the model. If they are left as
default (field="", spw="") all fields and/or spws in
the fluxdict (but those spws with fluxd=-1 will be skipped) are

used.

default: {}

usescratch -- If False: 'virtual' model is created. The model information is saved

either in the SOURCE_MODEL column in the SOURCE table (if one exists) or in the keys of the main table in the MS and model visibilities are evaluated on the fly when callibration or plotting in plotms.

If True: the model visibility will be evaluated and saved on disk in the MODEL_DATA column. This will increase your ms in size by a factor of 1.5 (w.r.t. the case when you only have the DATA and the CORRECTED_DATA column). Use True if you need to into with the MODEL_DATA in python, say. Also, use True if you need finer than field and selections using scans/time (and when use with intent selection, please see WARNING intent parameter description).

*By running usescratch=T, it will remove the existing virtual model from previous rusescratch=F will not remove the existing MODEL_DATA but in subsequent process the virtual model with matching field and spw combination will be used if it exists regardless of the presence of the MODEL_DATA column.

default: False

Returned dictionary:

When the setjy task is executed as setjy(vis='', ...), the flux densities used to set the model are returned as a Python dictionary with the format, {field Id: {spw Id: {fluxd: [I,Q,U,V] in Jy}, 'fieldName':field name }}, where field Id and spw Id are in string type.

simalma-task.html

0.1.110 simalma

Requires:

Synopsis

Simulation task for ALMA

Description

This task simulates ALMA observation including 12-m, ACA 7-m and total power arrays, and images and analyzes simulated data.

This task makes multiple calls to simobserve (to calculate visibilities and total power spectra), followed by gridding of total power spectra (if total power is requested), concatenation of the simulated visibilities, calls to the simanalyze task for visibility inversion and deconvolution and calculation of difference and fidelity images, and feathering of single dish and interferometric data.

These steps may not all be familiar to new users, so the simalma task runs by default in a "dryrun" mode, in which it assesses the user's input parameters and sky model, and prints an informational report including the required calls to other CASA tasks, both to the screen and to a text file in the project directory (defined below).

The user can modify their parameters based on the information, then either run with dryrun=False to actually call the other tasks to create the simulated data, or run the other tasks individually one at a time to better understand and control the process.

NOTE The ALMA project is refining the optimal method of combining the three types of data. If that best practice is changed after this release of CASA, the user can control the process by modifying the calls to the other CASA tasks.

More information is available at

http://casaguides.nrao.edu/index.php?title=Simulating_Observations_in_CASA Please contact the CASA helpdesk with any questions.

Arguments

Inputs

project root prefix for output file names

allowed: string

Default: sim

dryrun = True will only produce the informative report,

not run simobserve/analyze

allowed: bool

Default: True

skymodel model image to observe

allowed: string

Default:

inbright scale surface brightness of brightest pixel e.g.

"1.2Jy/pixel"

allowed: string

Default:

indirection set new direction e.g. "J2000 19h00m00 -40d00m00"

allowed: string

Default:

incell set new cell/pixel size e.g. "0.1arcsec"

allowed: string

Default:

incenter set new frequency of center channel e.g. "89GHz" (re-

quired even for 2D model) allowed: string

Default:

inwidth set new channel width e.g. "10MHz" (required even for

2D model)

allowed: string

Default:

complist componentlist to observe

allowed: string

Default:

compwidth bandwidth of components

allowed: string

Default: "8GHz"

setpointings

allowed: bool

Default: True

ptgfile list of pointing positions

allowed: string

Default: \$project.ptg.txt

integration integration (sampling) time

allowed: string Default: 10s

direction "J2000 19h00m00 -40d00m00" or "" to center on model

allowed: stringArray

Default:

mapsize angular size of grap or "" to cover model

allowed: stringArray

Default:

antennalist antenna position files of ALMA 12m and 7m arrays

allowed: stringArray

Default: alma.cycle1.1.cfg aca.cycle1.cfg

hourangle hour angle of observation center e.g. -3:00:00, or "tran-

sit"

$\begin{array}{c} \textbf{Returns} \\ \textbf{bool} \end{array}$

Example

Parameters:

skymodel -- input image (used as a model of the sky)

- * simalma requires a CASA or fits image. If you merely have a grid of numbers, you will need to write them out as fits or write a CASA script to read them in and use the ia tool to create an image and insert the data.
- * simalma does NOT require a coordinate system in the header. If the coordinate information is incomplete, missing, or you would like to override it, set the appropriate "in" parameters. NOTE that setting those parameters simply changes the header values, ignoring any values already in the image. No regridding is performed.
- * If you have a proper Coordinate System, simalma will do its best to generate visibilities from that, and then create a synthesis image according to the specified user parameters.
- * You can manipulate an image header manually with the "imhead" task.

inbright -- peak brightness in Jy/pixel, or "" for unchanged

* NOTE: "unchanged" will take the numerical values in your image and assume they are in Jy/pixel, even if it says some other unit in the header.

indirection -- central direction, or "" for unchanged
incell -- spatial pixel size, or "" for unchanged
incenter -- frequency of center channel e.g. "89GHz", or "" for unchanged
inwidth -- width of channels, or "" for unchanged - this should be a
 string representing a quantity with units e.g. "10MHz"

- * NOTE: only works reliably with frequencies, not velocities
- * NOTE: it is not possible to change the number of spectral planes of the sky model, only to relabel them with different frequencies

That kind of regridding can be accomplished with the CASA toolkit.

complist -- component list model of the sky, added to or instead of skymodel compwidth -- bandwidth of components; if simulating from components only, this defines the bandwidth of the MS and output images

setpointings -- calculate a map of pointings, or if false, the user should provide a ptgfile

- * if graphics are on, display the pointings shown on the model image
- * if a list of directions is not specified, observations with the ALMA 12m and ACA 7m arrays will observe a region of size "mapsize" using the same hexagonal algorithm as the ALMA OT, with Nyquist sampling.
- * The total power array maps a slightly (+1 primary beam) larger area than the 12m array does, to improve later image combination.

 It samples the region with lattice grids of spacing 0.33 lambda/D.
- ptgfile -- a text file specifying directions in the same
 format as the example, and optional integration times, e.g.
 #Epoch RA DEC TIME(optional)
 J2000 23h59m28.10 -019d52m12.35 10.0
 - * if the time column is not present in the file, it will use "integration" for all pointings.
 - * NOTE: at this time the file should contain only science pointings: simalma will observe these until totaltime is used up.
- integration --- Time interval for each integration e.g '10s'
 - * NOTE: to simulate a "scan" longer than one integration, use setpointings to generate a pointing file, and then edit the file to increase the time at each point to be larger than the parameter integration time.
- direction -- mosaic center direction e.g 'J2000 19h00m00 -40d00m00'
 - * can optionally be a list of pointings
 - * otherwise simalma will pack mapsize with grids proper for the array (see below).
- mapsize -- angular size of map e.g. '40arcsec' or ['1arcmin','30arcsec']
 - * set to "" to span the model image

- antennalist -- vector of ascii files containing antenna positions, one for each configuration of 7m or 12m dishes.
 - \ast NOTE: In this task, it should be an ALMA configuration.
 - * standard arrays are found in your CASA data repository, os.getenv("CASAPATH").split()[0]+"/data/alma/simmos/"
 - * a string of the form "alma; 0.5 arcsec" will be parsed into a 12m ALMA configuration see casaguides.nrao.edu

* note that if you don't add a unit, it will assume seconds.

totaltime --- total time of observations. This should either be a scalar time quantity expressed as a string e.g. '1h', '3600sec', '10min', or a vector of such quantities, corresponding to the elements of the antennalist vector, e.g. ['5min','20min','3h']. If you specify a scalar, that will be used for the highest resolution 12m configuration in antennalist, and any lower resolution 12m configurations, any 7m configurations, and any TP configurations will have observing times relative to totaltime of 0.5, 2, and 4, respectively.

tpnant -- the number of total power antennas to use in simulation.
tptime -- if tpnant>0, the user must specify the observing time for
 total power as a CASA quantity e.g. '4h'.

* NOTE: in CASA 4.2 this is not broken up among multiple days - a 20h track will include observations below the horizon, which is probably not what is desired.

pwv -- precipitable water vapor if constructing an atmospheric model.
 Set 0 for noise-free simulation. When pwv>0, thermal noise is
 applied to the simulated data.

* J. Pardo's ATM library will be used to construct anatmospheric profile for the ALMA site: altitude 5000m, ground pressure 650mbar, relhum=20%, a water layer of pwv at altitude of 2km, the sky brightness temperature returned by ATM, and internally tabulated receiver temperatures.

See the documents of simobserve for more details.

image -- option to invert and deconvolve the simulated measurement set(s)

- * NOTE: interactive clean or more parameters than the subset visible here are available by simply running the clean task directly.
- * if graphics turned on, display the clean image and residual image
- * uses Cotton-Schwab clean for single fields and Mosaic gridding for multiple fields (with Clark PSF calculation in minor cycles).

imsize -- image size in spatial pixels (x,y)

0 or -1 will use the model image size; example: imsize=[500,500] imdirection -- phase center for synthesized image. default is to center on the sky model.

cell -- cell size e.g '10arcsec'. "" defaults to the skymodel cell niter -- number of clean/deconvolution iterations, 0 for no cleaning threshold -- flux level to stop cleaning

graphics -- view plots on the screen, saved to file, both, or neither verbose -- print extra information to the logger and terminal overwrite -- overwrite existing files in the project subdirectory

Please see the documents of simobserve and simanalyze for the list of outputs produced.

0.1.111 simobserve

Requires:

Synopsis

visibility simulation task

Description

This task simulates interferometric or total power measurment sets It is currently optimized for JVLA and ALMA, although many observatories are included, and adding your own is simply a matter of providing an antenna location file (see below).

simobserve is meant to work in conjunction with the simanalyze task - Calling simobserve one more times will produce simulated measurement set(s), which are then gridded, inverted and deconvolved into output simulated images using simanalyze.

ALMA users are encouraged to use the simalma task, which provides additional information on the multiple simobserve and simanalyze calls required to simulate an ALMA observation which may consist of 12m interferometric, 7m interferometric, and 12m total power data. More information and examples are available at http://casaguides.nrao.edu/index.php?title=Simulating_Observations_in_CASA Please contact CASA experts with any questions.

Arguments

Inputs project root prefix for output file names allowed: string Default: \sin skymodel model image to observe allowed: string Default: inbright scale surface brightness of brightest pixel e.g. "1.2Jy/pixel" allowed: string Default: indirection set new direction e.g. "J2000 19h00m00 -40d00m00" allowed: string Default: incell set new cell/pixel size e.g. "0.1arcsec" allowed: string Default: incenter set new frequency of center channel e.g. "89GHz" (required even for 2D model) allowed: string Default: inwidth set new channel width e.g. "10MHz" (required even for 2D model) allowed: string Default: complist componentlist to observe allowed: string Default: compwidth bandwidth of components allowed: string Default: "8GHz" setpointings allowed: bool Default: True ptgfile list of pointing positions allowed: string Default: \$project.ptg.txt integration integration (sampling) time allowed: string Default: 10sdirection "J2000 19h00m00 -40d00m00" or "" to center on model allowed: stringArray Default: angular size of map or "" to cover model mapsize allowed: stringArray Default: hexagonal, square (raster), ALMA, etc maptype allowed: $577 \, string$ Default: hexagonal spacing pointingspacing in between pointings or "0.25PB" for ALMA default INT=lambda/D/sqrt(3),

pt source calibrator [experimental] allowed: string

string

SD=lambda/D/3

allowed:

Default:

caldirection

Returns

bool

Example

project -- the root filename for all output files.

skymodel -- input image (used as a model of the sky)

- * simalma requires a CASA or fits image. If you merely have a grid of numbers, you will need to write them out as fits or write a CASA script to read them in and use the ia tool to create an image and insert the data.
- * simalma does NOT require a coordinate system in the header. If the coordinate information is incomplete, missing, or you would like to override it, set the appropriate "in" parameters. NOTE that setting those parameters simply changes the header values, ignoring any values already in the image. No regridding is performed.
- * If you have a proper Coordinate System, simalma will do its best to generate visibilities from that, and then create a synthesis image according to the specified user parameters.
- * You can manipulate an image header manually with the "imhead" task.

inbright -- peak brightness in Jy/pixel, or "" for unchanged

* NOTE: "unchanged" will take the numerical values in your image and assume they are in Jy/pixel, even if it says some other unit in the header.

indirection -- central direction, or "" for unchanged
incell -- spatial pixel size, or "" for unchanged
incenter -- frequency of center channel e.g. "89GHz", or "" for unchanged
inwidth -- width of channels, or "" for unchanged - this should be a
 string representing a quantity with units e.g. "10MHz"

- * NOTE: only works reliably with frequencies, not velocities
- * NOTE: it is not possible to change the number of spectral planes of the sky model, only to relabel them with different frequencies That kind of regridding can be accomplished with the CASA toolkit.

complist -- component list model of the sky, added to or instead of skymodel see http://casaguides.nrao.edu/index.php?title=Simulation_Guide_Component_Lists_%28

compwidth -- bandwidth of components; if simulating from components only, this defines the bandwidth of the MS and output images

setpointings -- calculate a map of pointings, or if false, provide ptgfile
 * if graphics are on, display the pointings shown on the model image
ptgfile -- a text file specifying directions in the following

format, with optional integration times, e.g. #Epoch RA DEC TIME(optional) J2000 23h59m28.10 -019d52m12.35 10.0

- * if the time column is not present in the file, it will use "integration" for all pointings.
- * NOTE: at this time the file should contain only science pointings: simobserve will observe these, then optionally the calibrator, then the list of science pointings again, etc, until totaltime is used up.

integration --- Time interval for each integration e.g '10s'

- * NOTE: to simulate a "scan" longer than one integration, use setpointings to generate a pointing file, and then edit the file to increase the time at each point to be larger than the parameter integration time.
- direction -- mosaic center direction e.g 'J2000 19h00m00 -40d00m00'
 - * can optionally be a list of pointings
- * otherwise simobserve will pack mapsize according to maptype mapsize -- angular size of map
 - * set to "" to span the model image
- maptype -- hexagonal, square (rectangular raster),

"ALMA" for the same hex algorithm as the ALMA Cycle 1 OT or "ALMA2012" for the algorithm used in the Cycle 0 OT $\,$

pointingspacing -- spacing in between beams e.g 'larcsec'

"0.25PB" to use 1/4 of the primary beam FWHM,

"nyquist" will use lambda/d/2,

"" will use lambda/d/sqrt(3) for INT, lambda/d/3 for SD

- obsmode -- observation mode to calculate visibilities from a skymodel image (which may have been modified above), an optional component list, and a pointing file (which also may have been generated above)
 - st this parameter takes two possible values:
 - interferometer (or i)
 - singledish (or s)
 - * if graphics are on, this observe step will display the array (similar to plotants), the uv coverage, the synthesized (dirty) beam, and ephemeris information
 - * if simulating from component list, you should specify "compwidth", the desired bandwidth. There is not currently a way to specify the spectrum of a component, so simulations from a componentlist only will be continuum (1 chan)

refdate -- date of simulated observation eg: '2014/05/21' hourangle -- hour angle of observation e.g. '-3h'

* note that if you don't add a unit, it will assume hours totaltime --- total time of observation e.g '7200s' or if a number without units, interpreted as the number of times to repeat the map antennalist -- ascii file containing antenna positions.

each row has x y z coordinates and antenna diameter; header lines are required to specify the observatory name and coordinate system e.g.

- # observatory=ALMA
- # coordsys=UTM
- # datum=WGS84
- # zone=19
- * standard arrays are found in your CASA data repository, os.getenv("CASAPATH").split()[0]+"/data/alma/simmos/"
- * if "", simobserve will not not produce an interferometric MS
- * a string of the form "alma; 0.5 arcsec" will be parsed into a full 12m ALMA configuration. This only works for full ALMA and may fail to find the standard configuration files on some systems see casaguides.nrao.edu for more information.
- caldirection -- an unresolved calibrator can be observed interleaved with the science pointings.
 - * The calibrator is implemented as a point source clean component with this specified direction and flux=calflux
- sdant -- the index of the antenna in the list to use for total power. defaults to the first antenna on the list.

thermalnoise -- add thermal noise

- st this parameter takes two possible values:
- tsys-atm: J. Pardo's ATM library will be used to construct an atmospheric profile for the ALMA site: altitude 5000m, ground pressure 650mbar, relhum=20%, a water layer of user_pwv at altitude of 2km, the sky brightness temperature returned by ATM, and internally tabulated receiver temperatures
- tsys-manual: instead of using the ATM model, specify the zenith sky brightness and opacity manually. Noise is added and then the visibility flux scale is referenced above the atmosphere.
- * In either mode, noise is calculated using an antenna spillover efficiency of 0.96, taper of 0.86, surface accuracy of 25 and 300 microns for ALMA and EVLA respectively (using the Ruze formula for surface efficiency), correlator efficiencies of 0.95 and 0.91 for ALMA and EVLA, receiver temperatures for ALMA of
 - 17, 30, 37, 51, 65, 83,147,196,175,230 K interpolated between 35, 75,110,145,185,230,345,409,675,867 GHz,

```
for EVLA of 500, 70, 60, 55, 100, 130, 350 K interpolated between 0.33,1.47,4.89,8.44,22.5,33.5,43.3 GHz, for SMA of 67, 116, 134, 500 K interpolated between
```

212.,310.,383.,660. GHz

* These are only approximate numbers and do not take into account performance at edges of receiver bands, neither are they guaranteed to reflect the most recent measurements. Caveat emptor and use the sm tool to add noise if you want more precise control.

t_ground -- ground/spillover temperature in K
user_pwv -- precipitable water vapor if constructing an atmospheric model
t_sky -- atmospheric temperature in K [for tsys-manual]
tau0 -- zenith opacity at observing frequency [for tsys-manual]

* see casaguides.nrao.edu for more information on noise, in particular how to add a phase screen using the toolkit seed -- random number seed for noise generation

leakage -- add cross polarization corruption of this fractional magnitude

graphics -- view plots on the screen, saved to file, both, or neither verbose -- print extra information to the logger and terminal overwrite -- overwrite existing files in the project subdirectory

Output produced: (not all will always exist, depending on input parameters) To support different runs with different arrays, the names have the configuration name from antennalist appended.

project.[cfg].skymodel = 4d input sky model image (optionally) scaled
project.[cfg].skymodel.flat.regrid.conv = input sky regridded to match the
 output image, and convolved with the output clean beam
project.[cfg].skymodel.png = diagnostic figure of sky model with pointings

project.[cfg].ptg.txt = list of mosaic pointings
project.[cfg].quick.psf = psf calculated from uv coverage
project.[cfg].ms = noise-free measurement set
project.[cfg].noisy.ms = corrupted measurement set
project.[cfg].observe.png = diagnostic figure of uv coverage and
 visibilities

project.[cfg].simobserve.last = saved input parameters for simobserve task

0.1.112 simanalyze

Requires:

Synopsis

image and analyze measurement sets created with simobserve

Description

This task is for imaging and analyzing measurement sets (MSs) simulated with simobserve or simalma.

Arguments

Inputs

project root prefix for output file names

> allowed: string Default: sim

image (re)image project. * .mstoproject.image

> allowed: bool Default: True

imagename simulation output image to analyze (default = first

> \$project/*.image found) allowed: string Default: default

skymodel skymodel image to analyze (the .skymodel image cre-

ated by simobserve or simalma and used by one of those tasks to create an MS; if unspecified, will try to find one

similar to your specified output image name)

allowed: string

Default:

vis Measurement Set(s) to image

> allowed: string Default: default

modelimage lower resolution prior image to use in clean e.g. existing

> total power image allowed: string

Default:

output image size in pixels (x,y) or 0 to match model imsize

> allowed: intArray Default:

imdirection set output image direction, (otherwise center on the

model)

allowed: string

Default:

cell cell size with units e.g. "10arcsec" or "" to equal model

> allowed: string

Default:

interactive interactive clean? (make sure to set niter>0 also)

> allowed: bool Default: False

niter maximum number of iterations (0 for dirty image)

> allowed: int Default: 0

threshold flux level (+units) to stop cleaning

> allowed: string 0.1 mJvDefault:

weighting weighting to apply to visibilities. briggs will use ro-

bust=0.5

allowed: string Default: natural

Cleanbox(es), spask image(s), region(s), or a level mask

> allowed: any Default: variant

outertaper uv-taper on outer baselines in uv-plane

> allowed: stringArray

Default:

correct the output of synthesis images for primary beam pbcor

response?

Returns

void

Example

* "project" needs to be the directory of results generated by running simobserve or simalma. In particular \$project/\$project.skymodel will be required in order to compare output and input images.

mode image=True:

- * One should input one or more simulated MSs using the "vis" parameter. These can include a total power MS.

 Simanalyze will grid any total power MS,
 clean (invert and deconvolve) any interferometric MSs,
 and feather the results.
- * the "vis" parameter:
 - example: single MS: vis="mysim.alma.out03.ms"
 - example: multiple MSs: vis=["mysim.alma.out03.ms", "mysim.aca.tp.ms"]
 - one can use '\$project' and let the task automatically replace it with the project name, e.g., vis="\$project.noisy.ms,\$project.noisy.sd.ms". However, note that if you created measurement set(s) using simobserve, MS names will include the configuration, e.g. \$project.alma_out20.noisy.ms
 - setting "vis" to "default" will find and attempt to image all measurement sets (interferometric and single dish) in the project directory
- * Sometimes it is preferable to grid the single dish MS using the sdimaging task for more control. In that case one can input the resulting single dish imaging under "featherimage", only put interferometric MSs in "vis", and simanalyze will clean the interferometric and feather with your "featherimage".
- * Sometimes it is preferable to use a low resolution (single dish or synthesis) image as a prior model during clean deconvolution of a higher resolution interferometric MS. That is accomplished by putting the low-resolution image in "modelimage" and the MS to be deconvolved in "vis". NOTE: This is not the original skymodel that was used in simobserve or simalma. It is recommended to leave this blank unless the user is familiar with using a prior

in clean deconvolution. (see casaguides) NOTE 2: modelimage will not be used if the MS to be imaged is total power.

- * uses Cotton-Schwab clean for single fields and Mosaic gridding for multiple fields (with Clark PSF calculation in minor cycles).
- * interactive clean or use of more parameters than the subset visible here are available by simply running the clean task directly, then using simanalyze in the mode image=False (see below).
- * if graphics are turned on, this step will display the clean image and residual image
- * the "mask" parameter:

 Specification of cleanbox(es), mask image(s), primary beam coverage level, and/or region(s) to be used for cleaning. clean tends to perform better, and is less likely to diverge, if the clean component placement is limited by a mask to where real emission is expected to be. e.g. pixel ranges mask=[110,110,150,145], filename of mask image mask='myimage.mask', or a file with mask regions -- see help for the clean task for more information.

mode image=False:

* Sometimes the user has created a synthesized image themselves, most likely using the clean task, perhaps along with sdimaging and feather, or a previous call to simanalyze with image=True

* The user should input that simulated image as "imagename". It will have suffix .image if created by clean, simanalyze, or simalma

* simanalyze will attempt to find an appropriate skymodel image this is the *.skymodel image created by simobserve or simalma,
the (optionally rescaled) original sky model, which was used
to create the measurement set.

simanalyze will look in the project directory, but if there are multuple skymodels present it may not find the right one, so the "skymodel" parameter allows explicit specification.

mode analyze=True is used to create an image of the difference between the input skymodel and the simulated output image (whether that output image is being generated in the same call to simanalyze, with image=True, or has already been generated, and simanalyze is being called with image=False).

showuv -- display uv coverage showpsf -- display synthesized (dirty) beam (ignored in single dish simulation)

```
showmodel -- display sky model at original resolution
showconvolved -- display sky model convolved with output beam
showclean -- display the synthesized image
showresidual -- display the clean residual image (ignored in single dish simulation)
showdifference -- display difference between output cleaned image and
    input model sky image convolved with output clean beam
showfidelity -- display fidelity image
    fidelity = abs(input) / max[ abs(input-output), 0.7*rms(output) ]
```

Note that the RMS is calculated in the lower quarter of the image.

This is likely not the best choice, so you are encouraged to
measure RMS yourself in an off-source region using the viewer.

dryrun=True is an advanced technical mode only useful for interferometric (not single dish) data.

Output produced: (not all will always exist, depending on input parameters) To support different runs with different arrays, the names have the configuration name from antennalist appended.

project.[cfg].skymodel.flat.regrid.conv = input sky regridded to match
 the output image, and convolved with the output clean beam

 $\verb|project.[cfg].simanalyze.last = \verb|saved| input| \verb|parameters| for simanalyze task|$

Please see http://casaguides.nrao.edu, and contact the CASA helpdesk with questions.

slsearch-task.html

0.1.113slsearch

Requires:

Synopsis Search a spectral line table.

Arguments

Inputs

tablename Input spectral line table name to search. If not specified,

use the default table in the system.

allowed: string

Default:

outfile Results table name. Blank means do not write the table

to disk.

allowed: string

Default:

Frequency range in GHz. freqrange

> allowed: doubleArray

Default: 84,90

species Species to search for.

> allowed: stringArray

Default:

reconly List only NRAO recommended frequencies.

> bool allowed: Default: False

chemnames Chemical names to search for.

> allowed: stringArray

Default:

Resolved quantum numbers to search for. qns

> allowed: stringArray

Default:

intensity CDMS/JPL intensity range. -1 -> do not use an inten-

sity range.

allowed: doubleArray

Default:

S*mu*mu range in Debye**2. -1 -> do not use an smu2

S*mu*mu range.

allowed: doubleArray

Default:

log(A) (Einstein coefficient) range. -1 -> do not use a loga

loga range.

allowed: doubleArray

Default:

elLower energy state range in Kelvin. -1 -> do not use an

el range.

allowed: doubleArray

Default: -1

Upper energy state range in Kelvin. -1 -> do not use an eu

eu range.

allowed: doubleArray

Default:

rrlinclude Include RRLs in the result set?

> allowed: bool Default: True

rrlonly Include only RRks in the result set?

> allowed: bool Default: False

verbose List result set to logger (and optionally logfile)?

> allowed: bool Default: False

logfile List result set to this logfile (only used if verbose=True).

> allowed: string

Default:

Returns

bool

Example

PARAMETER SUMMARY

tablename Input spectral line table name to search. If not specified, use the default t

outfile Results table name. Blank means do not write the table to disk.

frequency range in GHz. species Species to search for.

reconly List only NRAO recommended frequencies.

chemnames Chemical names to search for.

qns Resolved quantum numbers to search for.

intensity CDMS/JPL intensity range. -1 -> do not use an intensity range.

S*mu*mu range in Debye**2. -1 -> do not use an S*mu*mu range.

loga log(A) (Einstein coefficient) range. -1 -> do not use a loga range.

el Lower energy state range in Kelvin. -1 -> do not use an el range.

eu Upper energy state range in Kelvin. -1 -> do not use an eu range.

rrlinclude Include RRLs in the result set?
rrlonly Include only RRLs in the result set?

verbose List result set to logger (and optionally logfile)?

logfile List result set to this logfile (only used if verbose=True).

append If true, append to logfile if it already exists, if false overwrite logfile:

Search the specified spectral line table. The results table can be written to disk by specified outfile is not specified (ie outfile=""), no table is created. Because Splatalogue do loga, eu, and el for radio recombination lines (rrls), one must specify to include RRLs output. In this case, RRLs will be included ignoring any filters on intensity, smu2, log list only RRLs. One can specify to list the search results to the logger via the verbose logger output is listed. If verbose=True, one can also specify that the results be listed exists, one can specify that the results be appended to it or to overwrite it with the results of the search results are to overwrite it with the results be appended to it or to overwrite it with the results are to overwrite it with the results be appended to it or to overwrite it with the results are to overwrite it with

put search results in a table but do not list to the logger slsearch("myspectrallines.tbl", verbose=False) smooth cal-task.html

0.1.114 smoothcal

Requires:

Synopsis

Smooth calibration solution(s) derived from one or more sources:

Description

A G- or T-type gain calibration can be smoothed. Amplitude and phase are currently smoothed with the same time. Calibration values will be smoothed over all fields.

Arguments

Inputs		
vis	Name of input visibility file (MS)	
	allowed:	string
	Default:	
tablein	Input calibration table	
	allowed:	string
	Default:	
caltable	Output calibration table (overwrite tablein if unspeci-	
	fied)	•
	allowed:	string
	Default:	
field	Field name list	
	allowed:	stringArray
	Default:	
$\operatorname{smoothtype}$	Smoothing filter to use	
	allowed:	string
	Default:	median
smooth time	Smoothing time (sec)	
	allowed:	any
	Default:	variant 60.0

Returns

void

Example

phase smoothing times are currently the same. Calibration values will be smoothed for only the specified fields. Smoothing is performed independently per field, per spw, and per antenna. Keyword arguments: vis -- Name of input visibility file default: none; example: vis='ngc5921.ms' tablein -- Input calibration table (G or T) default: none; example: tablein='ngc5921.gcal' caltable -- Output calibration table (smoothed) default: '' (will overwrite tablein); example: caltable='ngc5921_smooth.gcal' field -- subset of fields to select and smooth default: '' means all; example: field='0319_415_1,3C286' smoothtype -- The smoothing filter to be used for both amp and phase default: 'median'; example: smoothtype='mean' Options: 'median', 'mean'

default: 300.0; example: smoothtime=60.

smoothtime -- Smoothing filter time (sec)

A G- or T-type gain calibration can be smoothed. The amplitude and

spec fit-task.html

0.1.115specfit

Requires:

 ${\bf Synopsis}$ Fit 1-dimensional gaussians and/or polynomial models to an image or image region

Description

Arguments

Inputs

imagename Name of the input image

allowed: string

Default:

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane.

allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. De-

fault is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Default is to use all Stokes planes.

allowed: string

Default:

axis The profile axis. Default: use the spectral axis if one

exists, axis 0 otherwise (<0).

allowed: int

Default: -1

mask Mask to use. See help par.mask. Default is none..

allowed: string

Default:

ngauss Number of Gaussian elements. Default: 1.

allowed: int

Default: 1
poly Order of polynomial element. Default: do not fit a poly-

nomial (<0).

allowed: int Default: -1

estimates Name of file containing initial estimates. Default: No

initial estimates (""). allowed: string

Default:

minpts Minimum number of unmasked points necessary to at-

tempt fit.

allowed: int Default: 1

multifit If true, fit a profile along the desired axis at each pixel

in the specified region. If false, average the non-fit axis pixels and do a single fit to that average profile. Default

False.

allowed: 594 bool Default: False

model Name of model image. Default: do not write the model

image ("").

allowed: string

Default:

residual Name of residual image. Default: do not write the resid-

ual image ("").

allowed: string

Returns

record

Example

This task simultaneously fits one or more gaussian singlets lorentzian singlets, gaussian m

PARAMETER SUMMARY

imagename Name of the input (CASA, FITS, MIRIAD) image

box Rectangular region to select in direction plane. See "help par.box"

for details. Default is to use the entire direction plane.

Region selection. See "help par.region" for details. Default is to use the region

full image.

chans Channels to use. See "help par.chans" for details. Default is to use

all channels.

Stokes planes to use. See "help par.stokes" for details. Default is stokes

to use all Stokes planes.

axis Axis along which to do the fit(s). <0 means use the spectral axis or the

zeroth axis if a spectral axis is not present.

Mask to use. See help par.mask. Default is none. mask

Stretch the input mask if necessary and possible? Only used if a mask is spe stretch

See help par.stretch.

Maximum number of gaussians to fit. ngauss

poly Order of polynomial to fit. <0 means do not fit a polynomial.

Name of file containing initial gaussian estimates. estimates minpts Minimum number of points necessary to attempt a fit.

Fit models at each pixel in region (true) or average profiles and fit a sing multifit

model Name of model image to write. residual Name of residual image to write.

Name of amplitude solution image. Default: do not write the image ("") amp

Name of amplitude solution error image. Default: do not write the image ("" amperr

Name of center solution image. Default: do not write the image ("") center

Name of center solution error image. Default: do not write the image ("") centererr

Name of fwhm solution image. Default: do not write the image ("") fwhm

Name of fwhm solution error image. Default: do not write the image ("") fwhmerr

integral Name of integral solution image. Default: do not write the image ("") integralerr Name of integral solution error image. Default: do not write the image ("")

If true, return a record summarizing the fit results, if false, return false Stretch the mask if necessary and possible? See help par.stretch stretch

logresults Output results to logger?

wantreturn

Initial estimate of PCF profile (gaussian or lorentzian) amplitudes. pampest

pcenterest Initial estimate PCF profile centers, in pixels.

pfwhmest Initial estimate PCF profile FWHMs, in pixels.

pfix PCF profile parameters to fix during fit.

prix For profile parameters to fix during fit.

pfunc PCF singlet functions to fit. "gaussian" or "lorentzian" (minimal match supp

gmncomps Number of components in each Gaussian multiplet to fit.

gmampcon The amplitude ratio constraints for non-reference components to reference components to refer

Initial estimate of individual gaussian FWHMss in gaussian multiplets, in p

gmfix Parameters of individual gaussians in gaussian multiplets to fix during fit

logfile File in which to log results. Default is not to write a logfile.

append Append results to logfile? Logfile must be specified. Default is to append.

goodcenterrange Acceptable amplitude solution range. 0 => all amplitude solutions are accept goodcenterrange Acceptable center solution range in pixels relative to region start. [0.0] = goodfwhmrange Acceptable FWHM solution range in pixels. [0.0] => all FWHM solutions are acceptable amplitude solutions are acceptable for a solution f

sigma Standard deviation array or image name.

outsigma Name of output image used for standard deviation. Ignored if sigma is empty

This task simultaneously performs a non-linear, least squares fit using the Levenberg-Marque one or more lorentzian singlets, one or more gaussian multiplets, and/or a polynomial to one fitting algorithm may be found in AIPS++ Note 224 (http://www.astron.nl/casacore/trunk/casac by W.H. Press et al., Cambridge University Press. A gaussian/lorentzian singlet is a gaussia center position, and width) are all independent from any other feature that may be simultane more gaussian lines in which at least one (and possibly two or three) parameter of each line single (reference) profile in the multiplet. For example, one can specify a doublet in which amplitude of the zeroth line and/or the center of the first line is 20 pixels from the center line is identical (in pixels) to that of the zeroth line. There is no limit to the number of (except of course that the number of parameters to be fit should be significantly less than a single reference profile in a multiplet to which to tie constraints of parameters of the

AXIS

gmfwhmest

The axis parameter indicates on which axis profiles should be fit; a value <0 indicates the that the zeroth axis should be used.

MINIMUM NUMBER OF PIXELS

The minpts parameter indicates the minimum number of unmasked pixels that must be present in to be attempted. When multifit=T, positions with too few good points will be masked in any of

ONE FIT OF REGION AVERAGE OR PIXEL BY PIXEL FIT

The multifit parameter indicates if profiles should be fit at each pixel in the selected required and the fit done to that average profile (false).

POLYNOMIAL FITTING

The order of the polynomial to fit is specified only via the poly parameter. If poly<0, no

coefficients can be specified; these are determined automatically.

GAUSSIAN SINGLET FITTING

In the absence of an estimates file and no estimates being specified by the p*est parameters indicates the maximum number of gaussian singlets that should be fit. The initial estimates automatically in this case. If it deems appropriate, the fitter will fit fewer than this num ngauss is ignored (see below). ngauss is also ignored if the p*est parameters are specified is greater than zero. If estimates is not specified or the p*est parameters are not specified an error will occur as this indicates there is nothing to fit.

One can specify initial estimates of gaussian singlet parameters via an estimates file or the pfix parameters. The latter is the recommended way to specify these estimates as support for which option is used, an amplitude initial estimate must always be nonzero. A negative five

SPECIFYING INITIAL ESTIMATES FOR GAUSSIAN AND LORENTZIAN SINGLETS (RECOMMENDED METHOD) One may specify initial estimates via the pampest, pcenterest, and pfwhmest parameters. In these parameters can be numbers, pampest must be specified in image brightness units, pcentered pixel, and pfwhmest must be given in pixels. Optionally pfix can be specified and in can be a string. In it is coded which parameters should be held constant during the fix. Any (fwhm) is allowed; eg pfix="pc" means fix both the amplitude and center during the fit. In the singlets, these parameters must be specified as arrays of numbers. The length of the arrays the same for all the p*est parameters.

If no parameters are to be fixed for any of the singlets, pfix can be set to the empty string is to be fixed, pfix must be an array of strings and have a length equal to the p*est arrays should be represented as an empty string in the pfix array. So, for example, if one desires one, one must specify pfix=["", "f", ""], the empty strings indicating no parameters of the

In the case of multifit=True, the initial estimates, whether from the p*est parameters or for the first fit. This is normally the bottom left corner of the region selected. If masked attempted fit fails, the fitting proceeds to the next pixel with the pixel value of the lower successful fit has been performed, subsequent fits will use the results of a fit for a near initial estimate for the parameters at the current location. The fixed parameter string will

One specifies what type of PCF profile to fit via the pfunc parameter. A PCF function is one as both gaussian and lorentzian singlets can. If all singlets to be fit are gaussians, one of will be assumed to be gaussians. If at least one lorentzian is to be fit, pfunc must be specian array of strings (in the case of multiple singlets). The position of each string correspondent and pfix arrays. Minimal match ("g", "G", "l", or "L") is supported. So, if one wanted singlets, the zeroth and last of which were lorentzians, one would specify pfunc=["L", "G",

ESTIMATES FILE FOR GAUSSIAN SINGLETS (NONRECOMMENDED METHOD)

Initial estimates for gaussian singlets can be specified in an estimates file. Estimates file p*est parameters, so it is recommended users use those parameters instead. If an estimates must be 0 or empty and mgncomps must be 0 or empty. Only gaussian singlets can be specified more gaussian multiplets and/or one or more lorentzian singlets simultaneously, the p*est parameters in the stimates of the specified more gaussian multiplets and/or one or more lorentzian singlets simultaneously, the p*est parameters in the stimates file p*est parameters file p*est p*est

of all gaussian singlets to fit; one cannot use an estimates file in this case. If an estimate can be fit simultaneously by specifying the poly parameter. The estimates file must contain for all gaussian singlets to be fit. The number of gaussian singlets to fit is gotten from a comments which are indicated by a "#" at the beginning of a line. All non-comment lines will format of such a line is

[peak intensity], [center], [fwhm], [optional fixed parameter string]

The first three values are required and must be numerical values. The peak intensity must be center must be specified in pixels offset from the zeroth pixel, and fwhm must be specified represents the parameter(s) that should be held constant during the fit. Any combination of permitted, eg "fc" means hold the fwhm and the center constant during the fit. Fixed parametexample file:

```
# estimates file indicating that two gaussians should be fit
# first guassian estimate, peak=40, center at pixel number 10.5, fwhm = 5.8 pixels, all para
# fit
40, 10.5, 5.8
# second gaussian, peak = 4, center at pixel number 90.2, fwhm = 7.2 pixels, hold fwhm const
4, 90.2, 7.2, f
# end file
```

GAUSSIAN MULTIPLET FITTING

Any number of gaussian multiplets, each containing any number of two or more components, can polynomial and/or any number of gaussian and/or lorentzian singlets, the only caveat being significantly less than the number of data points. The gmncomps parameter indicates the number components in each multiplet. In the case of a single multiplet, an integer (>1) can be speciatingle quadruplet of gaussians. In the case of 2 or more multiplets, and array of integers gmncomps=[2, 4, 3] means 3 seperate multiples are to be fit, the zeroth being a doublet, the being a triplet.

Initial estimates of all gaussians in all multiplets are specified via the gm*est parameters starts with the zeroth component of the zeroth multiplet to the last component of the zeroth the first multiplet to the last component of the first multiplet, etc to the zeroth component of the last multiplet. The zeroth element of a multiplet is defined as the reference significance that it is the profile to which all constraints of all other profiles in that in our example of gmncomps=[2, 4, 3], gmampest, gmcenterest, and gmfwhmest must each be nine profiles summed over all multiplets) element arrays. The zeroth, second, and sixth elements in the zeroth, first, and second multiplet, respectively.

The fixed relationships between the non-reference profile(s) and the reference profile of a gmcentercon, and gmfwhmcon parameters. At least one, and any combination, of constraints can component of a multiplet. The amplitude ratio of a non-reference line to that of the reference the fwhm of a non-reference line to that of the reference line is set in gmfwhmcon. The office a non-reference line to that of the reference line is set in gmcentercon. In the case where non-reference line of any multiplet, the value of the associated parameter must be 0. In the

a single doublet, a constraint may be specified as a number or an array of a single number. and gmcentercon=[32.4] means there is a single doublet to fit where the amplitude ratio of to be 0.65 and the center of the first line is constrained to be offset by 32.4 pixels from of a total of three or more gaussians, the constraints parameters must be specified as array of gaussians summed over all multiplets minus the number of reference lines (one per multiple reference lines cannot be constrained by themselves). In the cases where an array must be specified not have that constraint, 0 should be specified. Here's an example

```
gmncomps=[2, 4, 3]

gmampcon= [0, 0.2, 0, 0.1, 4.5, 0]

gcentercon=[24.2, 45.6, 92.7, 0, -22.8, -33.5]

gfwhmcon=""
```

In this case we have our previous example of one doublet, one quadruplet, and one triplet. It that its center is offset by 24.2 pixels from the zeroth (reference) component. The first component and amplitude of 0.2 times that of the quadruplet's zeroth component and its center is constructed component. The second component of the quadruplet is constrained to have its center reference component and the third component is constrained to have an amplitude of 0.1 times. The first component of the triplet is constrained to have an amplitude of 4.5 times that of is constrained to be offset by -22.8 pixels from the reference component's center. The second its center offset by -33.5 pixels from the center of the reference component. No lines have for that parameter. Note that using 0 to indicate no constraint for line center means that of position as the reference component but having a different FWHM from the reference component try using a very small positive (or even negative) value for the center constraint.

Note that when a parameter for a line is constrained, the corresponding value for that composing and the value of the constrained parameter is automatically used instead. So let's a the following estimates:

```
gmampest = [1, .2, 2, .1, .1, .5, 3, 2, 5]
gmcenterest = [20, 10, 30, 45.2, 609, -233, 30, -859, 1]
```

Before any fitting is done, the constraints would be taken into account and these arrays won

```
gmampest = [1, .2, 2, .4, .1, .2, 3, 13.5, 5]
gmcenterest = [20, 44.2, 30, 75.6, 127.7, -233, 30, 7.2, -3.5]
```

The value of gmfwhmest would be unchanged since there are no FWHM constraints in this examp.

In addition to be constrained by values of the reference component, parameters of individual are specified via the gmfix parameter. If no parameters are to be fixed, gmfix can be specified array. In the case where any parameter is to be fixed, gmfix must be specified as an array components summed over all multiplets. These strings encode which parameters to be fixed for a component is to have no parameters fixed, an empty string is used. In other cases one or not be fixed using "p", "c", and/or "f" described above for fixing singlet parameters. There are to be aware of. In the case where a non-reference component parameter is constrained and the

set as fixed, that parameter in the non-reference parameter will automatically be fixed even the gmfix array. This is the only way the constraint can be honored afterall. In the convers non-reference component is specified as fixed, but the corresponding parameter in the reference an error will occur. Fixing an unconstrained parameter in a non-reference component is always parameters in a reference component (with the above caveat that corresponding constrained parameters) be silently held fixed as well).

The same rules that apply to singlets when multifit=True apply to multiplets.

LIMITING RANGES FOR SOLUTION PARAMETERS

In cases of low (or no) signal to noise spectra, it is still possible for the fit to converge nonsensical solution. The astronomer can use her knowledge of the source to filter out obvious Any solution which contains a NaN value as a value or error in any one of its parameters is invalid.

One can also limit the ranges of solution parameters to known "good" values via the goodamper parameters. Any combination can be specified and the limit constraints will be ANDed together that might be fit; choosing ranges on a component by component basis is not supported. If span array of exactly two numerical values must be given to indicate the range of acceptable at that parameter. goodamprange is expressed in terms of image brightness units. goodcenterrate from the zeroth pixel in the specified region. goodfwhmrange is expressed in terms of pixels given for FWHM range endpoints). In the case of a multiple-PCF fit, if any of the correspondence, the entire solution is considered to be invalid.

In addition, solutions for which the absolute value of the ratio of the amplitude error to tratio of the FWHM error to the FWHM exceeds 100 are automatically marked as invalid.

INCLUDING STANDARD DEVIATIONS OF PIXEL VALUES

If the standard deviations of the pixel values in the input image are known and they vary in near the edge of the band), they can be included in the sigma parameter. This parameter take array or image must have one of three shapes: 1. the shape of the input image, 2. the same of all axes being one except for the fit axis which must have length corresponding to its ledimensional with length equal the the length of the fit axis in the input image. In cases 2 be replicated such that the image that is ultimately used is the same shape as the input image. It is only the relative values that are important. A value of 0 means that pixel should not A has a higher standard deviation than pixel B, then pixel A is noisier than pixel B and will the weight of a pixel is the usual

weight = 1/(sigma*sigma)

In the case of multifit=F, the sigma values at each pixel along the fit axis in the hyperplathat pixel are averaged and the resultant averaged standard deviation spectrum is the one us such that the maximum value is 1. This mitigates a known overflow issue.

One can write the normalized standard deviation image used in the fit but specifying its narused as sigma for subsequent runs.

RETURNED DICTIONARY STRUCTURE

The dictionary returned (if wantreturn=True) has a (necessarily) complex structure. First, the abscissa unit and the ordinate unit described by simple strings. Next there are arrays afti quality. These arrays have the shape of the specified region collapsed along the fit axis axis having length of 1:

attempted: a boolean array indicating which fits were attempted (eg if too few unmasked point converged: a boolean array indicating which fits converged. False if the fit was not attempted valid:

a boolean array indicating which solutions fall within the specified valid ranges

section LIMITING RANGES FOR SOLUTION PARAMETERS for details).

niter: an int array indicating the number of iterations for each profile, <0 if the fit

ncomps: the number of components (gaussian singlets + lorentzian singlets + gaussian mult

<O if the fit did not converge

direction: a string array containing the world direction coordinate for each profile

There is a "type" array having number of dimensions equal to the number of dimensions in the the first n-1 dimensions is the same as the shape of the above arrays. The length of the last components fit. The values of this array are strings describing the components that were fit "GAUSSIAN" in the case of gaussian singlets, "LORENTZIAN" in the case of lorentzian singlets

If any gaussian singlets were fit, there will be a subdictionary accessible via the "gs" key "centerErr", "fwhm", "fwhmErr, "integral", and "integralErr". Each of these arrays will have above. The shape of the first n-1 dimensions will be the same as the shape of the arrays dechave length equal to the maximum number of gaussian singlets that were fit. Along this axis corresponding fit result or associated error (depending on the array's associated key) of the fit did not converge, or that particular component was excluded from the fit, a value of

If any lorentzian singlets were fit, their solutions will be accessible via the "ls" key. The as the "gs" arrays described above.

If any gaussian multiplets were fit, there will be subdictionaries accessible by keys "gm0" muliplets that were fit. Each of these dictionaries will have the same arrays described above will have length equal to the number of components in that particular multiplet. Each pixel value or error for that component number in the multiplet, eg the zeroth pixel along that at the parameter solution or error for the reference component of the multiplet.

The polynomial coefficient solutions and errors are not returned, although they are logged.

OUTPUT IMAGES

In addition to the returned dictionary, optionally one or more of any combination of output The model and residual parameters indicate the names of the model and residual images to be should not be written.

One can also write none, any or all of the solution and error images for Gaussian singlet, I via the parameters amp, amperr, center, centererr, fwhm, fwhmerr, integral, and integralerr

contain the arrays described for the associated parameter solutions or errors described in parameter, "_ls" is appended to the image names, in the case of Gaussian multiplets, "_gm" is a linear axis and repesents component number (and is named accordingly). In the case when Lorentzians are fitted, the image names are further appended with an underscore and the relevant the case of Gaussian multiplets, the image names are appended with an underscore, followed multiplet group, followed by an underscore, followed by the number of the component in that component number 4 of multiplet group number 3). Pixels for which fits were not attempted, the values of NaN (not a number) or INF (infinity) will be masked as bad.

Writing analogous images for polynomial coefficients is not supported.

EXAMPLE

res = specif(imagename="myspectrum.im", ngauss=2, box="3,3,4,5", poly=2, multifit=true, want

specsmooth-task.html

0.1.116specsmooth

Requires:

 ${\bf Synopsis} \\ {\bf Smooth \ an \ image \ region \ in \ one \ dimension}$

Description

Arguments

Inputs

imagename Name of the input image

allowed: string

Default:

outfile Output image name.

allowed: string

Default:

box Rectangular region to select in direction plane. See "help

par.box" for details. Default is to use the entire direction

plane.

allowed: string

Default:

chans Channels to use. See "help par.chans" for details. Chan-

nels must be contiguous. Default is to use all channels.

allowed: string

Default:

stokes Stokes planes to use. See "help par.stokes" for details.

Planes specified must be contiguous. Default is to use

all Stokes planes. allowed: string

Default:

region Region selection. See "help par.region" for details. De-

fault is to use the full image.

allowed: any Default: variant

mask Mask to use. See help par.mask. Default is none..

allowed: string

Default:

overwrite Overwrite the output if it exists?

allowed: bool Default: False

stretch Stretch the mask if necessary and possible? See help

par.stretch. Default False

allowed: bool
Default: False

axis The profile axis. Default: use the spectral axis if one

exists, axis 0 otherwise (<0).

allowed: int Default: -1

function Convolution function. hanning and boxcar are sup-

ported functions. Minimum match is supported.

allowed: string
Default: boxcar

width Width of boxcar, in pixels.

allowed: int Default: 2

dmethod Decimation method. "" means no decimation, "copy"

and "mean" are also supported (minimum match).

allowed: string
Default: copy

Returns

record

Example

axis

Smooth an image region in one dimension.

ARAMETER SUMMARY

imagename Name of the input (CASA, FITS, MIRIAD) image

box Rectangular region to select in direction plane. See "help par.box" for deta

Default is to use the entire direction plane. Only a single box may be spec-

chans Channels to use. See "help par.chans" for details. Channels must be contigue

Default is to use all channels.

stokes Stokes planes to use. See "help par.stokes" for details. Planes specified m

contiguous. Default is to use all Stokes planes.

region Region selection. See "help par.region" for details. Default is to use the

mask Mask to use. See help par.mask. Default is none.

overwrite If the specified outfile already exists, overwrite it if True.

stretch Stretch the input mask if necessary and possible? Only used if a mask is spe

See help par.stretch.

function Convolution function to use. Supported values are "boxcar" and "hanning". M.

match is supported.

width Width of boxcar in pixels. Used only if function parameter minimally matches

dmethod Plane decimation method. "" means no decimation should be performed. Other a

values are "copy" and "mean". Minimal match is supported. See below for deta

Pixel axis along which to do the convolution <0 means use the spectral axis

This application performs one dimensional convolution along a specified axis of an image or selected region of an image. Hanning smoothing and boxcar smoothing are supported. Both float valued and complex valued images are supported. Masked pixel values are set to zero prior to convolution. All nondefault pixel masks are ignored during the calculation. The convolution is done in the image domain (i.e., not with an FFT).

BOXCAR SMOOTHING

One dimensional boxcar convolution is defined by

$$z[i] = (y[i] + y[i+i] + ... + y[i+w])/w$$

where z[i] is the value at pixel i in the box car smoothed image, y[k]

is the pixel value of the input image at pixel k, and w is a postivie integer representing the width of the boxcar in pixels. The length of the axis along which the convolution is to occur must be at least w pixels in the selected region, unless decimation using the mean function is chosen in which case the axis length must be at least 2*w (see below).

If dmethod="" (no decimation), the length of the output axis will be equal to the length of the input axis - w + 1. The pixel mask, ORed with the OTF mask if specified, is copied from the selected region of the input image to the output image. Thus for example, if the selected region in the input image has six planes along the convolution axis, if the specified boxcar width is 2, and if the pixel values, which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26], then the corresponding output slice will be of length five pixels and the output pixel values will be [1.5, 3.5, 7.5, 13.5, 21.5].

If dmethod="copy", the output image is the image calculated if dmethod="", except that only every wth plane is kept. Both the pixel and mask values of these planes are copied directly to the output image, without further processing. Thus for example, if the selected region in the input image has six planes along the convolution axis, the boxcar width is chosen to be 2, and if the pixel values, which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26], the corresponding output pixel values will be [1.5, 7.5, 21.5].

If dmethod="mean", first the image described in the dmethod=""
case is calculated. Then, the ith plane of the output image is calculated by
averaging the i*w to the (i+1)*w-1 planes of this intermediate image. Thus, for
example, if the selected region in the input image has six planes along the
convolution axis, the boxcar width is chosen to be 2, and if the pixel values,
which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26],
then the corresponding output pixel values will be [2.5, 10.5]. Any pixels at the
end of the convolution axis of the intermediate image that do not fall into a complete bin of
width w are ignored. Masked values are taken into consideration when forming this
average, so if one of the values is masked, it is not used in the average. If at
least one of the values in the intermediate image bin is not masked, the
corresponding output pixel will not be masked.

HANNING SMOOTHING

Hanning convolution of one axis of an image is defined by

$$z[i] = 0.25*y[i-1] + 0.5*y[i] + 0.25*y[i+1]$$
 (equation 1)

where z[i] is the value at pixel i in the hanning smoothed image, and y[i-1], y[i], and y[i+1] are the values of the input image at pixels i-1, i, and i+1 respectively. The length of the axis along which the convolution is to occur must be at least three pixels in the selected region.

If dmethod="" (no decimation of image planes), the length of the output axis will be the same as that of the input axis. The output pixel values along the convolution axis will be related to those of the input values according to equation 1, except the first and last pixels. In that case,

$$z[0] = 0.5*(y[0] + y[1])$$

and,

$$z[N-1] = 0.5*(y[N-2] + y[N-1])$$

where N is the number of pixels along the convolution aixs. The pixel mask, ORed with the OTF mask if specified, is copied from the selected region of the input image to the output image. Thus for example, if the selected region in the input image has six planes along the convolution axis, and if the pixel values, which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26], the corresponding output pixel values will be [1.5, 2.5, 5.5, 10.5, 17.5, 21.5].

If dmethod="copy", the output image is the image calculated if dmethod="", except that only the odd-numbered planes are kept. Furthermore, if the number of planes along the convolution axis in the selected region of the input image is even, the last odd number plane is also discarded. Thus, if the selected region has N pixels along the convolution axis in the input image, along the convolution axis the output image will have (N-1)/2 planes if N is odd, or (N-2)/2 planes if N is even. The pixel and mask values are copied directly, without further processing. Thus for example, if the selected region in the input image has six planes along the convolution axis, and if the pixel values, which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26], the corresponding output pixel values will be [2.5, 10.5].

If dmethod="mean", first the image described in the dmethod="" case is calculated. The first plane and last plane(s) of that image are then discarded as described in the dmethod="copy" case. Then, the ith plane of the output image is calculated by averaging the (2*i)th and (2*i + 1)th planes of the intermediate image. Thus for example, if the selected region in the input image has six planes along the convolution axis, and if the pixel values, which are all unmasked, on a slice along this axis are [1, 2, 5, 10, 17, 26], the corresponding output pixel values will be [4.0, 14.0]. Masked values are taken into consideration when forming this average, so if one of the values is masked, it is not used in the average. If at least one of the values in the input pair is not masked, the corresponding output pixel will not be masked.

EXAMPLES

boxcar smooth the spectral axis by 3 pixels, say it's axis 2 and only

```
# write every other pixel
specsmooth(imagename="mynonsmoothed.im", outfile="myboxcarsmoothed.im",
axis=2, function="boxcar", dmethod="copy", width=3, overwrite=True)

# hanning smooth the spectral axis, say it's axis 2 and do not perform decimation
# of image planes
specsmooth(imagename="mynonsmoothed.im", outfile="myhanningsmoothed.im",
axis=2, dmethod=""," overwrite=True)
```

splattotable-task.html

0.1.117 splattotable

Requires:

Synopsis

Convert a downloaded Splatalogue spectral line list to a casa table.

Arguments

Inputs filenames Files containing Splatalogue lists.

allowed: stringArray

Default:

table Output table name. Must be specified.

allowed: string

Default:

Returns

bool

Example

PARAMETER SUMMARY

filenames Files containing Splatalogue lists. table Output table name. Must be specfied

This task reads a spectral line list(s) downloaded from Splatalogue (www.splatalogue.net) as can be queried via eg the slsearch task.

REQUIRMENTS OF THE DOWNLOADED FILES

The downloaded files must be in a specific format for this task to succeed. The columns are important things; one can filter the results as one desires using Splatalogue, but the particle. The columns which must be present in the downloaded file in this exact order are: "Splatalogue, But the particle." The columns which must be present in the downloaded file in this exact order are: "Splatalogue, "Resolved QNs", "CDMS/JPL Intensity", "Sijmu2 (D2)", "The columns in this exact order are: "Splatalogue, but the particle of the columns are in this exact order are: "Splatalogue, but the particle of the columns are intensity." The columns are intensity. "Sijmu2 (D2)", "The columns are intensity." The columns are intensity. The columns are intensity. The columns are intensity. The columns are intensity. The columns are intensity." The columns are intensity. The columns are intensi

"Log10 (Aij)", "EL (K)", "EU (K)", "Linelist". In order to get these columns in this order,

select exactly the following items on the Splatalogue search interface. Under "Specify Range Under "Line Strength Display" select exactly "CDMS/JPL Intensity",

"Sij mu2", and "Aij". Under "Energy Levels", one should select exactly "Elower (K)" and "Eugselect exactly "Display Ordered Frequency ONLY" and "Display NRAO Recommended Frequencies". the resulting page, one should select the Tab Field Separator and then export the list. The format for importing into CASA.

splattotable("mysplatlist.txt", "mynewsl.tbl", true)

split-task.html

0.1.118 split

Requires:

Synopsis

Create a visibility subset from an existing visibility set

Description

This is the new

implementation of split.

* The old implementation is available for a short time as oldsplit. * Task split2 has been renamed to split. The split2 alias will be removed soon. * Please, update your scripts to call split instead.

This new split task uses the MSTransform framework underneath. Split is the general purpose program to make a new data set that is a subset or averaged form of an existing data set. General selection parameters are included, and one or all of the various data columns (DATA, LAG_DATA and/or FLOAT_DATA, MODEL_DATA and/or CORRECTED_DATA) can be selected.

Split is often used after the initial calibration of the data to make a smaller Measurement Set with only the data that will be used in further flagging, imaging and/or self-calibration. Split can average over frequency (channels) and time (integrations).

Split also supports the Multi-MS (MMS) format as input. For more information about MMS, see the help of partition and mstransform.

Arguments

Inputs

vis Name of input Measurement set or Multi-MS

allowed: string

Default:

outputvis Name of output Measurement set or Multi-MS

allowed: string

Default:

Multi-MS.

allowed: bool Default: True

field Select field using ID(s) or name(s).

allowed: any Default: variant

spw Select spectral window/channels.

allowed: any Default: variant

scan Select data by scan numbers.

allowed: any Default: variant

antenna Select data based on antenna/baseline.

allowed: any Default: variant

correlation Correlation: " ==> all, correlation='XX,YY'.

allowed: any
Default: variant

timerange Select data by time range.

allowed: any Default: variant

intent Select data by scan intent.

allowed: any Default: variant

array Select (sub)array(s) by array ID number.

allowed: any Default: variant

uvrange Select data by baseline length.

allowed: any Default: variant

observation Select by observation ID(s).

allowed: any Default: variant

feed Multi-feed numbers: Not yet implemented.

allowed: any Default: variant

datacolumn Which data column(s) to process.

Example

```
Detailed Keyword arguments:
  vis -- Name of input Measurement set or Multi-MS.
      default: none;
      example: vis='ngc5921.ms'
  outputvis -- Name of output Measurement set or Multi-MS (MMS).
      default: none;
      example: outputvis='ngc5921_src.ms'
      IMPORTANT: if a .flagversions file with the name of the output MS exist, this task w
                 exit with an error. The user needs to rename or remove the existing flag
                 or choose a different output name for the MS.
  keepmms -- Create a Multi-MS as the output if the input is a Multi-MS.
      default: True
      By default it will create a Multi-MS when the input is a Multi-MS.
      The output Multi-MS will have the same partition axis of the input MMS.
      See 'help partition' for more information on the MMS format.
     NOTE: It is not possible to do time average with combine='scan'
            if the input MMS was partitioned with separationaxis='scan'
            or 'auto'. In this case, the task will abort with an error.
  --- Data Selection ---
 field -- Select field using field id(s) or field name(s).
           [run listobs to obtain the list iof d's or names]
      default: ''=all fields If field string is a non-negative
         integer, it is assumed to be a field index
         otherwise, it is assumed to be a field name
         field='0~2'; field ids 0,1,2
         field='0,4,5~7'; field ids 0,4,5,6,7
         field='3C286,3C295'; fields named 3C286 and 3C295
         field = '3,4C*'; field id 3, all names starting with 4C
  spw -- Select spectral window/channels
     default: ''=all spectral windows and channels
```

```
spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw = '*:3~64' channels 3 through 64 for all sp id's
               spw = ':3^64' will NOT work.
           NOTE: mstransform does not support multiple channel ranges per
                 spectral window (';').
scan -- Scan number range
    default: '' = all
antenna -- Select data based on antenna/baseline
    default: '' (all)
        Non-negative integers are assumed to be antenna indices, and
        anything else is taken as an antenna name.
    examples:
        antenna='5&6': baseline between antenna index 5 and index 6.
        antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
        antenna='5\&6:7\&8': baselines 5-6 and 7-8
        antenna='5': all baselines with antenna 5
        antenna='5,6,10': all baselines including antennas 5, 6, or 10
        antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                               10. (cross-correlations only. Use &&
                               to include autocorrelations, and &&&
                               to get only autocorrelations.)
        antenna='!ea03,ea12,ea17': all baselines except those that
                                   include EVLA antennas ea03, ea12, or
                                   ea17.
correlation -- Correlation types or expression.
    default: '' (all correlations)
    example: correlation='XX,YY'
timerange -- Select data based on time range:
    default: '' (all); examples,
      timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date, timerange defaults to the
      first day in the dataset
      timerange='09:14:0~09:54:0' picks 40 min on first day
      timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
       on next day
       timerange='09:44:00' data within one integration of time
```

```
timerange='>10:24:00' data after this time
array -- (Sub)array number range
    default: '' = all
uvrange -- Select data within uvrange (default units meters)
    default: ''=all; example:
        uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
        uvrange='>4klambda';uvranges greater than 4 kilo-lambda
        uvrange='0~1000km'; uvrange in kilometers
observation -- Select by observation ID(s)
    default: '' = all
feed -- Selection based on the feed - NOT IMPLEMENTED YET
    default: '' = all
datacolumn -- Which data column to use for processing (case-insensitive).
    default: 'corrected'; example: datacolumn='data'
    options: 'data', 'model', 'corrected', 'all', 'float_data', 'lag_data',
             'float_data,data', 'lag_data,data'.
        NOTE: 'all' = whichever of the above that are present. If the requested
                      column does not exist, the task will exit with an error.
keepflags -- Keep completely flagged rows in the output or drop them. This has no
             effect on partially flagged rows. All of the channels and correlations
             of a row must be flagged for it to be droppable, and a row must be
             well defined to be keepable.
        IMPORTANT: Regardless of this parameter, flagged data is never included in
                   channel averaging. On the other hand, partially flagged rows will
                   always be included in time averaging. The average value of the
                   flagged data for averages containing ONLY flagged data in the relevan
```

default: True (keep completely flagged rows in the output)

output channel will be written to the output with the corresponding flag set to True, while only unflagged data is used on averages where

there is some unflagged data with the flag set to False.

--- Channel averaging parameter ---

width -- Number of input channels to average to create an output channel. If a list is given, each bin will apply to one spw in

the selection.

default: 1 => no channel averaging.

options: (int) or [int]

example: chambin=[2,3] => average 2 channels of 1st selected spectral window and 3 in the second one.

--- Time averaging parameters ---

timebin -- Bin width for time averaging. When timebin is greater than Os,
the task will average data in time. Flagged data will be included
in the average calculation, unless the parameter keepflags is set to False.
In this case only partially flagged rows will be used in the average.
default: 'Os'

combine -- Let the timebin span across scan, state or both.

State is equivalent to sub-scans. One scan may have several state ids. For ALMA MSs, the sub-scans are limited to about 30s duration each. In these cases, the task will automatically add state to the combine parameter. To see the number of states in an MS, use the msmd tool. See help msmd.

NOTE: It is not possible to do time average with combine='scan' if the input MMS was partitioned with separationaxis='scan' or 'auto'. In this case, the task will abort with an error.

default: '' (separate time bins by both of the above)
options: 'scan', 'state', 'state,scan'

examples:

combine = 'scan'; can be useful when the scan number goes up with each integration as in many WSRT MSs.

combine = ['scan', 'state']: disregard scan and state
 numbers when time averaging.

combine = 'state,scan'; same as above.

spxfit-task.html

0.1.119 \mathbf{spxfit}

Requires:

 $\begin{tabular}{ll} \bf Synopsis \\ Fit a 1-dimensional \ model(s) \ to \ an \ image(s) \ or \ region \ for \ determination \ of \end{tabular}$ spectral index.

Description

Arguments

Inputs imagename Name of the input image(s) allowed: any Default: variant box Rectangular region to select in direction plane. See "help par.box" for details. Default is to use the entire direction plane. allowed: string Default: Region selection. See "help par.region" for details. Deregion fault is to use the full image. allowed: string Default: chans Channels to use. See "help par.chans" for details. Default is to use all channels. allowed: string Default: stokes Stokes planes to use. See "help par.stokes" for details. Default is to use all Stokes planes. allowed: string Default: axis The profile axis. Default: use the spectral axis if one exists, axis 0 otherwise (<0). allowed: int Default: -1 Mask to use. See help par.mask. Default is none. mask allowed: string Default: minpts Minimum number of unmasked points necessary to attempt fit. allowed: int Default: 1 multifit If true, fit a profile along the desired axis at each pixel in the specified region. If false, average the non-fit axis pixels and do a single fit to that average profile. Default False. allowed: bool Default: False Type of function to fit. "plp" = power logarithmic polyspxtype nomial, "ltp" = logarithmic transformed polynomial. allowed: string Default: plp REQUIRED. Initial estimates as array of numerical valspxest ues for the spectral index function coefficients. eg [1.5, -0.8] if fitting a plp function thought to be close to 1.5*(x/div)**(-0.8) or [0.4055, -0.8] if fitting an lpt function thought to be close to $\ln(1.5)$ - $0.8*\ln(x/\text{div})$.

div Divisor (numerical value or quantity) to use in the logarithmic terms of the plp or ltp function. 0 means cal-

doubleArray

cients during the fit. True means hold fixed.

boolArray

Fix the corresponding spectral index function coeffi-

allowed:

Default:

allowed:

Default:

spxfix

Returns

record

Example

This task fits a power logarithmic polynomial or a logarithmic tranformed polynomial to one

PARAMETER SUMMARY

imagename	Name of the input image(s). More than one image name can be given as an
	array, in which case the images are concatenated along the specified axis
	and the resultant image is what is used by the fitter. In this case,
	all images must have the same dimensions along all axes other than the fit a
box	Rectangular region to select in direction plane. See "help par.box" for deta
	Default is to use the entire direction plane.
region	Region selection. See "help par.region" for details. Default is to use the i
chans	Channels to use. See "help par.chans" for details. Default is to use all cha
stokes	Stokes planes to use. See "help par.stokes" for details. Default is to use a
axis	Axis along which to do the fit(s). <0 means use the spectral axis or the
	zeroth axis if a spectral axis is not present.
mask	Mask to use. See help par.mask. Default is none.
stretch	Stretch the input mask if necessary and possible? Only used if a mask is spe
	See help par.stretch.

minpts Minimum number of points necessary to attempt a fit.

multifit Fit models at each pixel in region (true) or average profiles and fit a sing spxtype Type of function to fit. "plp" => power logarithmic polynomial, "ltp" => log

transformed polynomial.

spxest REQUIRED. Initial estimates as array of numerical values for the spectral in function coefficients. eg [1.5, -0.8] if fitting a plp function thought to 1.5*(x/div)**(-0.8), or [0.4055, -0.8] if fitting an lpt function thought to

ln(1.5) - 0.8*ln(x/div).

spxfix Fix the corresponding spx function coefficients during the fit. True=>hold : div Divisor (numerical value or quantity) to use in the logarithmic terms of the

function. $0 \Rightarrow$ calculate a useful value on the fly.

spxsol Name of the function coeffecients solution image to write.

spxerr Name of the function coeffecients error image to write.

model Name of model image to write. residual Name of residual image to write.

wantreturn If true, return a record summarizing the fit results, if false, return false

stretch Stretch the mask if necessary and possible? See help par.stretch

logresults Output results to logger?

logfile File in which to log results. Default is not to write a logfile.

append Append results to logfile? Logfile must be specified. Default is to append. sigma Standard deviation numerical array, image name (string), or string array of

concatenated to create the sigma image that is used by the fitter.

outsigma Name of output image used for standard deviation. Ignored if sigma is empty

This application performs a non-linear, least squares fits using the Levenberg-Marquardt alglogarithmic transformed polynomial to pixel values along a specified axis of an image or image in AIPS++ Note 224 (http://www.astron.nl/casacore/trunk/casacore/doc/notes/224.html) and in University Press. These functions are most often used for fitting the spectral index and hig polynomial (plp) has the form

```
y = c0*(x/div)**(c1 + c2*ln(x/div) + c3*ln(x/div)**2 + ... + cn*ln(x/div)**(n - 1))
```

and a logarithmic transformed polynomial (ltp) is simply the result of this equation after

```
ln(y) = c0 + c1*ln(x/div) + c2*ln(x/div)**2 + ... + cn*ln(x/div)**n
```

Because the logarithm of the ordinate values must be taken before fitting a logarithmic translall non-positive pixel values are effectively masked for the purposes of fitting.

The coefficients of the two forms are equal to each other except that c0 in the second equal ln(c0) of the first. In the case of fitting a spectral index, which is traditionally represent equal to c1.

In both cases, div is a numerical value used to scale abscissa values so they are closer to improves the probability that the fit will converge. This parameter may be specified via the (the default) indicates that the application should determine a reasonable value for div, where the converge is the converge of the c

```
div = 10**int(log10(sqrt(min(x)*max(x))))
```

where min(x) and max(x) are the minimum and maximum abscissa values, respectively.

So, for example, if S(nu) is proportional to nu**alpha and you expect alpha to be near -0.8 1e9 Hz and your image(s) have spectral units of Hz, you would specify spxest=[1.5, -0.8] and or spxest=[0.405, -0.8] and div=1e9 if fitting an ltp function close to ln(1.5) - 0.8*ln(x/a)

A CAUTIONARY NOTE

Note that the likelihood of getting a reliable solution increases with the number of good do of the initial estimate. It is possible that the first solution found might not be the best so, if a solution is found, it is recommended that the fit be repeated using the solution of initial estimate for the new fit. This process should be repeated until the solutions from the convergent solution is very likely the best solution.

AXIS

The axis parameter indicates on which axis profiles should be fit; a value <0 indicates the

or if one does not exist, that the zeroth axis should be used.

MINIMUM NUMBER OF PIXELS

The minpts parameter indicates the minimum number of unmasked pixels that must be present in to be attempted. When multifit=T, positions with too few good points will be masked in any of

ONE FIT OF REGION AVERAGE OR PIXEL BY PIXEL FIT

The multifit parameter indicates if profiles should be fit at each pixel in the selected requeraged and the fit done to that average profile (false).

FUNCTION TYPE

Which function to fit is specified in the spxtype parameter. Only two values (case insensitually "plp" indicates that a power logarithmic polynomial should be fit. A value of "ltp" indicate polynomial should be fit.

INCLUDING STANDARD DEVIATIONS OF PIXEL VALUES

If the standard deviations of the pixel values in the input image are known and they vary in near the edge of the band), they can be included in the sigma parameter. This parameter take array or image must have one of three shapes: 1. the shape of the input image, 2. the same of all axes being one except for the fit axis which must have length corresponding to its 10 dimensional with length equal the the length of the fit axis in the input image. In cases 2 be replicated such that the image that is ultimately used is the same shape as the input image. It is only the relative values that are important. A value of 0 means that pixel should not A has a higher standard deviation than pixel B, then pixel A is noisier than pixel B and will the weight of a pixel is the usual

weight = 1/(sigma*sigma)

In the case of multifit=F, the sigma values at each pixel along the fit axis in the hyperplathat pixel are averaged and the resultant averaged standard deviation spectrum is the one us such that the maximum value is 1. This mitigates a known overflow issue.

One can write the normalized standard deviation image used in the fit by specifying its name used as sigma for subsequent runs.

RETURNED DICTIONARY STRUCTURE

The returned dictionary has a (necessarily) complex structure. First, there are keys "xUnit the abscissa unit and the ordinate unit described by simple strings. Next there are arrays gfit quality. These arrays have the shape of the specified region collapsed along the fit axis axis having length of 1:

attempted: a boolean array indicating which fits were attempted (eg if too few unmasked point converged: a boolean array indicating which fits converged. False if the fit was not attempted valid: a boolean array indicating which solutions fall within the specified valid ranges

which a value or error is NaN is automatically marked as invalid.

niter: an int array indicating the number of iterations for each profile, <0 if the fit

direction: a string array containing the world direction coordinate for each profile

There is a "type" array having number of dimensions equal to the number of dimensions in the the first n-1 dimensions is the same as the shape of the above arrays. The length of the last components fit. The values of this array are all "POWER LOGARITHMIC POLYNOMIAL" or "LOGARITH on which type function was fit.

There will be a subdictionary accessible via the "plp" or "ltp" key (depending on which type subkeys "solution" and "error" which will each have an array of values. Each of these arrays described above. The shape of the first n-1 dimensions will be the same as the shape of the final dimension will have length equal to the number of parameters that were fit. Along this corresponding fit result or associated error (depending on the array's associated key) of the fit was not attempted or did not converge, a value of NAN will be present.

OUTPUT IMAGES

In addition to the returned dictionary, optionally one or more of any combination of output The model and residual parameters indicate the names of the model and residual images to be should not be written.

The parameters spxsol and spxerr are the names of the solution and error images to write, rewhere more than one coefficient are fit, the image names will be appended with an underscore coefficient number ("_0", "_1", etc). These images contain the arrays for the associated parameteristic described in previous sections. Pixels for which fits were not attempted, did not converge, of NaN (not a number) or INF (infinity) will be masked as bad.

LPT vs PLP

Ultimately, the choice of which functional form to use in determining the spectral index is on the scientific goals. However, below is a summary of one user's experience and preference

If the weights are known or can be determined from the images (eg. the source-free image rms favor a weighted fit using the non-linear (power-law) model. An unweighted fit using the non-too much leverage to large flux values.

If the weights are unknown or will not be considered by the fitting algorithm, then I prefer this does not work well in low signal-to-noise regions. A conservative mask could be created but this could hinder many science objectives.

EXAMPLES

res = spxfit(imagename=["im0.im","im1.im"], multifit=true, spxtype="plp", spxest=[0.5,2,0.1]

statwt-task.html

0.1.120statwt

Requires:

 ${\bf Synopsis} \\ {\bf Reweight\ visibilities\ according\ to\ their\ scatter\ (Experimental)}$

Arguments

Inputs

vis Name of measurement set

allowed: string

Default:

dorms Use rms instead of stddev?

allowed: bool

Default: False

byantenna Estimate the noise per antenna -not implemented (vs.

per baseline)

allowed: bool Default: False

sepacs If solving by antenna, treat autocorrs separately (not

implemented)

allowed: bool Default: True

fitspw The signal-free spectral window:channels to estimate the

scatter from

allowed: any Default: variant

fitcorr The signal-free correlation(s) to estimate the scatter

from (not implemented) allowed: any Default: variant

combine Let estimates span changes in spw, corr, scan and/or

state

allowed: any Default: variant

timebin Bin length for estimates (not implemented)

allowed: string Default: 0s

minsamp Minimum number of unflagged visibilities for estimating

the scatter

allowed: int Default: 2

field Select field using ID(s) or name(s)

allowed: any Default: variant

spw Select spectral window/channels

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: any Default: yaniant

timerange Select data by time range

allowed: string

Default:

scan Select data by scan numbers

allowed: string

Default:

intent Select data by scan intents

Example

The WEIGHT and SIGMA columns of measurement sets are often set to arbitrary values (e.g. 1), or theoretically estimated from poorly known antenna and receiver properties. Many tasks (e.g. clean) are insensitive to an overall scale error in WEIGHT, but are affected by errors in the relative weights between visibilities. Other tasks, such as uvmodelfit, or anything which depends on theoretical estimates of the noise, require (reasonably) correct weights and sigmas. statwt empirically measures the visibility scatter (typically as a function of time, antenna, and/or baseline) and uses that to set WEIGHT and SIGMA. It is important that all necessary calibrations are applied to the data prior to running this task for correct determination of weights and sigmas.

Note: Some of the parameters (byantenna, sepacs, fitcorr, and timebin) are not fully implemented for CASA 3.4.

Ideally the visibilities used to estimate the scatter, as selected by fitspw and fitcorr, should be pure noise. If you know for certain that they are, then setting dorms to True will give the best result. Otherwise, use False (standard sample standard deviation). More robust scatter estimates like the interquartile range or median absolute deviation from the median are not offered because they require sorting by value, which is not possible for complex numbers.

default: False

byantenna -- Assume that the noise is factorable by antenna (feed).

If false, treat it separately for each baseline

(recommended if there is strong signal).

default: False (*** byantenna=True is not yet implemented)

sepacs -- If solving by antenna, treat autocorrelations separately.

(Acknowledge that what autocorrelations "see" is very different from what crosscorrelations see.)

default: True (*** not yet implemented) --- Data Selection (see help par.selectdata for more detailed information) fitspw -- The (ideally) signal-free spectral window:channels to estimate the scatter from. default: '' (All) fitcorr -- The (ideally) signal-free correlations to estimate the scatter from. default: '' (All) *** not yet implemented combine -- Let samples span multiple spws, corrs, scans, and/or states. combine = 'spw': Recommended when a line spans an entire spw - set fitspw to the neighboring spws and apply their weight to the line spw(s). However, the effect of the line signal per visibility may be relatively harmless compared to the noise difference between spws. combine = 'scan': Can be useful when the scan number goes up with each integration, as in many WSRT MSes. combine = ['scan', 'spw']: disregard scan and spw numbers when gathering samples. combine = 'spw,scan': Same as above. default: '' (None) timebin -- Sample interval. default: '0s' or '-1s' (1 integration at a time) example: timebin='30s' '10' means '10s'

- minsamp -- Minimum number of unflagged visibilities for estimating the scatter. Selected visibilities for which the weight cannot be estimated will be flagged. Note that minsamp is effectively at least 2 if dorms is False, and 1 if it is True.

*** not yet implemented

```
integer, it is assumed to be a field index
       otherwise, it is assumed to be a field name
      field='0~2'; field ids 0,1,2
      field='0,4,5~7'; field ids 0,4,5,6,7
      field='3C286,3C295'; fields named 3C286 and 3C295
      field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels for changing WEIGHT and SIGMA.
      default: ''=all spectral windows and channels
       spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
       spw='<2'; spectral windows less than 2 (i.e. 0,1)
       spw='0:5~61'; spw 0, channels 5 to 61
       spw='0,10,3:3~45'; spw 0,10 all channels, spw 3 - chans 3 to 45.
       spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
       spw = '*:3~64' channels 3 through 64 for all sp id's
               spw = ':3^64' will NOT work.
       statwt does not support multiple channel ranges per spectral
      window (';') because it is not clear whether to keep the ranges
       in the original spectral window or make a new spectral window
      for each additional range.
antenna -- Select antennas/baselines for changing WEIGHT and SIGMA.
      default: ', (all)
       Non-negative integers are assumed to be antenna indices, and
       anything else is taken as an antenna name.
       Examples:
       antenna='5&6': baseline between antenna index 5 and index 6.
       antenna='VA05&VA06': baseline between VLA antenna 5 and 6.
       antenna='5\&6:7\&8': baselines 5-6 and 7-8
       antenna='5': all baselines with antenna 5
       antenna='5,6,10': all baselines including antennas 5, 6, or 10
       antenna='5,6,10&': all baselines with *only* antennas 5, 6, or
                               10. (cross-correlations only. Use &&
                               to include autocorrelations, and &&&
                               to get only autocorrelations.)
       antenna='!ea03,ea12,ea17': all baselines except those that
                                   include EVLA antennas ea03, ea12, or
timerange -- Select data based on time range:
      default = '' (all); examples,
      timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date, timerange defaults to the
      first day in the dataset
      timerange='09:14:0~09:54:0' picks 40 min on first day
       timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min
```

```
on next day
               timerange='09:44:00' data within one integration of time
               timerange='>10:24:00' data after this time
scan -- Scan number range
            default: ''=all
        intent -- Select by scan intent (state). Case sensitive.
            default: '' = all
            Examples:
            intent = 'CALIBRATE_ATMOSPHERE_REFERENCE'
            intent = 'calibrate_atmosphere_reference'.upper() # same as above
            # Select states that include one or both of CALIBRATE_WVR.REFERENCE
            # or OBSERVE_TARGET_ON_SOURCE.
            intent = 'CALIBRATE_WVR.REFERENCE, OBSERVE_TARGET_ON_SOURCE'
        array -- (Sub)array number range
            default: ''=all
        correlation -- Select correlations, e.g. 'rr, ll' or ['XY', 'YX'].
                       default '' (all).
                       NB: In CASA v4.5, non-trivial correlation selection has
                       been disabled since it was not working correctly, and
                       it is likely undesirable to set the weights in a
                       correlation-dependent way.
        observation -- Select by observation ID(s).
                       default: '' = all
       datacolumn -- Which data column to calculate the scatter from
                  default='corrected'; example: datacolumn='data'
                  Options: 'data', 'corrected', 'model', 'float_data'
                  note: 'corrected' will fall back to DATA if CORRECTED_DATA
                        is absent.
```

tclean-task.html

0.1.121 tclean

Requires:

Synopsis

Radio Interferometric Image Reconstruction

Description

Form images from visibilities and reconstruct a sky model. This task handles continuum images and spectral line cubes, supports outlier fields, contains standard clean based algorithms along with algorithms for multi-scale and wideband image reconstruction, widefield imaging correcting for the w-term, full primary-beam imaging and joint mosaic imaging (with heterogeneous array support for ALMA).

Arguments

Inputs

vis Name(s) of input visibility file(s) de-

fault: none; example: vis='ngc5921.ms' vis=['ngc5921a.ms','ngc5921b.ms']; multiple MSes

allowed: any
Default: variant

selectdata Enable data selection parameters.

allowed: bool Default: True

field

Select fields to image or mosaic. Use field id(s) or name(s). ['go listobs' to obtain the list id's or names] default: "= all fields If field string is a non-negative integer, it is assumed to be a field index otherwise, it is assumed to be a field name field='0~2'; field ids 0,1,2 field='0,4,5~7'; field ids 0,4,5,6,7 field='3C286,3C295'; field named 3C286 and 3C295 field = '3,4C*'; field id 3, all names starting with 4C For multiple MS input, a list of field strings can be used: field = ['0~2','0~4']; field ids 0-2 for the first MS and 0-4 for the second field = '0~2'; field ids 0-2 for all input MSes

allowed: any Default: variant

spw

Select spectral window/channels NOTE: channels deselected here will contain all zeros if selected by the parameter mode subparameters. default: "=all spectral windows and channels spw= $^{\circ}0\sim2,4^{\circ}$; spectral windows 0.1,2.4 (all channels) spw='0:5 \sim 61'; spw 0, channels 5 to 61 spw='<2'; spectral windows less than 2 (i.e. 0,1) spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45. spw=' $0\sim2:2\sim6$ '; spw 0,1,2 with channels 2 through 6 in each. For multiple MS input, a list of spw strings can be used: $spw=['0','0\sim3']$; spw ids 0 for the first MS and 0-3 for the second spw= $^{\prime}0\sim3^{\prime}$ spw ids 0-3 for all input MS spw='3:10~20;50~60' for multiple channel ranges within spw id 3 spw='3:10 \sim 20;50 \sim 60,4:0 \sim 30' for different channel ranges for spw ids 3 and 4 $\text{spw}='0:0\sim10,1:20\sim30,2:1;2;3'; \text{ spw } 0, \text{ channels } 0-10,$ spw 1, channels 20-30, and spw 2, channels, 1,2 and 3 $\text{spw}='1\sim4;6:15\sim48'$ for channels 15 through 48 for spwids 1,2,3,4 and 6

allowed: any Default: variant

timerange

Range of ting to select from data default: " (all); examples, timerange = 'YYYYY/MM/DD/hh:mm:ss~YYYYY/MM/DD/hh:mm:ss*
Note: if YYYY/MM/DD is missing date defaults to first day in data set timerange='09:14:0~09:54:0' picks 40 min on first day timerange='25:00:00~27:30:00' picks 1 hr to 3 hr 30min on NEXT day timerange='09:44:00' pick data within one integration of time timerange='> 10:24:00' data after this

Returns

void

Example

This is the first release of our refactored imager code. Although most features have been used and validated, there are many details that have not been thoroughly tested. Feedback will be much appreciated.

Usage Examples :

- (A) A suite of test programs that demo all usable modes of tclean on small test datases https://svn.cv.nrao.edu/svn/casa/branches/release-4_5/gcwrap/python/scripts/tests
- (B) A set of demo examples for ALMA imaging https://casaguides.nrao.edu/index.php/TCLEAN_and_ALMA

testconcat-task.html

0.1.122 testconcat

Requires:

Synopsis

Concatenate the subtables of several visibility data sets, not the MAIN bulk data.

Arguments

Inputs	
vis	Name(s) of input visibility files to be test-concatenated allowed: stringArray Default:
testconcatvis	Name of output MS containing the merged subtables allowed: string Default:
freqtol	Frequency shift tolerance for considering data as the same spwid allowed: any Default: variant
dirtol	Direction shift tolerance for considering data as the same field allowed: any Default: variant
copypointing	Copy all rows of the POINTING table. allowed: bool Default: True

Example

The list of data sets given in the vis argument are concatenated into an output data set in testconcatvis without the bulk data of the MAIN table. This is useful for obtaining the information in the merged subtables without actually performing a time-consuming concatenation of the MAIN tables on disk.

Keyword arguments:

vis -- Name of input visibility files for which the subtables are to be combined
default: none; example: vis = 'mydata.ms',

vis=['src2.ms','ngc5921.ms','ngc315.ms']

testconcatvis -- Name of MS that will contain the concatenated subtables default: none; example: testconcatvis='test.ms'

freqtol -- Frequency shift tolerance for considering data to be in the same spwid. The number of channels must also be the same.

default: '' do not combine unless frequencies are equal

example: freqtol='10MHz' will not combine spwid unless they are within 10 MHz.

Note: This option is useful to combine spectral windows with very slight frequency differences caused by Doppler tracking, for example.

dirtol -- Direction shift tolerance for considering data as the same field default: '' means always combine.

example: dirtol='1.arcsec' will not combine data for a field unless their phase center differ by less than 1 arcsec. If the field names are different in the input data sets, the name in the output data set will be the first relevant data set in the list.

copypointing -- Make a proper copy of the POINTING subtable (can be time consuming).

If False, the result is an empty POINTING table.

default: True

tsdbaseline-task.html

0.1.123 tsdbaseline

Requires:

Synopsis

Fit/subtract a spectral baseline

Description

Task tsdbaseline fits and/or subtracts baseline from single-dish spectra. Given baseline parameters (baseline type, order, etc.), tsdbaseline computes the best-fit baseline for each spectrum by least-square fitting method and, if you want, subtracts it. The best-fit baseline parameters (including baseline type, coefficients of basis functions, etc.) and other values such as residual rms can be saved in various formats including ascii text (in human-readable format or CSV format) or baseline table (a CASA table). Tsdbaseline has another mode to 'apply' a baseline table to a MS data; for each spectrum in MS, the best-fit baseline is reproduced from the baseline parameters stored in the given baseline table and subtracted. Putting 'fit' and 'subtract' into separate processes can be useful for pipeline processing for huge dataset.

Arguments

Inputs infile name of input SD dataset allowed: string Default: datacolumn name of data column to be used ['data', 'float_data', or 'corrected' allowed: string Default: data select data by antenna name or ID, e.g. 'PM03' antenna allowed: string Default: field select data by field IDs and names, e.g. '3C2*' ("=all) allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: timerange select data by time range, e.g. $'09:14:0\sim09:54:0'$ ("=all) (see examples in help) allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: select data by polarization IDs, e.g. '0,1' ("=all) pol allowed: string Default: intent select data by observational intent, e.g. "*ON_SOURCE*" ("=all) allowed: string Default: maskmode mode of setting additional channel masks. 'list' and 'auto' are available now. allowed: string Default: list thresh S/N threshold for linefinder allowed: double Default: 5.0 avg_limit channel averaging for broad lines allowed: int Default: 4 minwidth the minimum channel width to detect as a line allowed: Default: channels to drop at beginning and end of spectrum edge allowed: intArray Default: 699blmode baselining mode ['fit' or 'apply'] allowed: string Default: fit

subtract baseline from input data [True, False]

format(s) of file(s) in which best-fit parameters are writ-

bool

True

ten ['text', 'csv', 'table' or "]

allowed:

Default:

dosubtract

blformat

Returns

void

Example

```
______
Keyword arguments
_____
infile -- name of input SD dataset
datacolumn -- name of data column to be used
        options: 'data', 'float_data', or 'corrected'
       default: 'data'
antenna -- select data by antenna name or ID
       default: '' (use all antennas)
       example: 'PM03'
field -- select data by field IDs and names
       default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                field='0,4,5~7' (field IDs 0,4,5,6,7)
                field='0,3C273' (field ID 0 or field named 3C273)
       this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
       default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
       this selection is in addition to the other selections to data
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss'
                Note: YYYY/MM/DD can be dropped as needed:
                timerange='09:14:00~09:54:00' # this time range
                timerange='09:44:00' # data within one integration of time
                timerange='>10:24:00' # data after this time
                timerange='09:44:00+00:13:00' #data 13 minutes after time
       this selection is in addition to the other selections to data
scan -- select data by scan numbers
       default: '' (use all scans)
```

```
example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
intent -- select data by observational intent, also referred to as 'scan intent'
        default: '' (use all scan intents)
        example: intent='*0N_SOURCE*' (any valid scan-intent expression accepted by the MSSource example:
        this selection is in addition to the other selections to data
maskmode -- mode of setting additional channel masks. When blmode='apply'
             and/or blfunc='variable', maskmode and its subparameters
             are ignored.
        options: 'list' and 'auto' ('interact' will be available later)
        default: 'list'
        example: maskmode='auto' runs linefinder to detect line regions
                 to be excluded from fitting. this mode requires three
                 expandable parameters: thresh, avg_limit, minwidth, and edge.
                 NOTE maskmode='auto' is EXPERIMENTAL.
                 USE WITH CARE! May need to tweak the expandable parameters.
                 maskmode='list' uses the given masklist only: no additional
                 masks applied.
                 maskmode='interact' allows users to manually modify the
                 mask regions by dragging mouse on the spectrum plotter GUI.
                 use LEFT or RIGHT button to add or delete regions,
                 respectively.
    >>> maskmode expandable parameters
        thresh -- S/N threshold for linefinder. a single channel S/N ratio
                  above which the channel is considered to be a detection.
                default: 5
        avg_limit -- channel averaging for broad lines. a number of
                     consecutive channels not greater than this parameter
                     can be averaged to search for broad lines.
                default: 4
        minwidth -- the minimum channel width to detect as a line.
                     a line with number of consecutive channels less
                     than this parameter will not be detected as a line.
                default: 4
        edge -- channels to drop at beginning and end of spectrum
                default: 0
                example: edge=[1000] drops 1000 channels at beginning AND end.
                         edge=[1000,500] drops 1000 from beginning and 500
                         from end.
        Note: For bad baselines threshold should be increased,
        and avg_limit decreased (r even switched off completely by
```

setting this parameter to 1) to avoid detecting baseline

undulations instead of real lines.

blmode -- baselining mode.

options: 'fit', 'apply'

default: 'fit'

example: blmode='fit' calculates the best-fit baseline based on given baseline type, then (if you set dosubtract=True) subtract it from each spectrum. The information about best-fit baselines (baseline type, order, coefficients, etc.) can be stored in various formats (cf. blformat). blmode='apply' reads a baseline table as well as input MS, reproduces the best-fit baseline via info written in the baseline table, then subtracts it from each spectrum.

>>> blmode expandable parameters

dosubtract -- execute baseline subtraction in addition to fitting.

Note that dosubtract=False will be ignored if
bloutput is given, that is, baseline subtraction
will be always executed for the input MS in case
bloutput is not specified.

options: (bool) True, False

default: True

blformat -- format(s) of file(s) in which best-fit parameters are
 written.

options: 'text', 'csv', 'table', and '' can be set for a single output. In case you want to output fitting results in multiple formats, a list containing the above keywords is accepted as well.

default: 'text'

example: (1) blformat='text' outputs an ascii text file with the best-fit baseline parameters written in human-readable format. It may be good to read, but you should mind it might be huge.

(2) blformat='csv' outputs a CSV file. For example, output of csv with blfunc='poly' is as below: #scan, beam, spw, pol, MJD[s], fitrange (i.e. inverse mask), blfunc 4,0,17,0,4915973292.23,[[252;3828]],poly,1,767.647,-0.00956208,26.3

. . .

- (3) blformat='table' outputs a baseline table which can be used to apply afterwards.
- (4) blformat='' doesn't output any parameter file.
- (5) blformat=['csv','table'] outputs both a CSV file and a baseline table.
- (6) If one or more ''s appear in blformat, they
 are all ignored. For example, if blformat=['',
 'text',''] is given, only 'text' will be output.
- (7) Elements of blformat other than ', must not

```
'text'] is not accepted.
        bloutput -- name(s) of file(s) in which best-fit parameters are
                    written. If bloutput is a null string '', name(s) of
                    baseline parameter file(s) will be set as follows:
                    <outfile>_blparam.txt for blformat='text',
                    <outfile>_blparam.csv for blformat='csv', and
                    <outfile>_blparam.bltable for blformat='table'.
                    Otherwise, blformat and bloutput must have the same
                    length, and one-to-one correspondence is assumed
                    between them. If there are '' elements in bloutput,
                    output file names will be set by following the above
                    rules. If there are '' elements in blformat, the
                    corresponding bloutput elements will be ignored.
                    Also, non-'' bloutput elements correspoding to
                    non-'' blformat elements must not be duplicated.
                default: ''
                example: (1) bloutput='' and blformat=['csv', 'table']:
                         outputs a csv file '<outfile>_blparam.csv'
                         and a baseline table '<outfile>_blparam.bltable'.
                         (2) bloutput=['foo.csv',''] and blformat=['csv',
                         'table']: outputs a csv file 'foo.csv' and a
                         baseline table '<outfile>_blparam.bltable'.
                         (3) bloutput=['foo.csv','bar.blt'] and blformat=
                         ['csv','']: outputs a csv file 'foo.csv' only.
                         (4) bloutput=['foo.csv','foo.csv','bar.blt'] and
                         blformat=['csv','','table']: the second 'foo.csv'
                         is ignored because it corresponds to the blformat
                         element '', and thus outputs a csv file 'foo.csv'
                         and a baseline table 'bar.blt'.
                         (5) bloutput=['foo.csv','foo.csv','bar.blt'] and
                         blformat=['csv','text','table']: will be error
                         since 'foo.csv' is duplicated.
                         (6) bloutput=['foo.csv', 'bar.blt'] and blformat=
                         ['csv','','table']: will be error since bloutput
                         and blformat have different lengths.
        bltable -- name of baseline table to apply
                default: ''
blfunc -- baseline model function. In cases blmode='apply' or blparam is
          set, blfunc and its subparameters are ignored.
        options: 'poly', 'chebyshev', 'cspline', or 'variable'
        default: 'poly'
        example: blfunc='poly' uses a single polynomial line of
                 any order which should be given as an expandable
                 parameter 'order' to fit baseline.
                 blfunc='chebyshev' uses Chebyshev polynomials.
```

be duplicated. For example, blformat=['text','',

blfunc='cspline' uses a cubic spline function, a piecewise cubic polynomial having C2-continuity (i.e., the second derivative is continuous at the joining points).

```
NOTE blfunc='variable' IS EXPERT MODE!!!
    >>> blfunc expandable parameters
        order -- order of baseline model function
                options: (int) (<0 turns off baseline fitting)
                default: 5
                example: typically in range 2-9 (higher values
                         seem to be needed for GBT)
        npiece -- number of the element polynomials of cubic spline curve
                options: (int) (<0 turns off baseline fitting)
                default: 2
        clipthresh -- clipping threshold for iterative fitting
                 default: 3
        clipniter -- maximum iteration number for iterative fitting
                default: 0 (no iteration, i.e., no clipping)
        blparam -- the name of text file that stores per spectrum fit
                   parameters. See below for details of format.
verbose -- (NOT SUPPORTED YET) output fitting results to logger. if False, the fitting results
           including coefficients, residual rms, etc., are not output to
           the CASA logger, while the processing speed gets faster.
        options: (bool) False
        default: False (verbose=True is currently unavailable)
showprogress -- (NOT SUPPORTED YET) show progress status for large data
        options: (bool) False (this capability is currently unavailable.)
        default: False
    >>> showprogress expandable parameter
        minnrow -- (NOT SUPPORTED YET) minimum number of input spectra to show progress star
                 default: 1000
outfile -- name of output file
       default: '' (<infile>_bs)
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
_____
```

DESCRIPTION

Task tsdbaseline performs baseline fitting/subtraction for single-dish spectra. The fit parameters, terms and rms of baseline can be saved into an ascii file

or baseline table. Subtracting baseline from data in input MS using existing baseline table is also possible.

BASELINE MODEL FUNCTION

The list of available model functions are shown above (see Keyword arguments section). In general 'cspline' or 'chebyshev' are recommended since they are more stable than others. 'poly' will work for lower order but will be unstable for higher order fitting.

SIGMA CLIPPING (ITERATIVE FITTING)

In general least square fitting is strongly affected by an extreme data so that the resulting fit makes worse. Sigma clipping is an iterative baseline fitting with data clipping based on a certain threshold. Threshold is set as a certain factor times rms of the resulting (baseline subtracted) spectra. If sigma clipping is on, baseline fit/removal is performed several times. After each baseline subtraction, the data whose absolute value is above threshold are detected and those data are excluded from the next round of fitting. By using sigma clipping, extreme data are excluded from the fit so that resulting fit is more robust.

The user is able to control a multiplication factor using parameter clipthresh for clipping threshold based on rms. Actual threshold for sigma clipping will be (clipthresh) x (rms of spectra). Also, the user can specify number of maximum iteration to the parameter clipniter.

In general, sigma clipping will lower the performance since it increases number of fits per spectra. However, it is strongly recommended to turn on sigma clipping unless you are sure that the data is free from any kind of extreme values that may affect the fit.

PER SPECTRUM FIT PARAMETERS

Per spectrum baseline fitting parameter is accepted in blfunc='variable'. Note this is an expert mode. The fitting parameters should be defined in a text file for each spectrum in the input MS. The text file should store commpa separated values in order of:

row ID, polarization ID, masklist, blfunc, order, npiece, nwave, clipthresh, clipniter, use_linefinder, thresh, edge, chan_avg_limit.

Each row in the text file must contain the following keys and values:

- * 'row': row number,
- * 'blfunc': function name.

tsdcal-task.html

0.1.124 tsdcal

Requires:

Synopsis

MS SD calibration task

Description

Task tsdcal is an implementation of a calibration scheme like as interferometry, i.e., generate caltables and apply them. Available calibration modes are 'ps', 'otfraster', and 'tsys'. Those modes generates caltables for sky or Tsys calibration. The caltables can be applied to the data by using calmode 'apply'. First two calibration modes, 'ps' and 'otfraster', generate sky calibration tables. The user should choose appropriate calibration mode depending on the data. Use case for each mode is as follows:

'ps': position switch (including OTF) with explicit reference (OFF) spectra 'otfraster': raster OTF scan without explicit OFFs

So, if the data contains explicit reference spectra, 'ps' should be used. Otherwise, 'otfraster' is appropriate for raster OTF data. Non-raster OTF data is not supported yet. In 'otfraster' mode, the task first try to find several integrations near edge as OFF spectra, then the data are calibrated using those OFFs. If the observing pattern is raster, you should use the 'otfraster' mode to calibrate data. The 'otfraster' mode is designed for OTF observations without explicit OFF spectra. However, these modes should work even if explicit reference spectra exist. In this case, these spectra will be ignored and spectra near edges detected by edge marker will be used as reference. Except for how to choose OFFs, the procedure to derive calibrated spectra is common for the above two modes. Selected (or preset) OFF integrations are separated by its continuity in time domain, averaged in each segment, then interpolated to timestamps for ON integrations. Effectively, it means that OFF integrations are averaged by each OFF spectrum for 'ps' mode, averaged by either ends of each raster row for 'otfraster' mode. The formula for calibrated spectrum is

Tsys * (ON - OFF) / OFF.

Arguments

Inputs

infile name of input SD dataset (must be MS)

allowed: string

Default:

calmode SD calibration mode

allowed: string
Default: ps

fraction fraction of the OFF data to mark

allowed: any

Default: variant 10%

noff number of the OFF data to mark

allowed: int Default: -1

width width of the pixel for edge detection

allowed: double Default: 0.5

elongated whether observed area is elongated in one direction or

not

allowed: bool Default: False

applytable (List of) sky and/or tsys tables

allowed: any Default: variant

interp Interpolation type in time[,freq]. Valid options are

"nearest", "linear", "cspline", or any numeric string that indicates an order of polynomial interpolation. You can specify interpolation type for time and frequency separately by joining two of the above options by comma

(e.g., "linear,cspline"). allowed: string

Default:

spwmap A dictionary indicating spw combinations to apply Tsys

calibration to target. The key should be spw for Tsys calibration and its associated value must be a list of

science spws to be applied.

allowed: any Default: variant

outfile name of output file (See a WARNING in help)

allowed: string

Default:

overwrite the output file if already exists

allowed: bool Default: False

field select data by field IDs and names, e.g. '3C2*' (" = all)

allowed: string

Default:

spw select data by spw4IDs (spectral windows), e.g., '3,5,7'

 $("=\mathrm{all})$

allowed: string

Default:

scan select data by scan numbers, e.g. '21~23' ("=all)

allowed: string

Default:

Returns

void

Example

```
Keyword arguments:
infile -- Name of input SD dataset
calmode -- Calibration mode. If you want to generate calibration table
           or apply existing calibration tables, set calmode to simple
           string. On the other hand, if you want to calibrate data
           on-the-fly, you have to set calmode to a composite calmode
           string separated by comma. So far, sky calibration has two
           types, 'ps' and 'otfraster'. If observation is
           configured to observe reference position, calmode must be
           'ps'. Otherwise, 'otfraster' should be used. Non-raster
           observing pattern is not supported yet (e.g., Lissajous).
        options: 'ps', 'otfraster', 'tsys', 'apply'
        default: 'ps'
        example: Here is an example for composite calmode.
                 'ps,apply' (do sky cal and apply)
                 'ps,tsys,apply' (do sky and Tsys cal and apply)
    >>> calmode expandable parameter
        fraction -- Edge marker parameter of 'otfraster'.
                    Specify a number of OFF integrations (at each
                    side of the raster rows in 'otfraster' mode)
                    as a fraction of total number of integrations.
                    In 'otfraster' mode, number of integrations
                    to be marked as OFF, n_off, is determined by
                    the following formula,
                        n_off = floor(fraction * n),
                    where n is number of integrations per raster
                    row. Note that n_off from both sides will be
                    marked as OFF so that twice of specified
                    fraction will be marked at most. For example,
                    if you specify fraction='10%', resultant
                    fraction of OFF integrations will be 20% at
                    most.
                default: '10%'
                options: '20%' in string style or float value less
                         than 1.0 (e.g. 0.15).
```

```
noff -- Edge marking parameter for 'otfraster'.
                It is used to specify a number of OFF spectra near
                edge directly. Value of noff comes before setting
                by fraction. Note that n_off from both sides will
                be marked as OFF so that twice of specified noff
                will be marked at most.
                default: -1 (use fraction)
                options: any positive integer
        applytable -- List of sky/Tsys calibration tables you want to
                default: ''
        interp -- Interpolation method in time and frequency axis.
                  Set comma separated method strings if you want
                  to use different interpolation in time and
                  frequency.
                options: 'linear', 'cspline', 'nearest',
                         any numeric string indicating an order
                         of polynomial.
                default: '' (linear in time and frequency)
                example: 'linear,cspline' (linear in time, cubic
                                           spline in frequency)
                         'linear,3' (linear in time, third order
                                     polynomial in frequency)
                         'nearest' (nearest in time and frequency)
        spwmap -- Dictionary defining transfer of Tsys calibration.
                  Key must be spw for Tsys and its value must be
                  a list of spws for science target.
                default: {}
                example: {1: [5,6], 3: [7,8]}
                         Tsys in spw 1 is transferred to spws 5 and 6
                         while Tsys in spw 3 is to spws 7 and 8.
field -- select data by field IDs and names
        default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                 field='0,4,5~7' (field IDs 0,4,5,6,7)
                 field='0,3C273' (field ID 0 or field named 3C273)
        this selection is in addition to the other selections to data
spw -- select data by spw IDs (spectral windows)
        NOTE this task only supports spw ID selction and ignores channel
        selection.
        default: '' (use all spws and channels)
        example: spw='3,5,7' (spw IDs 3,5,7; all channels)
                 spw='<2' (spw IDs less than 2, i.e., 0,1; all channels)
                 spw='30~45GHz' (spw IDs with the center frequencies in range 30-45GHz; all
```

'auto' is available only for 'otfraster'.

this selection is in addition to the other selections to data NOTE spw input must be '' (''= all) in calmode='tsys'.

scan -- select data by scan numbers

default: '' (use all scans)

example: scan='21~23' (scan IDs 21,22,23)

this selection is in addition to the other selections to data NOTE scan input must be '' (''= all) in calmode='tsys'.

outfile -- Name of output file

NOTE if you omit, behavior of the task depends on calmode. If calmode includes 'apply', then omitting outfile indicates that infile is overwritten by the calibrated data. In this case, you have to set overwrite to True. If calmode doesn't include 'apply', omitting outfile indicates that the task will use default outfile name based on infile and predefined suffix ('_sky' for sky, '_tsys' for Tsys).

overwrite -- overwrite the output file if already exists

options: (bool) True, False

default: False

NOTE this parameter is ignored when outform='ASCII'

DESCRIPTION:

Task tsdcal is an implementation of a calibration scheme like as interferometry, i.e., generate caltables and apply them. Available calibration modes are 'ps', 'otfraster', and 'tsys'. Those modes generates caltables for sky or Tsys calibration. The caltables can be applied to the data by using calmode 'apply'.

First two calibration modes, 'ps', and 'otfraster', generate sky calibration tables. The user should choose appropriate calibration mode depending on the data. Use case for each mode is as follows:

'ps': position switch (including OTF) with explicit reference (OFF) spectra 'otfraster': raster OTF scan without explicit OFFs

So, if the data contains explicit reference spectra, 'ps' should be used. Otherwise, 'otfraster' is appropriate for raster OTF, respectively. Non raster OTF data is not supported yet. In 'otfraster' mode, the task first try to find several integrations near edge as OFF spectra, then the data are calibrated using those OFFs. If the observing pattern is raster, you should use the 'otfraster' mode to calibrate data. The 'otfraster' mode is designed for OTF observations

without explicit OFF spectra. However, these modes should work even if explicit reference spectra exist. In this case, these spectra will be ignored and spectra near edges detected by edge marker will be used as reference.

Except for how to choose OFFs, the procedure to derive calibrated spectra is common for the above two modes. Selected (or preset) OFF integrations are separated by its continuity in time domain, averaged in each segment, then interpolated to timestamps for ON integrations. Effectively, it means that OFF integrations are averaged by each OFF spectrum for 'ps' mode, averaged by either ends of each raster row for 'otfraster' mode. The formula for calibrated spectrum is

```
Tsys * (ON - OFF) / OFF.
```

You can calibrate data on-the-fly like sdcal task by setting calmode to a composite calmode string separated by comma. For example, calmode='ps,apply' means doing sky calibration and apply it on-the-fly. In this case, caltable is generated as a temporary plain table and will be deleted at the end. Allowed calibration modes in this task is as follows:

```
ps
    generate sky caltable using 'ps' mode
otfraster
    generate sky caltable using 'otfraster' mode
    generate tsys caltable
apply
    apply caltables specified by applytable parameter
    generate temporary sky caltable using 'ps' mode and
    apply it. also apply caltables specified by applytable
ps, tsys, apply
    generate temporary sky caltable using 'ps' mode as well
    as temporary tsys caltable, and apply them.
otfraster, apply
    generate temporary sky caltable using 'otfraster' mode
    and apply it. also apply caltables specified by applytable
otfraster, tsys, apply
    generate temporary sky caltable using 'otfraster' mode
    as well as temporary tsys caltable, and apply them.
```

There are several control parameters for sky/Tsys calibration and application of caltables. See the above parameter description.

In ALMA, Tsys measurement is usually done using different spectral setup from spectral windows for science target. In this case, tsdcal transfers Tsys values to science spectral windows in the application stage. To do that, the user has to give a list of spectral windows for Tsys measurement as well as mapping between spectral windows for Tsys measurement and scicence target. These can be specified by parameters 'tsysspw' and 'spwmap', which are defined as subparameters of 'calmode'. For example, suppose that Tsys measurements for science windows 17, 19, 21, and 23 are done in spw 9, 11, 13, and 15, respectively. In this case, tsysspw and spwmap should be specified as follows:

```
tsysspw = '9,11,13,15'
spwmap = {9:[17],11:[19],13:[21],15:[23]}
```

Below is an example of full specification of task parameters for calmode of 'ps,tsys,apply':

```
default(tsdcal)
infile = 'foo.asap'
calmode = 'ps,tsys,apply'
spw = ''
tsysspw = '9,11,13,15'
spwmap = {9:[17],11:[19],13:[21],15:[23]}
outfile = 'bar.asap'
tsdcal()
```

Note that, in contrast to applycal task, spwmap must be a dictionary with Tsys spectral window as key and a list of corresponding science spectral window as value. Note also that the parameter 'spw' should not be used to specify a list of spectral windows for Tsys measurement. It is intended to select data to be calibrated so that the list should contain spectral windows for both science target and Tsys measurement. The task will fail if you use 'spw' instead of 'tsysspw'.

For Tsys calibration, the user is able to choose whether Tsys is averaged in spectral axis or not. If tsysavg is False (default), resulting Tsys is spectral value. On the other hand, when tsysavg is True, Tsys is averaged in spectral axis before output. The channel range for averaging is whole channels by default. If channel range is specified by tsysspw string, it is used for averaging. The user can specify channel range with ms selection syntax. For example,

```
tsysspw = '1:0~100'
```

specifies spw 1 for Tsys calibration and channel range between channel 0 and 100 for averaging. You can specify more than one ranges per spw.

tsysspw = '1:0~100;200~400'

In this case, selected ranges are between 0 and 100 plus 200 and 400. Note that even if multiple ranges are selected, the task average whole ranges together and output single averaged value. You can specify multiple spws by separating comma.

 $tsysspw = '1:0^{\sim}100,3:400^{\sim}500'$ Note that specified channel range is ignored if tsysavg is False.

tsdfit-task.html

0.1.125 tsdfit

Requires:

Synopsis

Fit a spectral line

Description

Task tsdfit is a basic line-fitter for single-dish spectra. It assumes that the spectra have been calibrated in tsdcal or sdreduce.

Outputs xstatRETURN ONLY: a Python dictionary of line statistics allowed: Default: variant Inputs infile name of input SD dataset allowed: string Default: datacolumn name of data column to be used ['data', 'float_data', or 'corrected_data'] allowed: string Default: data antenna select data by antenna name or ID, e.g. 'PM03' allowed: string Default: select data by field IDs and names, e.g. '3C2*' ("=all) field allowed: string Default: select data by IF IDs (spectral windows), e.g. '3,5,7' spw ("=all)allowed: string Default: select data by time range, e.g. '09:14:0~09:54:0' ("=all) timerange (see examples in help) allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: pol select data by polarization IDs, e.g. '0,1' ("=all) allowed: Default: observational intent select data by intent, e.g. '*ON_SOURCE*' ("=all) allowed: string Default: fitfunc function for fitting allowed: string Default: gaussian fitmode mode for fitting allowed: string Default: list nfit list of number of lines to fit in maskline region. allowed: intArray Default: thresh S/N threshold for linefinder allowed: double Default: 552 min_nchan minimum number of consecutive channels for linefinder allowed: int Default: 3 avg_limit channel averaging for broad lines

allowed:

Default:

allowed:

box_size

int

double

running mean box size

Returns

variant

Example

```
______
Keyword arguments
_____
infile -- name of input SD dataset
datacolumn -- name of data column to be used
        options: 'data', 'float_data', or 'corrected_data'
       default: 'data'
antenna -- select data by antenna name or ID
       default: '' (use all antennas)
       example: 'PM03'
field -- select data by field IDs and names
       default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                field='0,4,5~7' (field IDs 0,4,5,6,7)
                field='0,3C273' (field ID 0 or field named 3C273)
       this selection is in addition to the other selections to data
spw -- select data by IF IDs (spectral windows)/channels
       default: '' (use all IFs and channels)
        example: spw='3,5,7' (IF IDs 3,5,7; all channels)
                spw='<2' (IF IDs less than 2, i.e., 0,1; all channels)
                spw='30~45GHz' (IF IDs with the center frequencies in range 30-45GHz; all
                spw='0:5~61' (IF ID 0; channels 5 to 61; all channels)
                spw='3:10~20;50~60' (select multiple channel ranges within IF ID 3)
                spw='3:10~20,4:0~30' (select different channel ranges for IF IDs 3 and 4)
                spw='1~4;6:15~48' (for channels 15 through 48 for IF IDs 1,2,3,4 and 6)
       this selection is in addition to the other selections to data
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss'
                Note: YYYY/MM/DD can be dropped as needed:
                timerange='09:14:00~09:54:00' # this time range
                timerange='09:44:00' # data within one integration of time
                timerange='>10:24:00' # data after this time
                timerange='09:44:00+00:13:00' #data 13 minutes after time
       this selection is in addition to the other selections to data
scan -- select data by scan numbers
       default: '' (use all scans)
```

```
example: scan='21~23' (scan IDs 21,22,23)
        this selection is in addition to the other selections to data
pol -- select data by polarization IDs
        default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
intent -- select data by observational intent, also referred to as 'scan intent'
        default: '' (use all scan intents)
        example: intent='*ON_SOURCE*' (any valid scan-intent expression accepted by the MSSe
        this selection is in addition to the other selections to data
fitfunc -- function for fitting
        options: 'gaussian', 'lorentzian'
        default: 'gaussian'
fitmode -- mode for fitting
        options: 'list' ('auto' and 'interact' will be available later)
        default: 'list'
        example: 'list' will use channel ranges specified in the parameter
                        spw to fit for lines
                 'auto' will use the linefinder to fit for lines
                        using the following parameters
                 'interact' allows adding and deleting mask
                        regions by drawing rectangles on the plot
                        with mouse. Draw a rectangle with LEFT-mouse
                        to ADD the region to the mask and with RIGHT-mouse
                        to DELETE the region.
    >>> fitmode expandable parameters
        thresh -- S/N threshold for linefinder. a single channel S/N ratio
                  above which the channel is considered to be a detection.
                default: 5
        min_nchan -- minimum number of consecutive channels required to
                     pass threshold
                       default: 3
        avg_limit -- channel averaging for broad lines. a number of
                     consecutive channels not greater than this parameter
                     can be averaged to search for broad lines.
                default: 4
        box_size -- running mean box size specified as a fraction
                    of the total spectrum length
                default: 0.2
        edge -- channels to drop at beginning and end of spectrum
                default: 0
                example: edge=[1000] drops 1000 channels at beginning AND end.
                         edge=[1000,500] drops 1000 from beginning and 500
                         from end
```

Note: For bad baselines threshold should be increased,

```
and avg_limit decreased (or even switched off completely by
        setting this parameter to 1) to avoid detecting baseline
        undulations instead of real lines.
nfit -- list of number of lines to fit in each region specified by the
        parameter spw
        default: [0] (no fitting)
        example: nfit=[1] for single line in single region,
                 nfit=[2] for two lines in single region,
                 nfit=[1,1] for single lines in each of two regions, etc.
outfile -- name of output file
        default: no output fit file
        example: 'mysd.fit'
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
Returns
_____
a Python dictionary of line statistics
    keys: 'peak', 'cent', 'fwhm', 'nfit'
```

example: each value except for 'nfit' is a list of lists with

a list of 2 entries [fitvalue,error] per component. e.g. xstat['peak']=[[234.9, 4.8],[234.2, 5.3]]

DESCRIPTION

Task tsdfit is a basic line-fitter for single-dish spectra. It assumes that the spectra have been calibrated in tsdcal or sdreduce.

for 2 components.

Note that multiple scans, IFs, and polarizations can in principle be handled, but we recommend that you use scan, field, spw, and pol to give a single selection for each fit.

FITMODE

As described in the parameter description section, tsdfit implements a fitting mode 'list' so far. The 'list' mode allows users to set initial guess manually. Only controllable parameter for the guess is range of the line region and number of lines per region. In 'list' mode, users must give line region via spw parameter by using ms selection syntax while number of lines per region can be

specified via nfit parameter. For example,

```
spw = '17:1500~2500'
nfit = [1]
```

will set line region between channels 1500 and 2500 for spw 17, and indicate that there is only one line in this region. Specifying single region with multiple line is also possible but is not recommended.

tsdsmooth-task.html

0.1.126 tsdsmooth

Requires:

Synopsis

Smooth spectral data

Description

Task tsdsmooth performs smoothing along spectral axis using user-specified smoothing kernel. Currently gaussian and boxcar kernels are supported.

Inputs infile name of input SD dataset allowed: string Default: datacolumn name of data column to be used ['data', 'float_data', or 'corrected' allowed: string Default: data antenna select data by antenna name or ID, e.g. 'PM03' allowed: string Default: select data by field IDs and names, e.g. '3C2*' ("=all) field allowed: string Default: select data by spectral window IDs, e.g. '3,5,7' ("=all) spw allowed: string Default: timerange select data by time range, e.g. $'09:14:0\sim09:54:0'$ ("=all) (see examples in help) allowed: string Default: select data by scan numbers, e.g. '21~23' ("=all) scan allowed: string Default: pol select data by polarization IDs, e.g. '0,1' ("=all) allowed: string Default: intent select data observational by intent, e.g. '*ON_SOURCE*' ("=all) allowed: string Default: kernel spectral smoothing kernel type allowed: string gaussian Default: kwidth smoothing kernel width in channel allowed: int Default: outfile name of output file allowed: string Default: overwrite overwrite the output file if already exists bool allowed: Default: False

Returns

Example

```
Keyword arguments
-----
infile -- name of input SD dataset
datacolumn -- name of data column to be used
        options: 'data', 'float_data', or 'corrected'
       default: 'data'
antenna -- select data by antenna name or ID
       default: '' (use all antennas)
        example: 'PM03'
field -- select data by field IDs and names
       default: '' (use all fields)
        example: field='3C2*' (all names starting with 3C2)
                field='0,4,5~7' (field IDs 0,4,5,6,7)
                field='0,3C273' (field ID 0 or field named 3C273)
       this selection is in addition to the other selections to data
spw -- select data by spectral window IDs/channels
        default: '' (use all spws and channels)
        example: spw='3,5,7' (spw IDs 3,5,7; all channels)
                spw='<2' (spw IDs less than 2, i.e., 0,1; all channels)
                spw='30~45GHz' (spw IDs with the center frequencies in range 30-45GHz; all
                spw='0:5~61' (spw ID 0; channels 5 to 61; all channels)
                spw='3:10~20;50~60' (select multiple channel ranges within spw ID 3)
                spw='3:10~20,4:0~30' (select different channel ranges for spw IDs 3 and 4)
                spw='1~4;6:15~48' (for channels 15 through 48 for spw IDs 1,2,3,4 and 6)
       this selection is in addition to the other selections to data
timerange -- select data by time range
        default: '' (use all)
        example: timerange = 'YYYY/MM/DD/hh:mm:ss'
                Note: YYYY/MM/DD can be dropped as needed:
                timerange='09:14:00~09:54:00' # this time range
                timerange='09:44:00' # data within one integration of time
                timerange='>10:24:00' # data after this time
                timerange='09:44:00+00:13:00' #data 13 minutes after time
       this selection is in addition to the other selections to data
scan -- select data by scan numbers
       default: '' (use all scans)
        example: scan='21~23' (scan IDs 21,22,23)
```

```
this selection is in addition to the other selections to data
pol -- select data by polarization IDs
       default: '' (use all polarizations)
        example: pol='0,1' (polarization IDs 0,1)
        this selection is in addition to the other selections to data
intent -- select data by observational intent, also referred to as 'scan intent'
       default: '' (use all scan intents)
        example: intent='*0N_SOURCE*' (any valid scan-intent expression accepted by the MSSe
        this selection is in addition to the other selections to data
kernel -- type of spectral smoothing kernel
        options: 'gaussian', 'boxcar'
        default: 'gaussian' (no smoothing)
   >>>kernel expandable parameter
       kwidth -- width of spectral smoothing kernel
                options: (int) in channels
                default: 5
outfile -- name of output file
       default: '' (<infile>_bs)
overwrite -- overwrite the output file if already exists
        options: (bool) True, False
        default: False
        NOTE this parameter is ignored when outform='ASCII'
```

DESCRIPTION

Task tsdsmooth performs smoothing along spectral axis using user-specified smoothing kernel. Currently gaussian and boxcar kernels are supported.

0.1.127 uvcontsub

Requires:

Synopsis Continuum fitting and subtraction in the uv plane

Description

Inputs

vis Name of input MS. Output goes to vis + ".contsub"

(will be overwritten if already exists)

allowed: string

Default:

field Select field(s) using id(s) or name(s)

allowed: any
Default: variant

fitspw Spectral window:channel selection for fitting the contin-

uum

allowed: string

Default:

exclude chans exclude Spectral window:channel selection in fitspw for

fitting

allowed: bool Default: False

combine Data axes to combine for the continuum estimation

(none, or spw and/or scan) allowed: string

Default:

solint Continuum fit timescale (int recommended!)

allowed: any

Default: variant int Polynomial order for the fits

allowed: int
Default: 0

spw Spectral window selection for output

allowed: string

Default:

want_cont Create vis + ".cont" to hold the continuum estimate.

allowed: bool Default: False

Example

fitorder

Continuum fitting and subtraction in the uv plane:

This task estimates the continuum emission by fitting polynomials to the real and imaginary parts of the spectral windows and channels selected by fitspw. This fit represents a model of the continuum in all channels.

The fitted continuum spectrum is subtracted from all channels selected in spw, and the result (presumably only line emission) is stored in a new MS (vis + ".contsub"). If an MS with the output name already exists, it will be overwritten. It will read from the CORRECTED_DATA column of vis if it is present, or DATA if it is not. Whichever column is read is presumed to have already been calibrated.

> If want_cont is True, the continuum fit is placed in a second new MS (vis + '.cont', also overwritten if it already exists). N.B. because the continuum model is necessarily a smoothed fit, images made with it are liable to have their field of view reduced in some strange way. Images of the continuum should be made by simply excluding the line channels (and probably averaging the remaining ones) in clean.

```
Keyword arguments:
```

vis -- Name of input visibility file default: none; example: vis='ngc5921.ms'

field -- Field selection for continuum estimation and subtraction.

The estimation and subtraction is done for each selected field in turn. (Run listobs to get lists of the ID and names.)

default: field = '' means select all fields

field = 1 # will get field_id=1 (if you give it an

integer, it will retrieve the source with that index.

field = '1328+307' specifies source '1328+307'

field = '13*' will retrieve '1328+307' and any other fields beginning with '13'

fitspw -- Selection of spectral windows and channels to use in the fit for the continuum, using general spw:chan syntax.

The ranges of channels also can be specified by frequencies as in the MS selection syntax (spw ids are required but '*' can be used, see the example below).

See the note under combine.

default: '' (all)

example: fitspw='0:5~30;40~55'

--> select the ranges by channels in the spw id 0

fitspw='0:5~30;40~55,1:10~25;45~58,2'

--> select channel ranges 5-30 and 40-55 for the spw id 0, 10-25 and 45-58 for spwid 1, and use all channels for

fitspw='0:113.767~114.528GHz;114.744~115.447GHz'

--> select the ranges by frequencies in the spw id 0

fitspw='0:113.767~114.528GHz;114.744~115.447GHz,1:111.892~112.654GHz

--> select the different ranges by frequencies for the spw fitspw='*:113.767~114.528GHz;114.744~115.447GHz'

```
--> select the same frequency ranges for all the relevant :
                  >>> expandable parameter for fitspw
                    excludechans - if True, it will exclude the spws:channels specified in fitspw
                                                   for the fit
                                 default: False (use fitspw for the fit)
                                 example: fitspw='0:114.528GHz~114.744GHz'; excludechans=True
                                                    --> exclude the frequency range, 114.528GHz - 114.744GHz in the specific control of the specific contr
                 combine -- Data axes to combine for the continuum estimate.
                 It must include 'spw' if spw contains spws that are not in
                 fitspw!
                                 default: '' --> solutions will break at scan, field, and spw
                                             boundaries according to solint
                             Options: '', 'spw'', 'scan', or 'spw, scan'
                             example: combine='spw' --> form spw-merged continuum estimate
solint -- Timescale for per-baseline fit (units optional)
default (recommended): 'int' --> no time averaging, do a
                                                                                 fit for each integration and let the
                                                                                 noisy fits average out in the image.
example: solint='10s' --> average to 10s before fitting
                                                   10 or '10' --> '10s' (unitless: assumes seconds)
                                 options: 'int' --> per integration
                                                   'inf' --> per scan
                                 If solint is longer than 'int', the continuum estimate can be
                                 corrupted by time smearing!
fitorder -- Polynomial order for the fits of the continuum w.r.t.
                                         frequency. fitorders > 1 are strongly discouraged
                                         because high order polynomials have more flexibility, may
                                         absorb line emission, and tend go wild at the edges of
                                         fitspw, which is not what you want.
default: 0 (constant); example: fitorder=1
spw -- Optional per spectral window selection of channels to include
                               in the output. See the note under combine.
                               The spectral windows will be renumbered to start from 0, as in
              split.
want_cont -- Create vis + '.cont' to hold the continuum estimate.
default: 'False'; example: want_cont=True
The continuum estimate will be placed in vis + '.cont'
                 async -- Run task in a separate process (return CASA prompt)
                                 default: False; example: async=True
```

uvcontsub3-task.html

0.1.128 uvcontsub3

Requires:

Synopsis

An experimental clone of uvcontsub

Description

Inputs

vis Name of input MS. Output goes to vis + ".contsub"

allowed: string

Default:

fitspw Spectral window:channel selection for fitting the contin-

uum

allowed: string

Default:

combine Data axes to combine for the continuum estimation

 $(\mathrm{none}\ (")\ \mathrm{or}\ \mathrm{spw})$

allowed: string

Default:

fitorder Polynomial order for the fits

allowed: int Default: 0

 $\label{eq:select} \text{field}(s) \text{ using } \mathrm{id}(s) \text{ or } \mathrm{name}(s)$

allowed: any
Default: variant

spw Spectral window selection for output

allowed: string

Default:

scan Select data by scan numbers

allowed: string

Default:

intent Select data by scan intents

allowed: string

Default:

correlation Select correlations

allowed: any Default: variant

observation Select by observation ID(s)

allowed: any
Default: variant

Example

uvcontsub3 is an experimental clone of uvcontsub with the goal of taking less time and temporary disk space.

Continuum fitting and subtraction in the uv plane:

This task estimates the continuum emission by fitting polynomials to the real and imaginary parts of the spectral windows and channels selected by fitspw. This fit represents a model of the continuum in all channels.

The fitted continuum spectrum is subtracted from all channels selected in spw, and the result (presumably only line emission) is stored in a new MS (vis + ".contsub").

It will read from the CORRECTED_DATA column of vis if it is present, or DATA if it is not. Whichever column is read is presumed to have already been calibrated.

Keyword arguments:

vis -- Name of input visibility file
 default: none; example: vis='ngc5921.ms'

fitspw -- Selection of spectral windows and channels to use in the fit for the continuum, using general spw:chan syntax.

See the note under combine.

default: '' (all)

example: fitspw='0:5~30;40~55'

fitorder -- Polynomial order for the fits of the continuum w.r.t.

frequency. fitorders > 1 are strongly discouraged
because high order polynomials have more flexibility, may
absorb line emission, and tend go wild at the edges of
fitspw, which is not what you want.

default: 0 (constant); example: fitorder=1

field -- Field selection for continuum estimation and subtraction.

The estimation and subtraction is done for each selected field in turn. (Run listobs to get lists of the ID and names.) default: ''=all fields. If the field string is a non-negative integer, it is assumed to be a field index otherwise, it is assumed to be a field name field='0~2'; field ids 0,1,2 field='0,4,5~7'; field ids 0,4,5,6,7

```
field='3C286,3C295'; fields named 3C286 and 3C295
               field = '3,4C*'; field id 3, all names starting with 4C
        spw -- Select spectral windows for the output.
               default: ''=all spectral windows
               N.B. uvcontsub3 does not yet support exclusion by channels for
                    the output. Meanwhile, use split to further reduce the size
                    of the output MS if desired.
               spw='0~2,4'; spectral windows 0,1,2,4
               spw='<2'; spectral windows less than 2 (i.e. 0,1)
scan -- Scan number range
            default: ''=all
        intent -- Select by scan intent (state). Case sensitive.
            default: '' = all
            Examples:
            intent = 'CALIBRATE_ATMOSPHERE_REFERENCE'
            intent = 'calibrate_atmosphere_reference'.upper() # same as above
            # Select states that include one or both of CALIBRATE_WVR.REFERENCE
            # or OBSERVE_TARGET_ON_SOURCE.
            intent = 'CALIBRATE_WVR.REFERENCE, OBSERVE_TARGET_ON_SOURCE'
        correlation -- Select correlations, e.g. 'rr, ll' or ['XY', 'YX'].
                       default '' (all).
        observation -- Select by observation ID(s).
                       default: '' = all
```

uv model fit-task.html

0.1.129 uvmodelfit

Requires:

Synopsis

Fit a single component source model to the uv data

Description

Fit a single component source model to the uv data

Inputs

vis Name of input visibility file

allowed: string

Default:

field Select field using field id(s) or field name(s)

allowed: string

Default:

spw Select spectral window/channels

allowed: string

Default:

selectdata Other data selection parameters

allowed: bool Default: True

timerange Select data based on time range

allowed: string

Default:

uvrange Select data within uvrange (default units meters)

allowed: any Default: variant

antenna Select data based on antenna/baseline

allowed: string

Default:

scan Scan number range

allowed: string

Default:

msselect Optional complex data selection (ignore for now)

allowed: string

Default:

niter Number of fitting iterations to execute

allowed: int Default: 5

comptype component model type: P(oint), G(aussian), or D(isk)

allowed: string
Default: P

sourcepar Starting guess for component parameters (3 values for

type P, 5 for G and D) allowed: doubleArray Default: 1.0 0.0 0.0

varypar Control which parameters to let vary in the fit

allowed: boolArray

Default:

outfile Optional output component list table

allowed: string

Default:

Example

```
are available: P=point; G=Gaussian; D=Disk. Fitting parameters can
        be held fixed.
                         The results are given in the log and placed in a
        components file.
Keyword arguments:
vis -- Name of input visibility file
default: none; example: vis='ngc5921.ms'
--- Data Selection
       field -- Select data based on field id(s) or name(s)
                default: '' (all); example: field='1'
                field='0~2' # field ids inclusive from 0 to 2
                field='3C*' # all field names starting with 3C
        spw -- Select data based on spectral window
                default: '' (all); example: spw='1'
                spw='<2' #spectral windows less than 2
                spw='>1' #spectral windows greater than 1
selectdata -- Select a subset of the visibility using MSSelection
                default: False; example: selectdata=True
        timerange -- Select data based on time range:
                default = '' (all); example,
                timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
                Note: YYYY/MM/DD can be dropped as needed:
                timerange='09:14:0~09:54:0' # this time range
                timerange='09:44:00' # data within one integration of time
                timerange='>10:24:00' # data after this time
                timerange='09:44:00+00:13:00' #data 13 minutes after time
        uvrange -- Select data within uvrange (default units kilo-lambda)
               default: '' (all); example:
               uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lamgda
               uvrange='>4klambda';uvranges greater than 4 kilo lambda
               uvrange='0~1000km'; uvrange in kilometers
        antenna -- Select data based on antenna/baseline
                default: '' (all); example: antenna='5&6' baseline 5-6
                antenna='5\&6:7\&8' #baseline 5-6 and 7-8
                antenna='5' # all baselines with antenna 5
                antenna='5,6' # all baselines with antennas 5 and 6
        scan -- Select data based on scan number - New, under developement
                default: '' (all); example: scan='>3'
        msselect -- Optional data selection (field,spw,time,etc)
```

Fit a single component source model to the uv data. Three models

```
default:'' means select all; example:msselect='FIELD_ID==0',
msselect='FIELD_ID IN [0,1,2]' means select fields 0,1 and 2
msselect='FIELD_ID <= 1 means select fields 0, 1</pre>
                msselect='FIELD_ID==0 && ANTENNA1 IN [0] && ANTENNA2 IN [2:26]'
   means select field 0 and antennas 0 to 26, except antenna 1.
                Other msselect fields are: 'DATA_DESC_ID', 'SPECTRAL_WINDOW_ID',
'POLARIZATION_ID', 'SCAN_NUMBER', 'TIME', 'UVW'
See ccokbook for more details
niter -- Number of fitting iterations to execute
default: 5; example: niter=20
comptype -- component model type
default: 'P';
Options: 'P' (point source), 'G' (elliptical gaussian),
         'D' (elliptical disk)
sourcepar -- Starting guess for component parameters
default: [1,0,0]; (for comptype='P')
IF comptype = 'P' then
  sourcepar = [flux,xoff,yoff] where
    flux = Jy, xoff = offset east (arcsec), yoff = offset north (arcsec).
IF comptype = 'G' or 'D', then
  sourcepar = [flux,xoff,yoff,majax,axrat,pos] where
    majax = FWHM along the major axis (arcsec), axrat < 1 is
                    the ratio of minor to major axis, pos=angle in deg
varypar -- Control which parameters to let vary in the fit
default: [] (all vary);
example: vary=[F,T,T]
        examples:
     fit a point:
        comptype = 'P'
sourcepar = [0.4, 0.2, -0.3];
varypar = [T,T,T]
     fit a circular Gaussian:
comptype = 'G'
sourcepar = [1.4,0.3,-0.2,0.3, 1, 0]
        = [ T , T , T , T , F, F]
varypar
outfile -- Optional output component list table
default: ''; example: outfile='componentlist.cl'
```

uvsub-task.html

0.1.130 uvsub

Requires:

Synopsis

Subtract/add model from/to the corrected visibility data.

Description

This function subtracts model visibility data (MODEL_DATA column) from corrected visibility data (CORRECTED_DATA column) leaving the residuals in the corrected data column. If the parameter 'reverse' is set true, the process is reversed. Note the DATA column is left untouched. If the ms has no CORRECTED _DATA column, one is made, copying DATA column, ahead of doing the uvsub process

Arguments

Inputs	
vis	Name of input visibility file (MS)
	allowed: string
	Default:
reverse	reverse the operation (add rather than subtract)
	allowed: bool
	Default: False

Returns

void

Example

Help for uvsub task

This function subtracts model visibility data from corrected visibility

data leaving the residuals in the corrected data column. If the parameter 'reverse' is set true, the process is reversed.

Please note the model visibility used is the one that has been saved in the MODEL_DATA of the CORRECTED_DATA column is the one that is modified. If no CORRECTED_DATA column exists in the a copy of the DATA column is saved in it before the uvsub operation selected is performed.

Keyword arguments:

vis -- Name of input visibility file (MS)

default: none; example: vis='ngc5921.ms'

reverse -- Reverse the operation (add rather than subtract)

default: False; example: reverse=true

uvsub(vis='ngc5921.ms', reverse=False)

viewer-task.html

0.1.131 viewer

Requires:

Synopsis

View an image or visibility data set

Description

The viewer will display images in raster, contour, vector or marker form. Images can be blinked, and movies are available for spectral-line image cubes. For measurement sets, many display and editing options are available. The viewer can be run outside of casapy by typing ¡casaviewer¿. Executing viewer ¡viewer¿ will bring up a display panel window, which can be resized. If no data file was specified, a Load Data window will also appear. Click on the desired data file and choose the display type; the rendered data should appear on the display panel.

A Data Display Options window will also appear. It has drop-down subsections for related options, most of which are self-explanatory. The state of the viewer – loaded data and related display options – can be saved in a 'restore' file for later use. You can provide the restore filename on the command line or select it from the Load Data window. See the cookbook for more details on using the viewer.

Inputs infile (Optional) Name of file to visualize. allowed: string Default: displaytype (Optional) Type of visual rendering (raster, contour, vector or marker). lel if an lel expression is given for infile (advanced). allowed: string Default: raster channel (Optional) access a specific channel in the image cube allowed: int Default: 0 (Optional) zoom in/out by increments zoom allowed: Default: outfile (Optional) name of the output file to generate allowed: string Default: outscale (Optional) amount to scale output bitmap formats (non-PS, non-PDF) allowed: double Default: 1.0 (Optional) output DPI for PS/PDF outdpi allowed: int Default: outformat (Optional) format of the output e.g. jpg or pdf (this is

overridden by the output files extension allowed: string

Default: jpg

outlandscape (Optional) should the output mode be landscape (PS or

PDF)

allowed: bool Default: False

gui (Optional) Display the panel in a GUI.

allowed: bool Default: True

Returns

void

Example

```
examples of usage:
viewer
viewer "myimage.im"
viewer "mymeasurementset.ms"
viewer "myrestorefile.rstr"
viewer "myimage.im", "contour"
viewer "'myimage1.im' - 2 * 'myimage2.im'", "lel"
Keyword arguments:
infile -- Name of file to visualize
default: ''
example: infile='ngc5921.image'
If no infile is specified the Load Data window
will appear for selecting data.
displaytype -- (optional): method of rendering data
visually (raster, contour, vector or marker).
You can also set this parameter to 'lel' and
provide an lel expression for infile (advanced).
default: 'raster'
example: displaytype='contour'
Note: the filetype parameter is optional; typing of
data files is now inferred:
        example: viewer infile='my.im'
obsolete: viewer infile='my.im', filetype='raster'
        the filetype is still used to load contours, etc.
```

wvrgcal-task.html

0.1.132 wvrgcal

Requires:

Synopsis

Generate a gain table based on Water Vapour Radiometer data

Description

Information about the observation and the performance of WVRGCAL is written to the CASA logger and also returned in a dictionary; see the CASA cookbook for a more detailed description of these parameters. The dictionary element 'success' is True if no errors occurred.

Of particular note is the discrepancy parameter (Disc): high values (¿ a few hundred microns) may indicate some levels of cloud contamination and the effect of applying the WVRGCAL correction should be checked; values ¿ 1000 um in all antennas have currently been found to indicate that WVRGCAL correction should not be used.

vis – Name of input visibility file default: none; example: vis='ngc5921.ms' caltable – Name of output gain calibration table default: none; example: caltable='ngc5921.wvr'

toffset – Time offset (sec) between interferometric and WVR data default: 0 (ALMA default for cycle 1, for cycle 0, i.e. up to Jan 2013 it was -1) segsource – Do a new coefficient calculation for each source default: True tie – Prioritise tieing the phase of these sources as well as possible (requires segsource=True) default: [] example: ['3C273,NGC253', 'IC433,3C279'] sourceflag – Flag the WVR data for these source(s) as bad and do not produce corrections for it (requires segsource=True) default: [] (none) example: ['3C273']

nsol – Number of solutions for phase correction coefficients during this observation. By default only one set of coefficients is generated for the entire observation. If more sets are requested, then they will be evenly distributed in time throughout the observation. Values ¿ 1 require segsource=False. default: 1

disperse – Apply correction for dispersion default: False wvrflag – Regard the WVR data for these antenna(s) as bad and use interpolated values instead default: [] (none) example: ['DV03','DA05','PM02'] statfield – Compute the statistics (Phase RMS, Disc) on this field only default: " (all)

statsource – Compute the statistics (Phase RMS, Disc) on this source only default: " (all)

smooth – Smooth the calibration solution on the given timescale default: " (no smoothing), example: '3s' smooth on a timescale of 3 seconds scale – Scale the entire phase correction by this factor default: 1. (no scaling) spw – List of the spectral window IDs for which solutions should be saved into the caltable default: [] (all spectral windows), example [17,19,21,23] wvrspw - List of the spectral window IDs from which the WVR data should be taken default: [] (all WVR spectral windows), example [0] reversespw – Reverse the sign of the correction for the listed SPWs (only neede for early ALMA data before Cycle 0) default: " (none), example: reversespw=' $0\sim2.4$ '; spectral windows 0.1.2.4cont – Estimate the continuum (e.g., due to clouds) default: False maxdistm – maximum distance (m) an antenna may have to be considered for being part of the antenna set (minnuments to 3 antennas) for the interpolation of a solution for a flagged antenna default: 500. minnumants – minimum number of near antennas required for interpolation default: 2 mingoodfrac – If the fraction of unflagged data for an antenna is below this value (0. to 1.), the antenna is flagged. default: 0.8 usefieldtab – derive the antenna AZ/EL values from the FIELD rather than the POINTING table default: False refant – use the WVR data from this antenna for calculating the dT/dL parameters (can give ranked list) default: " (use the first good or interpolatable antenna), examples: 'DA45' - use DA45 ['DA45', 'DV51'] - use DA45 and if that is not good, use DV51 instead offsetstable – (experimental) subtract the temperature offsets in this table from the WVR measurements before using them to calculate the phase corrections default: " (do not apply any offsets) examples: 'uid__A002_Xabd867_X2277.cloud_offsets' use the given table

Inputs

vis Name of input visibility file

allowed: string

Default:

caltable Name of output gain calibration table

allowed: string

Default:

toffset Time offset (sec) between interferometric and WVR data

allowed: double

Default: 0

segsource Do a new coefficient calculation for each source

allowed: bool Default: True

sourceflag Regard the WVR data for these source(s) as bad and do

not produce corrections for it (requires segsource=True)

allowed: stringArray

Default:

tie Prioritise tieing the phase of these sources as well as

possible (requires segsource=True)

allowed: stringArray

Default:

nsol Number of solutions for phase correction coefficients

(nsol>1 requires segsource=False)

allowed: int Default: 1

disperse Apply correction for dispersion

allowed: bool Default: False

wvrflag Regard the WVR data for these antenna(s) as bad and

replace its data with interpolated values from neighbour-

ing antennas

allowed: stringArray

Default:

statfield Compute the statistics (Phase RMS, Disc) on this field

only

allowed: string

Default:

statsource Compute the statistics (Phase RMS, Disc) on this source

only

allowed: string

Default:

smooth Smooth calibration solution on the given timescale

allowed: string

Default:

scale Scale the entire phase correction by this factor

allowed: double Default: 1.

spw List of the spectral window IDs for which solutions

should be saved into the caltable

allowed: intArray

Default:

wvrspw List of the spectral window IDs from which the WVR

data should be taken allowed: intArray

Default:

reversespw Reverse the sign of the correction for the listed SPWs

${\bf Returns}$

variant

Example

 virtual concat-task.html

0.1.133 virtualconcat

Requires:

Synopsis

Concatenate several visibility data sets into a multi-MS

Inputs						
vis	List of names of input visibility files to be concatenated					
	allowed: stringArray					
	Default:					
concatvis	Name of the output visibility file (a multi-MS)					
	allowed: string					
	Default:					
freqtol	Frequency shift tolerance for considering data as the same spwid					
	allowed: any					
	Default: variant					
dirtol	Direction shift tolerance for considering data as the same field					
	allowed: any					
	Default: variant					
respectname	If true, fields with a different name are not merged even					
	if their direction agrees					
	allowed: bool					
	Default: True					
visweightscale	List of the weight scaling factors to be applied to the					
	individual MSs					
	allowed: doubleArray					
	Default:					
keepcopy	If true, a copy of the input MSs is kept in their original					
	place.					
	allowed: bool					
	Default: False					
copypointing	If true, keep the POINTING table information in the					
	output MMS. If false, don't. allowed: bool					
	anowed: bool Default: True					
	Default: 11 ue					

Example

The list of data sets given in the vis argument are moved into an output multi-MS data set concatvis and virtually concatenated.

NOTE: This task will modify the input datasets by moving them and reindexing them. If you want to keep a copy of your original data, please set the parameter keepcopy to True.

There is no limit to the number of input data sets.

If none of the input data sets have any scratch columns (model and corrected columns), none are created in the concatvis. Otherwise these columns are created on output and initialized to their default value (1 in model column, data in corrected column) for those data with no input columns.

Spectral windows for each data set with the same chanelization, and within a specified frequency tolerance of another data set will be combined into one spectral window.

A field position in one data set that is within a specified direction tolerance of another field position in any other data set will be combined into one field. The field names need not be the same---only their position is used.

Each appended dataset is assigned a new observation id if the corresponding rows in the observation table are not the same.

```
Keyword arguments:
```

other examples:

```
virtualconcat(vis=['src2.ms','ngc5921.ms'], concatvis='out.mms')
    will concatenate 'ngc5921.ms' and 'src2.ms' into a file named
    'out.mms'; the original 'ngc5921.ms' and 'src2.ms' are gone.
    'out.mms' is a multims. As most of the data is only moved, not
```

copied, this is faster and subsequent tasks can run in parallel on the subMSs of $\operatorname{out.mms}$.

virtualconcat(vis=['src2.ms','ngc5921.ms'], concatvis='out.mms', keepcopy=True)
 will concatenate 'ngc5921.ms' and 'src2.ms' into a file named
 'out.mms'; the original 'ngc5921.ms' and 'src2.ms' are as before
 but you consume more disk space and time for the copy.

Note: run flagmanager to save flags in the concatvis

freqtol -- Frequency shift tolerance for considering data to be in the same spwid. The number of channels must also be the same.

default: '' do not combine unless frequencies are equal

example: freqtol='10MHz' will not combine spwid unless they are within 10 MHz.

Note: This option is useful to combine spectral windows with very slight frequency differences caused by Doppler tracking, for example.

dirtol -- Direction shift tolerance for considering data as the same field default: '' means always combine.

example: dirtol='1.arcsec' will not combine data for a field unless their phase center differ by less than 1 arcsec. If the field names are different in the input data sets, the name in the output data set will be the first relevant data set in the list.

respectname -- If true, fields with a different name are not merged even if their direction agrees (within dirtol).

default: True

visweightscale -- The weights of the individual MSs will be scaled in the concatenated output MS by the factors in this list. Useful for handling heterogeneous arrays. Use plotms to inspect the "Wt" column as a reference for determining the scaling factors. See the cookbook for more details.

example: [1.,3.,3.] - scale the weights of the second and third MS by a factor 3. default: [] (empty list) - no scaling

copypointing -- If true, the POINTING table information will be present in the output.

If false, the result is an empty POINTING table.

default: true

vishead-task.html

0.1.134 vishead

Requires:

Synopsis

List, summary, get, and put metadata in a measurement set

Description

List, summary, get, and put "header" information in a measurement set.

Arguments

Inputs								
vis	Name of input visibility file							
	allowed: string							
	Default:							
mode	options: list, summary, get, put							
	allowed: string							
	Default: summary							
listitems	items to list ([] for all)							
	allowed: stringArray							
	Default: telescope observer project field							
	freq_group_name spw_name sched-							
	ule schedule_type release_date							
hdkey	keyword to get/put							
V	allowed: string							
	Default:							
hdindex	keyword index to get/put, counting from zero. "==>all							
	allowed: string							
	Default:							
hdvalue	value of hdkey							
	allowed: any							
	Default: variant							

Example

This task allows the user to manipulate some meta-data parameters in a measurement set. The mode='list' shows those keywords that are presently implemented, with their values. The contents associated with the keywords can be obtained (get) and changed (put).

The modes that are available are:

Parameters currently implemented are (June 1, 2009):

```
cal_grp
field
                      Field names
                      Field Observing codes
fld_code
freq_group_name
log
                      Observer name
observer
project
                      Project name
                      Phase tracking centers for each field
ptcs
release_date
schedule
schedule_type
                      Spectral parameters?
spw_name
                      Source Names (=Field Names?)
source_name
telescope
                      Telescope Name
```

Keyword arguments:

```
ex: hdindex='2'; hdindex=''->put/get full array;
          --- value to be put in the MS (used in put mode only)
hdvalue
          ex: hdvalue=array(['MyTelescope'])
Examples:
   To transfer the parameters to useful python items requires some care.
   taskname = 'vishead'
   default()
   vis = '3C84C.ms'
   mode = 'get'
   to get a field name (string),
      hdkey = 'field'; hdindex = '2'; hdvalue=vishead();
               print hdvalue[0] = the name for field='2'
   to get an phase center (number)
      hdkey = 'ptcs'; hdindex = '1'; hdvalue = vishead();
               hdvalue[0][0] gives the ra, hdvalue[0][1] gives the dec in field '1'
   taskname = 'vishead'
   default()
   vis = '3C84C.ms'
   mode = 'put'
  To change a string,
      hdkey = 'field'; hdindex = '2'; hdvalue = 'junk'; vishead()
           field='2' is renamed 'junk'
  To change a number, (egs. ra of field=1 to 0.5 radian)
      is too complicated to figure out!
```

visstat-task.html

0.1.135visstat

Requires:

 ${\bf Synopsis}$ Displays statistical information from a Measurement Set, or from a Multi-MS

Outputs xstat Statistical information for the selected measurement set allowed: any Default: variant Inputs Name of Measurement Set or Multi-MS vis allowed: string Default: axis Which values to use allowed: string Default: amplitude datacolumn Which data column to use (data, corrected, model) allowed: string Default: data useflags Take flagging into account? allowed: bool Default: True spectral-window/frequency/channel spwallowed: string Default: field "==>all,Field names or field index numbers: $field='0\sim2,3C286'$ allowed: Default: selectdata More data selection parameters (antenna, timerange etc) allowed: bool Default: True antenna/baselines: "==>all, antenna = '3,VA04' antenna allowed: string Default: uvrange uv range: "==>all; uvrange = '0~100klambda', default units=meters allowed: string Default: timerange time range: "==>all, timerange='09:14:0 \sim 09:54:0' allowed: string Default: correlation Select data based on correlation allowed: string Default: scan numbers: "==>all scan allowed: string Default:

(sub)array numbers: "==>all

string

observation ID number(s): " = all

69Y

variant

allowed:

Default:

allowed:

Default:

array

observation

Returns

void

Example

This task returns statistical information about data in a Measurement Set or Multi-MS.

The following values are computed: mean value, sum of values, sum of squared values, median, median absolute deviation, quartile, minimum, maximum, variance, standard deviation, and root mean square.

The following axes are supported: uvw, flag, weight, sigma, antenna1, antenna2, feed1, feed2, field_id, array_id, data_desc_id, flag_row, interval, scan, scan_number, time, weight_spectrum, amp, amplitude, phase, real, imag, imaginary, and uvrange.

Optionally, the statistical information can be computed based only on a given subset of the measurement set.

Note: If the MS consists of inhomogeneous data, for example several spectral windows each having a different number of channels, it may be necessary to use selection parameters to select a homogeneous subset of the MS, e.g. spw='2'.

Keyword arguments:

axis -- Which data to analyze.

default: 'amplitude'
axis='phase'
axis='imag'
axis='scan_number'
axis='flag'

The phase of a complex number is in radians in the range [-pi; pi[.

```
datacolumn -- Which data column to use for complex data.
       default: 'data'
       datacolumn='data'
       datacolumn='corrected'
       datacolumn='model'
useflags -- Take MS flags into account?
       default: True
       useflag=False
       useflag=True
If useflags=False, flagged values are included in the statistics.
If useflags=True, any flagged values are not used in the statistics.
spw -- Select data based on spectral window and channels
       default: '' (all); example: spw='1'
       spw='<2' #spectral windows less than 2
       spw='>1' #spectral windows greater than 1
       spw='0:0~10' # first 10 channels from spw 0
       spw='0:0~5;56~60' # multiple separated channel chunks.
field -- Select data based on field id(s) or name(s)
       default: '' (all); example: field='1'
       field='0~2' # field ids inclusive from 0 to 2
       field='3C*' # all field names starting with 3C
selectdata -- Other data selection parameters
       default: True
antenna -- Select data based on baseline
       default: '' (all); example: antenna='5&6' baseline 5-6
       antenna='5\&6;7\&8' #baseline 5-6 and 7-8
       antenna='5' # all baselines with antenna 5
       antenna='5,6' # all baselines with antennas 5 and 6
correlation -- Correlation types
       default: '' (all);
       example: correlation='RR LL'
uvrange -- Select data within uvrange (default units meters)
       default: '' (all); example:
       uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
       uvrange='>4klambda';uvranges greater than 4 kilo-lambda
       uvrange='0~1000km'; uvrange in kilometers
timerange -- Select data based on time range:
       default = '' (all); example,
       timerange = 'YYYY/MM/DD/hh:mm:ss"YYYY/MM/DD/hh:mm:ss'
       Note: YYYY/MM/DD can be dropped as needed:
       timerange='09:14:0~09:54:0' # this time range
       timerange='09:44:00' # data within one integration of time
```

timerange='>10:24:00' # data after this time
 timerange='09:44:00+00:13:00' #data 13 minutes after time
scan -- Select data based on scan number
 default: '' (all); example: scan='>3'
array -- Selection based on the antenna array
observation -- Selection by observation ID(s).
 default: '' (all); example: observation='1~3'

visstat 2-task.html

0.1.136visstat2

Requires:

 ${\bf Synopsis}$ Displays statistical information from a Measurement Set, or from a Multi-MS

Outputs xstatStatistical information for the selected measurement set allowed: any Default: variant Inputs Name of Measurement Set or Multi-MS vis allowed: string Default: axis Which values to use allowed: string Default: amplitude datacolumn Which data column to use (data, corrected, model, float_data) allowed: string Default: data useflags Take flagging into account? allowed: bool Default: True spectral-window/frequency/channel spw allowed: string Default: field Field names or field index numbers: "==>all, $field='0\sim2.3C286'$ allowed: string Default: selectdata More data selection parameters (antenna, timerange etc) allowed: bool True Default: antenna antenna/baselines: "==>all, antenna = '3,VA04' allowed: string Default: uv range: "==>all; uvrange = '0~100klambda', default uvrange units=meters allowed: string Default: time range: "==>all, timerange='09:14:0 \sim 09:54:0' timerange allowed: string Default: correlation Select data based on correlation allowed: string Default: scan numbers: "==>all scan allowed: string Default: (sub)array numbers: "==>all array allowed: string Default: observation ID number(s): " = all observation allowed: any Default: variant

Average data in time.

bool

False

allowed:

Default:

timebin Bin width for time averaging. allowed: string

timeaverage

Returns

void

Example

This task returns statistical information about data in a Measurement Set or Multi-MS.

The following values are computed: mean value, sum of values, sum of squared values, median, median absolute deviation, quartile, minimum, maximum, variance, standard deviation, and root mean square.

The following axes are supported: uvw, flag, weight, sigma, antenna1, antenna2, feed1, feed2, field_id, array_id, data_desc_id, flag_row, interval, scan, scan_number, time, weight_spectrum, amp, amplitude, phase, real, imag, imaginary, and uvrange.

Optionally, the statistical information can be computed based only on a given subset of the measurement set.

Note: If the MS consists of inhomogeneous data, for example several spectral windows each having a different number of channels, it may be necessary to use selection parameters to select a homogeneous subset of the MS, e.g. spw='2'.

Keyword arguments:

```
vis --- Name of input Measurement Set or Multi-MS
default: '', example: vis='my.ms'
```

axis -- Which data to analyze.

default: 'amplitude'
axis='phase'
axis='imag'
axis='scan_number'
axis='flag'

The phase of a complex number is in radians in the range [-pi; pi[.

```
datacolumn -- Which data column to use for complex data.
default: 'data'
datacolumn='data'
datacolumn='corrected'
datacolumn='model'
datacolumn='float_data'
useflags -- Take MS flags into account?
default: True
useflag=False
useflag=True
If useflags=False, flagged values are included in the statistics.
If useflags=True, any flagged values are not used in the statistics.
spw -- Select data based on spectral window and channels
default: '' (all); example: spw='1'
spw='<2' #spectral windows less than 2
spw='>1' #spectral windows greater than 1
spw='0:0~10' # first 10 channels from spw 0
spw='0:0~5;56~60' # multiple separated channel chunks.
field -- Select data based on field id(s) or name(s)
default: '' (all); example: field='1'
field='0~2' # field ids inclusive from 0 to 2
field='3C*' # all field names starting with 3C
selectdata -- Other data selection parameters
default: True
antenna -- Select data based on baseline
default: '' (all); example: antenna='5&6' baseline 5-6
antenna='5\&6;7\&8' #baseline 5-6 and 7-8
antenna='5' # all baselines with antenna 5
antenna='5,6' # all baselines with antennas 5 and 6
correlation -- Correlation types
default: '' (all);
example: correlation='RR LL'
uvrange -- Select data within uvrange (default units meters)
default: '' (all); example:
uvrange='0~1000klambda'; uvrange from 0-1000 kilo-lambda
uvrange='>4klambda';uvranges greater than 4 kilo-lambda
uvrange='0~1000km'; uvrange in kilometers
timerange -- Select data based on time range:
default = '' (all); example,
timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
Note: YYYY/MM/DD can be dropped as needed:
timerange='09:14:0~09:54:0' # this time range
```

timerange='09:44:00' # data within one integration of time timerange='>10:24:00' # data after this time timerange='09:44:00+00:13:00' #data 13 minutes after time scan -- Select data based on scan number default: '' (all); example: scan='>3' array -- Selection based on the antenna array observation -- Selection by observation ID(s). default: '' (all); example: observation='1~3'

--- Time averaging parameters ---

timeaverage -- Average data in time. Flagged data will be included in the average calculation, unless the parameter keepflags is set to False. In this case only partially flagged rows will be used in the average.

WEIGHT_SPECTRUM/SIGMA_SPECTRUM will be used (if present) in addition to the flags to compute a weighted average. The calculation is done in the same way as for the channel average case but across the time axis.

Otherwise (if WEIGHT_SPECTRUM/SIGMA_SPECTRUM are not present)

mstransform will use WEIGH/SIGMA instead, as in split.

default: False

timebin -- Bin width for time averaging.
default: 'Os'

timespan -- Let the timebin span across scan, state or both. State is equivalent to sub-scans. One scan may have several state ids. For ALMA MSs, the sub-scans are limited to about 30s duration each. In these cases, the task will automatically add state to the timespan parameter. To see the number of states in an MS, use the msmd tool. See help msmd.

default: '' (separate time bins by both of the above)
options: 'scan', 'state', 'state,scan'

examples:

timespan = 'scan'; can be useful when the scan number goes up with each integration as in many WSRT MSs. timespan = ['scan', 'state']: disregard scan and state numbers when time averaging. timespan = 'state,scan'; same as above.

maxuvwdistance -- Provide a maximum separation of start-to-end baselines that can be included in an average. (int) default: 0.0 (given in meters)

widebandpbcor-task.html

0.1.137 widebandpbcor

Requires:

Synopsis

Wideband PB-correction on the output of the MS-MFS algorithm

Description

WideBand Primary-beam correction. It computes a set of PBs at the specified frequencies, calculates Taylor-coefficient images that represent the PB spectrum, performs a polynomial division to PB-correct the output Taylor-coefficient images from clean(nterms¿1), and recompute spectral index (and curvature) using the PB-corrected Taylor-coefficient images

Inputs
vis Name of measurement set.

allowed: string

Default:

imagename Name-prefix of multi-termimages to operate on.

allowed: string

Default:

nterms Number of taylor terms to use

allowed: int Default: 2

threshold Intensity above which to re-calculate spectral index

allowed: string

Default:

action PB-correction (pbcor) or only calc spectral-index (cal-

calpha)

allowed: string Default: pbcor

reffreq Reference frequency (if specified in clean)

allowed: string

Default:

pbmin PB threshold below which to not correct

allowed: double Default: 0.2

field Fields to include in the PB calculation

allowed: string

Default:

spwlist List of N spw ids

allowed: intArray

Default:

chanlist List of N channel ids

allowed: intArray

Default:

weightlist List of N weights (relative)

allowed: doubleArray

Default:

Returns

void

Example

Wide-band Primary-beam correction

- (1) Compute a set of Primary Beams at the specified frequencies
- (2) Calculate Taylor-coefficient images that represent the PB spectrum
- (3) Perform a polynomial division to PB-correct the output Taylor-coefficient images from the MS-MFS algorithm (clean(nterms>1))
- images from the MS-MFS algorithm (clean(nterms>1))
 (4) Recompute spectral index (and curvature) using the corrected Taylor-coefficient images from the MS-MFS algorithm (clean(nterms>1))
- [Optionally, skip PB-correction, and only recalculate spectral index with a different threshold]

This is a temporary task, meant for use until projection-based gridding algorithms are available via the 'clean' task.

An output directory named imagename.pbcor.workdirectory is created, and filled with an image-cube of the evaluated primary beams at all specified frequencies, Taylor-coefficients, and a 'spectral index' due to the primary beam.

Note that for the actual pb-correction, only the Taylor-coefficient images are used.

Task parameters :

imagename -- Pre-name of input and output images. Same as in the clean task.

example : imagename = 'run1'

Restored-images (run1.image.tt0,etc) and residual images (run1.residual.tt0 must be available on disk.

nterms -- Number of Taylor terms to be used to model the frequency-dependence of the primary beam.

example : nterms = 2

nterms must be less than or equal to the number of frequencies specified via spwlist, chanlist and weightlist.

nterms=1 will do a standard division by the average PB computed over all specified frequencies.

threshold -- Flux level in the restored intensity map, below which to not recalculate spectral index.

example : threshold = '0.1Jy'

action -- Choice of PB-correction with spectral-index recalculation or only spectral-index recalculation (using the specified threshold) example : action='pbcor' or action='calcalpha'

With action='pbcor', the following output images are created/overwritten.

- imagename.pbcor.workdirectory : This directory contains an image cube with PBs at the list of specified frequencies, and Taylor-coefficient images that describe the PB spectrum.
 - imagename.pb.cube : Concatenated cube of PBs
 - imagename.pb.tt0, tt1, ...: Taylor coefficients describing the PB spe
 - imagename.pb.alpha: Spectral index of the PB (for information only)
- imagename.image.pbcor.tt0,tt1,... : Corrected Taylor coefficients
- imagename.pbcor.image.alpha : Corrected Spectral Index
- imagename.pbcor.image.alpha.error : New error map.

With action='calcalpha', the following output images are created/overwritten

- imagename.image.alpha : Corrected Spectral Index
- imagename.image.alpha.error : New error map.

 $\hbox{reffreq $\hbox{--}$ Reference frequency about which the Taylor-expansion is defined.}$

example : reffreq = '1.5GHz'

If left unspecified, it is picked from the input restored image.

Note: If reffreq was specified during task clean to produce the images it must be specified here.

example : pbmin = 0.1

field -- Field selection for the Primary Beam calculation.

example : field = '3C291'

This field selection must be identical to that used in 'clean'

spwlist -- List of SPW ids for which to make separate Primary Beams chanlist -- List of channel ids, within the above SPW ids, at which to make PBs.

example : spwlist=[0,1,2], chanlist=[32,32,32]

Make PBs at frequencies corresponding to channel 32 of

spws 0,1 and 2.

example : spwlist=[0,0,0], chanlist=[0,10,20]

Make PBs at frequencies corresponding to channels 0,10,20

of spw 0

Primary beams are computed at these specified frequencies and for pointings selected by 'field'. Taylor-coefficients that represent

the PB spectrum are computed from these images.

makes a difference only with very lop-sided weights.

The first frequency had less usable data due to flagged RFS but the other two had relatively equal weight.

These weights are applied to the PB spectrum while computing PB Taylor-coefficients. Setting weights to anything other than 1.0

widefield-task.html

0.1.138 widefield

Requires:

Synopsis

Wide-field imaging and deconvolution with selected algorithm

Description

This is the main wide-field imaging/deconvolution task. It uses the wprojection method for a large field of view, can make many facets, and can include outlier fields. Several deconvolution algorithms are supported. Interactive cleaning is also supported

Inputs

vis name of input visibility file

allowed: stringArray

Default:

imagename Pre-name of output images

allowed: any Default: variant

outlierfile Text file with image names, sizes, centers

allowed: string

Default:

field Field Name

allowed: string

Default:

spw Spectral windows:channels: " is all

allowed: any Default: variant

selectdata Other data selection parameters

allowed: bool Default: False

timerange Range of time to select from data

allowed: string

Default:

uvrange Select data within uvrange

allowed: string

Default:

antenna Select data based on antenna/baseline

allowed: string

Default:

scan scan number range

allowed: string

Default:

mode Type of selection (mfs, channel, velocity, frequency)

allowed: string
Default: mfs

niter Maximum number of iterations

allowed: int Default: 500

Default: 500
Loop gain for cleaning

gain Loop gain for cleaning

allowed: double Default: 0.1

threshold Flux level to stop cleaning. Must include units

allowed: any

Default: variant 0.0Jy

psfmode Algorithm to use (clark, hogbom)

allowed: string Default: 707 lark

ftmachine Gridding method for the image (wproject, ft)

allowed: string

Default:

facets Number of facets along each axis in main image only

allowed: int Default: 3

wprojplanes Number of planes to use in wprojection convolution

inction

Returns

void

Example

Wide-field imaging and deconvolution with selected algorithm:

This is the main wide-field imaging/deconvolution task. It uses the wprojection method for a large field of view, can make many facets, and can include outlier fields. Several deconvolution algorithms are supported. Interactive cleaning is also supported.

For making large images (>2000 on a size), see hints at the end of the descriptions. For making images larger than about 5000x5000, the available memory must be larger than 2 Gbytes. For such images therefore a computer with a 64-bit operating system may be needed.

```
Keyword arguments:
vis -- Name of all input visibility files
        default: none; example: vis='ngc5921.ms'
        example: vis=['data01.ms', 'data02.ms']
imagename -- Pre-name of output images:
        default: none; example: imagename='n5921'
        if outlier fields are included, then
           imagename=['n5921', 'outlier1', outlier2']
           and the first imagename is the wide-field image
        output images names are: n5921.clean, n5921.residual,
        n5921.model, n5921.interactive.mask
mode -- Type of selection
        default: 'mfs'; example: mode='channel';
        Options: 'mfs', channel, velocity, frequency'
alg -- Algorithm to use
        default: 'clark';
        Options: 'clark', 'hogbom', 'multiscale', 'entropy'
            Strongly advise 'clark'. multiscale and entropy
            well-tested.
imsize -- Image pixel size (x,y)
        default = [256,256]; example: imsize=[500,500], or imsize=500
```

```
example for multiple fields: imsize=[(1000, 1000), (100, 100)]
cell -- Cell size (x,y)
       default=['1arcsec,'1arcsec']
       example: cell=['0.5arcsec,'0.5arcsec'], or cell='0.5arcsec'
phasecenter -- direction position or the field for the image center
        A list of the above is needed for multiple-fields
       default: '' -->field='0' as center; example: phasecenter='6'
           phasecenter='J2000 19h30m00 -40d00m00'
           phasecenter=['J2000 19h30m00 -40d00m00', 'J2000 19h57m00 40d00m00']
              for wide-field, plus one outlier field.
stokes -- Stokes parameters to image
       default='I'; example: stokes='IQUV';
       Options: 'I','IV','IQU','IQUV'
niter -- Number iterations, set to zero for no CLEANing
       default: 500; example: niter=500
gain -- Loop gain for CLEANing
       default: 0.1; example: gain=0.1
threshold -- Flux level at which to stop CLEANing (units=mJy)
       default: 0.0; example: threshold=0.0
mask -- Name(s) of mask image(s) used for CLEANing
       default: '' example: mask='orion.mask'
       Number of mask fields must equal number of imaged fields
cleanbox -- List of [blc-x,blc-y,trc-x,trc-y] values
       default: []; example: cleanbox=[110,110,150,145]
       Note: This can also be a filename with clean values:
       fieldindex blc-x blc-y trc-x trc-y
       cleanbox = 'interactive' is very useful.
--- Data Selection
nchan -- Number of channels to select
       default: 1; example: nchan=45
start -- Start channel, O-relative
       default=0; example: start=5
        if mode='frequency' then a frequency value e.g start='1.4GHz'
width -- Channel width (value > 1 indicates channel averaging)
       default=1; example: width=5
        if mode='frequency' then a frequency value e.g width='10kHz'
step -- Step in channel number
       default=1; example: step=2
field -- Select field using field id(s) or field name(s).
          [run listobs to obtain the list id's or names]
       default: ''=all fields
       If field string is a non-negative integer, it is assumed a field index
         otherwise, it is assumed a field name
       field='0~2'; field ids 0,1,2
       field='0,4,5~7'; field ids 0,4,5,6,7
       field='3C286,3C295'; field named 3C286 adn 3C295
```

```
field = '3,4C*'; field id 3, all names starting with 4C
            example for multiple ms in vis parameter:
            field=['0~2', '1,2']
     spw -- Select spectral window/channels
            default: ''=all spectral windows and channels
            spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
            spw='<2'; spectral windows less than 2 (i.e. 0,1)
            spw='0:5~61'; spw 0, channels 5 to 61
            spw='0,10,3:3~45'; spw 0,10 all channels, spw 3, channels 3 to 45.
            spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
            spw='0:0^{-}10;15^{-}60'; spectral window 0 with channels 0-10,15-60
            spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
                     spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
            For multiple ms in vis parameter:
            spw=['0,10,3:3~45', '<2']
     timerange -- Select time range subset of data (not implemented yet)
         default='' meaning no time selection
         example: timerange='YYYY/MM/DD/HH:MM:SS.sss'
         timerange='< YYYY/MM/DD/HH:MM:SS.sss'</pre>
         timerange='> YYYY/MM/DD/HH:MM:SS.sss'
         timerange='ddd/HH:MM:SS.sss'
         timerange='< ddd/HH:MM:SS.sss'
         timerange='> ddd/HH:MM:SS.sss'
     restfreq -- Specify rest frequency to use for image
         default='' (i.e., try to use the restfreq specified in the visibility data)
     --- Weighting
     weighting -- Weighting to apply to visibilities
             default='natural'; example: weighting='uniform';
             Options: 'natural', 'uniform', 'briggs', 'briggsabs', 'radial', 'superuniform'
     robust -- 'briggs' and 'brigssabs' robustness parameter
             default=0.0; example: robust=0.5;
             Options: -2.0 to 2.0; -2 (uniform)/+2 (natural)
     npixels -- number of pixels to determine uv-cell size for weight calculation
              -- Used with superuniform or briggs weighting schemes
               example: npixels=3
     --- widefield controls
     ftmachine -- Gridding method for the image;
             ft (standard interferometric gridding).
             wproject (wprojection algorithm for gridding)
             default: wproject
     wprojplanes -- Number w-projection planes to use for gridding
             default: 256
             example: wprojplanes=64
Good value = BMAX(klambda) * Map width(arcmin)^2 / 600
```

```
facets -- Number of facets along one axis on central image
                image is divided in facets x facets rectangles.
                default: 1
                example: facets=3 makes 3x3 images to cover the field
if ftmachine = 'ft', only faceting is used
                if ftmachine = 'wproject', both wplanes and faceting
                         can be used (see below).
        cyclefactor -- Change the threshold at which the deconvolution cycle will
                stop and degrid and subtract from the visibilities. For bad PSFs,
                reconcile often (cyclefactor=4 or 5); For good PSFs, use
                cyclefactor 1.5 to 2.0.
                default: 2.5; example: cyclefactor=4, but decreases speed considerably.
                <cycle threshold = cyclefactor * max sidelobe * max residual>
        cyclespeedup -- Cycle threshold doubles in this number of iterations
                default: -1; example: cyclespeedup=500
        --- MEM parameters (Experimental, not well-tested)
        sigma -- Target image sigma
                default: '0.001Jy'; example: sigma='0.1Jy'
        targetflux -- Target flux for final image
                default: '1.0Jy'; example: targetflux='200Jy'
        constrainflux -- Constrain image to match target flux;
                otherwise, targetflux is used to initialize model only.
                default: False; example: constrainflux=True
        prior -- Name of MEM prior images
                default: ['']; example: prior='source_mem.image'
        --- Multi-scale parameters (Experimental, not well-tested)
        negcomponent -- Stop component search when the largest scale has found this
                number of negative components; -1 means continue component search
                even if the largest component is negative.
                default: 2; example: negcomponent=-1
        scales -- Used for alg='multiscale'; set a number of scales or a vector
                default: [0,3,10]; example: scales=[0.0,3.0,10.0, 30]
        -- interactive masking
        npercycle -- when cleanbox is set to 'interactive',
           this is the number of iterations between each clean to update mask
           interactively. However, this number can be adjusted during execution.
uvtaper -- Apply additional uv tapering of the visibilities.
               default: uvtaper=False; example: uvtaper=True
                  uvtaper=True expandable parameters
                     outertaper -- uv-taper on outer baselines in uv-plane
                           [bmaj, bmin, bpa] taper Gaussian scale in uv or
```

angular units. NOTE: uv taper in (klambda) is

roughly on-sky FWHM(arcsec/200)

default: outertaper=[]; no outer taper applied
 example: outertaper=['5klambda'] circular taper
 FWHM=5 kilo-lambda
 outertaper=['5klambda','3klambda','45.0deg']
 outertaper=['10arcsec'] on-sky FWHM 10"
 outertaper=['300.0'] default units are meters
 in aperture plane
innertaper -- uv-taper in center of uv-plane
 NOT YET IMPLEMENTED

restoringbeam -- Output Gaussian restoring beam for CLEAN image [bmaj, bmin, bpa] elliptical Gaussian restoring beam default units are in arc-seconds for bmaj,bmin, degrees for bpa default: restoringbeam=[]; Use PSF calculated from dirty beam.

example: restoringbeam=['10arcsec'] circular Gaussian FWHM 10" example:
restoringbeam=['10.0','5.0','45.0deg'] 10"x5"

calready -- if True will create scratch columns if they are not there. And after clean completes the predicted model visibility is from the clean components are written to the ms.

async -- Run asynchronously
 default = False; do not run asychronously

at 45 degrees

HINTS ON RUNNING WIDEFIELD

1. Decide if the images will be specified directly in the inputs or with an outlier file. For more than a few fields, an outlier file more convenient.

Direct Method:

Text file method (in outlier.txt)

imagename = 'M1'
outlierfile = 'outlier.txt'
[phasecenter, imsize ignored]

Contents of outlier.txt

C	0	1024	1024	13	27	20.98	43	26	28.0
С	1	128	128	13	30	52.158	43	23	08.00
С	2	128	128	13	24	08.163	43	09	48.00

In both cases the following images will be made:

```
M1_0.image, M1_1.image, M1_2.image cleaned images
M1.0.model, M1_1.model, M1_2.model model images
M1.0.residual, M1_1.residual, M1_2.residual residual images
```

2. Wprojection: It is fastest to use wprojection without faceting.
 ftmachine = 'wproject'
 wprojplane = NN

The value of NN should be chosen as small as possible to reduce execution time. The algorithm $\ \ \,$

 $NN = BMAX(klambda) * imagewidth (arcmin)^2 / 600, with a minimum of 16, should be adequate.$

- 3. Depending on the memory of the computer, a limit of about 5000x5000 may occur for example if a computer has 2Gbyte of RAM. Also a 32-bit computer has a maximum limit of 2Gbyte memory usable per process, irrespective of how much physical RAM is present. Hence it is recommended to move to a 64-bit computer with more than 2 GByte of RAM for >5000x5000 images
- 4. For data with extremely large 'w' values, i.e low frequency, long baseline and very widefield image, the wprojection convolution can be very large and either not fit in memory or slow for processing. In these cases you should consider using both ftmachine='wproject' and facets=xx where is 3.

Permissions

 Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

- Permission is granted to copy and distribute modified versions of this
 manual under the conditions for verbatim copying, provided that the entire
 resulting derived work is distributed under the terms of a permission notice
 identical to this one.
- Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions, except that this permission notice may be stated in a translation approved by AUI.