

Clone custom plug-in resource backups

SnapCenter Software

NetApp June 24, 2021

Table of Contents

Clone custom plug-in resource backups	
Clone from a backup	
Clone backups using PowerShell cmdlets	
Monitor custom plug-in resource clone operations	
Cancel custom plug-in resource clone operations	

Clone custom plug-in resource backups


The clone workflow includes performing the clone operation and monitoring the operation.

About this task

You might clone resource backups for the following reasons:

- To test functionality that has to be implemented using the current resource structure and content during application development cycles
- · For data extraction and manipulation tools when populating data warehouses
- · To recover data that was mistakenly deleted or changed

The following workflow shows the sequence in which you must perform the clone operation:



You can also use PowerShell cmdlets manually or in scripts to perform backup, restore, and clone operations. For detailed information about PowerShell cmdlets, use the SnapCenter cmdlet help or see the SnapCenter Software Cmdlet Reference Guide.

Clone from a backup

You can use SnapCenter to clone a backup. You can clone from primary or secondary backup. The capabilities of the clone operations depends upon the plug-in that you use.

What you will need

- · You must have backed up the resources or resource group.
- The default clone operation only clones storage objects. Clone operations at the application level can only be performed if the custom plug-in provides that capability.
- You should ensure that the aggregates hosting the volumes should be in the assigned aggregates list of the storage virtual machine (SVM).

Steps

- 1. In the left navigation pane, click **Resources**, and then select the appropriate plug-in from the list.
- 2. In the **Resources** page, filter resources from the **View** drop-down list based on resource type.

The resources are displayed along with information such as type, host or cluster name, associated

resource groups and policies, and status.

3. Select the resource or resource group.

You must select a resource if you select a resource group.

The resource or resource group topology page is displayed.

- 4. From the **Manage Copies** view, select **Backups** either from the primary or secondary (mirrored or vaulted) storage systems.
- 5. Select the data backup from the table, and then click
- 6. In the Locations page, perform the following:

For this field	Do this
Clone server	By default, the source host is populated. If you want to specify a different host, select the host on which the clone should be mounted and the plug-in is installed.
Clone suffix	This is mandatory when the clone destination is the same as the source. Enter a suffix that will be appended to the newly cloned resource name. The suffix ensures that the cloned resource is unique on the host. For example, rs1_clone. If you are cloning to the same host as the original resource, you must provide a suffix to differentiate the cloned resource from the original resource; otherwise, the operation fails.

If the resource selected is a LUN and if you are cloning from a secondary backup, then the destination volumes are listed. Single source can have multiple destination volumes.

7. In the **Settings** page, perform the following:

For this field	Do this
Initiator name	Enter the host initiator name, which is either a IQDN or WWPN.
Igroup protocol	Select Igroup protocol.



Settings page is displayed only if the storage type is LUN.

8. In the **Scripts** page, enter the commands for pre clone or post clone that should be run before or after the clone operation, respectively. Enter the mount command to mount a file system to a host.

For example:

- Pre clone command: delete existing databases with the same name
- Post clone command: verify a database or start a database.

```
Mount command for a volume or qtree on a Linux machine: mount<VSERVER_NAME>:%<VOLUME_NAME_Clone /mnt>
```

9. In the **Notification** page, from the **Email preference** drop-down list, select the scenarios in which you want to send the emails.

You must also specify the sender and receiver email addresses, and the subject of the email.

- 10. Review the summary and click **Finish**.
- 11. Monitor the operation progress by clicking **Monitor** > **Jobs**.

Clone backups using PowerShell cmdlets

The clone workflow includes planning, performing the clone operation, and monitoring the operation.

What you will need

You must have prepared the PowerShell environment to execute the PowerShell cmdlets.

For information about PowerShell cmdlets, use the SnapCenter cmdlet help or see the SnapCenter Software Cmdlet Reference Guide.

Steps

1. Initiate a connection session with the SnapCenter Server for a specified user by using the Open-SmConnection cmdlet.

```
Open-SmConnection -SMSbaseurl https:\\snapctr.demo.netapp.com:8146/
```

2. List the backups that can be cloned using the Get-SmBackup or Get-SmResourceGroup cmdlet.

This example displays information about all available backups:

```
      C:\PS>PS C:\> Get-SmBackup

      BackupId
      BackupName
      BackupTime

      BackupType
      -------
      -------

      1
      Payroll Dataset_vise-f6_08... 8/4/2015
      11:02:32 AM

      Full Backup
      2
      Payroll Dataset_vise-f6_08... 8/4/2015
      11:23:17 AM
```

```
PS C:\> Get-SmResourceGroup
   Description
   CreationTime
                             : 10/10/2016 4:45:53 PM
   ModificationTime : 10/10/2016 4:45:53 PM
   EnableEmail
                             : False
   EmailSMTPServer
   EmailFrom
   EmailTo
   EmailSubject
   EnableSysLog
                             : False
   ProtectionGroupType : Backup
EnableAsupOnFailure : False
   Policies
                             : {}
   HostResourceMaping : {}

Configuration : SMCoreContracts.SmCloneConfiguration

LastBackupStatus : Completed
   VerificationServer
   EmailBody
   EmailNotificationPreference : Never
   VerificationServerInfo :
   SchedulerSOLInstance
   CustomText
   CustomSnapshotFormat
                             : False
   SearchResources
   ByPassCredential : False
   IsCustomSnapshot
   MaintenanceStatus : Production
   PluginProtectionGroupTypes : {SMSQL}
   IsInternal
                             : False
   EnableEmailAttachment
                          : False
   VerificationSettings
                              : {}
                             : NFS DB
   Name
   Type
                              : Group
   Ιd
                              : 2
   Host
   UserName
   Passphrase
   Deleted
                              : False
                              : SMCoreContracts.SmAuth
   Auth
   IsClone
                              : False
                              : 0
   CloneLevel
   Hosts
```

StorageName ResourceGroupNames PolicyNames Description CreationTime : 10/10/2016 4:51:36 PM ModificationTime : 10/10/2016 5:27:57 PM EnableEmail : False EmailSMTPServer EmailFrom EmailTo EmailSubject EnableSysLog : False : Backup ProtectionGroupType EnableAsupOnFailure : False Policies : {} HostResourceMaping : {} : SMCoreContracts.SmCloneConfiguration : Failed Configuration LastBackupStatus VerificationServer EmailBody EmailNotificationPreference : Never VerificationServerInfo SchedulerSQLInstance CustomText CustomSnapshotFormat SearchResources : False ByPassRunAs : False IsCustomSnapshot : Production MaintenanceStatus PluginProtectionGroupTypes : {SMSQL} Tag IsInternal : False EnableEmailAttachment : False VerificationSettings : {} Name : Test Type : Group Id : 3 Host UserName Passphrase Deleted : False Auth : SMCoreContracts.SmAuth IsClone : False CloneLevel : 0 Hosts

```
StorageName :

ResourceGroupNames :

PolicyNames :
```

3. Initiate a clone operation from a clone resource group or an existing backup using the New-SmClone cmdlet.

This example creates a clone from a specified backup with all logs:

```
New-SmClone -BackupName Verify_delete_clone_on_qtree_windows_scc54_10-04-2016_19.05.48.0886 -Resources
@{"Host"="scc54.sccore.test.com";"Uid"="QTREE1"} -
CloneToInstance scc54.sccore.test.com -Suffix '_QtreeCloneWin9'
-AutoAssignMountPoint -AppPluginCode 'DummyPlugin' -initiatorname
'iqn.1991-
05.com.microsoft:scc54.sccore.test.com' -igroupprotocol 'mixed'
```

4. View the status of the clone job by using the Get-SmCloneReport cmdlet.

This example displays a clone report for the specified job ID:

```
PS C:\> Get-SmCloneReport -JobId 186
   SmCloneId
                     : 1
   SmJobId
                     : 186
   StartDateTime
                    : 8/3/2015 2:43:02 PM
   EndDateTime
                     : 8/3/2015 2:44:08 PM
   Duration
                     : 00:01:06.6760000
   Status
                     : Completed
   ProtectionGroupName : Draper
   SmProtectionGroupId : 4
   PolicyName
                    : OnDemand Clone
   SmPolicyId
                     : 4
   BackupPolicyName
                     : OnDemand Full Log
   SmBackupPolicyId
                     : 1
   CloneHostName
                     : SCSPR0054212005.mycompany.com
   CloneHostId
   CloneName
                     : Draper clone 08-03-2015 14.43.53
                    : {Don, Betty, Bobby, Sally}
   SourceResources
   ClonedResources : {Don DRAPER, Betty DRAPER, Bobby DRAPER,
Sally DRAPER}
   SmJobError
                      :
```

Monitor custom plug-in resource clone operations

You can monitor the progress of SnapCenter clone operations by using the Jobs page. You might want to check the progress of an operation to determine when it is complete or if there is an issue.

About this task

The following icons appear on the Jobs page, and indicate the state of the operation:

- In progress
- Completed successfully
- x Failed
- Completed with warnings or could not start due to warnings.
- D Queued
- O Canceled

Steps

- 1. In the left navigation pane, click Monitor.
- In the Monitor page, click Jobs.
- 3. In the **Jobs** page, perform the following steps:
 - a. Click roto filter the list so that only clone operations are listed.
 - b. Specify the start and end dates.
 - c. From the **Type** drop-down list, select **Clone**.
 - d. From the **Status** drop-down list, select the clone status.
 - e. Click **Apply** to view the operations that are completed successfully.
- 4. Select the clone job, and then click **Details** to view the job details.
- 5. In the Job Details page, click View logs.

Cancel custom plug-in resource clone operations

You can cancel clone operations that are gueued.

You should be logged in as the SnapCenter Admin or job owner to cancel clone operations.

About this task

- You can cancel a clone operation from either the Monitor page or the Activity pane.
- You cannot cancel a running clone operation.
- You can use the SnapCenter GUI, PowerShell cmdlets, or CLI commands to cancel the clone operations.
- If you selected **All members of this role can see and operate on other members objects** in Users\Groups page while creating a role, you can cancel the queued backup operations of other members while using that role.

Step

Perform one of the following actions:

From the	Action
Monitor page	a. In the left navigation pane, click Monitor > Jobs.b. Select the operation, and click Cancel Job.
Activity pane	 a. After initiating the clone operation, click on the Activity pane to view the five most recent operations.
	b. Select the operation.
	c. In the Job Details page, click Cancel Job .

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.