Fluid Dynamics of the Environment

Jonathan Michael Foonlan Tsang

$\mathrm{May}\ 3,\ 2015$

Contents

T	inte	nternal gravity waves							
	1.1	The minimal mathematics version							
	1.2	A more rigorous derivation							
	1.3	Wave velocities							
	1.4	Motion of fluid particles							
	1.5	Equipartition of energy							
	1.6	Oscillating cylinders							
	1.7	Reflexions							
		1.7.1 Properties of reflected beams							
		1.7.2 Energy density upon reflexion							
		1.7.3 Subcritical and supercritical reflexions							
	1.8	Ray tracing							
	1.9	Wave attractors							
		1.9.1 Rectangular basins							
		1.9.2 Trapezoidal basin							
		1.9.3 More complex geometries							
		1.9.4 Energy spectrum for attractor							
	1.10	Decay along a beam							
		Reflexions from rough topology							
		1.11.1 Subcritical reflexion from a sinusoidal							
		1.11.2 Supercritical reflexions from a sinusoidal							
	1.12	Non-linear stratification							
		Leewaves							
		1.13.1 Kelvin ship waves							
		1.13.2 Extended range of hills							
		1.13.3 Causality							
	1.14	Shear flows							
		1.14.1 Sheared base state							
		1.14.2 Ray tracing in a shear flow							
		1.14.3 *Three-dimensional forcing							
		1.14.4 *Effect of viscosity							
		1.14.5 *Blocking							
	1.15	Columnar modes							
		*Stokes drift in internal waves							
		Resonant triads							
2	Turl	bulence primer 13							
	2.1	Basics of turbulence							
		2.1.1 What is turbulence?							
		2.1.2 Vortex stretching							
		2.1.3 Energy dissipation: Kolmogorov's theory (1941)							
		2.1.4 Two-dimensional turbulence							
	2.2	Simplistic approaches to modelling turbulence							

		2.2.1	Molecular diffusion	
		2.2.2	The closure problem	
		2.2.3	The k - ϵ model	
		2.2.4	Turbulent diffusion models	
		2.2.5	Prandtl's mixing length model	
		2.2.6	Entrainment: Diffusion of turbulence	
	2.3	Mixing	{	18
		2.3.1	What is mixing?	
		2.3.2	The energy budget	19
	2.4	*Stably	y stratified flows	20
		2.4.1	Stratification modifies turbulence	20
	2.5	*Mixin	ng efficiency	20
	2.6	*Intern	nal mixing	20
		2.6.1	Kelvin-Helmholtz instability	20
		2.6.2	Stratified shear flow	20
		2.6.3	Holmboe instability	20
		2.6.4	Entrainment by internal mixing	20
_	~.			
3		llow wa		21
			uction	
	3.2		waves on an interface	
			Dispersion relation	
			Properties of interfacial waves	
		3.2.3	The short wave limit	
		3.2.4	The long wave limit	
	9.9	3.2.5	Energy	
	3.3		w water equations	
		3.3.1 $3.3.2$	Mathematical definition of 'shallow'	
		3.3.3	Derivation from first principles	
		3.3.4	More than one layer	
		3.3.4	Derivation by averaging	
	3.4		bolic systems	
	5.4	3.4.1	A model for traffic flow	
		3.4.1 $3.4.2$	Shallow water as a hyperbolic system	
		3.4.3	Matrix formulation	
		3.4.4	General approach to hyperbolic systems	
			Implications of hyperbolic nature	
		3.4.6	The dam break problem	
		3.4.7	Entrainment into shallow water flows	
	3.5	-	y currents	
	0.0	3.5.1	A moving dam problem	
		3.5.2	Description	
		3.5.3	Early models	
		3.5.4	Cavity flows	
		3.5.5	*Morden and Beiburg	
		3.5.6	Gravity currents and characteristics	
		3.5.7	Modelling gravity currents	
		3.5.8	Real life is more complex	
			•	
4	Jets	, plum	es and thermals	27
	4.1	Jets .		27
	4.2	Genera	1 1	28
		4.2.1	•	28
		4.2.2		28
	4.3			29
		4.3.1	Steady Boussinesq plumes	29

		4.3.2 Time-dependent plumes	29
		4.3.3 Steady non-Boussinesq plumes	29
4	.4	Plumes in a stratified environment	29
		4.4.1 Rise height	29
		4.4.2 Series solution in Boussinesq fluid	29
4	.5	*Thermal in a homogeneous environment	20
4	.6	*Thermals in a stratified environment	29
5 P	ar	ticle-laden and granular flow	c
5.	.1	Types of particulate flows	30
5.	.2	Modelling a particulate gravity current	C
5.	.3	Physics within a particle gravity current	C
5.	5.4 Sedimenting particle-laden flows		
		5.4.1 Type I: Free settling of individual particles	1
		5.4.2 Type II: Flocculent settling, particle coalescence	3
		5.4.3 Type III: Hindered (zone) settling	34
		5.4.4 Type IV: Compressional settling, compacting	34
5.	.5	Sediment transport	
5.	.6	Aqueous and aeolian bedforms (dunes)	5
5.	.7	Dry granular flows, rheology, segregation	5

1 Internal gravity waves

1.1 The minimal mathematics version

In a stably stratified fluid, consider a parcel of fluid. If the parcel is raised from its original position, then it will be heavier than the surrounding fluid, and will sink back down. If it is lowered, then buoyancy will push it back up. Thus density differences provide a restoring force to a parcel displaced vertically.

Let $\rho(z)$ be the density of the fluid, with z vertically upwards so that $\frac{\mathrm{d}\rho}{\mathrm{d}z} < 0$. If the parcel has volume V and is displaced vertically by a height H, then the density difference between the parcel and the surrounding fluid is

$$\Delta \rho = \frac{\mathrm{d}\rho}{\mathrm{d}z} H \tag{1.1}$$

and the downwards force on the parcel is therefore

$$F = gV\Delta\rho = gV\frac{\mathrm{d}\rho}{\mathrm{d}z}H\tag{1.2}$$

Meanwhile, the mass of the particle is

$$m = \rho V \tag{1.3}$$

and so Newton's law F = ma gives the acceleration

$$a = -\frac{g}{\rho} \frac{\mathrm{d}\rho}{\mathrm{d}z} H \tag{1.4}$$

which is in the opposite direction to the displacement.

Assume that the fluid is *Boussinesq*, so that density differences are small compared to a reference density ρ_0 , and fluid accelerations are small compared to gravity. Then we make the approximation $\rho \approx \rho_0$ except when densities are multiplied by gravity. We define the *buoyancy frequency* (or *Brunt-Väisälä frequency*) N, such that

$$N^2 = -\frac{g}{\rho_0} \frac{\mathrm{d}\rho}{\mathrm{d}z} \,. \tag{1.5}$$

Then

$$a = -N^2 H (1.6)$$

so parcels of fluid execute oscillations with frequency $\omega = N$.

In the oceans, $N \approx 10^{-2} \text{s}^{-1}$.

The above argument is not quite valid, because we cannot ignore continuity: we cannot simply displace a parcel of fluid without displacing some other fluid around it. Rather, we should consider displacing an entire slab of fluid and making it oscillate in its plane. But the same argument works.

Suppose a slab makes an angle θ to the vertical and is displaced by d in that direction. Then the displacement in the vertical direction is $d\cos\theta$. A similar argument shows that the slab will execute oscillations with frequency

$$\omega = N\cos\theta \tag{1.7}$$

1.2 A more rigorous derivation

We can derive the above more rigorously by starting from the governing equations of an incompressible inviscid fluid:

$$\nabla \cdot \boldsymbol{u} = 0 \tag{1.8}$$

$$\rho_t + \nabla \cdot (\rho u) = 0 \tag{1.9}$$

$$(\rho \mathbf{u})_t + \nabla \cdot (\rho \mathbf{u} \mathbf{u}) = -\nabla p + \rho \mathbf{g} \tag{1.10}$$

which may also be written as

$$\nabla \cdot \boldsymbol{u} = 0 \tag{1.11}$$

$$\rho_t + \boldsymbol{u} \cdot \boldsymbol{\nabla} \rho = 0 \tag{1.12}$$

$$\rho(\boldsymbol{u}_t + \boldsymbol{u} \cdot \nabla \boldsymbol{u}) = -\nabla p + \rho \boldsymbol{g}. \tag{1.13}$$

We perturb about the stationary stratified state, writing

$$\rho = \bar{\rho}(z) + \rho' \tag{1.14}$$

$$p = \bar{p}(z) + p' \tag{1.15}$$

and assume that the primed quantities and u are small. Then linearising the governing equations gives

$$\nabla \cdot \boldsymbol{u} = 0 \tag{1.16}$$

$$\frac{\mathrm{d}\bar{p}}{\mathrm{d}z} = -g\bar{\rho} \tag{1.17}$$

$$\rho_t = -w \frac{\mathrm{d}\bar{\rho}}{\mathrm{d}z} \tag{1.18}$$

$$\bar{\rho}\boldsymbol{u}_t = -\boldsymbol{\nabla}p' - g\rho'\boldsymbol{e}_z. \tag{1.19}$$

For a Boussinesq fluid, $\rho \approx \rho_0$ except when multiplied by g, so (1.19) becomes

$$\boldsymbol{u}_t = -\frac{1}{\rho_0} \boldsymbol{\nabla} p' - \frac{g}{\rho_0} \rho' \boldsymbol{e}_z. \tag{1.20}$$

Take $\nabla \cdot (1.20)$ and use $\nabla \cdot \boldsymbol{u} = 0$ to get

$$\nabla^2 p' = -g \, \frac{\partial \rho'}{\partial z} \tag{1.21}$$

and then take ∇^2 of the z-component of (1.20) to get

$$\nabla^2 w_t = -\frac{g}{\rho_0} (\rho'_{zz} - \nabla^2 \rho') \tag{1.22}$$

Differentiating with respect to time and using the equation for ρ'_t gives

$$\nabla^2 w_t t = \frac{g}{\rho_0} \left(\nabla^2 - \frac{\partial^2}{\partial z^2} \right) (w \bar{\rho}_z)$$
 (1.23)

$$\approx N^2 \left(\frac{\partial^2}{\partial z^2} - \mathbf{\nabla}^2 \right) w \tag{1.24}$$

where the approximation applies for a Boussinesq fluid.

Plane wave eigenvalue problem For normal mode perturbations of the form

$$w = \hat{w} \exp(i(\mathbf{k} \cdot \mathbf{x} - \omega t)) \tag{1.25}$$

where $\mathbf{k} = (k, l, m)$, we get the dispersion relation

$$\omega^2 = N^2 \frac{k^2 + l^2}{k^2 + l^2 + m^2} \tag{1.26}$$

How do we relate this to the argument with slabs, and recover (1.7)? We note that the slabs that we considered were lines of constant phase, i.e. of constant $k \cdot x$. So k is perpendicular to the slab. Hence if the slab makes an angle θ with the upwards vertical, then k makes an angle θ with the horizontal, and so

$$\cos \theta = \frac{k^2 + l^2}{k^2 + l^2 + m^2} \tag{1.27}$$

as required.




Figure 1: The geometric relationship between phase velocity, group velocity and wavevector.

Evanescent waves Note that if $\omega > N$ then there are no real solutions to (??). Rather, (k, l, m) must be complex and have an imaginary component, which means $e^{i\mathbf{k}\cdot\mathbf{x}}$ decays exponentially as \mathbf{x} increases in a certain direction. Such 'waves' are called evanescent waves. A source which oscillates at a frequency ω will cause localised disturbances and energy is not carried away.

Wave velocities 1.3

From the dispersion relation, we obtain the phase and group velocities in the usual way:

$$\boldsymbol{c}_p = \frac{\omega}{|\boldsymbol{k}|} \hat{\boldsymbol{k}} \tag{1.28}$$

$$=\frac{N}{k}\cos\theta\hat{k}\tag{1.29}$$

$$= \frac{N}{k} \cos \theta \hat{\mathbf{k}}$$

$$= N \sqrt{\frac{k^2 + l^2}{k^2 + l^2 + m^2}} (k, l, m)$$
(1.29)

and

$$\boldsymbol{c}_g = \frac{\partial \omega}{\partial \boldsymbol{k}} \tag{1.31}$$

$$= -N\sin\theta \,\frac{\partial\theta}{\partial\mathbf{k}} \tag{1.32}$$

$$= -N \sin \theta \frac{\partial \theta}{\partial \mathbf{k}}$$

$$= \frac{N}{|\mathbf{k}|^3 \sqrt{k^2 + l^2}} (km^2, lm^2, -(k^2 + l^2)m)$$
(1.32)

Note that

$$\boldsymbol{c}_p \cdot \boldsymbol{c}_g = 0 \tag{1.34}$$

so the phase and group velocities are perpendicular; and note that the group and phase velocities have z-components in opposite directions. See figure 1.

The phase velocity is the velocity at which crests move, or more abstractly the velocity at which phase is advected. The group velocity is the velocity with which wavepackets propagate, and can be interpreted as a rate and direction of energy transfer. The group velocity makes an angle θ with the vertical.

1.4 Motion of fluid particles

If u = (u, 0, w) and

$$u = \hat{u} \exp(i(\mathbf{k} \cdot \mathbf{x} - \omega t)) \tag{1.35}$$

$$w = \hat{w} \exp(i(\mathbf{k} \cdot \mathbf{x} - \omega t)) \tag{1.36}$$

(1.37)

then $\nabla \cdot \boldsymbol{u} = 0$ gives

$$\hat{u} = -\frac{m}{k}\hat{w} \tag{1.38}$$

which tells us that fluid particles oscillate parallel to the group velocity and perpendicularly to the wavevector. We can obtain the displacements by integrating with respect to time, or equivalently by dividing by $-i\omega$.

1.5 Equipartition of energy

Dotting (1.20) with \boldsymbol{u} and some manipulation gives us

$$\frac{\partial}{\partial t} \left(\frac{1}{2} \rho_0 \boldsymbol{u}^2 + \frac{1}{2} \frac{g^2}{\rho_0 N^2} \rho'^2 \right) + \boldsymbol{\nabla} \cdot (p' \boldsymbol{u}) = 0, \tag{1.39}$$

the equation of conservation of energy. We identify $\frac{1}{2}\rho_0 u^2$ as kinetic energy density and $\frac{1}{2}\frac{g^2}{\rho_0 N^2}\rho'^2$ as potential energy density. (Energy density is energy per unit volume.)

For normal modes, we can calculate time-averages, and find that

$$\langle \text{kinetic energy density} \rangle = \langle \text{potential energy density} \rangle$$
 (1.40)

Note that we must take real parts before multiplying together any quantities.

1.6 Oscillating cylinders

Suppose a cylinder (or any other object) is suspended in a stratified medium. At time t=0, it is impulsively started to oscillate at frequency $\omega < N$. The impulsive start of the cylinder generates an entire spectrum of transient wave modes, which generates IGWs propagating at different values of θ . After some time, when the transients have decayed, we see a single mode of IGWs propagating at $\theta = \cos^{-1}(\omega/N)$ to the vertical.

1.7 Reflexions

1.7.1 Properties of reflected beams

At a boundary, the normal velocity component must be continuous. For a rigid stationary boundary, this means that the normal velocity component must vanish.

Suppose z = 0 is a rigid stationary boundary, with a plane wave incident from z > 0. What is the reflected wave? We have

$$w = w_I + w_R \tag{1.41}$$

$$w_I = \hat{w}_I \exp(i(\mathbf{k}_I \cdot \mathbf{x} - \omega t)) \tag{1.42}$$

$$w_R = \hat{w}_I \exp(i(\mathbf{k}_R \cdot \mathbf{x} - \omega t)); \tag{1.43}$$

the two waves must have the same ω and $k_I = k_R$; the boundary condition gives $\hat{w}_I + \hat{w}_R = 0$. And causality implies that $m_R = -m_I$.




Figure 2: Super- and sub-critical reflexions.

When a plane wave reflects off a flat boundary which is not horizontal, then the incident and reflected waves make the same angle (but reflected) with the vertical or horizontal, so that they have the same $\omega = N \cos \theta$. (Note that for IGWs, θ is the angle between a wave's direction and the vertical.) In general, the angle of incidence and angle of reflexion are not equal. Depending on how the angle of the incident wave compares with the slope of the boundary, one of two things may happen: see Figure 2.

From Figure 2 we can see that reflexions change the wavenumber of the wave and can act to focus or defocus the rays, depending on direction. Let α be the angle that the plane boundary makes with the vertical. We define the quantity

$$\gamma = \frac{\sin(\alpha - \theta)}{\sin(\alpha + \theta)} \tag{1.44}$$

to characterise the focusing power of a reflexion.

After a lot of manipulation, we can show that focusing reflexions change the amplitude and wavenumber according to

$$k_R = \gamma k_I \tag{1.45}$$

$$A_R = \gamma A_I \tag{1.46}$$

and that defocusing reflexions have the opposite effect:

$$k_R = \gamma^{-1} k_I \tag{1.47}$$

$$A_R = \gamma^{-1} A_I. \tag{1.48}$$

1.7.2 Energy density upon reflexion

The energy density per unit wavelength is

$$\tilde{E} \sim \lambda A^2$$
. (1.49)

After a focusing reflexion, λ is divided by γ but A is multiplied by γ , so \tilde{E} is multiplied by γ . Hence the energy density per wavelength is increased after a focusing reflexion.

The energy density per unit length is

$$\hat{E} = \frac{1}{\lambda}\tilde{E} \tag{1.50}$$

and so \hat{E} is multiplied by γ^2 after a focusing reflexion.

1.7.3 Subcritical and supercritical reflexions

In a subcritical reflexion, the boundary has a shallower slope than the wave $(\theta < \alpha)$, and the vertical propagation of the wave is reversed by the reflexion. The horizontal direction of propagation is maintained.

In a supercritical reflexion, $\theta > \alpha$ and the vertical direction of propagation is maintained but the horizontal direction is reversed.

When θ and α are very similar, then γ becomes very large. So waves will have very large amplitudes, and nonlinear effects and viscosity become important.

1.8 Ray tracing

Since the frequency is preserved upon reflexion, the angle to the vertical θ is conserved, so waves tend to propagate along well-defined rays. Depending on the shape of the domain and its boundaries, repeated reflexions can lead to trapping, to amplitudes increasing, and eventually to wave-breaking. Nonlinear effects become important if the amplitude of waves is increased sufficiently.

We must take note of causality to determine which direction is appropriate.

1.9 Wave attractors

- 1.9.1 Rectangular basins
- 1.9.2 Trapezoidal basin
- 1.9.3 More complex geometries
- 1.9.4 Energy spectrum for attractor

1.10 Decay along a beam

Here we will derive the behaviour for a beam in a viscous fluid with constant kinematic viscosity ν . The linearised equations are now

$$\frac{\partial u}{\partial t} + \frac{1}{\rho_0} \frac{\partial p}{\partial x} = \nu \nabla^2 u \tag{1.51}$$

$$\frac{\partial w}{\partial t} + \frac{1}{\rho_0} \frac{\partial p}{\partial z} - b = \nu \nabla^2 w \tag{1.52}$$

$$\frac{\partial b}{\partial t} + N^2 w = 0 \tag{1.53}$$

$$\nabla \cdot \boldsymbol{u} = 0 \tag{1.54}$$

where

$$b = \frac{-g(\rho - \rho_0)}{\rho_0} \tag{1.55}$$

is the buoyancy.

Introduce a streamfunction ψ such that $(u, w) = (-\psi_z, w = \psi_x)$. Then some cross-differentiation eliminates p and b to give

$$\nabla^2 \psi_{tt} + N^2 \psi_{xx} = \nu \nabla^4 \psi_t. \tag{1.56}$$

The $\nu \nabla^4 \psi_t$ term acts to damp waves. We could look for plane-wave solutions to (1.56) in the usual way, and obtain the dispersion relation

$$\omega^2 + i\nu(k^2 + m^2) - N^2 \cos^2 \theta = 0 \tag{1.57}$$

where $\cos \theta = k/|\mathbf{k}|$ as usual. Given (k, m), we could solve (1.57) for ω .

But often we are more interested in the spatial decay of a beam that is generated by oscillations at a fixed ω . We expect that the beam would still propagate in the direction $\theta = \cos^{-1}(\omega/N)$, but with a decaying amplitude.

1.11 Reflexions from rough topology

1.11.1 Subcritical reflexion from a sinusoidal

1.11.2 Supercritical reflexions from a sinusoidal

1.12 Non-linear stratification

If N is not constant but varies with z (say), then waves will not follow straight paths but will refract. If N varies very slowly with z, over lengthscales much larger than a wavelength, then the WKB method can be used to find the trajectory of a wave. We use the fact that $\omega = N(z) \cos \theta$ is constant along any beam to determine θ , the angle between the beam and the vertical.

1.13 Leewaves

When a medium flows past an obstacle and waves are formed in the wake, it is possible to get standing waves (also known as stationary waves). When standing IGWs occur in the atmosphere as a wind flows past obstacles such as mountains, these are known as leewayes.

1.13.1 Kelvin ship waves

As an aside to introduce standing waves, we consider a ship moving with velocity $U = Ue_x$ in deep water. The surface waves have a dispersion relation

$$\omega^2 = g|\mathbf{k}|\tag{1.58}$$

and phase

$$\phi = \mathbf{k} \cdot \mathbf{x} - \omega t. \tag{1.59}$$

Let x' denote a position vector relative to the ship, so that x' = x - Ut. Then

$$\phi = \mathbf{k} \cdot \mathbf{x}' + (\mathbf{k} \cdot \mathbf{U} - \omega)t. \tag{1.60}$$

Hence waves that are stationary in the frame of the ship have

$$\mathbf{k} \cdot \mathbf{U} = \omega \tag{1.61}$$

$$U\cos\theta = |\boldsymbol{c}_g| \tag{1.62}$$

where, in this section, θ is the angle between U and k.

For these waves, c_g and c_p are parallel, and $|c_g| = \frac{1}{2}|c_p| = \frac{1}{2}U\cos\theta$. This is the speed at which wave packets travel. Some geometry then tells us the shape that these waves make behind the ship.

In shallow water, surface waves are not dispersive and such stationary waves are not seen.

1.13.2 Extended range of hills

Now we consider leewaves, i.e. stationary atmospheric IGWs as a wind of speed U flows, from left to right, over a sinusoidal mountain range which has wavelength λ_T and so topographical wavenumber $k_T = 2\pi/\lambda$.

An observer in the frame of the mountains sees the leewaves as having a constant phase. The frequency of the forcing must therefore be

$$\omega = k_T U = \frac{2\pi U}{\lambda_T} \tag{1.63}$$

and the wave crests make an angle $\theta = \cos^{-1}(\omega/N)$ with the vertical. The phase velocity is aligned with the wave crests, so that the observer sees the waves as being stationary.

We move to a frame moving with the wind, in which the mountains are moving with speed U to the left. This does not change the angle between the wave crests and the vertical. But in the new frame the group velocity is $\mathbf{c}'_g = \mathbf{c}_g - \mathbf{U}$, and is aligned with the crests.

1.13.3 Causality

1.14 Shear flows

1.14.1 Sheared base state

Suppose the background stratified fluid is not stationary but has velocity U = (U(z), 0, 0). Linearising the full governing equations of motion about this base state by writing u = U + (u', v', w'), and a lot of manipulation to eliminate everything apart from w', eventually gives

$$\left(\frac{\partial}{\partial t} + U\frac{\partial}{\partial x}\right)^2 \nabla^2 w' + N^2 \frac{\partial^2 w'}{\partial x^2} - U'' \left(\frac{\partial}{\partial t} + U\frac{\partial}{\partial x}\right) \frac{\partial w'}{\partial x} = 0.$$
 (1.64)

Note that this reduces to 1.24 if $U \equiv 0$. If U is constant, then a change of frame would recover 1.24 as expected.

For flows which are steady (in this frame of reference), we have

$$\frac{\partial^2}{\partial x^2} \nabla^2 w' + \left(\frac{N^2}{U^2} - \frac{U''}{U}\right) \frac{\partial^2 w'}{\partial x^2} = 0. \tag{1.65}$$

Integrating twice with respect to x then gives

$$\nabla^2 w' + \left(\frac{N^2}{U^2} - \frac{U''}{U}\right) w' = 0. {(1.66)}$$

If U and N are constant, or very slowly varying, then we can search for plane wave solutions

$$w' = w_0 e^{i(kx+mz)} \tag{1.67}$$

which satisfy

$$-(k^2 + m^2) + \frac{N^2}{U^2} = 0 (1.68)$$

or $|\mathbf{k}| = N/U$ as before. Note that this is also true whenever

$$\frac{N^2}{U^2} - \frac{U''}{U} \tag{1.69}$$

is constant.

1.14.2 Ray tracing in a shear flow

When the length scale over which U and N change is much larger than the wavelength of internal waves, we can consider the important wave properties as being instantaneous in the local state of the background flow. This is the WKB approximation. Rays follow the group velocity relative to the fluid. However, in our frame of reference the waves appear stationary, and so the phase velocity must be parallel to the wave crests and the group velocity antiparallel with the wavenumber vector. We can thus take the trajectory of a wave propagating with the mean flow as

$$\frac{\mathrm{d}z}{\mathrm{d}x} = \frac{c_{gz}}{U - c_{gx}} = \frac{m}{k} \tag{1.70}$$

where \boldsymbol{c}_g is the group velocity relative to the fluid.

Recalling that $k^2 + m^2 = N^2/U^2$, and assuming that k is conserved along the ray and $U''/U \ll N^2/U^2$, then

$$m^2 = \frac{N^2}{U^2} - k^2 \tag{1.71}$$

and so

$$\frac{\mathrm{d}z}{\mathrm{d}x} = \left(\left(\frac{N}{kU}\right)^2 - 1\right)^{1/2}.\tag{1.72}$$

Waves cannot propagate through a level where kU/N=1.

In the atmosphere, U/N tends to increase with height as U increases.

- 1.14.3 *Three-dimensional forcing
- 1.14.4 *Effect of viscosity
- 1.14.5 *Blocking
- 1.15 Columnar modes
- 1.16 *Stokes drift in internal waves
- 1.17 Resonant triads

2 Turbulence primer

Most environmental and geophysical flows occur at high Reynolds numbers. At high Reynolds numbers, laminar solutions to the Navier-Stokes equations are unstable, and the flows are turbulent.

2.1 Basics of turbulence

Throughout this and the next section, assume that the density ρ is constant and uniform.

2.1.1 What is turbulence?

Although there is no simple definition for turbulence, turbulent flows can be characterised by a few properties:

- Turbulent flows are dominated by inertia, since $Re \gg 1$. Viscosity plays a small (but crucial) role.
- Turbulent flows are vortical, not irrotational. However, vortical flows need not be turbulent.
- Turbulent flows involve a range of length scales. Vortices exist at both large and small length scales: "Big whorls have little whorls, which feed on their velocity, // And little whorls have lesser whorls, and so on to viscosity." —Lewis Richardson.

Turbulent flows are unpredictable and simulating them numerically may be difficult as they may be numerically unstable. However, it may be possible to predict certain statistics of the flow, such as the behaviour of the mean flow or mean pressure (noting that fluctuations about these means may be great). Some features of turbulence can be shown to be universal.

Lewis Richardson's couplet describes the two processes at work in a turbulent flow. *Vortex stretching* is responsible for creating small vortices out of large ones, while *energy dissipation* causes small vortices to decay.

2.1.2 Vortex stretching

Vortex stretching is the main process by which energy is transferred from large scales to smaller scales.

Taking the curl of the Navier-Stokes equation gives the *vorticity equation*:

$$\frac{\partial \omega}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \boldsymbol{\omega} = \boldsymbol{\omega} \cdot \boldsymbol{\nabla} \boldsymbol{u} + \nu \boldsymbol{\nabla}^2 \boldsymbol{\omega}$$
 (2.1)

The second term on the RHS of (2.1) means that vorticity is diffused with diffusion constant ν . This is a minor effect in flows with Re $\gg 1$. The first term means that when a parcel of fluid is stretched into a column, its vorticity increases and becomes aligned with the column. Thus stretching a vortex takes energy to a smaller scale. However, if the vortex column is compressed, not nearly as much energy is taken back to the large scale, since the compression in general de-aligns the vorticity vector and the column.

2.1.3 Energy dissipation: Kolmogorov's theory (1941)

We know that energy is dissipated in a fluid at a rate

$$\Delta = \int_{V} \mu |\nabla u|^2 dV \tag{2.2}$$

(or expressed in terms of the strain rate tensor, using $|\nabla u|^2 = 2e_{ij}e_{ij}$). In a volume with characteristic length L,

$$\Delta \sim L^3 |\nabla u|^2. \tag{2.3}$$

For a laminar flow with characteristic velocity U in a box with sides L, $|\nabla u| \sim U/L$ and so

$$\Delta \sim \mu \frac{U^2}{L^2} L^3 = \mu U^2 L.$$
 (2.4)

However, for a turbulent flow, the energy dissipation is much faster than this, because the velocity gradients are over much smaller distances, and so $|\nabla u| \gg U/L$.

Although the large-scale structure of the flow might have characteristic lengthscale L, the small-scale structure of the flow should be described by another lengthscale η , called the *Kolmogorov length scale* or the *Kolmogorov microscale*. This is the lengthscale at which the effects of vortex stretching and dissipation balance each other.

To summarise: The flow is externally driven (continually or initially) at the lengthscale L, energy cascades to smaller lengthscales by vortex stretching; viscosity acts more and more strongly at these smaller lengthscales. Eventually, energy cascades down to the lengthscale η and proceeds no more.

Let U(k) be the Fourier transform of the velocity u(x), using the normalisation

$$U(\mathbf{k}) = \frac{1}{\sqrt{2\pi}} \int_{V} \mathbf{u}(\mathbf{x}) e^{-i\mathbf{k}\cdot\mathbf{x}} d\mathbf{x}.$$
 (2.5)

Let

$$E(\mathbf{k}) = \frac{1}{2}\rho \mathbf{U}(\mathbf{k}) \cdot \mathbf{U}(\mathbf{k}) *$$
(2.6)

be the energy density spectrum. (In defining these Fourier transforms, we are assuming that ρ is constant and uniform.) The total kinetic energy is

$$KE = \int E(\mathbf{k})d\mathbf{k} \tag{2.7}$$

with the integral taken over wavenumber space. For isotropic turbulence, U and E depend only on the magnitude $k = |\mathbf{k}|$.

Since density is constant, we will find it convenient to rewrite the above expressions without ρ , so that the dimension M may be set to 1. We therefore work with the energy dissipation rate

$$\epsilon = \int_{V} \nu |\nabla \boldsymbol{u}|^2 dV \tag{2.8}$$

which has dimensions L^2T^{-3} , and with the energy spectrum

$$E(k) = \frac{1}{2} \mathbf{U}(k) \cdot \mathbf{U}(k) *$$
(2.9)

which has dimensions L^3T^{-2} . We write

$$KE = \int E(k)dk \tag{2.10}$$

for the kinetic energy per unit mass, with dimensions L^2T^{-2} .

Kolmogorov made two hypotheses about isotropic turbulent flows. These hypotheses allow us to make progress by dimensional analysis, but they do not follow from first principles, and their predictions must be verified experimentally.

First hypothesis The rate of dissipation of energy (per unit density), ϵ (dimensions L^2T^{-3}), depends only on viscosity ν (dimensions L^2T^{-1}) and on the microscale η . In particular, ϵ and η are not to depend on the large lengthscale L.

By dimensional analysis, this hypothesis allows us to construct η :

$$\eta = (\nu^3/\epsilon)^{1/4} \tag{2.11}$$

Note that in a system in equilibrium, the rate of dissipation of energy is equal to the rate of energy input. ¹

¹We can have a dynamic equilibrium, but not a static one, since turbulent flow is not steady.

Second hypothesis The energy density E(k) (dimensions L^3T^{-2}) depends only on the rate of dissipation ϵ and on k (dimensions L^{-1}).

By dimensional analysis,

$$E(k) = C\epsilon^{2/3}k^{-5/3} \tag{2.12}$$

for some constant C.

This second hypothesis is not completely valid. If the flow is in a bounded domain with characteristic lengthscale L, or if the flow is driven at the lengthscale L, then the hypothesis is not valid at wavenumbers $k \sim 1/L$ or below. And the hypothesis is also not valid when $k \sim 1/\eta$, where the details of dissipation start to be important.

However, for the range $1/L \ll k \ll 1/\eta$, known as the *inertial range*, the hypothesis is justified and is supported by experimental evidence: (2.12) is reproduced by experimental data.

2.1.4 Two-dimensional turbulence

A turbulent flow in two dimensions is different from one in three dimensions, since for a two-dimensional flow the vortex stretching term in (2.1) is always zero. Vorticity is conserved, and there is no cascade of energy to smaller lengthscales. Dotting (2.1) with ω gives us the *enstrophy equation*:

$$\frac{\mathrm{D}}{\mathrm{D}t} \left(\frac{1}{2} |\boldsymbol{\omega}|^2 \right) = \nu \left(\boldsymbol{\nabla}^2 \frac{1}{2} |\boldsymbol{\omega}|^2 - |\boldsymbol{\nabla}\boldsymbol{\omega}|^2 \right). \tag{2.13}$$

The scalar quantity $\frac{1}{2}|\omega|^2$ is called the *enstrophy density*.

We obtain a very similar equation for the kinetic energy density by dotting the Navier-Stokes equation with u:

$$\frac{\mathrm{D}}{\mathrm{D}t} \left(\frac{1}{2} |\boldsymbol{u}|^2 \right) = \nu \left(\boldsymbol{\nabla}^2 \frac{1}{2} |\boldsymbol{u}|^2 - |\boldsymbol{\nabla} \boldsymbol{u}|^2 \right). \tag{2.14}$$

Equations 2.13 and 2.14 tell us that in a 2D flow, enstrophy and kinetic energy are redistributed by diffusion (first term on RHS) as well as dissipated (second term).

Since total enstrophy (enstrophy density integated across the volume) must decrease, there must be a net movement of energy to larger lengthscales (i.e. smaller k). Total enstrophy is proportional to $\int k^2 E(k) dk$, so if E(k) increases at high k, this increase must be balanced by a greater increase in E(k) at low k, so that $\int k^2 E(k) dk$ never increases.

Hence there is an anticascade of energy to larger scales, and a cascade of enstrophy to smaller scales.

2.2 Simplistic approaches to modelling turbulence

Instead of starting from first principles and trying to solve the Navier-Stokes equations for a turbulent system directly, it is often easier, and fruitful, to model the effects of turbulence instead.

2.2.1 Molecular diffusion

A direct approach is to model all scales down to the microscale $\eta = (\nu^3/\epsilon)^{1/4}$. The energy spectrum (2.12) predicts that the kinetic energy per unit volume will be

KE density =
$$\int_{1/L}^{1/\eta} E(k)dk \propto (\epsilon L)^{2/3}$$
 (2.15)

giving a characteristic velocity

$$u \propto \sqrt{\text{KE density}} \propto (\epsilon L)^{1/3}$$
 (2.16)

and therefore a Reynolds number

$$Re = \frac{uL}{\nu} \propto \frac{\epsilon^{1/3} L^{4/3}}{\nu}.\tag{2.17}$$

Note that we calculate this Reynolds number using a characteristic velocity calculated only from the turbulent properties, not taking into account any large-scale velocities (such as one driving the flow).

Since $\eta = (\nu^3/\epsilon)^{1/4}$, we have

$$Re = \left(\frac{L}{\eta}\right)^{4/3} \gg 1. \tag{2.18}$$

For moderately large Re, direct numerical simulation (DNS) may be possible, but usually Re is so large that DNS is impractical or impossible.

The problem would be even worse if the fluid were not of uniform and constant density. The mass diffusivity κ and the momentum diffusivity ν are compared by the *Schmidt number* $Sc = \nu/\kappa$. For salt water, $Sc \approx 1000$. In order to simulate the diffusion of mass, we would have to look at an even smaller scale, the *Batchelor scale* $\lambda_B = \eta/Sc^{1/2}$.

2.2.2 The closure problem

A turbulent flow u, and the associated pressure field p, can be decomposed into its mean part \overline{u} , and a fluctuating part u' that fluctuates about 0: $\overline{u'} = 0$. We can model a turbulent flow by ignoring the details of these fluctuations, and looking only at how these fluctuations affect the mean part. ²

Beginning with the Navier-Stokes equations:

$$\rho \frac{\mathbf{D}}{\mathbf{D}t} \boldsymbol{u} = -\boldsymbol{\nabla} p + \mu \boldsymbol{\nabla}^2 \boldsymbol{u} + \boldsymbol{f}$$
 (2.19)

and averaging, we obtain

$$\rho\left(\frac{\partial \overline{\boldsymbol{u}}}{\partial t} + \overline{\boldsymbol{u}} \cdot \nabla \overline{\boldsymbol{u}}\right) = -\nabla \overline{p} + \mu \nabla^2 \overline{\boldsymbol{u}} + \boldsymbol{f} - \rho \overline{\boldsymbol{u}' \cdot \nabla \boldsymbol{u}'}$$
(2.20)

(assuming that the body force f is a constant). The fluctuations are still present in the quadratic term $-\rho \overline{u'} \cdot \nabla \overline{u'}$ on the RHS, because (2.19) is nonlinear. ³ We cannot remove such nonlinear terms by more averaging, as that simply introduces further nonlinear terms. This is the *closure problem*: we cannot close the system as we do not know how to deal with these terms. Many approximate closures have been proposed, but none are universally applicable.

Note that

$$-\rho \overline{\boldsymbol{u}' \cdot \boldsymbol{\nabla} \boldsymbol{u}'} = -\rho \boldsymbol{\nabla} \cdot (\overline{\boldsymbol{u}' \boldsymbol{u}'}) \tag{2.21}$$

and so the fluctuations affect the mean flow as though they were an additional stress force, with stress tensor

$$\sigma^{(R)} = -\rho \overline{u'u'}. \tag{2.22}$$

This 'stress' is called the Reynolds stress.

2.2.3 The k- ϵ model

The most commonly used closure model is the k- ϵ model, where $k = \frac{1}{2} \boldsymbol{u}' \cdot \boldsymbol{u}'$ is the turbulent kinetic energy (per unit density), and ϵ is the energy dissipation. The model states that

$$\rho \frac{\mathbf{D}}{\mathbf{D}t} k = \nabla \cdot \left(\frac{\mu_T}{\sigma_k} \nabla k\right) + 2\mu_T \mathbf{S} : \mathbf{S} - \rho \epsilon$$
(2.23)

where

$$\mu_T = C_\mu \rho \frac{k^2}{\epsilon} \tag{2.24}$$

is the turbulent viscosity,

$$S = \frac{1}{2} (\nabla \overline{u} + (\nabla \overline{u})^T)$$
(2.25)

²The mean can be taken as a time average or as a local spatial average, but this detail is unimportant for what follows.

³If we had a non-constant ρ , then we would have further such quadratic terms, such as the turbulent buoyancy flux $\overline{u'} \cdot \nabla \rho$.

is the strain rate tensor corresponding to the mean flow, and $C_{\mu} \approx 0.09$ and $\sigma_k \approx 1.00$ are constants that are determined empirically. Equations 2.20 and 2.23 together specify the problem for \overline{u} completely.

Essentially, the model describes how turbulent kinetic energy is governed. We can interpret (2.23) as follows:

- The first term on the RHS represents the diffusion of turbulent kinetic energy, at some (non-constant) rate μ_T/σ_k .
- The second term represents the generation of turbulent kinetic energy, by means of vortex stretching.
- The third term represents the dissipation of turbulent kinetic energy.

Equation 2.23 can be re-written as

$$\rho \frac{D}{Dt} \epsilon = \nabla \cdot \left(\frac{\mu_T}{\sigma_{\epsilon}} \nabla \epsilon \right) + 2C_{1\epsilon} \frac{\epsilon}{k} \mu_T \mathbf{S} : \mathbf{S} - C_{2\epsilon} \rho \frac{\epsilon^2}{k}$$
(2.26)

where $\sigma_{\epsilon} \approx 1.30$, $C_{1\epsilon} \approx 1.44$ and $C_{2\epsilon} \approx 1.92$ are constants that are determined empiracally.

Experiments and simulations find that these constants are universal.

2.2.4 Turbulent diffusion models

As discussed, the vortex stretching process is irreversible and takes energy to smaller lengthscales. There is little back-scatter: smaller lengthscales do not strongly affect the larger scales, except as a sink of energy. This is why we can consider the mean flow as in (2.20) and ignore the behaviour of the fluctuations, except as a sink of energy.

This suggests replacing the Reynolds stress with an additional viscosity term that mimics the diffusion of momentum and dissipation of energy without actually describing how this happens. That is, we take

$$-\overline{u'u'} = \nu_T S \tag{2.27}$$

where ν_T is called the (turbulent) eddy viscosity. We also write $\mu_T = \rho \nu_T$. The force due to Reynolds stresses is therefore

$$\nabla \cdot \sigma^{(R)} = \nabla \cdot (-\rho \overline{u'u'}) \tag{2.28}$$

$$= \rho \nabla \cdot (\nu_T S) \tag{2.29}$$

$$= \rho(\nabla \nu_T \cdot \mathbf{S} + \nu_T \nabla \cdot \mathbf{S}) \tag{2.30}$$

$$= \rho(\nabla \nu_T \cdot \mathbf{S} + \frac{1}{2}\nu_T \nabla^2 \overline{\mathbf{u}}). \tag{2.31}$$

Putting this into the averaged Navier-Stokes equations gives us

$$\left(\frac{\partial \overline{\boldsymbol{u}}}{\partial t} + \overline{\boldsymbol{u}} \cdot \boldsymbol{\nabla} \overline{\boldsymbol{u}}\right) = -\frac{1}{\rho} \boldsymbol{\nabla} \overline{p} + \left(\nu + \frac{1}{2}\nu_T\right) \boldsymbol{\nabla}^2 \overline{\boldsymbol{u}} + \frac{1}{\rho} \boldsymbol{f} + \boldsymbol{\nabla} \nu_T \cdot \boldsymbol{S}. \tag{2.32}$$

Closure models that do this are called turbulent diffusion models. Different models propose different expressions for ν_T : this is usually not constant, but may depend on the position or on \overline{u} .

2.2.5 Prandtl's mixing length model

Prandtl's mixing length model is a turbulent diffusion model, in which

$$\nu_T = ku'l \tag{2.33}$$

where l is some mixing length, $u' = \sqrt{|u'|^2}$ is the turbulence intensity, and the Prandtl ratio $k \approx 0.4$ is another empirically-determined constant. The mixing length represents the lengthscale of turbulent eddies; it may vary with position, and depends on the geometry of the problem.

The law of the wall For example, in the domain z > 0 bounded by a wall at z = 0, the lengthscale l of turbulent eddies is assumed to scale with z. The turbulence intensity is assumed to be some constant q. Hence $\nu_T = kqz$. The horizontal shear stress is also assumed to be constant.

Assuming that the mean flow is $\overline{u} = U(z)e_x$, the x-component of Equation 2.32 gives us

$$0 = \frac{1}{\rho}G + \left(\nu + \frac{1}{2}\nu_T\right)\frac{d^2U}{dz^2} + \frac{1}{2}kq\frac{dU}{dz}$$
 (2.34)

where $G = -\frac{\partial \overline{p}}{\partial x}$ is the horizontal pressure gradient, which is some constant.

In the case G = 0, we can solve (2.34) exactly to give us

$$U(z) = \frac{A}{kq} \log(2\nu + kqz) \tag{2.35}$$

where A is some constant. The condition that shear stress is (approximately) constant allows us to write A in terms of the bed shear stress, the shear stress on z = 0.

For $z \ll \frac{\nu}{kq}$, (2.35) says that $U(z) \propto z$, as we would expect for a boundary layer. In this region, molecular viscosity ν is dominant. However, for larger z, U(z) is logarithmic in z:

$$U(z) \sim \frac{u_*}{\kappa} \log \frac{z}{z_0} \tag{2.36}$$

This is the law of the wall. Here u_* is called the slip velocity and z_0 the roughness height; $\kappa \approx 0.41$ is a dimensionless constant called von Karmen's constant.

The law of the wall does not hold when z becomes too large, when other effects such as small pressure gradients take hold, or when the mixing length is no longer $l \sim z$, but it is a good approximation for boundary layers.

2.2.6 Entrainment: Diffusion of turbulence

Consider a turbulent patch of length scale l and turbulence intensity u', surrounded by irrotational fluid outside the patch. The vortical motion within the patch will draw in the external fluid, straining and diffusing vorticity into it. Thus the size of the patch will increase; its boundaries move out at a rate proportional to u'.

The diffusivity of turbulence is called the turbulent diffusivity, written κ_T , with $\kappa_T \sim u'l$. This is not to be confused with turbulent viscosity, though both are $\sim u'l$ with similar (but not necessarily equal) constants of proportionality.

This diffusivity of turbulence can explain the growth of the Rayleigh-Taylor instability in a tall tube.

2.3 Mixing

We now drop the assumption that ρ is constant and uniform.

2.3.1 What is mixing?

Mixing is the blending of fluid particles with different properties, such as density, salinity or temperature. (These properties are related to each other.) There are two processes responsible for mixing:

- Stirring is the intermingling of fluid particles of different properties. This produces large gradients in these properties.
- Diffusion drives a flux down a gradient that reduces these gradients between adjacent fluid particles.

Diffusion is an irreversible process: there is a 'preferred' direction for fluxes, down a gradient; but stirring (on its own) is reversible. Diffusion is a slow process that occurs at the molecular level, whereas stirring can happen quickly and over large lengthscales. Together, stirring and diffusion can cause irreversible mixing.

In general, a scalar property S is governed by the advection-diffusion equation

$$\frac{\mathbf{D}}{\mathbf{D}t}S = \kappa \nabla^2 S \tag{2.37}$$

where κ (dimensions L^2T^{-1}) is the molecular diffusivity of S. This is often very small: the diffusivity of heat in air is $\approx 10^{-5}m^2s^{-1}$ and the diffusivity of salt in water is $\approx 10^{-9}m^2s^{-1}$. The timescale for diffusing across a length l is therefore $t \sim l^2/\kappa$, which is huge: heat takes a day to diffuse across a metre in air, and salinity takes thirty years to diffuse a metre.

However, stirring (represented by the advection term) can help to create large gradients in S, which increases the rate of diffusion (by reducing l).

2.3.2 The energy budget

Consider an incompressible Boussinesq fluid with a linear equation of state. ⁴ Assume that dissipative heating is unimportant, and ignore any heating effects from dilution, chemical potential energy, and so on.

Begin with the momentum equation for a variable-density fluid:

$$\frac{\mathbf{D}}{\mathbf{D}t}\rho\boldsymbol{u} = -\boldsymbol{\nabla}p - \rho g\boldsymbol{e}_z + \rho\nu\boldsymbol{\nabla}^2\boldsymbol{u}$$
(2.38)

and dot with u. Since

$$\boldsymbol{u} \cdot \boldsymbol{\nabla} p = \boldsymbol{\nabla} \cdot (p\boldsymbol{u}) \tag{2.39}$$

for an incompressible fluid, and

$$\boldsymbol{u} \cdot \rho g \boldsymbol{e}_z = \frac{D}{Dt} (\rho g z) - \boldsymbol{\nabla} \cdot (g z \kappa \boldsymbol{\nabla} \rho) + g \kappa \frac{\partial \rho}{\partial z}$$
(2.40)

(where we have used the advection-diffusion equation for ρ , with mass diffusivity κ), we have:

$$\frac{\mathrm{D}}{\mathrm{D}t} \left(\frac{1}{2} \rho |\boldsymbol{u}|^2 + \rho gz \right) + \boldsymbol{\nabla} \cdot \left(p\boldsymbol{u} - \frac{1}{2} \rho \nu \boldsymbol{\nabla} |\boldsymbol{u}|^2 - gz\kappa \boldsymbol{\nabla} \rho \right) = -g\kappa \frac{\partial \rho}{\partial z} - \rho \nu |\boldsymbol{\nabla} \boldsymbol{u}|^2. \tag{2.41}$$

This is an equation descibing kinetic and potential energy density. The energy of a parcel of fluid changes due to diffusion, because:

- work is done on it by pressure from neighbouring parcels, causing an energy flux pu;
- viscosity causes the diffusion of kinetic energy, with energy flux $-\frac{1}{2}\rho\nu\nabla|u|^2$;
- mass diffusion causes the diffusion of potential energy, with energy flux $-qz\kappa\nabla\rho$.

The energy of a parcel also changes due to:

- mass diffusion raising the centre of mass, changing the potential energy at a rate $-g\kappa \frac{\partial \rho}{\partial z}$;
- dissipation due to viscosity, decreasing the kinetic energy at a rate $\rho\nu|\nabla u|^2$.

These processes, whose terms appear on the RHS of (2.41), are irreversible.

If there are no fluxes of mass or momentum from the boundaries of V, then integrating the energy equation gives us:

$$\frac{d}{dt}(KE + PE) = W - \epsilon \tag{2.42}$$

where $KE = \int_V \frac{1}{2} \rho |\boldsymbol{u}|^2 dV$ and $PE = \int_V \rho gz dV$ be the total kinetic and potential energy of the system, $W = -\int_S p\boldsymbol{u} \cdot \boldsymbol{n} dS$ is the rate of pressure working and $\epsilon = \int_V \rho \nu \boldsymbol{\nabla} |\boldsymbol{u}|^2 dV$ is the rate of dissipation.

Energy is dissipated into heat. Kinetic and potential energy can be converted into each other, but mixing and dissipation cause irreversible.

⁴Incompressibility means that $\nabla \cdot u = 0$, but this does not mean that the density ρ is constant; ρ is governed by the advection-diffusion equation.

2.4 *Stably stratified flows

Not covered.

2.4.1 Stratification modifies turbulence

2.5 *Mixing efficiency

Not covered.

2.6 *Internal mixing

Not covered.

- 2.6.1 Kelvin-Helmholtz instability
- 2.6.2 Stratified shear flow
- 2.6.3 Holmboe instability
- 2.6.4 Entrainment by internal mixing

3 Shallow water

- 3.1 Introduction
- 3.2 Linear waves on an interface
- 3.2.1 Dispersion relation
- 3.2.2 Properties of interfacial waves
- 3.2.3 The short wave limit
- 3.2.4 The long wave limit
- **3.2.5** Energy
- 3.3 Shallow water equations
- 3.3.1 Mathematical definition of 'shallow'
- 3.3.2 Derivation from first principles
- 3.3.3 Boussinesq versus non-Boussinesq
- 3.3.4 More than one layer
- 3.3.5 Derivation by averaging
- 3.4 Hyperbolic systems
- 3.4.1 A model for traffic flow
- 3.4.2 Shallow water as a hyperbolic system
- 3.4.3 Matrix formulation
- 3.4.4 General approach to hyperbolic systems
- 3.4.5 Implications of hyperbolic nature




Figure 3: Characteristics for the St. Venant solution.

3.4.6 The dam break problem

Suppose initially we have $h = h_0$ in x < 0 and h = 0 in x > 0, and u = 0 everywhere. What happens?⁵. We let $c = \sqrt{gh}$ and $c_0 = \sqrt{gh_0}$ for convenience; $h = c^2/g$. As before, C_{\pm} characteristics travel with velocity $\lambda_{\pm} = u \pm c$ and the quantities $u \pm 2c$ are constant on C_{\pm} characteristics respectively.

The characteristics are sketched in Figure 3.

In Region I, where $x < -c_0 t$, both C_- and C_+ characteristics come from the region x < 0 at t = 0, and so u = 0 and $c = c_0$.

Assume that the C_+ characteristics from x < 0 fill Region II, the region between $x = -c_0t$ and to the left of the front. (We should check that these characteristics do in fact move faster than the front.) Then $u + 2c = 2c_0$ everywhere in that region. But also u - 2c is constant along C_- characteristics. Hence u and u must independently be constant along u characteristics. Hence u are characteristics have constant slope u and u must independently be constant along u characteristics.

If X_{-} is the position of a C_{-} characteristic, then

$$\frac{\mathrm{d}X_{-}}{\mathrm{d}t} = u - c. \tag{3.1}$$

So C_{-} characteristics which start at the origin are given by

$$\frac{x}{t} = u - c. ag{3.2}$$

⁵The following discussion is largely based on the discussion at http://www.wikiwaves.org/Nonlinear_Shallow_Water_Waves




Figure 4: The St. Venant solution.

We solve (3.2) together with $u + 2c = 2c_0$ to solve for u and c:

$$u = \frac{2}{3} \left(c_0 + \frac{x}{t} \right) \tag{3.3}$$

$$c = \frac{1}{3} \left(2c_0 - \frac{x}{t} \right) \tag{3.4}$$

$$h = \frac{1}{9g} \left(2c_0 - \frac{x}{t} \right)^2. \tag{3.5}$$

In particular, h = 0 at $x = 2c_0t$, so the front moves at speed $2c_0$. On the other hand,

$$\lambda_{+} = u + c \tag{3.6}$$

$$= \frac{4}{3}c_0 + \frac{x}{3t} \tag{3.7}$$

(3.8)

is the speed at which the C_+ characteristics move.

This is called the St. Venant solution, and it is sketched in Figure 4. It is not observed in practice. In practice, bottom drag and form drag have important effects which resist motion. Bottom drag is significant if the current is much more dense than the ambient. Form drag is significant if the ambient is much more dense than the current, or if the density difference is small.

3.4.7 Entrainment into shallow water flows

Turbulent often produces mixing: the blending of fluid particles of a different character. If we have a turbulent shallow water flow, then not only does the turbulence transport momentum within the flow, but it can also drive mixing between




Figure 5: Schematic for entrainment/detrainment for a shallow layer.

the flow and the ambient fluid. In particular, if the turbulence is in the moving shallow water layer, then it can cause the layer to entrain ambient fluid into the layer, affecting its volume, density and possibly its momentum.

This is true for *miscible fluids*. Immiscible fluids can entrain each other, but the resulting two-phase flow will separate again if allowed to.

Shallow water flows may be unstable both to short wave instabilities, such as Kelvin-Helmholtz and Holmboe instabilities, and to long wave instabilities.

Entrainment reduces the density contrast and therefore reduces g'. It also increases the volume of the layer of fluid, so increases h. For a quiescent ambient, the result of entrainment is that g'h is conserved. Also, the fluid that is being drawn in has a different (zero) momentum.

The setup is sketched in Figure 5. Assume that the ambient fluid density ρ_2 is constant, so that only the density in the layer ρ_1 changes. Let w_e be the speed of entrainment and w_d the speed of 'detrainment'. Then, by considering fluxes in and out of a control volume:

• Conservation of volume gives

$$\frac{\partial h}{\partial t} + \frac{\partial}{\partial x} (u_1 h) = w_e - w_d. \tag{3.9}$$

• Conservation of mass gives

$$\frac{\partial}{\partial t} (\rho_1 h) + \frac{\partial}{\partial x} (u_1 \rho_1 h) = w_e \rho_2 - w_d \rho_1 \tag{3.10}$$

or, using conservation of volume,

$$\frac{\partial \rho_1}{\partial t} + u_1 \frac{\partial rho_1}{\partial x} = -\frac{w_e}{h} (\rho_1 - \rho_2) \tag{3.11}$$

• The momentum balance (ignoring drag) gives

$$\frac{\partial}{\partial t} \left(\rho_1 h u_1 \right) + \frac{\partial}{\partial x} \left(u_1 \rho_1 h u_1 + \frac{1}{2} (\rho_1 - \rho_2) g h^2 \right) = w_e \rho_2 u_2 - w_d \rho_1 u_1. \tag{3.12}$$

We get this by taking the pressure to be hydrostatic and equal to p_0 at some reference height z_0 . Then the horizontal pressure gradient, integrated over the horizontal cross section, is

$$\int_0^h \frac{\partial p}{\partial x} dz = \int_0^h \frac{\partial}{\partial x} \left(p_0 + \rho_2 g(z_0 - z) + (\rho_1 - \rho_2) g(h - z) \right) dz \tag{3.13}$$

$$=\cdots$$
 (3.14)

$$= \frac{\partial}{\partial x} \left(\frac{1}{2} g(\rho_1 - \rho_2) h^2 \right). \tag{3.15}$$

Using conservation of mass, the momentum equation can also be written as

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial t} + g \frac{\rho_1 - \rho_2}{\rho_1} \frac{\partial h}{\partial x} + \frac{gh}{2\rho_1} \frac{\partial}{\partial x} (\rho_1 - \rho_2) = -w_e \frac{\rho_2}{\rho_1} \frac{u_1 - u_2}{h}$$
(3.16)

Note that conservation of volume does not strictly hold: Mass is conserved, but the density of a mixture will be different from the density of its constituents. For 'linear mixing', we can ignore changes in volume. We work in the Boussinesq approximation where $\rho_{1,2}$ are approximately equal, and assume that the ambient fluid is stationary: $u_2 = 0$. Then (3.16) reduces to

$$\frac{\partial u_1}{\partial t} + u_1 \frac{\partial u_1}{\partial t} + g' \frac{\partial h}{\partial x} + \frac{h}{2} \frac{\partial g'}{\partial x} = -w_e \frac{u_1}{h}$$
(3.17)

where $g' = g(\rho_1 - \rho_2)/\rho$. If we also write (3.11) in terms of g', then

$$\frac{\partial g'}{\partial t} + u_1 \frac{\partial g'}{\partial x} = -g' \frac{w_e}{h} \tag{3.18}$$

$$\frac{\partial g'}{\partial t} + u_1 \frac{\partial g'}{\partial x} = -g' \frac{w_e}{h}$$

$$\frac{\partial h}{\partial t} + u_1 \frac{\partial h}{\partial x} + h \frac{\partial u_1}{\partial x} = w_e - w_d$$
(3.18)

$$\frac{\partial u_1}{\partial t} + \frac{h}{2} \frac{\partial g'}{\partial x} + g' \frac{\partial h}{\partial x} + u_1 \frac{\partial u_1}{\partial x} = -u_1 \frac{w_e}{h}$$
(3.20)

or, in matrix form,

$$\begin{pmatrix} u_1 & 0 & 0 \\ 0 & u_1 & h \\ \frac{h}{2} & g' & u_1 \end{pmatrix} \begin{pmatrix} g' \\ h \\ u_1 \end{pmatrix}_x + \begin{pmatrix} g' \\ h \\ u_1 \end{pmatrix}_t = \begin{pmatrix} -g' \frac{w_e}{h} \\ w_e - w_d \\ -u_1 \frac{w_e}{h} \end{pmatrix}. \tag{3.21}$$

The system is still hyperbolic, as the matrix still admits three real, distinct eigenvalues: $\lambda = u_1$ and $\lambda = u_1 \pm (g'h)^{1/2}$. The latter two represent interfacial waves as before; the characteristic with $\lambda = u_1$ represents the advection of density. Since the RHS of (3.21) is nonzero, the evolution equations along those characteristics are inhomogeneous:

• Along the $\lambda = u_1$ characteristic, we have

$$\frac{\partial g'}{\partial s} = -g' \frac{w_e}{/h}; \tag{3.22}$$

• along the $\lambda = u_1 + (g'h)^{1/2}$ characteristic,

$$\frac{h}{2\sqrt{g'}}\frac{\partial g'}{\partial s} + \sqrt{g'}\frac{\partial h}{\partial s} + \sqrt{h}\frac{\partial u_1}{\partial s} = -\frac{1}{2}\sqrt{g'}w_e + \sqrt{g'}(w_e + w_d) - u_1\frac{w_e}{\sqrt{h}}.$$
(3.23)

- 3.5 Gravity currents
- 3.5.1 A moving dam problem
- 3.5.2 Description
- 3.5.3 Early models
- 3.5.4 Cavity flows
- 3.5.5 *Morden and Beiburg
- 3.5.6 Gravity currents and characteristics
- 3.5.7 Modelling gravity currents
- 3.5.8 Real life is more complex

4 Jets, plumes and thermals

A jet is a continuous directed release of fluid with a specified momentum from an isolated source (such as blowing from lips). A plume is a continuous release of buoyant fluid from an isolated source, with, ideally, no mass or momentum flux (e.g. a candle). The direction of a plume is given by g. A thermal is an isolated release of a finite patch of buoyancy.

Note that 'continuous', 'stable' and 'steady' are distinct terms, and no one of them implies either of the other.

We will assume that jets and plumes are axisymmetric and self-similar, so that any averaged quantity $\bar{\phi}$ can be written as

$$\bar{\phi} = \Phi(z)f(r/b) \tag{4.1}$$

where b is the 'radius' of the plume. The averaging may be an ensemble average or a temporal average. Specific forms for the function f may be taken. The simplest form for f is the top-hat profile

$$f(x) = \begin{cases} 0 & \text{if } x > 1\\ 1 & \text{if } x < 1. \end{cases}$$
 (4.2)

Other forms, such as the Gaussian $f(x) = \exp(-x^2)$, may also be used.

4.1 Jets

We define

$$\pi Q = \frac{1}{T} \int_0^T \int_0^\infty \int_{-\pi}^{\pi} wr \,\mathrm{d}\theta \,\mathrm{d}r \,\mathrm{d}t \tag{4.3}$$

$$\pi M = \frac{1}{T} \int_0^T \int_0^\infty \int_{-\pi}^{\pi} w^2 r \,\mathrm{d}\theta \,\mathrm{d}r \,\mathrm{d}t \tag{4.4}$$

(4.5)

as, respectively, the volume flux and momentum flux divided by density. The integral over t enacts a time-averaging. The π 's on the LHS are for convenience. For a top hat profile, these become

$$\pi Q = \pi b^2 W \tag{4.6}$$

$$\pi M = \pi b^2 W^2 \tag{4.7}$$

where we write W instead of w to emphasise that this is an averaged velocity, reserving w for the fluctuating local velocity. We have

$$W = M/Q (4.8)$$

$$b = Q/M^{1/2} (4.9)$$

Consider a steady jet travelling in the z direction. As the fluid in the jet travels, it entrains the surrounding fluid with entrainment velocity u_e . Experiments find that

$$u_e = \alpha W \tag{4.10}$$

where the entrainment coefficient α is between 0.065 and 0.080 for a top hat profile. Thus, the volume flux satisfies

$$\pi \frac{\mathrm{d}Q}{\mathrm{d}z} = 2\pi b u_e \tag{4.11}$$

$$=2\pi b\alpha W \tag{4.12}$$

$$= 2\alpha \pi M^{1/2}. (4.13)$$

Meanwhile, conservation of momentum gives

$$\pi \frac{\mathrm{d}M}{\mathrm{d}z} = 0. \tag{4.14}$$

Hence $M = M_0$ is constant along the plume. This gives

$$Q = 2\alpha M_0^{1/2} (z + z_{\nu}) \tag{4.15}$$

$$b = \alpha(z + z_{\nu}) \tag{4.16}$$

$$W = \frac{M_0^{1/2}}{2\alpha(z+z_\nu)}. (4.17)$$

So, the jet's thickness increases linearly with z, and the fluid velocity decreases with z. The point $z = -z_{\nu}$ is the 'virtual origin' of the jet: it looks as though there is a point source of momentum at this point, even though boundary conditions are being specified at z = 0.

4.2 General plume equations

4.2.1 Self-similar plumes

For plumes, the density of the fluid is not homogeneous, and so we need to consider fluxes of mass and momentum, rather than fluxes of volume and $\frac{\text{momentum}}{\text{density}}$. Therefore, we define

$$\pi Q = \frac{1}{T} \int_0^T \int_0^\infty \int_{-\pi}^\pi \hat{\rho} w r \,\mathrm{d}\theta \,\mathrm{d}r \,\mathrm{d}t \tag{4.18}$$

$$\pi M = \frac{1}{T} \int_0^T \int_0^\infty \int_{-\pi}^{\pi} \hat{\rho} w^2 r \, \mathrm{d}\theta \, \mathrm{d}r \, \mathrm{d}t \tag{4.19}$$

(4.20)

as the mass flux and momentum flux respectively. We also define

$$\pi F = \frac{1}{T} \int_0^T \int_0^\infty \int_{-\pi}^{\pi} (\rho_0 - \hat{\rho}) gwr \,d\theta \,dr \,dt$$

$$\tag{4.21}$$

as the buoyancy flux. Here $\hat{\rho}$ is the instantaneous, fluctuating density inside the plume, and ρ_0 is the density of the surrounding fluid. For top-hat profiles, these become

$$\pi Q = \pi \rho b^2 W \tag{4.22}$$

$$\pi M = \pi \rho b^2 W^2 \tag{4.23}$$

$$\pi F = \pi (\rho_0 - \rho) g b^2 W \tag{4.24}$$

where ρ is the density in the plume averaged across a cross-section. We also have

$$W = M/Q (4.25)$$

$$b = Q/(\rho M)^{1/2} \tag{4.26}$$

$$g' = F/Q. (4.27)$$

4.2.2 Time-dependent plume equations

Volume, mass and momentum balances on the plume give

$$\frac{\partial}{\partial t} \left(\pi b^2 \right) + \frac{\partial}{\partial z} \left(\pi b^2 W \right) = 2\pi b u_e \tag{4.28}$$

$$\frac{\partial}{\partial t} \left(\pi \rho b^2 \right) + \frac{\partial}{\partial z} \left(\pi \rho b^2 W \right) = 2\pi \rho_0 b u_e \tag{4.29}$$

$$\frac{\partial}{\partial t} \left(\pi \rho b^2 W \right) + \frac{\partial}{\partial z} \left(\pi \rho b^2 W^2 \right) = \pi b^2 (\rho_0 - \rho) g \tag{4.30}$$

(4.31)

which can also be written as

$$\frac{\partial}{\partial t} \left(\pi b^2 \right) + \frac{\partial}{\partial z} \left(\pi b^2 W \right) = 2\pi b u_e \tag{4.32}$$

$$\frac{\partial \rho}{\partial t} + W \frac{\partial \rho}{\partial z} = \frac{2(\rho_0 - \rho)u_e}{b} \tag{4.33}$$

$$\frac{\partial W}{\partial t} + W \frac{\partial W}{\partial z} = \frac{g(\rho_0 - \rho)}{\rho} - 2\frac{\rho_0}{\rho} \frac{u_e W}{b}$$
(4.34)

Experiments show that the entrainment velocity for plumes is

$$u_e = \alpha \left(\frac{\rho}{\rho_0}\right)^{1/2} W \tag{4.35}$$

where α is between 0.1 and 0.16 (but again depends on the top-hat profile). For Boussinesq plumes, $\rho \sim \rho_0$ and so $u_e \sim \alpha W$.

It can be shown that, in the Boussinesq case, the system is not hyperbolic, but is parabolic, and admits similarity solutions, as expected.

4.3 Plumes in a homogeneous environment

4.3.1 Steady Boussinesq plumes

It is found that F is constant.

4.3.2 Time-dependent plumes

4.3.3 Steady non-Boussinesq plumes

4.4 Plumes in a stratified environment

Now the ambient density ρ_0 is a function of height. This must be accounted for in the equation for F. It is found that F is not constant, and a power-law solution does not exist.

4.4.1 Rise height

4.4.2 Series solution in Boussinesq fluid

4.5 *Thermal in a homogeneous environment

4.6 *Thermals in a stratified environment

5 Particle-laden and granular flow

We consider the flow of a current consisting of a fluid with a well-mixed suspension of particles, with the particles denser than the fluid. The difference in density means that *buoyancy* has a role to play. The flow is driven by a pressure gradient and affected by the effects of buoyancy. Viscosity is negligible, so buoyancy and inertia balance each other.

Particles can settle out of suspension (*sedimentation*) or be *entrained* into suspension. This means the concentration of the particles in the suspension changes. So the density difference between the suspension and the ambient fluid changes too.

5.1 Types of particulate flows

We model four types of particulate gravity currents. The models are ad-hoc and apply to different geophysical situations, where different assumptions may be made about the flows and the particles:

Grain suspension by fluid turbulence Examples include pyroclastic flows, turbidity currents ⁶ and powder snow ⁷. In such flows, the particles may be very concentrated and denser than the fluid, but they are kept in suspension by the turbulent flow of the fluid; any particles which settle quickly undergo *resuspension*.

Liquefied and fluidised flow Examples include dense snow avalanches and *some* mudflows. In these cases, the flow is dominant and the particles move with the flow; in this regime, particles do not interact with each other (*cohesionlessness*), as they are separated from each other (*grain dispersion*)). Their effect is to increase the viscosity of the fluid. However, this limits the possibility of turbulence, and so particles can settle out at the base of the fluid.

Dry grain flow and interactions Examples include sand dune avalanches and rock slides. Now the particles interact with each other, colliding fequently; the fluid acts as a lubricant.

Grain-supported matrix Examples include debris flows and lahars, or large boulders suspended in a muddy matrix. Now cohesion has a large rôle to play. The flow of mud and slurries are non-Newtonian. Effects of cohesion, friction, pore pressure, etc. may be modelled using other stress-shear rate relationships (*rheological models*), including power laws, Bingham plastic models nad Herschel-Bulkley models. In the latter two models, the fluid has a *yield strength*: a minimum shear stress must be applied before any flow occurs.

5.2 Modelling a particulate gravity current

5.3 Physics within a particle gravity current

A particle gravity current can be modelled as having a main body and a base. In the main body, there is a well-mixed suspension of particles in a turbulent flow; in the base, the particles and fluid have low velocity and particles are settling out.

Let

- ρ_0 denote the density of the fluid;
- μ_0 denote the viscosity of the fluid;
- ρ_p denote the density of the particles;

⁶Wikipedia: A turbidity current is a current of rapidly moving, sediment-laden water moving down a slope through water, or another fluid. The current moves because it has a higher density than the fluid through which it flowsthe driving force of a turbidity current derives from its sediment, which renders the turbid water denser than the clear water above. The deposit of a turbidity current is called a turbidite.

⁷Wikipedia: Freshly fallen, uncompacted snow. The density and moisture content of powder snow can vary widely; snowfall in coastal regions and areas with higher humidity is usually heavier than a similar depth of snowfall in an arid or continental region. Light, dry (low moisture content, typically 47% water content) powder snow is prized by skiers and snowboarders. It is often found in the Rocky Mountains of North America and in most regions in Japan.

• ϕ denote the concentration of particles.

Then the bulk density of the fluid-particle mixture is

$$\rho_l = \rho_0 + \phi(\rho_p - \rho_0) \tag{5.1}$$

and the reduced gravity is

$$g' = g \frac{\rho_l - \rho_0}{\rho_0} = \phi g \frac{\rho_p - \rho_0}{\rho_0} = \phi g_0'$$
 (5.2)

where

$$g_0' = g \frac{\rho_p - \rho_0}{\rho_0}. (5.3)$$

5.4 Sedimenting particle-laden flows

We now assume that particles are small compared to the scale of motion, so that the presence of an individual particle has a negligible effect on the bulk flow. However, the collective of particles will have an effect. We also assume that particles sediment slowly, over a timescale much larger than that of the flow; and that particles are numerous and well-mixed, so that we can talk of the 'concentration' of particles, rather than having to study individual particles.

Note that although we use the word 'particles', all of this theory could just as well apply to bubbles or to droplets; a bubble can be regarded as a particle with density negligible compared to that of the fluid; the reduced gravity is negative.

The suspension changes the bulk properties of the fluid. As discussed, the suspension has density

$$\rho_l = \rho_0 + \phi(\rho_p - \rho_0) \tag{5.4}$$

where ϕ is the concentration by volume. We model the viscosity of the suspension as having a power law dependence on the concentration:

$$\mu = \mu_0 \left(1 - \frac{\phi}{\phi_{max}} \right)^{-n\phi_{max}} \tag{5.5}$$

where ϕ_{max} is the maximum suspension concentration that can be supported. For spherical particles, $n = \frac{5}{2}$.

We define the particle Reynolds number

$$Re_p = \frac{\rho_l D u_s}{\mu} \tag{5.6}$$

which governs many properties of the flow. Here D is the diameter of a particle, and u_s is the settling velocity, which we will determine.

When particles sediment out of suspension, we are left with a *clarified* fluid, devoid of particles, and a concentrated suspension at the bottom where all the particles gather.

Sedimenting flows can exhibit four types of behaviour, depending on Re_p and on the concentration ϕ :

- Type I: Free settling of individual particles
- Type II: Flocculant settling: Coaleescence of particles
- Type III: Hindered (zone) settling: Restricted, fluid motion
- Type IV: Compression settling: Mechanical support

We will discuss Types I and III in detail. Types II and IV involve complicated particle-particle interactions.

5.4.1 Type I: Free settling of individual particles

This occurs when particles are very well-separated from each other, and so do not interact with each other. This occurs at very low concentrations (the *dilute limit*).

⁸Whv?

The particle Reynolds number When a sphere of diameter D moves at a speed u_s through otherwise unmoving fluid, its behaviour depends on the particle Reynolds number $\text{Re}_p = \frac{\rho_t D u_s}{\mu}$. If $\text{Re}_p \ll 1$ then the flow past the sphere is laminar; the sphere travels smoothly. But if $10^3 \ll \text{Re}_p \ll 2 \cdot 10^5$ then the flow is in the inertial regime; the sphere travels roughly, and the boundary layer on the sphere is turbulent. Various other regimes are possible for different values of Re_p ; they are discussed in Middleton and Southard (1984).

The drag coefficient By dimensional analysis, the drag F_D on a particle travelling at u_s through a fluid is

$$F_D = C_D \frac{1}{2} \rho_l u_s^2 A_p \tag{5.7}$$

where A_p is the planar area of the particle. (See Prandtl and Tietjens, 1957 for details.) The dimensionless coefficient C_D is called the *drag coefficient*, and depends on the Reynolds number. The dependence may be found empirically:

• When $\text{Re}_p \ll 1$, then C_D is inversely proportional to Re_p :

$$C_D = \frac{24}{\text{Re}_p} \tag{5.8}$$

- When $0.2 < \text{Re}_p < 10^3$, there is a transitional region.
- When $10^3 < \text{Re}_p < 2 \cdot 10^5$, C_D is approximately constant for cylinders, spheres and discs. For these shapes, $C_D \approx 0.44$.
- At $\text{Re}_p \approx 2 \cdot 10^5$, the drag coefficient drops very quickly before increasing much more slowly again. This is called the *drag crisis regime*, and arises because of a flow separation.

The settling velocity So what is the settling velocity u_s ? We consider the momentum balance on a particle in suspension. The forces acting on the particle are drag, buoyancy and gravity, and so:

$$m\frac{\mathrm{d}u}{\mathrm{d}t} = F_g - F_b - F_D \tag{5.9}$$

$$F_D = C_D \frac{1}{2} \rho_l u^2 A_p \tag{5.10}$$

$$F_b = \rho_l g V \tag{5.11}$$

$$F_q = \rho_v g V \tag{5.12}$$

where V is the volume of the particle. The expression for F_b is given by Archimedes' law: the buoyancy force is g times the mass of fluid displaced. (Note that the fluid displaced is said to have density ρ_l rather than ρ_0 , though the two are approximately equal in the dilute limit.) Setting $\frac{du}{dt} = 0$ and solving for u gives us the terminal velocity, which is the settling velocity.

For a sphere of diameter D, we have $V = \frac{1}{6}\pi D^3$ and $A_p = \frac{1}{4}\pi D^2$, and so

$$u_s = \sqrt{\frac{4g(\rho_p - \rho_l)D}{3C_D\rho_l}}. (5.13)$$

Recall that in the Stokes regime with $\text{Re}_p < 0.2$, we have $C_D = \frac{24}{\text{Re}_p}$. Hence:

$$F_D = 3\pi u_s \mu D \tag{5.14}$$

$$u_s = \frac{g(\rho_p - \rho_l)D^2}{18\mu} \tag{5.15}$$

with $u_s \propto D^2$ and dependent on μ . But in the inertial, turbulent regime, with $10^3 < \text{Re}_p < 2 \cdot 10^5$, we have $C_D = 0.44$ constant, and

$$F_D = 0.055\pi \rho_l u_s^2 D^2 \tag{5.16}$$

$$u_s = 1.74\sqrt{\frac{g(\rho_p - \rho_l)D}{\rho_l}} \tag{5.17}$$

with $u_s \propto D^{1/2}$ and not dependent on μ .

These predictions are confirmed by observations: the Stokes regime holds for fine grains such as silt, whereas the inertial regime holds for very coarse sand, granules and pebbles (provided that particle-particle interactions may be neglected). However, for D between 0.1mm and 1mm (such as for medium or coarse sand), we are in the transitional regime where neither the Stokes nor the turbulent predictions hold well. Many equations have been proposed to describe the intermediate region, including the $Ferguson-Church\ equation.^9$

Advection and diffusion of particles The concentration of particles ϕ is governed by an advection-diffusion equation:

$$\frac{\partial \phi}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \phi = D \boldsymbol{\nabla}^2 \phi \tag{5.18}$$

where D now denotes the diffusion coefficient, not the particle diameter. The settling velocity which we have so far calculated was for an otherwise stationary fluid, so in (5.18) the particle velocity u is equal to

$$\mathbf{u} = (u, v, w) + (0, 0, -u_s) \tag{5.19}$$

where (u, v, w) is the mean velocity of the fluid.¹⁰

If there is no mean background fluid flow, then (5.18) reduces to

$$\frac{\partial \phi}{\partial t} - u_s \frac{\partial \phi}{\partial z} = D \nabla^2 \phi. \tag{5.20}$$

If we neglect dependencies on x and y, then (5.20) is Burgers' equation.

The diffusion coefficient D depends on Re_p and whether the flow is laminar or turbulent. In the laminar regime, diffusion of particles is due to molecular (Brownian) diffusion:

$$D = D_B \sim \frac{kT}{6\pi\mu r} \tag{5.21}$$

where r is the radius of particles, k is the Boltzmann constant and T is the temperature. Molecular diffusion is a very slow process unless r is very small, such as for aerosol particles.

However, in the turbulent regime, diffusion of particles is due to turbulent diffusivity:

$$D = D_T \sim u^* h \tag{5.22}$$

where $u^* = \sqrt{\frac{\tau_b}{\rho}}$ is the shear velocity (friction velocity), τ_b is the shear stress at the bottom, and h is some turbulence length scale, such as the distance from the bottom.

Note that if we ignore diffusivity in Equation 5.20 and set D=0, then the resulting equation admits shocks. This is because when the diffusivity is small, we have fronts where the concentration changes very sharply. To calculate the speed at which these fronts move, we can use the Rankine-Hugoniot conditions.

5.4.2 Type II: Flocculent settling, particle coalescence

In this regime, particles may coalesce together to form larger particles, which have larger settling velocities. Therefore settling in this regime occurs quicker than if particles do not coalesce. There is no mathematical theory to model this regime.

 $^{^9 \}mathrm{See}\ \mathrm{http://hinderedsettling.com/2013/08/09/grain-settling-python/.}$

¹⁰We can have fluid flow even if there is no mean fluid flow, if we are in a turbulent regime.

5.4.3 Type III: Hindered (zone) settling

When there are many particles, then particles no longer settle at the u_s which we have calculated, but at some slower velocity u_h , a hindered settling velocity. The hindered settling velocity depends on ϕ and on u_s . As ϕ increases, u_h decreases. As ϕ approaches ϕ_{max} , then more complicated inter-particle interactions take place and we start to have compression settling.

The model that we will use is

$$u_h = u_s \left(1 - \frac{\phi}{\phi_m ax} \right)^{\alpha} \tag{5.23}$$

where α is some empirically determined constant which depends on the flow regime.¹¹ Richardson and Zaki (1954) found that for ϕ up to 0.35, $\alpha = 4.65$ in the laminar regime $\text{Re}_p < 0.2$ and $\alpha = 2.39$ in the regime $\text{Re}_p > 500$.

The settling flux is

$$Q_h = u_h \phi. (5.24)$$

In a suspension with a steady concentration profile $\phi(z)$, the settling flux of particles downwards is balanced by diffusive flux upwards. Thus the concentration satisfies the *Rouse equation*:

$$\phi(z)u_h(z) = -D \frac{\mathrm{d}\phi(z)}{\mathrm{d}z} \tag{5.25}$$

where D is a diffusivity. This tends to happen if the flow is turbulent and D is large.

Nonlinear kinematic wave equation If $\phi = \phi(z,t)$ and diffusivity is small (which happens if the flow is laminar) then, as we have seen before, ϕ obeys the 'traffic equation'

$$\frac{\partial \phi}{\partial t} + \frac{\partial \phi u_h}{\partial z} = 0 \tag{5.26}$$

which may be solved by the method of characteristics. Again, solutions to this equation have shocks, which represent sharp fronts in a settling suspension.

Settling of particles on inclines

5.4.4 Type IV: Compressional settling, compacting

This regime occurs in regions of very high concentration. Stirring or tapping can allow the liquid to escape. The packing fraction may increase locally, leading to increased stability.

5.5 Sediment transport

Particles in a fluid can move by several means. Particles which are in suspension (the *suspended load*) or which have dissolved (the *dissolved load*) will move with the flow. Particles which have settled to the bottom of the fluid can roll or slide along the bottom, or by hopping (*saltation*). In a river, silt and clay tend to move by suspension; sand particles, which are larger, by saltation; gravel, larger still, by rolling and sliding.

A particle out of suspension does not necessarily move when there is a flow. A rock on the bed starts to move only when the flow exerts a critical shear stress on the bed. However, if the flow is turbulent then a sudden eddy may be able to move the rock: turbulent flows are stochastic, and need to be modelled as such.

Transport will change the morphology of the bed by erosion deposition: a strong flow can break up large rocks into smaller pieces. This in turn changes whether these particles are able to be suspended or settle out of suspension.

 $^{^{11} \}mbox{Following}$ 'A physical introduction to suspension dynamics'.

5.6 Aqueous and aeolian bedforms (dunes)

5.7 Dry granular flows, rheology, segregation

Most granular materials do not fill the space that they occupy, but instead have a packing fraction ϕ . The packing fraction is variable for a given material: a collection of uniform rigid spheres has a maximum packing fraction of $\phi \approx 0.74$, but randomly packed spheres have typically $\phi \approx 0.64$. The value of the packing fraction depends on the history of the material: that is, how it came to be arranged as it is. A pile of sand could have very different packing fractions depending on whether the sand was simply poured onto a surface, or slowly added and packed together.

A granular flow with particles of different sizes or densities will exhibit *segregation*. Larger particles will tend to come to the top of the flow. We can demonstrate this by shaking a jar containing sand and marbles.