Lecture 15: x86-64 assembly language, code generation

David Hovemeyer

October 24, 2022

601.428/628 Compilers and Interpreters





Today

- ► x86-64 assembly language
- ► x86-64 tips
- ► Code generation

x64-64 assembly language

x86-64 assembly language

- ➤ Your compiler (in Assignments 3–6) will generate x86-64 assembly language
- ➤ x86-64 is the dominant instruction set architecture for general purpose computing (laptops, servers, etc.)
 - ► ARM is making inroads, though
- ► It's a 64-bit architecture
 - Registers are 64 bits wide
 - ► Memory addresses are 64 bits

x86-64 registers


Register(s)	Note
%rip	Instruction pointer
%rax	Function return value
%rdi, %rsi	
%rbx, %rcx, %rdx	
%rsp, %rbp	Stack pointer, frame pointer
%r8, %r9,, %r15	

All of these registers are 64 bits (8 bytes)

Aside from %rip and %rsp, all of these are general-purpose registers

"Sub"-registers

- ► For historical reasons (evolution of x86 architecture from 16 to 64 bits), each data register is divided into
 - ► Low byte
 - Second lowest byte
 - ► Lowest 2 bytes (16 bits)
 - ► Lowest 4 bytes (32 bits)
- ► E.g., %rax register has %al, %ah, %ax, %eax:



Naming of sub-registers

		Sub-re	gister
Register	32 bit	16 bit	Lowest 8 bit
%rax	%eax	%ax	%al
%rbx	%ebx	%bx	%bl
%rcx	%ecx	%cx	%cl
%rdx	%edx	%dx	%dl
%rdi	%edi	%di	%dil
%rsi	%esi	%si	%sil
%rsp	%esp	%sp	%spl
%rbp	%ebp	%bp	%bpl
$ m \%r8^{1}$	%r8d	%r8w	%r8b



 $^{^1\}mathrm{Same}$ pattern for %r9–%r15

Stack

- ► The %rsp register is the *stack pointer*
 - ► Contains address of "top" of stack
 - ► Stack grows down (from high to low addresses), so %rsp decreases as stack grows

Assembly language syntax

- ► Each instruction has a mnemonic (mov, push, add, etc.)
- ▶ Most instructions will have one or two *operands* that specify data values (input and/or output)
 - ► At most **one** operand can be a memory reference
- ► On Linux, the standard tools use "AT&T" assembly syntax
 - Source is first operand, destination is second
- For instructions that do computations, destination operand is also a source value!
 - ► I.e., they are destructive
 - ► This makes code generation a bit interesting

Labels

- ➤ A label gives a name to the address of a location in memory (code or data)
 - ► Eventual runtime address generally not known ahead of time, linker and/or dynamic linker will resolve prior to execution
- Used to refer to procedures
- ▶ Used to refer to intermediate locations within procedure (local labels)
- Used to refer to global data and constants

Operand size suffixes

➤ You will notice that instruction mnemonics sometimes use suffixes to indicate the operand size:

Suffix	Bytes	Bits	Note
b	1	8	"Byte"
W	2	16	"Word"
1	4	32	"Long" word
q	8	64	"Quad" word

(Use of w to mean 16 bits shows 16-bit origins of x86)

- ► E.g., movq means move a 64 bit value
- ➤ You can often omit the operand size suffix, but it's helpful for readability, and can even catch bugs

Assembly operands

Assume count and arr are global variables, R is a register, N is an immediate, S is 1, 2, 4, or 8

Type	Syntax	Example	Note
Memory ref	Addr	count	Absolute memory address
I mmediate	\$N	\$8, \$arr	\$arr is address of arr
Register	R	%rax	
Memory ref	(<i>R</i>)	(%rax)	Address = %rax
Memory ref	N(R)	8(%rax)	$Address = \mathtt{\%rax} + 8$
Memory ref	(R,R)	(%rax,%rsi)	$Address = \mathtt{\%rax} + \mathtt{\%rsi}$
Memory ref	N(R,R)	8(%rax,%rsi)	$Address = \rank{rax} + \rak{rsi} + 8$
Memory ref	(R,S)	(,%rsi,4)	$Address = \mathtt{\%rsi} { imes 4}$
Memory ref	(R,R,S)	(%rax,%rsi,4)	$Address = \mathtt{\%rax} + (\mathtt{\%rsi} \times \mathtt{4})$
Memory ref	N(R,S)	8(,%rsi,4)	$Address = (\mathtt{\%rsi}{ imes}4) + 8$
Memory ref	N(R,R,S)	8(%rax,%rsi,4)	$Address = \mathtt{\%rax} + (\mathtt{\%rsi} \times 4) + 8$

Data movement

90% of assembly code is data movement (made-up statistic)

- mov: copy source operand to destination operand
 - Register
 - Memory location (only one operand can be memory location)
 - Immediate value (source operand only)
- ► Stack manipulation: push and pop instructions
 - Generally used for saving and restoring register values
 - ▶ push: decrement %rsp by operand size, copy operand to (%rsp)
 - ▶ pop: copy (%rsp) to operand, increment %rsp by operand size

Data movement examples

Instruction	Note
movq \$42, %rax	Store the constant value 42 in %rax
movq %rax, %rdi	Copy 8 byte value from %rax to %rdi
movl %eax, 4(%rdx)	Move 4 byte value from %eax to memory at address %rdx+4
pushq %rbp	Decrement %rsp by 8,
	store contents of %rbp in memory location %rsp
popq %rbp	Load contents of memory location %rsp into %rbp,
	increment %rsp by 8

ALU operations

- ► ALU = "Arithmetic Logic Unit"
- ► An ALU is a hardware component within the CPU that does computations (of various kinds) on data values
 - ► Addition/subtraction
 - ► Logical operations (shifts, bitwise and/or/negation), etc.
- ▶ So, ALU instructions are the ones that do computations on values
 - ► Typically, ALU operates only on integer values
 - CPU will typically have floating-point unit(s) for operations on FP values

lea instruction

- ▶ lea stands for "Load Effective Address"
- ► Instructions that allow a memory reference as an operand generally do an address computation
 - ► E.g., movl 12(%rdx, %rsi, 4), %eax
 - ► Computed address (for source memory location) is %rdx+(%rsi×4)+12
- The lea instruction computes a memory address, but does not access a memory location
 - ► E.g., leaq 12(%rdx, %rsi, 4), %rdi
 - ▶ Quite similar to the address-of (&) operator in C and C++



Addition, subtraction

- add and sub instructions add and subtract integer values
- ▶ Two operands, second operand modified to store the result
 - ▶ Note that either operand (but not both) could be a memory reference
- ► E.g.,

```
movq $1, %r9
movq $2, %r10
addq %r9, %r10
/* %r10 now contains the value 3 */
```

- Overflow is possible!
 - ► Can detect using condition codes

Other ALU operations

There are lots of other ALU instructions!

- ▶ inc, dec (increment and decrement)
- ► Multiplication and division
- ► Logical/bitwise operations

Consult your favorite x86-64 reference for details

Control flow, condition codes

- ▶ Intra-procedural control flow: unconditional jump, conditional jump
- ► Target is the address of an instruction (in the same procedure)
 - Usually specified by a label
- ► Conditional jump check a *condition code*
 - ► E.g., "jump if equal", "jump if less than", etc.
- ► Most ALU instructions set condition codes
- Most useful one is the cmp instruction

Comparing values

- cmp instruction: essentially the same as sub, except that it doesn't modify the "result" operand
 - Useful for comparing integer values
- ► Annoying quirk: AT&T syntax puts the operands in the opposite of the order you might expect
 - ► E.g., cmpl %eax, %ebx computes %ebx %eax and sets condition codes appropriately

Conditional jump

Most often, we want to use the result of a comparison in order to influence a conditional jump instruction (used for implementing if/else logic and eventually-terminating loops)

Examples (^ means XOR, ~ means NOT, & means AND, | means OR):

Instruction	Condition for jump	Meaning
je, jz	ZF	jump if equal
jl	SF ^ OF	jump if less
jle	(SF ^ OF) ZF	jump if less than or equal
jg	~(SF ^ OF) & ~ZF	jump if greater
jge	~(SF ^ OF)	jump if greater than or equal
ja	~CF & ~ZF	jump if above (unsigned)
jae	~CF	jump if above or equal (unsigned)
jb	CF	jump if below (unsigned)
jbe	CF ZF	jump if below or equal (unsigned)

call and ret

- ► call instruction: calls procedure
 - %rip contains address of instruction following call instruction
 - ▶ Push %rip onto stack (as though pushq %rip was executed): this is the return address
 - ► Change %rip to address of first instruction of called procedure
 - Called procedure starts executing
- ▶ ret instruction: return from procedure
 - ▶ Pop saved return address from stack into %rip (as though popq %rip was executed)
 - Execution continues at return address

Stack alignment

- ➤ The Linux x86-64 calling conventions require %rsp to be a multiple of 16 at the point of a procedure call (to ensure that 16 byte values can be accessed on the stack if necessary)
- ▶ Issue: on entry to a procedure, %rsp mod 16 = 8 because the call instruction (which called the procedure) pushed %rip (the program counter) onto the stack

Ensuring correct stack alignment

- ► To ensure correct stack alignment:
 - ► On procedure entry: subq \$8, %rsp
 - ▶ Prior to procedure return: addq \$8, %rsp
- ► The Linux printf function will segfault if the stack is misaligned

Register use conventions

- ► Very important issue:
 - ► There is only one set of registers
 - Procedures must share them
 - Register use conventions are rules that all procedures use to avoid conflicts
- Another important issue:
 - ▶ How are argument values passed to called procedures?
 - Calling conventions typically designate that some argument values are passed in specific registers
 - Procedure return value is typically returned in a specific register

x86-64 Linux register use conventions

- ► Arguments 1–6 passed in %rdi, %rsi, %rdx, %rcx, %r8, %r9
 - ► Argument 7 and beyond, and "large" arguments such as pass-by-value struct data, passed on stack
- ► Integer or pointer return value returned in %rax
- ► Caller-saved registers: %r10, %r11 (and also the argument registers)
- ► Callee-saved registers: %rbx, %rbp, %r12, %r13, %14, %r15

Caller-saved vs. callee-saved

- ▶ What happens to register contents when a procedure is called?
- ► Callee-saved registers: caller may assume that the procedure call will preserve their value
 - ▶ In general, all procedures must save their values to memory before modifying them, and restore them before returning
- ► Caller-saved registers: caller must *not* assume that the procedure call will preserve their value
 - In general any procedure can freely modify them
 - ► A caller might need to save their contents to memory prior to calling a procedure and restore the value afterwards

Using registers

- Using registers correctly and effectively is one of the main challenges of assembly language programming
- ► Some advice:
 - ▶ Use caller-saved registers (%r10, %r11, etc.) for very short-term temporary values or computations
 - ▶ You can use the argument registers as (caller-saved) temporary registers
 - Understand that called procedures could modify them!
 - ► Use callee-saved registers for longer term values that need to persist across procedure calls
 - Use pushq/popq to save and restore their values on procedure entry and exit



x86-64 tips

Know where to put things

- ► The .section directive specifies which "section" of the executable program assembled code or data will be placed in
- ▶ Put things in the right place!
- ► Code goes in .text
- Read-only data such as string constants go in .rodata
- Uninitialized (zero-filled) variables and buffers go in .bss
 - ▶ Use the .space directive to indicate how large these are
- ▶ Initialized (non-zero-filled) variables and buffers go in .data
 - ► There are various directives such as .byte, .2byte, .4byte, etc. to specify initialized data values

Labels

- ► Labels are names representing addresses of code or data in memory
- ► For functions and global variables, use appropriate names
 - ► Functions and data exported to other modules must be marked with .glob1
- ► For control-flow targets within a function, use *local labels*
 - ► These are labels which start with .L (dot, followed by upper case L)
 - ▶ The assembler will not add these to the module's symbol table
 - ▶ Using "normal" labels for control flow makes debugging difficult because gdb thinks they are functions!

Using gdb

- ► You can debug assembly programs using gdb!
- ► "Debugging by adding print statements" is less practical for assembly programs than programs in a high level language
 - ▶ Which isn't to say it's not possible or (occasionally) useful
- ▶ Being able to use gdb confidently will greatly enhance your ability to develop working assembly language programs

gdb tips

- ► Set breakpoints (break main, break myProg.S:123)
- ▶ where: see current call stack
- disassemble (or just disas): display assembly code of current function (not necessary if code has debug symbols)
- step: step to next instruction
- next: step to next instruction (stepping over call instructions)
- ▶ Use \$ prefix to refer to registers (e.g., \$rax, \$edi, etc.)
- ▶ Use print and casts to C data types when inspecting data:
 - ▶ Print 64 bit value %rsp points to: print *(unsigned long *)\$rsp
 - ▶ Print character string %rdi points to: print (char *)\$rdi
 - ▶ Print fourth element of array of int elements that %r12 points to: print ((int *)\$r12)[3]



Code generation

Initial code generation

- ▶ Important milestone in compiler development: generate working code
- ► Goal is to generate *working* code, not necessarily *efficient code*
- Later optimization passes improve code quality
- ► Approach: use control-flow graph as IR
 - Nodes are basic blocks
 - Each basic block is sequence of instructions
 - ▶ Jump instructions must be last
- Could generate "high-level" (machine-independent) instructions
- Or, could generate instructions equivalent to target assembly language

High-level code generation

- ► Suggested approach: first generate *high-level* code
 - ► Abstract "RISC-like" instructions
 - ► Similar to ILOC from textbook
- ► Infinite number of virtual registers
- ► Focus on *what* operations the program will execute when it runs
- Claim: this representation will be relatively easy to analyze, transform
- ► Translation to target (x86-64) code can happen once we've eliminated redundancies/inefficiencies in the high-level code


Code generation strategy

- ► Build symbol tables, determine storage requirements (size and offset) for variables
- Code generator is an AST visitor
 - ► Code generation is essentially a bottom-up process
- Assume registers can be allocated as needed
- Value computed by each expression is held in a register
- Scalar variables (e.g., int) can have virtual registers allocated as their storage


Example program

```
int main(void) {
  int n, i, sum;
 n = 11;
  i = 1;
  sum = 0;
  while (i \le n) {
    sum = sum + i;
    i = i + 1;
  return sum;
```

Example program AST



Example program AST (executable statements)



Example program AST (executable statements)

