### Lecture 13: Intermediate representations

David Hovemeyer

October 16, 2023

601.428/628 Compilers and Interpreters



# Agenda

- ▶ Purpose of intermediate representations
- ► ASTs
- ► Linear IRs
- ► Control-flow graphs
- ► IR forms and compiler phases
- ► Are IRs necessary?

# Purpose of IRs

# What is an intermediate representation (IR)?

- ► "Intermediate representation" is a general term for any data structure which represents the program (or part of the program) being translated by the compiler
- Compilers typically have various *phases* for which different forms of IR are appropriate
- Examples:
  - Abstract Syntax Tree (AST)
  - ► Three-address code (a.k.a. "quads")
  - ► Control-flow graph

### Facts, annotation of IR

- ▶ IRs represent *facts* about the program
  - ► An IR can be *annotated* by these facts to make them available for compiler phases that need them
- ► Kinds of facts:
  - ► Facts that are directly embodied by the source code
  - ► Facts *inferred* from the program's syntax and semantics
  - ► Facts that are created/chosen by the compiler (decisions made to enable translation to the target language)

## Examples of facts

- ► "Fact" = "something that is true at a particular program location"
- **Examples**:
  - ► The name "a" refers to a variable of type int (embodied by the source code)
  - ▶ The variable "a" contains the value 123 (inferred fact)
  - ► The storage for variable "a" is located at offset 12 in the stack frame (created fact)

# Abstract Syntax Trees

# Abstract Syntax Trees

- ► ASTs are a "condensed" form of the parse tree based on the derivation found by the parser based on the source language's syntax rules
  - ► Nodes are labeled to identify what kind of source construct they represent (function def, variable declaration, etc.)
- ► AST nodes can be annotated with useful information
  - Pointer to symbol table entry
  - Type
  - ▶ Whether or not an expression is an Ivalue
  - ► Etc.

# Example C program

```
int main(int argc, char **argv) {
  return argc + 1;
}
```

# AST of example C program

```
AST_UNIT
+--AST_FUNCTION_DEFINITION
  +--AST_BASIC_TYPE
   | +--TOK INT[int]
  +--TOK IDENT[main]
  +--AST_FUNCTION_PARAMETER_LIST
   | +--AST_FUNCTION_PARAMETER
     | +--AST_BASIC_TYPE
     | | +--TOK INT[int]
     | +--AST NAMED DECLARATOR
           +--TOK IDENT[argc]
     +--AST FUNCTION PARAMETER
        +--AST BASIC TYPE
         | +--TOK CHAR[char]
        +--AST POINTER DECLARATOR
            +--AST POINTER DECLARATOR
              +--AST NAMED DECLARATOR
                  +--TOK IDENT[argv]
  +--AST_STATEMENT_LIST
      +--AST_RETURN_EXPRESSION_STATEMENT
         +--AST_BINARY_EXPRESSION
            +--TOK PLUS[+]
            +--AST VARIABLE REF
             +--TOK_IDENT[argc]
            +--AST_LITERAL_VALUE
               +--TOK INT LIT[1]
```

# AST implementation

- ► AST is just a tree
- ► Each node labeled with "tag" indicating meaning of construct
- ▶ Add member variables as needed to store annotations in nodes

#### NodeBase class

- ▶ In Assignments 3–5, the Node class inherits from NodeBase
- ▶ You can modify NodeBase to add member variables, member functions
- ► That way, if we needed to give you an updated version of Node, you wouldn't lose the things you added

### Things to put in NodeBase

```
class NodeBase {
private:
   Symbol *m_symbol;
   std::shared_ptr<Type> m_type;
   bool m_is_lvalue;
   // etc...
```

Note that the pointer to Symbol (a symbol table entry object) should be a "dumb" pointer because Symbol objects are owned by the SymbolTable object in which they reside

#### Aside: source to source translation

- ► A compiler's target language doesn't need to be assembly language: it could be *source code*
- ► The target language could even be the same as (or similar to) the source language
- ▶ In a source-to-source translator, the syntax tree representing the original source code should contain enough information to reproduce it precisely
  - ► Which means you would need to avoid simplifications that would lose information


#### Aside: DAGs

- ► DAGs (Directed Acyclic Graphs) can be useful for recognizing and avoiding redundancy in computations
- ▶ Idea is to represent repeated computations with a single representation

# DAG example

Computation:  $a \times (3+b) - (3+b)/c$ 


As AST:



# DAG example

Computation:  $a \times (3+b) - (3+b)/c$ 

As DAG:



#### DAGs: worthwhile?

- Redundancies made explicit with DAGs could enable generation of more efficient code
- ► E.g., a recursive treewalk, when visiting a previously-visited portion of the DAG, could make use of the result of the previously-emitted code
- ► However, there are good techniques to find and eliminate redundant computations in linear IRs (e.g., value numbering)
- Personal opinion: I'm a bit skeptical whether tree-based optimizations are worth the effort

# Linear IRs

#### Linear IRs

- ▶ A *linear IR* is an intermediate representation a sequence of instructions
- ► Reasons why this is useful:
  - ▶ Is "closer" to target code than AST
  - Concisely represents the operations the program needs to perform when it is executed
  - Can be fairly convenient for analysis and optimization
- ▶ Disadvantage: doesn't naturally capture control flow (because execution is not sequential when there is a branch)
  - ► Control-flow graphs extend linear IRs to naturally represent control flow

### Quads

- Quads are a common approach to implementing a linear IR
- ► Each instruction consists of
  - ► A single operation
  - Between 0 and 3 operands
  - ▶ Most instructions: one destination operand, two source operands
- ► An operand could represent
  - 1. A literal (immediate) value
  - 2. A register
  - 3. A memory reference via a pointer stored in a register
- Other forms of operands could be represented, but the ones above are sufficient in general

# Quads (format, examples)

General format of a quad:

Example:

Expressed as "assembly language":

mov\_q, vr10, vr11, vr12

Note that some opcodes might not require all three operands:

# "High-level" linear IR

- ► Many compilers have a "high-level" linear IR form (usually implemented as quads) which is not directly related to the target language
- ► Typically, the high-level IR
  - ▶ Is RISC-like (ALU operations have two source operands, one destination operand)
  - ► Has an "infinite" number of registers
  - ► Various opcodes to represent computations on values, loads from/stores to memory, comparisons, control flow
- Why is this kind of representation useful?

# Why high-level linear IR is useful

- ► A high-level linear IR represents the operations that the source program should perform
- ▶ Because it's "RISC-like", computed values are given explicit names
  - ► For example, in add\_q vr10, vr11, vr12, the sum of the 64-bit values in vr11 and vr12 is given the name vr10
  - ► An important class of optimizations involves detecting when a value that is needed has been computed previously
  - ▶ If each computation places its result in a location (register) with a distinct name, it maximizes the extent to which computed values are available
  - ▶ Because high-level instructions don't modify the contents of source operands, they don't "destroy" computed values which might be useful



# Why not use an IR based on the target language?

- ➤ Since the eventual goal of the compiler is to produce a translation of the source language to the target language, why not have an IR based on the target language?
- ► Answer: we *will* need an IR based on the target language; we'll refer to this as the "low-level" linear IR
- ► However, before creating the low-level IR, the compiler will first produce a translation as high-level IR
  - ▶ It should be reasonably straightforward to translate the high-level linear IR to equivalent low-level linear IR

### Benefits of a high-level IR

- ► Compiler can have multiple "back ends" which translate to different target languages (e.g., x86-64 assembly and ARM assembly)
- ▶ Optimizations can be implemented on the high-level IR (which is designed to be amenable to analysis)
  - ▶ Optimizations on low-level code are also possible and useful, but optimizations on high-level IR are inherently shared between back ends)
- ► The target language may have features which make analysis and optimization more difficult
  - ► E.g., x86 instructions generally make one operand both a source and a destination

### Instruction implementation

```
class Instruction {
private:
  int m opcode;
  unsigned m_num_operands;
  Operand m operands[3];
  // ...
public:
  // ...
  unsigned get num operands() const;
  const Operand &get operand(unsigned index) const;
  void set_operand(unsigned index, const Operand &operand);
  // ...
};
```

Idea: an Instruction is a quad with up to three operands

# Operand implementation

```
class Operand {
public:
  enum Kind { /* ...members... */ };
private:
  Kind m_kind;
  int m basereg, m index reg;
  long m imm ival; // also used for offset and scale
  std::string m_label;
public:
  // ...
  Kind get_kind() const;
  int get base reg() const;
  int get_index_reg() const;
  long get_imm_ival() const;
  long get_offset() const;
  long get_scale() const;
  // ...
```

Idea: an operand represents a register, memory reference via a pointer in a register, an immediate integer value, or a label

A memory reference can optionally have an offset, index, and/or scaling factor

### Instruction sequence implementation

```
class InstructionSequence {
                                        Idea: an InstructionSequence is a
private:
                                        sequence of Instruction objects
  struct Slot {
                                        (quads)
    std::string label;
    Instruction *ins;
  };
                                        Each Instruction may (optionally)
  std::vector<Slot> m instructions;
                                        have a label (to allow it to be a control
  std::string m next label;
                                        flow target)
public:
  // ...
  void append(Instruction *ins);
  unsigned get length() const;
  Instruction *get_instruction(unsigned index) const;
  void define label(const std::string &label);
  std::string get_label_at_index(unsigned index) const;
  unsigned get_index_of_labeled_instruction(const std::string &label) const;
  // ...
                                                         4 D > 4 B > 4 B > 4 B > 9 Q P
```

### Aside: memory use

- ► Since an IR is an in-memory representation of a program (or part of a program), the amount of memory it occupies can be significant
- ► For an ahead-of-time compiler on a modern system with a large amount of main memory, might not be a huge concern
- ► For a just-in-time (JIT) compiler, size of IR could be *very* significant

### Aside: level of detail in high-level IR

- ► In designing a high-level linear IR, there is a question concerning how "detailed" the instructions should be
- ► More specifically, how close are the high-level IR instructions to operations in the source program?

# Example: assigning to an array element

Consider the following C code:

```
a[i] = x;
```

Assume vr10 is a pointer to the first element of a, vr11 is the variable i, vr12 is the variable x, and the elements of a are 8 bytes in size.

How to translate this statement into high-level IR?

# Option 1: high-level

```
Translating a[i] = x;
mov_q (vr10,vr11,8), vr12
```

This translation assumes the high-level IR has an indexed and scaled addressing mode for memory references.

# Option 2: low-level

 $mov_q$ 

(vr14), vr12

```
Translating a[i] = x;

mul_q vr13, vr11, $8  /* compute element offset */
add q vr14, vr10, vr13  /* add offset to base address */
```

This translation does an explicit computation of the memory address of the element at index i (note that vr13 and vr14 are "temp registers" allocated to store partial results of the address computation)

# Which approach is better?

Opinion: the low-level approach is better.

Making the high-level IR more complicated will make it more complicated to analyze and transform.

► It will also make the IR larger (in memory)

Techniques such as peephole optimization can be *very* effective for replacing explicit address computations with "fancy" addressing modes supported by the target language.

More generally, "simple and explicit" is good for earlier (higher-level) IR forms.

# Control-flow graphs

### Labels and control flow

The Instructions in an InstructionSequence can have labels, which can be referenced by control flow instructions.

#### Example C function:

```
int min(int a, int b) {
  if (a < b)
    return a;
  else
    return b;
}</pre>
```

### High-level IR code for min function

```
enter $0
mov_l vr10, vr1
mov_l vr11, vr2
cmplt_l vr12, vr10, vr11
cjmp_f vr12, .L1
mov_l vr0, vr10
jmp .Lmin_return
.L1: mov_l vr0, vr11
jmp .Lmin_return
.Lmin_return: leave $0
ret
```

Note: vr0 is the return value register, and vr1 and vr2 are argument registers

#### Observation

Analyzing and optimizing a sequence of instructions is complicated if there is control flow.

Idea: it's easier to analyze and transform "straight line" sequences of instructions

A *basic block* is an instruction sequence in which only the last instruction can be a jump or conditional jump

▶ Within the basic block, execution is strictly sequential

A control-flow graph is graph in which the nodes are basic blocks

► A directed edge from node "A" to node "B" indicates that control may flow from the end of "A" to the beginning of "B"



### Control-flow graphs


A *control-flow graph* is a graph of *basic blocks* representing one function in the program

A *basic block* is a sequence of instructions (e.g., quads) such that if there is a branch, it is the last instruction in the sequence

A control-flow graph should have a single entry node and a single exit node

▶ If the function has multiple return statements, each basic block ending with a return implicitly jumps to the common exit block

## Example control-flow graph (min function)



### Role of control-flow graphs


- ► Control-flow graphs allow for analyses and transformations which take control-flow into account
  - ► Especially: *dataflow* analyses
- ► A linear IR can be freely converted to and from a control-flow graph as necessary
- ▶ We'll have much more to say about control-flow graphs later on

## IR forms and compiler phases

### IR forms and compiler phases

- ▶ Different IR forms are appropriate at different points in the overall transformation from source code to target code
- ► The computations to make progress in the transformation are sometimes organized into "phases"
  - ► The process of moving towards the eventual target code representation is sometimes called "lowering"
- What these phases are called and what they do varies significantly from compiler to compiler

### Possible organization



Note that optimizations will convert between linear IR and control-flow graphs as necessary



# Are IRs necessary?

### Utility and cost of IRs

- ► Intermediate representations are useful to allow analysis and transformation of code so that the quality of the generated code can be improved
- ► However, IRs can require significant memory
- ▶ If we're not too concerned about the absolute efficiency of the generated code, we could just generate it "on the fly"

## "On the fly" translation

- Examples of on the fly codegen:
  - ► Tiny C compiler (tcc): https://bellard.org/tcc/
  - ➤ Some language virtual machines work this way when generating the initial translation of a function (e.g., JikesRVM's baseline compiler)
- ► This approach can make sense if the goal is to generate code quickly