Part I Syllabus

Lecture	Date	Subject
1	10/08/2016	Introduction
2	10/08/2016	Layered network architecture & Physical resilience
3	17/08/2016	Data link layer – flow control
4	17/08/2016	Data link layer – error control
5	24/08/2016	Data link layer – HDLC
6	24/08/2016	Local area network – introduction
7	31/08/2016	Local area network – MAC
8	31/08/2016	Local area network – Ethernet
9	07/09/2016	Local area network – WLAN
10	07/09/2016	Packet switch network - Introduction
11	14/09/2016	Packet switch network – queue analysis
12	14/09/2016	Review and examples



Drinking from Fire Hose









WWW.PHDCOMICS.COM



CE3005/CPE302 Computer Networks

Lecture 3 Data Link Layer (DLL): Flow Control




Contents

Data Link Layer Fundamentals

- DLL Services
- Framing mechanisms
- Link configuration

Flow Control in DLL

- Main purpose of flow control
- Stop-and-wait mechanism
- Sliding window mechanism






Data Link Layer Fundamentals



Data Link Layer: Roles

DLL Services

- Framing: encapsulate each network-layer datagram within a link-layer frame before transmission over the link
- Link Access: MAC protocol specifying the rules by which a frame is transmitted onto the link
- Flow Control: control of data flow to ensure sender not overwhelm the receiver with data
- Reliable Delivery: move each network-layer datagram across the link without error



Sublayer in Local Area Networks



Framing

Byte Oriented (Character Oriented):

- Information is framed into a fixed 8-bit basic unit.
- Some of these basic units are used for signaling (protocol control).
- Good solution when digital technology was in its primitive age (late 60s).

Bit Oriented (HDLC)


- A flag is used to frame the bits sent.
- Header/Trailer are used to describe the content of a frame. Frames may be used for control.
- Used by all modern protocols (eg HDLC, PPP, Ethernet, etc).



Byte-Oriented Async. Transmission

Pre-determined frame format

- Start/stop bit
- Parity check bit
- Data bits





Link Configuration/Access

- Objective: determine who gets to transmit at when on a link
- Topology: physical arrangement of stations
 - Point-to-Point: pairs of hosts are directly connected
 - Broadcast: all stations share a single channel


Duplexity

- Half Duplex: Only one party may transmit at a time.
- Full Duplex: Allows simultaneous transmission and reception between two parties (eg two logical halfduplex channels on a single physical channel).




Topology

Point-to-point:



Point-to-Multipoint (Broadcast):



All terminals share the same medium controlled by the primary station (mainframe)




Flow Control



Functions and Mechanisms

Flow control

- Ensuring that a transmitting station does not overwhelm a receiving station with data, i.e., buffers at the receiver do not get overflow.
- No frame error




Two Flow-Control Mechanisms

- Stop-and-Wait
- Sliding Window



Stop-and-Wait Flow Control



Operations:

- ① A packs binary information into a frame
- ② A sends the frame to B
- ③ A waits for an ACK
- When B has received the frame, B sends an ACK
- **⑤** When A has received the ACK, A repeats **①**



Frame Flow in Stop-and-Wait

ACK1 means the receiver expects f_1 , implying f_0 is received successfully sender receiver time



Flow-Control Performance: Throughput

Throughput (U) (Link Utilization) =
$$\frac{\text{carries useful information}}{\text{the total time}} = \frac{T_{frame}}{T_{cycle}}$$

$$\frac{T_{cycle}}{T_{frame}} = \frac{T_{frame}}{T_{cycle}} + T_{prop} + T_{proc} + T_{ack} + T_{prop} + T_{proc}$$

$$\frac{T_{cycle}}{T_{frame}} = \frac{T_{frame}}{T_{proc}} + T_{proc} + T_{ack} + T_{prop} + T_{proc}$$

$$\frac{T_{cycle}}{T_{frame}} = \frac{T_{frame}}{T_{proc}} + T_{proc} + T_{ack} + T_{prop} + T_{proc}$$

$$\frac{T_{cycle}}{T_{frame}} = \frac{T_{frame}}{T_{proc}} + T_{proc} + T_{prop} + T_{prop} + T_{prop} + T_{proc}$$

$$\frac{T_{cycle}}{T_{frame}} = \frac{T_{frame}}{T_{prop}} + T_{prop} + T_{$$

Throughput for Stop-and-Wait

Assumptions

- Input is saturated
- No error
- Ignoring T_{ack} & T_{proc}

We get:

$$T_{cycle} = T_{frame} + 2 T_{prop}$$


Then:

$$U = T_{frame} / (T_{frame} + 2 T_{prop})$$

= 1 / (1+2a)

Where:

$$a = T_{prop} / T_{frame}$$



$$U = \frac{1}{1 + 2a}$$

Parameter a is also as Normalized Propagation Delay



Example

A communication link exists between two nodes A and B. The transmission rate on the link is 2.4 Mbps. The distance between A and B is 50 km and the signal velocity is 2x108 m/s. The frame length is 300 bytes. No frame error. Calculate the link unitization for the stop-&-wait flow control mechanism.



R= 2.4 Mbps, L=300 bytes =2400bits H=50km, $v = 2x10^8 \, m/s$

U=1/(1+2a)
$$\longrightarrow$$
 a = T_p/T_f \longrightarrow $T_p=H/V=5x10^4/2x10^8 = 250 \ \mu s$

U=1/(1+2*0.25)
$$\leftarrow$$
 a = 0.25 \leftarrow T_f=L/R=2400/2.4x10⁶ = 1000 μ s = 2/3



Stop-and-Wait: Disadvantages

- If frame or ACK is lost, long waiting time is expected
 - Using a TIMEOUT control in the sender
- If the propagation time is long, the sender must wait a long time before it can perform the next transmission
 - Use Buffers at the sender/receiver (sliding window operation)

$$U = \frac{1}{1 + 2a}$$

Sliding Window Flow Control

- Allows multiple frames to be in transit.
- Sender and Receiver have buffer N long.
- Sender can send up to N frames without receiving ACKs.
- Each frame is labeled.
- ACK includes number of next expected frame.
- Sequence No. bounded by field size (k bits)
 - Frames are numbered modulo 2^k
 - Sequence number [0, 2^k-1]




Sliding Window Operations


Sender

- Move lower bound when frames sent
- Move upper bound when acks received

Receiver

- Move lower
 bound when
 frames received
- Move upper bound when acks sent








Sliding Window Operations

- Sender maintains a window, containing frame numbers that can be transmitted.
- Sender window shrinks from trailing edge (left side) as frames are sent.
- Frames are buffered at the sender until acknowledged.
- Receiver maintains a window as well, its window shrinks from trailing edge as frames are received.
- Receiver's window expands from the leading edge (right side) as ACKs are sent.
- Sender's window expands from the leading edge as ACKs are received.



Sliding Window: Example





Sliding Window Algorithm


```
/* Protocol 4 (sliding window) is bidirectional. */
                                        /* must be 1 for protocol 4 */
#define MAX SEQ 1
typedef enum (frame arrival, cksum err, timeout) event type;
#include "protocol.h"
void protocol4 (void)
                                         /* 0 or 1 only */
 seg nr next frame to send;
 seq_nr frame_expected;
                                         /* 0 or 1 only */
                                         /* scratch variables */
 frame r, s:
                                         /* current packet being sent */
 packet buffer;
 event_type event;
 next frame to send = 0;
                                         /* next frame on the outbound stream */
 frame_expected = 0;
                                         /* frame expected next */
 from_network_layer(&buffer);
                                         /* fetch a packet from the network layer */
                                         /* prepare to send the initial frame */
 s.info = buffer:
 s.seq = next_frame_to_send;
                                         /* insert sequence number into frame */
 s.ack = 1 - frame expected;
                                         /* piggybacked ack */
                                         /* transmit the frame */
 to physical layer(&s):
 start timer(s.seq);
                                         /* start the timer running */
 while (true) {
     wait for event(&event);
                                         /* frame_arrival, cksum_err, or timeout */
     if (event == frame arrival) {
                                         /* a frame has arrived undamaged. */
          from_physical_layer(&r);
                                         /* go get it */
          if (r.seq == frame_expected) { /* handle inbound frame stream. */
               to network layer(&r.info);
                                           /* pass packet to network layer */
               inc(frame_expected);
                                         /* invert seq number expected next */
                                                   /* handle outbound frame stream. */
          if (r.ack == next_frame_to_send) {
                                         /* turn the timer off */
               stop_timer(r.ack);
               from_network_layer(&buffer);
                                                   /* fetch new pkt from network layer */
               inc(next_frame_to_send);/* invert sender's sequence number */
     s.info = buffer:
                                         /* construct outbound frame */
     s.seq = next frame to send;
                                         /* insert sequence number into it */
                                         /* seg number of last received frame */
    s.ack = 1 - frame expected:
                                         /* transmit a frame */
     to physical layer(&s);
     start_timer(s.seq);
                                         /* start the timer running */
```



Window Size Consideration

Say, Window Size, N = 3 with k=1 bit Sequence number





(i) Is the second 0 a new frame or the retransmitted frame?


or a new frame?

① Which frame is to be transmitted next after receiving ack1?




Sliding Window: Other Features

 Receiver can acknowledge frames without permitting further transmission (by sending 'Receive Not Ready', RNR frame). Receiver must send a normal acknowledgement to resume.



ACK can be piggybacked on the data frames in the reverse direction.



Sliding Window: Performance

- Performance depends upon (error-free operation):
 - Parameter a, and
 - Window size, N.
- Assumption: T_{ack} and T_{proc} are negligible.
- Frame transmission time = 1 (normalized to itself)
- Normalized propagation delay (one-way) = a
- We need to consider two cases:
 - $N \ge 2a$ +1: Station can transmit continuously without exhausting its window → U = 1.0
 - N < 2a + 1: Station's window is exhausted at t = N, and the station cannot send additional frames until t = 2a + 1, $\rightarrow U = N/(1 + 2a)$



Case I: $N \ge 2a + 1$ (U=1)

$$t = 0$$

A

Frame 1

B

 $t = 1$

A

Frame 2

Frame 2

Frame 3

Frame 2

B

 $t = a + 1$

A

Frame $a + 1$

Frame $a + 1$

Frame $a + 1$

Frame $a + 1$

Frame $a + 2$

Frame $a + 3$

Frame $a + 3$

Frame $a + 4$

Fram

UNIVERSITY

Case II: N < 2a + 1 (U=N/2a)

$$t = 0$$

A

Frame 1

B

 $t = 1$

A

Frame a

Frame a-1

Frame a

Frame 3

Frame 2

Frame 1

B

 $t = a+1$

A

Frame N

Frame N-1

Frame N-2

Frame N-2

Frame N-2

Frame N-2

Frame N-2

B

 $t = 2a+1$

A

Frame N

Frame N-1

B

Frame N-1

Frame N-1

Frame N-1

Frame N-1

Frame N-1

B


UNIVERSITY

Sliding Window: Performance


Window Size = N

$$T_{useful} = N^* T_{frame}$$

 $T_{cycle} = T_{frame} + 2^* T_{prop}$



Flow Control: Link Utilization



Link Utilization versus a



Learning Objectives

Data Link Layer Fundamentals

To understand its (four) main functions

Flow Control

- To understand its main purpose
- Stop-and-Wait Flow-Control Mechanism
 - Operational protocol
 - Link utilization calculation
- Sliding Window Flow-Control Mechanism
 - Operational protocol
 - Window size determination
 - Link utilization calculation (two cases)

