

OSPRAY AN OPEN, SCALABLE, PARALLEL, RAY TRACING BASED RENDERING ENGINE FOR HIGH-FIDELITY VISUALIZATION

Version 1.3.0 June 6, 2017

Contents

1	OSP		verview 4							
	1.1	OSPR	ay Support and Contact							
	1.2		on History							
2	Buil	Building OSPRay from Source 1								
	2.1	Prerec	quisites							
	2.2	Comp	iling OSPRay							
3	OSP	Ray AF	PI 14							
	3.1	Initial	ization							
		3.1.1	Command Line Arguments							
		3.1.2	Manual Device Instantiation							
		3.1.3	Environment Variables							
		3.1.4	Error Handling and Status Messages 16							
		3.1.5	Loading OSPRay Extensions at Runtime							
	3.2	Objec	ts							
		3.2.1	Parameters							
		3.2.2	Data							
	3.3	Volun	nes							
		3.3.1	Structured Volume							
		3.3.2	Transfer Function							
	3.4	Geom	etries							
		3.4.1	Triangle Mesh							
		3.4.2	Spheres							
		3.4.3	Cylinders							
		3.4.4	Streamlines							
		3.4.5	Isosurfaces							
		3.4.6	Slices							
		3.4.7	Instances							
	3.5	Rende	erer							
		3.5.1	SciVis Renderer							
		3.5.2	Path Tracer							
		3.5.3	Model							
		3.5.4	Lights							
		3.5.5	Materials							
		3.5.6	Texture							
		3.5.7	Texture Transformations							
		3.5.8	Cameras							
		3.5.9	Picking							
	3.6		ebuffer							
	5.0		Operation							
	3.7		ering							

CONTENTS 3

4	Para	llel Rendering with MPI	38
	4.1	Prerequisites for MPI Mode	38
	4.2	Enabling the MPI module in your build	38
	4.3	Modes of using OSPRay's MPI features	38
	4.4	Running an application with the "offload" device	39
	4.5	Running an application with the "distributed" device	40
5	Exai	nples	41
	5.1	Tutorial	41
	5.2	Example Viewer	42
	5.3	Demos	42

Chapter 1 OSPRay Overview

OSPRay is an open source, scalable, and portable ray tracing engine for high-performance, high-fidelity visualization on Intel® Architecture CPUs. OSPRay is released under the permissive Apache 2.0 license.

The purpose of OSPRay is to provide an open, powerful, and easy-to-use rendering library that allows one to easily build applications that use ray tracing based rendering for interactive applications (including both surface- and volume-based visualizations). OSPRay is completely CPU-based, and runs on anything from laptops, to workstations, to compute nodes in HPC systems.

OSPRay internally builds on top of Embree and ISPC (Intel® SPMD Program Compiler), and fully utilizes modern instruction sets like Intel® SSE4, AVX, AVX2, and AVX-512 to achieve high rendering performance, thus a CPU with support for at least SSE4.1 is required to run OSPRay.

1.1 OSPRay Support and Contact

OSPRay is under active development, and though we do our best to guarantee stable release versions a certain number of bugs, as-yet-missing features, inconsistencies, or any other issues are still possible. Should you find any such issues please report them immediately via OSPRay's GitHub Issue Tracker (or, if you should happen to have a fix for it,you can also send us a pull request); for missing features please contact us via email at ospray@googlegroups.com.

For recent news, updates, and announcements, please see our complete news/updates page.

Join our mailing list to receive release announcements and major news regarding OSPRay.

1.2 Version History

1.2.1 Changes in v1.3.0:

- New MPI distributed device to support MPI distributed applications using OSPRay collectively for "in-situ" rendering (currently in "alpha")
 - Enabled via new mpi_distributed device type
 - Currently only supports raycast renderer, other renderers will be supported in the future
 - All API calls are expected to be exactly replicated (object instances and parameters) except scene data (geometries and volumes)
 - The original MPI device is now called the mpi_offload device to differentiate between the two implementations

- Support of Intel[®] AVX-512 for next generation Intel[®] Xeon[®] processor (codename Skylake), thus new minimum ISPC version is 1.9.1
- Thread affinity of OSPRay's tasking system can now be controlled via either device parameter setAffinity, or commandline parameter osp:setaffinity, or environment variable OSPRAY_SET_AFFINITY
- Changed behavior of the background color in the SciVis renderer: bgColor now includes alpha and is always blended (no backgroundEnabled anymore). To disable the background don't set bgColor, or set it to transparent black (0, 0, 0, 0)
- Geometries "spheres" and "cylinders" now support texture coordinates
- The GLUT- and Qt-based demo viewer applications have been replaced by an example viewer with minimal dependencies
 - Building the sample applications now requires GCC 4.9 (previously 4.8) for features used in the C++ standard library; OSPRay itself can still be built with GCC 4.8
 - The new example viewer based on ospray::sg (called ospExample-ViewerSg) is the single application we are consolidating to, ospExampleViewer will remain only as a deprecated viewer for compatibility with the old ospGlutViewer application
- Deprecated ospCreateDevice(); use ospNewDevice() instead
- Improved error handling
 - Various API functions now return an OSPError value
 - ospDeviceSetStatusFunc replaces the deprecated ospDeviceSetErrorMsgFunc
 - New API functions to query the last error (ospDeviceGetLastErrorCode() and ospDeviceGetLastErrorMsg()) or to register an error callback with ospDeviceSetErrorFunc()
 - Fixed bug where exceptions could leak to C applications

1.2.2 Changes in v1.2.1:

Various bugfixes related to MPI distributed rendering, ISPC issues on Windows, and other build related issues

1.2.3 Changes in v1.2.0:

- Added support for volumes with voxelType short (16-bit signed integers). Applications need to recompile, because OSPDataType has been re-enumerated
- Removed SciVis renderer parameter aoWeight, the intensity (and now color as well) of AO is controlled via "ambient" lights. If aoSamples is zero (the default) then ambient lights cause ambient illumination (without occlusion)
- New SciVis renderer parameter aoTransparencyEnabled, controlling whether object transparency is respected when computing ambient occlusion (disabled by default, as it is considerable slower)
- Implement normal mapping for SciVis renderer
- Support of emissive (and illuminating) geometries in the path tracer via new material "Luminous"
- Lights can optionally made invisible by using the new parameter isVisible (only relevant for path tracer)
- OSPRay Devices are now extendable through modules and the SDK
 - Devices can be created and set current, creating an alternative method for initializing the API
 - New API functions for committing parameters on Devices

- Removed support for the first generation Intel® Xeon Phi™ coprocessor (codename Knights Corner)
- Other minor improvements, updates, and bugfixes:
 - Updated Embree required version to v2.13.0 for added features and performance
 - New API function ospDeviceSetErrorMsgFunc() to specify a call-back for handling message outputs from OSPRay
 - Add ability to remove user set parameter values with new ospRemoveParam() API function
 - The MPI device is now provided via a module, removing the need for having separately compiled versions of OSPRay with and without MPI
 - OSPRay build dependencies now only get installed if OSPRAY_IN-STALL DEPENDENCIES CMake variable is enabled

1.2.4 Changes in v1.1.2:

· Various bugfixes related to normalization, epsilons and debug messages

1.2.5 Changes in v1.1.1:

- Fixed support of first generation Intel Xeon Phi coprocessor (codename Knights Corner) and the COI device
- · Fix normalization bug that caused rendering artifacts

1.2.6 Changes in v1.1.0:

- New "scivis" renderer features
 - Single sided lighting (enabled by default)
 - Many new volume rendering specific features
 - * Adaptive sampling to help improve the correctness of rendering high frequency volume data
 - * Pre-integration of transfer function for higher fidelity images
 - * Ambient occlusion
 - * Volumes can cast shadows
 - * Smooth shading in volumes
 - * Single shading point option for accelerated shading
- · Added preliminary support for adaptive accumulation in the MPI device
- Camera specific features
 - Initial support for stereo rendering with the perspective camera
 - Option architectural in perspective camera, rectifying vertical edges to appear parallel
 - Rendering a subsection of the full view with imageStart/imageEnd supported by all cameras
- This will be our last release supporting the first generation Intel Xeon Phi coprocessor (codename Knights Corner)
 - Future major and minor releases will be upgraded to the latest version of Embree, which no longer supports Knights Corner
 - Depending on user feedback, patch releases are still made to fix bugs
- Enhanced output statistics in ospBenchmark application
- Many fixes to the OSPRay SDK
 - Improved CMake detection of compile-time enabled features

- Now distribute OSPRay configuration and ISPC CMake macros
- Improved SDK support on Windows
- OSPRay library can now be compiled with -Wall and -Wextra enabled
 - Tested with GCC v5.3.1 and Clang v3.8
 - Sample applications and modules have not been fixed yet, thus applications which build OSPRay as a CMake subproject should disable them with -DOSPRAY_ENABLE_APPS=OFF and -DOSPRAY_ENABLE_MODULES=OFF
- · Minor bug fixes, improvements, and cleanups
 - Regard shading normal when bump mapping
 - Fix internal CMake naming inconsistencies in macros
 - Fix missing API calls in C++ wrapper classes
 - Fix crashes on MIC
 - Fix thread count initialization bug with TBB
 - CMake optimizations for faster configuration times
 - Enhanced support for scripting in both ospGlutViewer and osp-Benchmark applications

1.2.7 Changes in v1.0.0:

- New OSPRay SDK
 - OSPRay internal headers are now installed, enabling applications to extend OSPRay from a binary install
 - CMake macros for OSPRay and ISPC configuration now a part of binary releases
 - * CMake clients use them by calling include(\${OSPRAY_USE_ FILE}) in their CMake code after calling find_package(ospray)
 - New OSPRay C++ wrapper classes
 - * These act as a thin layer on top of OSPRay object handles, where multiple wrappers will share the same underlying handle when assigned, copied, or moved
 - * New OSPRay objects are only created when a class instance is explicitly constructed
 - * C++ users are encouraged to use these over the ospray.h API
- Complete rework of sample applications
 - New shared code for parsing the commandline
 - Save/load of transfer functions now handled through a separate library which does not depend on Qt
 - Added ospCvtParaViewTfcn utility, which enables ospVolumeViewer to load color maps from ParaView
 - GLUT based sample viewer updates
 - * Rename of ospModelViewer to ospGlutViewer
 - * GLUT viewer now supports volume rendering
 - * Command mode with preliminary scripting capabilities, enabled by pressing ':' key (not available when using Intel C++ Compiler (icc))
 - Enhanced support of sample applications on Windows
- New minimum ISPC version is 1.9.0
- Support of Intel® AVX-512 for second generation Intel Xeon Phi processor (codename Knights Landing) is now a part of the OSPRAY_BUILD_ISA CMake build configuration

- Compiling AVX-512 requires icc to be enabled as a build option
- Enhanced error messages when ospLoadModule() fails
- Added OSP_FB_RGBA32F support in the DistributedFrameBuffer
- Updated Glass shader in the path tracer
- · Many miscellaneous cleanups, bugfixes, and improvements

1.2.8 Changes in v0.10.1:

- Fixed support of first generation Intel Xeon Phi coprocessor (codename Knights Corner)
- Restored missing implementation of ospRemoveVolume()

1.2.9 Changes in v0.10.0:

- Added new tasking options: Cilk, Internal, and Debug
 - Provides more ways for OSPRay to interact with calling application tasking systems
 - * Cilk: Use Intel® Cilk™ Plus language extensions (icc only)
 - * Internal: Use hand written OSPRay tasking system
 - * Debug: All tasks are run in serial (useful for debugging)
 - In most cases, Intel Threading Building Blocks (Intel TBB) remains the fastest option
- Added support for adaptive accumulation and stopping
 - ospRenderFrame now returns an estimation of the variance in the rendered image if the framebuffer was created with the OSP_FB_ VARIANCE channel
 - If the renderer parameter varianceThreshold is set, progressive refinement concentrates on regions of the image with a variance higher than this threshold
- Added support for volumes with voxelType ushort (16-bit unsigned integers)
- OSPTexture2D now supports sRGB formats actually most images are stored in sRGB. As a consequence the API call ospNewTexture2D() needed to change to accept the new OSPTextureFormat parameter
- Similarly, OSPRay's framebuffer types now also distinguishes between linear and sRGB 8-bit formats. The new types are OSP_FB_NONE, OSP_FB_RGBA8, OSP_FB_SRGBA, and OSP_FB_RGBA32F
- Changed "scivis" renderer parameter defaults
 - All shading (AO + shadows) must be explicitly enabled
- OSPRay can now use a newer, pre-installed Embree enabled by the new OSPRAY_USE_EXTERNAL_EMBREE CMake option
- New ospcommon library used to separately provide math types and OS abstractions for both OSPRay and sample applications
 - Removes extra dependencies on internal Embree math types and utility functions
 - ospray.h header is now C99 compatible
- Removed loaders module, functionality remains inside of ospVolumeViewer
- Many miscellaneous cleanups, bugfixes, and improvements:
 - Fixed data distributed volume rendering bugs when using less blocks than workers
 - Fixes to CMake find_package() config

- Fix bug in GhostBlockBrickVolume when using doubles
- Various robustness changes made in CMake to make it easier to compile OSPRay

1.2.10 Changes in v0.9.1:

- Volume rendering now integrated into the "scivis" renderer
 - Volumes are rendered in the same way the "dvr" volume renderer renders them
 - Ambient occlusion works with implicit isosurfaces, with a known visual quality/performance trade-off
- Intel Xeon Phi coprocessor (codename Knights Corner) COI device and build infrastructure restored (volume rendering is known to still be broken)
- New support for CPack built OSPRay binary redistributable packages
- Added support for HDRI lighting in path tracer
- Added ospRemoveVolume() API call
- Added ability to render a subsection of the full view into the entire framebuffer in the perspective camera
- · Many miscellaneous cleanups, bugfixes, and improvements:
 - The depthbuffer is now correctly populated by in the "scivis" renderer
 - Updated default renderer to be "ao1" in ospModelViewer
 - Trianglemesh postIntersect shading is now 64-bit safe
 - Texture2D has been reworked, with many improvements and bug fixes
 - Fixed bug where MPI device would freeze while rendering frames with Intel TBB
 - Updates to CMake with better error messages when Intel TBB is missing

1.2.11 Changes in v0.9.0:

The OSPRay v0.9.0 release adds significant new features as well as API changes.

- Experimental support for data-distributed MPI-parallel volume rendering
- New SciVis-focused renderer ("raytracer" or "scivis") combining functionality of "obj" and "ao" renderers
 - Ambient occlusion is quite flexible: dynamic number of samples, maximum ray distance, and weight
- Updated Embree version to v2.7.1 with native support for Intel AVX-512 for triangle mesh surface rendering on the Intel Xeon Phi processor (codename Knights Landing)
- OSPRay now uses C++11 features, requiring up to date compiler and standard library versions (GCC v4.8.0)
- Optimization of volume sampling resulting in volume rendering speedups of up to $1.5\mathrm{x}$
- · Updates to path tracer
 - Reworked material system
 - Added texture transformations and colored transparency in OBJ material
 - Support for alpha and depth components of framebuffer
- Added thinlens camera, i.e. support for depth of field
- Tasking system has been updated to use Intel Threading Building Blocks (Intel TBB)
- The ospGet*() API calls have been deprecated and will be removed in a subsequent release

1.2.12 Changes in v0.8.3:

- Enhancements and optimizations to path tracer
 - Soft shadows (light sources: sphere, cone, extended spot, quad)
 - Transparent shadows
 - Normal mapping (OBJ material)
- Volume rendering enhancements:
 - Expanded material support
 - Support for multiple lights
 - Support for double precision volumes
 - Added ospSampleVolume() API call to support limited probing of volume values
- New features to support compositing externally rendered content with OSPRay-rendered content
 - Renderers support early ray termination through a maximum depth parameter
 - New OpenGL utility module to convert between OSPRay and OpenGL depth values
- Added panoramic and orthographic camera types
- Proper CMake-based installation of OSPRay and CMake find_package() support for use in external projects
- Experimental Windows support
- Deprecated ospNewTriangleMesh(); use ospNewGeometry("triangles") instead
- · Bug fixes and cleanups throughout the codebase

1.2.13 Changes in v0.8.2:

- Initial support for Intel AVX-512 and the Intel Xeon Phi processor (codename Knights Landing)
- Performance improvements to the volume renderer
- Incorporated implicit slices and isosurfaces of volumes as core geometry types
- Added support for multiple disjoint volumes to the volume renderer
- Improved performance of ospSetRegion(), reducing volume load times
- Improved large data handling for the shared_structured_volume and block_bricked_volume volume types
- Added support for DDS horizon data to the seismic module
- Initial support in the Qt viewer for volume rendering
- Updated to ISPC 1.8.2
- Various bug fixes, cleanups and documentation updates throughout the codebase

1.2.14 Changes in v0.8.1:

- The volume renderer and volume viewer can now be run MPI parallel (data replicated) using the --osp:mpi command line option
- Improved performance of volume grid accelerator generation, reducing load times for large volumes
- The volume renderer and volume viewer now properly handle multiple isosurfaces
- · Added small example tutorial demonstrating how to use OSPRay
- Several fixes to support older versions of GCC

Bug fixes to ospSetRegion() implementation for arbitrarily shaped regions and setting large volumes in a single call

- Bug fix for geometries with invalid bounds; fixes streamline and sphere rendering in some scenes
- Fixed bug in depth buffer generation

1.2.15 Changes in v0.8.0:

- Incorporated early version of a new Qt-based viewer to eventually unify (and replace) the existing simpler GLUT-based viewers
- Added new path tracing renderer (ospray/render/pathtracer),
- · roughly based on the Embree sample path tracer
- · Added new features to the volume renderer:
 - Gradient shading (lighting)
 - Implicit isosurfacing
 - Progressive refinement
 - Support for regular grids, specified with the gridOrigin and gridSpacing parameters
 - New shared_structured_volume volume type that allows voxel data to be provided by applications through a shared data buffer
 - New API call to set subregions of volume data (ospSetRegion())
- Added a subsampling-mode, enabled with a negative spp parameter; the first frame after scene changes is rendered with reduced resolution, increasing interactivity
- Added multi-target ISA support: OSPRay will now select the appropriate ISA at run time
- Added support for the Stanford SEP file format to the seismic module
- Added --osp:numthreads <n> command line option to restrict the number of threads OSPRay creates
- Various bug fixes, cleanups and documentation updates throughout the codebase

1.2.16 Changes in v0.7.2:

- · Build fixes for older versions of GCC and Clang
- Fixed time series support in ospVolumeViewer
- Corrected memory management for shared data buffers
- Updated to ISPC 1.8.1
- Resolved issue in XML parser

Chapter 2 Building OSPRay from Source

The latest OSPRay sources are always available at the OSPRay GitHub repository. The default master branch should always point to the latest tested bugfix release.

2.1 Prerequisites

OSPRay currently supports Linux, Mac OS X, and Windows. In addition, before you can build OSPRay you need the following prerequisites:

• You can clone the latest OSPRay sources via:

```
git clone https://github.com/ospray/ospray.git
```

- To build OSPRay you need CMake, any form of C++11 compiler (we recommend using GCC, but also support Clang and the Intel® C++ Compiler (icc)), and standard Linux development tools. To build the example viewers, you should also have some version of OpenGL.
- Additionally you require a copy of the Intel® SPMD Program Compiler (ISPC). Please obtain a copy of the latest binary release of ISPC (currently 1.9.1) from the ISPC downloads page. The build system looks for ISPC in the PATH and in the directory right "next to" the checked-out OSPRay sources.¹ Alternatively set the CMake variable ISPC_EXECUTABLE to the location of the ISPC compiler.
- Per default OSPRay uses the Intel[®] Threading Building Blocks (TBB) as tasking system, which we recommend for performance and flexibility reasons. Alternatively you can set CMake variable OSPRAY_TASKING_SYSTEM to OpenMP, Internal, or Cilk (icc only).
- OSPRay also heavily uses Embree, installing version 2.13 or newer is required. If Embree is not found by CMake its location can be hinted with the variable embree DIR.

Depending on your Linux distribution you can install these dependencies using yum or apt-get. Some of these packages might already be installed or might have slightly different names.

Type the following to install the dependencies using yum:

```
sudo yum install cmake.x86_64
sudo yum install tbb.x86_64 tbb-devel.x86_64
```

Type the following to install the dependencies using apt-get:

¹ For example, if OSPRay is in ~/Projects/
ospray, ISPC will also be searched in ~/
Projects/ispc-v1.9.1-linux

```
sudo apt-get install cmake-curses-gui
sudo apt-get install libtbb-dev
```

Under Mac OS X these dependencies can be installed using MacPorts:

sudo port install cmake tbb

2.2 Compiling OSPRay

Assume the above requisites are all fulfilled, building OSPRay through CMake is easy:

· Create a build directory, and go into it

```
user@mymachine[~/Projects]: mkdir ospray/release
user@mymachine[~/Projects]: cd ospray/release
```

(We do recommend having separate build directories for different configurations such as release, debug, etc).

• The compiler CMake will use will default to whatever the CC and CXX environment variables point to. Should you want to specify a different compiler, run cmake manually while specifying the desired compiler. The default compiler on most linux machines is gcc, but it can be pointed to clang instead by executing the following:

```
user@mymachine[~/Projects/ospray/release]: cmake
   -DCMAKE_CXX_COMPILER=clang++ -DCMAKE_C_COMPILER=clang ...
```

CMake will now use Clang instead of GCC. If you are ok with using the default compiler on your system, then simply skip this step. Note that the compiler variables cannot be changed after the first cmake or ccmake run.

• Open the CMake configuration dialog

```
user@mymachine[~/Projects/ospray/release]: ccmake ..
```

 Make sure to properly set build mode and enable the components you need, etc; then type 'c'onfigure and 'g'enerate. When back on the command prompt, build it using

```
user@mymachine[~/Projects/ospray/release]: make
```

• You should now have libospray. so as well as a set of example application. You can test your version of OSPRay using any of the examples on the OSPRay Demos and Examples page.

Chapter 3 OSPRay API

To access the OSPRay API you first need to include the OSPRay header

```
#include "ospray/ospray.h"
```

where the API is compatible with C99 and C++.

3.1 Initialization

In order to use the API, OSPRay must be initialized with a "device". A device is the object which implements the API. Creating and initializing a device can be done in either of two ways: command line arguments or manually instantiating a device.

3.1.1 Command Line Arguments

The first is to do so by giving OSPRay the command line from main() by calling

```
OSPError ospInit(int *argc, const char **argv);
```

OSPRay parses (and removes) its known command line parameters from your application's main function. For an example see the tutorial. For possible error codes see section Error Handling and Status Messages. It is important to note that the arguments passed to ospInit() are processed in order they are listed. The following parameters (which are prefixed by convention with "--osp:") are understood:

3.1.2 Manual Device Instantiation

The second method of initialization is to explicitly create the device yourself, and possibly set parameters. This method looks almost identical to how other objects are created and used by OSPRay (described in later sections). The first step is to create the device with

```
OSPDevice ospNewDevice(const char *type);
```

where the type string maps to a specific device implementation. OSPRay always provides the "default" device, which maps to a local CPU rendering device. If it is enabled in the build, you can also use "mpi" to access the MPI multi-node rendering device (see Parallel Rendering with MPI section for more information). Once a device is created, you can call

```
void ospDeviceSet1i(OSPDevice, const char *id, int val);
```

Table 3.1 - Command line parameters accepted by OSPRay's ospInit.

Parameter	Description		
osp:debug	enables various extra checks and debug output, and disables multi-threading		
osp:numthreads <n></n>	use n threads instead of per default using all detected hardware threads		
osp:loglevel <n></n>	set logging level, default 0; increasing n means increasingly verbose log messages		
osp:verbose	shortcut forosp:loglevel 1		
osp:vv	shortcut forosp:loglevel 2		
osp:module: <name></name>	load a module during initialization; equivalent to calling ospLoadModule(name)		
osp:mpi	enables MPI mode for parallel rendering with the mpi_offload device, to be used in conjunction with mpirun; this will automatically load the "mpi" module if it is not yet loaded or linked		
osp:mpi-offload	same asosp:mpi		
osp:mpi-distributed	same asosp:mpi, but will create an mpi_distributed device instead; Note that this will likely require application changes to work properly		
osp:logoutput <dst></dst>	convenience for setting where error/status messages go; valid values for dst are cerr and cout		
osp:device: <name></name>	use name as the type of device for OSPRay to create; e.gosp:device:default gives you the default local device; Note if the device to be used is defined in a module, remember to passosp:module: <name> first</name>		
osp:setaffinity <n></n>	if 1, bind software threads to hardware threads; 0 disables binding; default is 1 on KNL and 0 otherwise $$		

or

void ospDeviceSetString(OSPDevice, const char *id, const char *val);

to set parameters on the device. The following parameters can be set on all devices:

Table 3.2 – Parameters shared by all devices.

Туре	Name	Description
int	numThreads	number of threads which OSPRay should use
int	logLevel	logging level
int	debug	set debug mode; equivalent to logLevel=2 and numThreads=1
int	setAffinity	bind software threads to hardware threads if set to 1; 0 disables binding omitting the parameter will let OSPRay choose

Once parameters are set on the created device, the device must be committed with

void ospDeviceCommit(OSPDevice);

To use the newly committed device, you must call

void ospSetCurrentDevice(OSPDevice);

This then sets the given device as the object which will respond to all other OSPRay API calls.

Users can change parameters on the device after initialization (from either method above), by calling

OSPDevice ospGetCurrentDevice();

This function returns the handle to the device currently used to respond to OSPRay API calls, where users can set/change parameters and recommit the device. If changes are made to the device that is already set as the current device, it does not need to be set as current again.

3.1.3 Environment Variables

Finally, OSPRay's generic device parameters can be overridden via environment variables for easy changes to OSPRay's behavior without needing to change the application (variables are prefixed by convention with "OSPRAY_"):

Variable	Description
OSPRAY_THREADS	equivalent toosp:numthreads
OSPRAY_LOG_LEVEL	equivalent toosp:loglevel
OSPRAY_LOG_OUTPUT	equivalent toosp:logoutput
OSPRAY_DEBUG	equivalent toosp:debug
OSPRAY_SET_AFFINITY	equivalent toosp:setaffinity

Table 3.3 – Environment variables interpreted by OSPRay.

3.1.4 Error Handling and Status Messages

The following errors are currently used by OSPRay:

Name	Description
OSP_NO_ERROR	no error occurred
OSP_UNKNOWN_ERROR	an unknown error occurred
OSP_INVALID_ARGUMENT	an invalid argument was specified
OSP_INVALID_OPERATION	the operation is not allowed for the specified object
OSP_OUT_OF_MEMORY	there is not enough memory to execute the command
OSP_UNSUPPORTED_CPU	the CPU is not supported (minimum ISA is SSE4.1)

Table 3.4 – Possible error codes, i.e. valid named constants of type OSPError.

These error codes are either directly return by some API functions, or are recorded to be later queried by the application via

OSPError ospDeviceGetLastErrorCode(OSPDevice);

A more descriptive error message can be queried by calling

const char* ospDeviceGetLastErrorMsg(OSPDevice);

Alternatively, the application can also register a callback function of type

```
typedef void (*OSPErrorFunc)(OSPError, const char* errorDetails);
```

via

void ospDeviceSetErrorFunc(OSPDevice, OSPErrorFunc);

to get notified when errors occur.

Applications may be interested in messages which OSPRay emits, whether for debugging or logging events. Applications can call

```
void ospDeviceSetStatusFunc(OSPDevice, OSPStatusFunc);
```

in order to register a callback function of type

```
typedef void (*OSPStatusFunc)(const char* messageText);
```

which OSPRay will use to emit status messages. By default, OSPRay uses a callback which does nothing, so any output desired by an application will require that a callback is provided. Note that callbacks for C++ std::cout and std::cerr can be alternatively set through ospInit() or the OSPRAY_LOG_OUT-PUT environment variable.

3.1.5 Loading OSPRay Extensions at Runtime

OSPRay's functionality can be extended via plugins, which are implemented in shared libraries. To load plugin name from libospray_module_<name>.so (on Linux and Mac OS X) or ospray_module_<name>.dll (on Windows) use

```
OSPError ospLoadModule(const char *name);
```

Modules are searched in OS-dependent paths, which include the application directory. ospLoadModule returns OSP_NO_ERROR if the plugin could be successfully loaded.

3.2 Objects

All entities of OSPRay (the renderer, volumes, geometries, lights, cameras, ...) are a specialization of OSPObject and share common mechanism to deal with parameters and lifetime.

An important aspect of object parameters is that parameters do not get passed to objects immediately. Instead, parameters are not visible at all to objects until they get explicitly committed to a given object via a call to

```
void ospCommit(OSPObject);
```

at which time all previously additions or changes to parameters are visible at the same time. If a user wants to change the state of an existing object (e.g., to change the origin of an already existing camera) it is perfectly valid to do so, as long as the changed parameters are recommitted.

The commit semantic allow for batching up multiple small changes, and specifies exactly when changes to objects will occur. This is important to ensure performance and consistency for devices crossing a PCI bus, or across a network. In our MPI implementation, for example, we can easily guarantee consistency among different nodes by MPI barrier'ing on every commit.

Note that OSPRay uses reference counting to manage the lifetime of all objects, so one cannot explicitly "delete" any object. Instead, to indicate that the application does not need and does not access the given object anymore, call

```
void ospRelease(OSPObject);
```

This decreases its reference count and if the count reaches 0 the object will automatically get deleted.

3.2.1 Parameters

Parameters allow to configure the behavior of and to pass data to objects. However, objects do *not* have an explicit interface for reasons of high flexibility and a more stable compile-time API. Instead, parameters are passed separately to objects in an arbitrary order, and unknown parameters will simply be ignored. The following functions allow adding various types of parameters with name id to a given object:

```
// add a C-string (zero-terminated char *) parameter
void ospSetString(OSPObject, const char *id, const char *s);
// add an object handle parameter to another object
void ospSetObject(OSPObject, const char *id, OSPObject object);
// add an untyped pointer -- this will *ONLY* work in local rendering!
void ospSetVoidPtr(OSPObject, const char *id, void *v);
// add scalar and vector integer and float parameters
void ospSetf (OSPObject, const char *id, float x);
void ospSet1f (OSPObject, const char *id, float x);
void ospSet1i (OSPObject, const char *id, int32_t x);
void ospSet2f (OSPObject, const char *id, float x, float y);
void ospSet2fv(OSPObject, const char *id, const float *xy);
void ospSet2i (OSPObject, const char *id, int x, int y);
void ospSet2iv(OSPObject, const char *id, const int *xy);
void ospSet3f (OSPObject, const char *id, float x, float y, float z);
void ospSet3fv(OSPObject, const char *id, const float *xyz);
void ospSet3i (OSPObject, const char *id, int x, int y, int z);
void ospSet3iv(OSPObject, const char *id, const int *xyz);
void ospSet4f (OSPObject, const char *id, float x, float y, float z, float w);
void ospSet4fv(OSPObject, const char *id, const float *xyzw);
// additional functions to pass vector integer and float parameters in C++
void ospSetVec2f(OSPObject, const char *id, const vec2f &v);
void ospSetVec2i(OSPObject, const char *id, const vec2i &v);
void ospSetVec3f(OSPObject, const char *id, const vec3f &v);
void ospSetVec3i(OSPObject, const char *id, const vec3i &v);
void ospSetVec4f(OSPObject, const char *id, const vec4f &v);
```

Users can also remove parameters that have been explicitly set via an ospSet call. Any parameters which have been removed will go back to their default value during the next commit unless a new parameter was set after the parameter was removed. The following API function removes the named parameter from the given object:

```
void ospRemoveParam(OSPObject, const char *id);
```

3.2.2 Data

There is also the possibility to aggregate many values of the same type into an array, which then itself can be used as a parameter to objects. To create such a new data buffer, holding numItems elements of the given type, from the initialization data pointed to by source and optional creation flags, use

The call returns an OSPData handle to the created array. The flag OSP_DATA_ SHARED_BUFFER indicates that the buffer can be shared with the application. In this case the calling program guarantees that the source pointer will remain valid for the duration that this data array is being used. The enum type OSP-DataType describes the different data types that can be represented in OSPRay; valid constants are listed in the table below.

Type/Name	Description
OSP_DEVICE	API device object reference
OSP_VOID_PTR	void pointer
OSP_DATA	data reference
OSP_OBJECT	generic object reference
OSP_CAMERA	camera object reference
OSP_FRAMEBUFFER	framebuffer object reference
OSP_LIGHT	light object reference
OSP_MATERIAL	material object reference
OSP_TEXTURE	texture object reference
OSP_RENDERER	renderer object reference
OSP_MODEL	model object reference
OSP_GEOMETRY	geometry object reference
OSP_VOLUME	volume object reference
OSP_TRANSFER_FUNCTION	transfer function object reference
OSP_PIXEL_OP	pixel operation object reference
OSP_STRING	C-style zero-terminated character string
OSP_CHAR	8 bit signed character scalar
OSP_UCHAR	8 bit unsigned character scalar
OSP_UCHAR[234]	and [234]-element vector
OSP_USHORT	16 bit unsigned integer scalar
OSP_INT	32 bit signed integer scalar
OSP_INT[234]	and [234]-element vector
OSP_UINT	32 bit unsigned integer scalar
OSP_UINT[234]	and [234]-element vector
OSP_LONG	64 bit signed integer scalar
OSP_LONG[234]	and [234]-element vector
OSP_ULONG	64 bit unsigned integer scalar
OSP_ULONG[234]	and [234]-element vector
OSP_FLOAT	32 bit single precision floating point scalar
OSP_FLOAT[234]	and [234]-element vector
OSP_FLOAT3A	and aligned 3-element vector
OSP_DOUBLE	64 bit double precision floating point scalar

Table 3.5 – Valid named constants for OSPDataType.

To add a data array as parameter named id to another object call

void ospSetData(OSPObject, const char *id, OSPData);

3.3 Volumes

Volumes are volumetric datasets with discretely sampled values in 3D space, typically a 3D scalar field. To create a new volume object of given type type use

```
OSPVolume ospNewVolume(const char *type);
```

The call returns NULL if that type of volume is not known by OSPRay, or else an OSPVolume handle.

3.3.1 Structured Volume

Structured volumes only need to store the values of the samples, because their addresses in memory can be easily computed from a 3D position. A common type of structured volumes are regular grids. OSPRay supports two variants that differ in how the volumetric data for the regular grids is specified.

The first variant shares the voxel data with the application. Such a volume type is created by passing the type string "shared_structured_volume" to ospNewVolume. The voxel data is laid out in memory in XYZ order and provided to the volume via a data buffer parameter named "voxelData".

The second regular grid variant is optimized for rendering performance: data locality in memory is increased by arranging the voxel data in smaller blocks. This volume type is created by passing the type string "block_bricked_volume" to ospNewVolume. Because of this rearrangement of voxel data it cannot be shared the with the application anymore, but has to be transferred to OSPRay via

```
OSPError ospSetRegion(OSPVolume, void *source,
const vec3i &regionCoords,
const vec3i &regionSize);
```

The voxel data pointed to by source is copied into the given volume starting at position regionCoords, must be of size regionSize and be placed in memory in XYZ order. Note that OSPRay distinguishes between volume data and volume parameters. This function must be called only after all volume parameters (in particular dimensions and voxelType, see below) have been set and <code>before ospCommit(volume)</code> is called. If necessary then memory for the volume is allocated on the first call to this function.

The common parameters understood by both structured volume variants are summarized in the table below. If voxelRange is not provided for a volume OSPRay will compute it based on the voxel data, which may result in slower data updates.

3.3.2 Transfer Function

Transfer functions map the scalar values of volumes to color and opacity and thus they can be used to visually emphasize certain features of the volume. To create a new transfer function of given type type use

```
OSPTransferFunction ospNewTransferFunction(const char *type);
```

The call returns NULL if that type of transfer functions is not known by OS-PRay, or else an OSPTransferFunction handle to the created transfer function. That handle can be assigned to a volume as parameter "transferFunction" using ospSetObject.

One type of transfer function that is built-in in OSPRay is the linear transfer function, which interpolates between given equidistant colors and opacities. It is create by passing the string "piecewise_linear" to ospNewTransferFunction and it is controlled by these parameters:

Table 3.6 – Parameters to configure a structured volume.

Type	Name	Default	Description
vec3i	dimensions		number of voxels in each dimension (x, y, z)
string	voxelType		data type of each voxel, currently supported are:
			"uchar" (8 bit unsigned integer)
			"short" (16 bit signed integer)
			"ushort" (16 bit unsigned integer)
			"float" (32 bit single precision floating point)
			"double" (64 bit double precision floating point)
vec2f	voxelRange		minimum and maximum of the scalar values
vec3f	gridOrigin	(0, 0, 0)	origin of the grid in world-space
vec3f	gridSpacing	(1, 1, 1)	size of the grid cells in world-space
bool	gradientShadingEnabled	false	volume is rendered with surface shading wrt. to normalized gradient
bool	preIntegration	false	use pre-integration for transfer function lookups
bool	singleShade	true	shade only at the point of maximum intensity
bool	adaptiveSampling	true	adapt ray step size based on opacity
float	adaptiveScalar	15	modifier for adaptive step size
float	adaptive Max Sampling Rate	2	maximum sampling rate for adaptive sampling
float	samplingRate	0.125	sampling rate of the volume (this is the minimum step size for adaptive sampling)
vec3f	specular	gray 0.3	specular color for shading
vec3f	volume Clipping Box Lower	disabled	lower coordinate (in object-space) to clip the volume values
vec3f	volumeClippingBoxUpper	disabled	upper coordinate (in object-space) to clip the volume values

Type	Name	Description
vec3f[]	colors	data array of RGB colors
float[]	opacities	data array of opacities
vec2f	valueRange	domain (scalar range) this function maps from

Table 3.7 – Parameters accepted by the linear transfer function.

3.4 Geometries

Geometries in OSPRay are objects that describe surfaces. To create a new geometry object of given type use

OSPGeometry ospNewGeometry(const char *type);

The call returns NULL if that type of geometry is not known by OSPRay, or else an OSPGeometry handle.

3.4.1 Triangle Mesh

A traditional triangle mesh (indexed face set) geometry is created by calling ospNewGeometry with type string "triangles". Once created, a triangle mesh recognizes the following parameters:

Table 3.8 – Parameters defining a triangle mesh geometry.

3.4.2 Spheres

A geometry consisting of individual spheres, each of which can have an own radius, is created by calling ospNewGeometry with type string "spheres". The spheres will not be tessellated but rendered procedurally and are thus perfectly round. To allow a variety of sphere representations in the application this geometry allows a flexible way of specifying the data of center position and radius within a data array:

Table 3.9 – Parameters defining a spheres geometry.

Туре	Name	Default	Description
float	radius	0.01	radius of all spheres (if offset_radius is not used)
OSPData	spheres	NULL	memory holding the spatial data of all spheres
int	bytes_per_sphere	16	size (in bytes) of each sphere within the spheres array
int	offset_center	0	offset (in bytes) of each sphere's "vec3f center" position (in object-space) within the spheres array
int	offset_radius	-1	offset (in bytes) of each sphere's "float radius" within the spheres array (-1 means disabled and use radius)
vec4f[] / vec3f(a)[]	color	NULL	data array of colors (RGBA/RGB), color is constant for each sphere
vec2f[]	texcoord	NULL	data array of texture coordinates, coordinate is constant for each sphere

3.4.3 Cylinders

A geometry consisting of individual cylinders, each of which can have an own radius, is created by calling ospNewGeometry with type string "cylinders". The cylinders will not be tessellated but rendered procedurally and are thus perfectly round. To allow a variety of cylinder representations in the application this geometry allows a flexible way of specifying the data of offsets for start position, end position and radius within a data array. All parameters are listed in the table below.

For texturing each cylinder is seen as a 1D primitive, i.e. a line segment: the 2D texture coordinates at its vertices v0 and v1 are linearly interpolated.

3.4.4 Streamlines

A geometry consisting of multiple stream lines of constant radius is created by calling ospNewGeometry with type string "streamlines". The stream lines are

Туре	Name	Default	Description
float	radius	0.01	radius of all cylinders (if offset_radius is not used)
OSPData	cylinders	NULL	memory holding the spatial data of all cylinders
int	bytes_per_cylinder	24	size (in bytes) of each cylinder within the cylinders array
int	offset_v0	0	offset (in bytes) of each cylinder's "vec3f v0" position (the start vertex, in object-space) within the cylinders array
int	offset_v1	12	offset (in bytes) of each cylinder's "vec3f v1" position (the end vertex, in object-space) within the cylinders array
int	offset_radius	-1	offset (in bytes) of each cylinder's "float radius" within the cylinders array (-1 means disabled and use radius instead)
vec4f[] / vec3f(a)[]	color	NULL	data array of colors (RGBA/RGB), color is constant for each cylinder
OSPData	texcoord	NULL	data array of texture coordinates, in pairs (each a vec2f at vertex v0 and v1)

internally assembled from connected (and rounded) cylinder segments and are thus perfectly round. The parameters defining this geometry are listed in the table below.

Туре	Name	Description
float	radius	radius of all stream lines, default 0.01
vec3fa[]	vertex	data array of all vertices for <i>all</i> stream lines
vec4f[]	vertex.color	data array of corresponding vertex colors (RGBA)
int32[]	index	data array of indices to the first vertex of a link

Table 3.11 – Parameters defining a streamlines geometry.

Each stream line is specified by a set of (aligned) vec3fa control points in vertex; all vertices belonging to to the same logical stream line are connected via cylinders of a fixed radius radius, with additional spheres at each vertex to make for a smooth transition between the cylinders.

A streamlines geometry can contain multiple disjoint stream lines, each streamline is specified as a list of linear segments (or links) referenced via index: each entry e of the index array points the first vertex of a link (vertex[index[e]]) and the second vertex of the link is implicitly the directly following one (vertex[index[e]+1]). For example, two stream lines of vertices (A-B-C-D) and (E-F-G), respectively, would internally correspond to five links (A-B, B-C, C-D, E-F, and F-G), and would be specified via an array of vertices [A,B,C,D,E,F,G], plus an array of link indices [0,1,2,4,5].

3.4.5 Isosurfaces

OSPRay can directly render multiple isosurfaces of a volume without first tessellating them. To do so create an isosurfaces geometry by calling ospNewGeometry with type string "isosurfaces". Each isosurface will be colored according to the provided volume's transfer function.

3.4.6 Slices

One tool to highlight interesting features of volumetric data is to visualize 2D cuts (or slices) by placing planes into the volume. Such a slices geometry is created

Туре	Name	Description
float[]	isovalues	data array of isovalues
OSPVolume	volume	handle of the volume to be isosurfaced

Table 3.12 – Parameters defining an isosurfaces geometry.

by calling ospNewGeometry with type string "slices". The planes are defined by the coefficients (a,b,c,d) of the plane equation ax+by+cz+d=0. Each slice is colored according to the provided volume's transfer function.

Туре	Name	Description
vec4f[]	planes	data array with plane coefficients for all slices
OSPVolume	volume	handle of the volume that will be sliced

Table 3.13 – Parameters defining a slices geometry.

3.4.7 Instances

OSPRay supports instancing via a special type of geometry. Instances are created by transforming another given model model ToInstantiate with the given affine transformation transform by calling

OSPGeometry ospNewInstance(OSPModel modelToInstantiate, const affine3f &transform);

3.5 Renderer

A renderer is the central object for rendering in OSPRay. Different renderers implement different features and support different materials. To create a new renderer of given type use

OSPRenderer ospNewRenderer(const char *type);

The call returns NULL if that type of renderer is not known, or else an OS-PRenderer handle to the created renderer. General parameters of all renderers are

Type	Name	Description
OSPModel OSPCamera	model camera	the model to render the camera to be used for rendering
OSPLight[]	lights	data array with handles of the lights
float	epsilon	ray epsilon to avoid self-intersections, relative to scene diameter, default 10 ⁻⁶
int	spp	samples per pixel, default 1
int	maxDepth	maximum ray recursion depth
float	varianceThreshold	threshold for adaptive accumulation

Table 3.14 – Parameters understood by all renderers.

OSPRay's renderers support a feature called adaptive accumulation, which accelerates progressive rendering by stopping the rendering and refinement of image regions that have an estimated variance below the varianceThreshold. This feature requires a framebuffer with an OSP_FB_VARIANCE channel.

3.5.1 SciVis Renderer

The SciVis renderer is a fast ray tracer for scientific visualization which supports volume rendering and ambient occlusion (AO). It is created by passing the type string "scivis" or "raytracer" to ospNewRenderer. In addition to the general parameters understood by all renderers the SciVis renderer supports the following special parameters:

Туре	Name	Default	Description
bool	shadowsEnabled	false	whether to compute (hard) shadows
int	aoSamples	0	number of rays per sample to compute ambient occlusion
float	aoDistance	10^{20}	maximum distance to consider for ambient occlusion
bool	aoTransparencyEnabled	false	whether object transparency is respected when computing ambient occlusion (slower)
bool	oneSidedLighting	true	if true back-facing surfaces (wrt. light source) receive no illumination
float / vec3f / vec4f	bgColor	black, transparent	background color and alpha (RGBA)
OSPTexture2D	maxDepthTexture	NULL	screen-sized float texture with maximum far distance per pixel

Table 3.15 – Special parameters understood by the SciVis renderer.

Note that the intensity (and color) of AO is controlled via an ambient light. If aoSamples is zero (the default) then ambient lights cause ambient illumination (without occlusion).

Per default the background of the rendered image will be transparent black, i.e. the alpha channel holds the opacity of the rendered objects. This facilitates transparency-aware blending of the image with an arbitrary background image by the application. The parameter bgColor can be used to already blend with a constant background color (and alpha) during rendering.

The SciVis renderer supports depth composition with images of other renderers, for example to incorporate help geometries of a 3D UI that were rendered with OpenGL. The screen-sized texture maxDepthTexture must have format OSP_TEXTURE_R32F and flag OSP_TEXTURE_FILTER_NEAREST. The fetched values are used to limit the distance of primary rays, thus objects of other renderers can hide objects rendered by OSPRay.

3.5.2 Path Tracer

The path tracer supports soft shadows, indirect illumination and realistic materials. In addition to the general parameters understood by all renderers the path tracer supports the following special parameters:

3.5.3 **Model**

Models are a container of scene data. They can hold the different geometries and volumes as well as references to (and instances of) other models. A model is associated with a single logical acceleration structure. To create an (empty) model call

OSPModel ospNewModel();

The call returns an OSPModel handle to the created model. To add an already created geometry or volume to a model use

Table 3.16 - Special	narameters	understood by	the noth tracer
1able 3.16 - Special	barameters	unaerstooa by	the bath tracer.

Туре	Name	Default	Description
float	minContribution	0.01	sample contributions below this value will be neglected to speed-up rendering
float	maxContribution	∞	samples are clamped to this value before they are accumulated into the framebuffer
OSPTexture2D	backplate	NULL	texture image used as background, replacing visible lights in infinity (e.g. the HDRI light)

```
void ospAddGeometry(OSPModel, OSPGeometry);
void ospAddVolume(OSPModel, OSPVolume);
```

An existing geometry or volume can be removed from a model with

```
void ospRemoveGeometry(OSPModel, OSPGeometry);
void ospRemoveVolume(OSPModel, OSPVolume);
```

3.5.4 **Lights**

To let the given renderer create a new light source of given type type use

```
OSPLight ospNewLight(OSPRenderer renderer, const char *type);
```

The call returns NULL if that type of camera is not known by the renderer, or else an OSPLight handle to the created light source. All light sources¹ accept the following parameters:

Туре	Name	Default	Description
vec3f(a)	color	white	color of the light
float	intensity	1	intensity of the light (a factor)
bool	isVisible	true	whether the light can be directly seen

The following light types are supported by most OSPRay renderers.

3.5.4.1 Directional Light / Distant Light

The distant light (or traditionally the directional light) is thought to be very far away (outside of the scene), thus its light arrives (almost) as parallel rays. It is created by passing the type string "distant" to ospNewLight. In addition to the general parameters understood by all lights the distant light supports the following special parameters:

Type	Name	Description
vec3f(a)	direction	main emission direction of the distant light
float	angularDiameter	apparent size (angle in degree) of the light

Setting the angular diameter to a value greater than zero will result in soft shadows when the renderer uses stochastic sampling (like the path tracer). For instance, the apparent size of the sun is about 0.53°.

¹ The HDRI Light is an exception, it knows about intensity, but not about color.

Table 3.17 – Parameters accepted by the all lights.

Table 3.18 – Special parameters accepted by the distant light.

3.5.4.2 Point Light / Sphere Light

The sphere light (or the special case point light) is a light emitting uniformly in all directions. It is created by passing the type string "sphere" to ospNewLight. In addition to the general parameters understood by all lights the sphere light supports the following special parameters:

Type	Name	Description
vec3f(a)	position	the center of the sphere light, in world-space
float	radius	the size of the sphere light

Table 3.19 – Special parameters accepted by the sphere light.

Setting the radius to a value greater than zero will result in soft shadows when the renderer uses stochastic sampling (like the path tracer).

3.5.4.3 **Spot Light**

The spot light is a light emitting into a cone of directions. It is created by passing the type string "spot" to ospNewLight. In addition to the general parameters understood by all lights the spot light supports the special parameters listed in the table.

Table 3.20 - Special parameters accepted by the spot light.

Туре	Name	Description
vec3f(a)	position	the center of the spot light, in world-space
vec3f(a)	direction	main emission direction of the spot
float	openingAngle	full opening angle (in degree) of the spot; outside of this cone is no illumination
float	penumbraAngle	size (angle in degree) of the "penumbra", the region between the rim (of the illumination cone) and full intensity of the spot; should be smaller than half of openingAngle
float	radius	the size of the spot light, the radius of a disk with normal direction




Figure 3.1 – Angles used by SpotLight.

Setting the radius to a value greater than zero will result in soft shadows when the renderer uses stochastic sampling (like the path tracer).

3.5.4.4 Quad Light

The quad² light is a planar, procedural area light source emitting uniformly on one side into the half space. It is created by passing the type string "quad" to ospNewLight. In addition to the general parameters understood by all lights the spot light supports the following special parameters:

² actually a parallelogram

Туре	Name	Description
vec3f(a)	position	world-space position of one vertex of the quad light
vec3f(a)	edge1	vector to one adjacent vertex
vec3f(a)	edge2	vector to the other adjacent vertex

Table 3.21 – Special parameters accepted by the quad light.




Figure 3.2 – Defining a Quad Light.

The emission side is determined by the cross product of edge1×edge2. Note that only renderers that use stochastic sampling (like the path tracer) will compute soft shadows from the quad light. Other renderers will just sample the center of the quad light, which results in hard shadows.

3.5.4.5 HDRI Light

The HDRI light is a textured light source surrounding the scene and illuminating it from infinity. It is created by passing the type string "hdri" to ospNewLight. In addition to the parameter intensity the HDRI light supports the following special parameters:

Table 3.22 – Special parameters accepted by the HDRI light.

Туре	Name	Description
vec3f(a)	up	up direction of the light in world-space
vec3f(a)	dir	direction to which the center of the texture will be mapped to (analog to panoramic camera)
OSPTexture2D	map	environment map in latitude / longitude format

Note that the currently only the path tracer supports the HDRI light.

3.5.4.6 Ambient Light

The ambient light surrounds the scene and illuminates it from infinity with constant radiance (determined by combining the parameters color and intensity). It is created by passing the type string "ambient" to ospNewLight.

Note that the SciVis renderer uses ambient lights to control the color and intensity of the computed ambient occlusion (AO).

3.5.4.7 Emissive Objects

The path tracer will consider illumination by geometries which have a light emitting material assigned (for example the Luminous material).

3.5.5 Materials

Materials describe how light interacts with surfaces, they give objects their distinctive look. To let the given renderer create a new material of given type type call



Figure 3.3 – Orientation and Mapping of an HDRI Light.

OSPMaterial ospNewMaterial(OSPRenderer, const char *type);

The call returns NULL if the material type is not known by the renderer, or else an OSPMaterial handle to the created material. The handle can then be used to assign the material to a given geometry with

void ospSetMaterial(OSPGeometry, OSPMaterial);

3.5.5.1 OBJ Material

The OBJ material is the workhorse material supported by both the SciVis renderer and the path tracer. It offers widely used common properties like diffuse and specular reflection and is based on the MTL material format of Lightwave's OBJ scene files. To create an OBJ material pass the type string "OBJMaterial" to ospNewMaterial. Its main parameters are

Туре	Name	Default	Description
vec3f vec3f	Kd Ks	white 0.8 black	diffuse color specular color
float	Ns	10	shininess (Phong exponent), usually in $[2-10^4]$
float	d	opaque	opacity
vec3f	Tf	black	transparency filter color
OSPTexture2D	map_Bump	NULL	normal map

Table 3.23 – Main parameters of the OBJ material.

In particular when using the path tracer it is important to adhere to the principle of energy conservation, i.e. that the amount of light reflected by a surface is not larger than the light arriving. Therefore the path tracer issues a warning and renormalizes the color parameters if the sum of Kd, Ks, and Tf is larger than one in any color channel. Similarly important to mention is that almost all materials of the real world reflect at most only about 80% of the incoming light. So even for a white sheet of paper or white wall paint do better not set Kd larger than 0.8; otherwise rendering times are unnecessary long and the contrast in the final images is low (for example, the corners of a white room would hardly be discernible).

Note that currently only the path tracer implements colored transparency with Tf.

Normal mapping can simulate small geometric features via the texture map_Bump. The normals n in the normal map are wrt. the local tangential shading coordinate system and are encoded as 1/2(n+1), thus a texel $(0.5,0.5,1)^3$ represents the unperturbed shading normal (0,0,1). Because of this encoding an sRGB gamma texture format is ignored and normals are always fetched as linear from a normal map. Note that the orientation of normal maps is important for a visually consistent look: by convention OSPRay uses a coordinate system with the origin in the lower left corner; thus a convexity will look green towards the top of the texture image (see also the example image of a normal map). If this is not the case flip the normal map vertically or invert its green channel.

 $^{^3}$ respectively (127, 127, 255) for 8 bit textures




Figure 3.4 – Normal map representing an exalted square pyramidal frustum.

All parameters (except Tf) can be textured by passing a texture handle, prefixed with "map_". The fetched texels are multiplied by the respective parameter value. Texturing requires geometries with texture coordinates, e.g. a triangle mesh with vertex.texcoord provided. The color textures map_Kd and map_Ks are typically in one of the sRGB gamma encoded formats, whereas textures map_Ns and map_d are usually in a linear format (and only the first component is used). The path tracer additionally supports texture transformations for all textures.

3.5.5.2 Glass

The path tracer offers a realistic a glass material, supporting refraction and volumetric attenuation (i.e. the transparency color varies with the geometric thickness). To create a Glass material pass the type string "Glass" to ospNewMaterial. Its parameters are

Type	Name	Default	Description
float	eta	1.5	index of refraction
vec3f	attenuation Color	white	resulting color due to attenuation
float	attenuation Distance	1	distance affecting attenuation

Table 3.24 – Parameters of the Glass material.

For convenience, the rather counterintuitive physical attenuation coefficients will be calculated from the user inputs in such a way, that the attenuation-Color will be the result when white light traveled trough a glass of thickness attenuationDistance.

3.5.5.3 **Luminous**

The path tracer supports the Luminous material which emits light uniformly in all directions and which can thus be used to turn any geometric object into a light source. It is created by passing the type string "Luminous" to ospNewMaterial. The amount of constant radiance that is emitted is determined by combining the general parameters of lights: color and intensity.

3.5.6 Texture

To create a new 2D texture of size size (in pixels) and with the given format and flags use

The call returns NULL if the texture could not be created with the given parameters, or else an OSPTexture2D handle to the created texture. The supported texture formats are:

Name	Description
OSP_TEXTURE_RGBA8	8 bit $[0-255]$ linear components red, green, blue, alpha
OSP_TEXTURE_SRGBA	8 bit sRGB gamma encoded color components, and linear alpha
OSP_TEXTURE_RGBA32F	32 bit float components red, green, blue, alpha
OSP_TEXTURE_RGB8	8 bit $[0-255]$ linear components red, green, blue
OSP_TEXTURE_SRGB	8 bit sRGB gamma encoded components red, green, blue
OSP_TEXTURE_RGB32F	32 bit float components red, green, blue
OSP_TEXTURE_R8	8 bit [0–255] linear single component
OSP_TEXTURE_R32F	32 bit float single component

Table 3.25 - Supported texture formats by ospNewTexture2D, i.e. valid constants of type OSPTextureFormat.

The texel data addressed by source starts with the texels in the lower left corner of the texture image, like in OpenGL. Similar to data buffers the texel data can be shared by the application by specifying the OSP_TEXTURE_SHARED_BUFFER flag. Per default a texture fetch is filtered by performing bi-linear interpolation of the nearest 2×2 texels; if instead fetching only the nearest texel is desired (i.e. no filtering) then pass the OSP_TEXTURE_FILTER_NEAREST flag. Both texture creating flags can be combined with a bitwise OR.

3.5.7 Texture Transformations

Many materials with textures also offer to manipulate the placement of these textures with the help of texture transformations. If so, this convention shall be used. The following parameters (prefixed with "texture_name.") are combined into one transformation matrix:

Type	Name	Description
vec4f	transform	interpreted as 2×2 matrix (linear part), column-major
float	rotation	angle in degree, counterclock-wise, around center
vec2f	scale	enlarge texture, relative to center (0.5, 0.5)
vec2f	translation	move texture in positive direction (right/up)

Table 3.26 – Parameters to define texture coordinate transformations.

The transformations are applied in the given order. Rotation, scale and translation are interpreted "texture centric", i.e. their effect seen by an user are relative to the texture (although the transformations are applied to the texture coordinates).

3.5.8 Cameras

To create a new camera of given type type use

OSPCamera ospNewCamera(const char *type);

The call returns NULL if that type of camera is not known, or else an OSPCamera handle to the created camera. All cameras accept these parameters:

Type	Name	Description
vec3f(a)	pos	position of the camera in world-space
vec3f(a)	dir	main viewing direction of the camera
vec3f(a)	up	up direction of the camera
float	nearClip	near clipping distance
vec2f	imageStart	start of image region (lower left corner)
vec2f	imageEnd	end of image region (upper right corner)

Table 3.27 – Parameters accepted by all cameras.

The camera is placed and oriented in the world with pos, dir and up. The region of the camera sensor that is rendered to the image can be specified in normalized screen-space coordinates with imageStart (lower left corner) and imageEnd (upper right corner). This can be used, for example, to crop the image or to achieve asymmetrical view frusta. Note that values outside the default range of [0-1] are valid, which is useful to easily realize overscan or film gate, or to emulate a shifted sensor.

3.5.8.1 Perspective Camera

The perspective camera implements a simple thinlens camera for perspective rendering, supporting optionally depth of field and stereo rendering, but no motion blur. It is created by passing the type string "perspective" to ospNewCamera. In addition to the general parameters understood by all cameras the perspective camera supports the special parameters listed in the table below.

Table 3.28 - Parameters accepted by the perspective camera.

Туре	Name	Description
float	fovy	the field of view (angle in degree) of the frame's height
float	aspect	ratio of width by height of the frame
float	apertureRadius	size of the aperture, controls the depth of field
float	focusDistance	distance at where the image is sharpest when depth of field is enabled
bool	architectural	vertical edges are projected to be parallel
int	stereoMode	0: no stereo (default), 1: left eye, 2: right eye, 3: side-by-side
float	interpupillary Distance	distance between left and right eye when stereo is enabled

Note that when setting the aspect ratio a non-default image region (using imageStart & imageEnd) needs to be regarded.

In architectural photography it is often desired for aesthetic reasons to display the vertical edges of buildings or walls vertically in the image as well, regardless of how the camera is tilted. Enabling the architectural mode achieves this by internally leveling the camera parallel to the ground (based on the up direction) and then shifting the lens such that the objects in direction dir are centered in the image. If finer control of the lens shift is needed use imageStart & imageEnd. Because the camera is now effectively leveled its image plane and thus the plane of focus is oriented parallel to the front of buildings, the whole façade appears sharp, as can be seen in the example images below.

3.5.8.2 Orthographic Camera

The orthographic camera implements a simple camera with orthographic projection, without support for depth of field or motion blur. It is created by passing the



Figure 3.5 – Example image created with the perspective camera, featuring depth of field.



Figure 3.6 – Enabling the architectural flag corrects the perspective projection distortion, resulting in parallel vertical edges.




Figure 3.7 – Example 3D stereo image using stereoMode side-by-side.

type string "orthographic" to ospNewCamera. In addition to the general parameters understood by all cameras the orthographic camera supports the following special parameters:

Type	Name	Description
float	height	size of the camera's image plane in y, in world coordinates
float	aspect	ratio of width by height of the frame

Table 3.29 – Parameters accepted by the orthographic camera.

For convenience the size of the camera sensor, and thus the extent of the scene that is captured in the image, can be controlled with the height parameter. The same effect can be achieved with imageStart and imageEnd, and both methods can be combined. In any case, the aspect ratio needs to be set accordingly to get an undistorted image.

3.5.8.3 Panoramic Camera

The panoramic camera implements a simple camera without support for motion blur. It captures the complete surrounding with a latitude / longitude mapping and thus the rendered images should best have a ratio of 2:1. A panoramic camera is created by passing the type string "panoramic" to ospNewCamera. It is placed and oriented in the scene by using the general parameters understood by all cameras.

3.5.9 Picking

To get the world-space position of the geometry (if any) seen at [0-1] normalized screen-space pixel coordinates screenPos use

```
void ospPick(OSPPickResult*, OSPRenderer, const vec2f &screenPos);
```

The result is returned in the provided OSPPickResult struct:

```
typedef struct {
   vec3f position; // the position of the hit point (in world-space)
   bool hit; // whether or not a hit actually occurred
} OSPPickResult;
```



Figure 3.8 – Example image created with the orthographic camera.



Figure 3.9 – Latitude / longitude map created with the panoramic camera.

Note that ospPick considers exactly the same camera of the given renderer that is used to render an image, thus matching results can be expected. If the camera supports depth of field then the center of the lens and thus the center of the circle of confusion is used for picking.

3.6 Framebuffer

The framebuffer holds the rendered 2D image (and optionally auxiliary information associated with pixels). To create a new framebuffer object of given size size (in pixels), color format, and channels use

The parameter format describes the format the color buffer has *on the host*, and the format that ospMapFrameBuffer will eventually return. Valid values are:

Name	Description
OSP_FB_NONE	framebuffer will not be mapped by the application
OSP_FB_RGBA8	8 bit [0–255] linear component red, green, blue, alpha
OSP_FB_SRGBA	8 bit sRGB gamma encoded color components, and linear alpha
OSP_FB_RGBA32F	32 bit float components red, green, blue, alpha

Table 3.30 - Supported color formats of the framebuffer that can be passed to ospNewFrameBuffer, i.e. valid constants of type OSPFrameBufferFormat.

The parameter frameBufferChannels specifies which channels the framebuffer holds, and can be combined together by bitwise OR from the values of OSPFrameBufferChannel listed in the table below.

Name	Description
OSP_FB_COLOR	RGB color including alpha
OSP_FB_DEPTH	euclidean distance to the camera (<i>not</i> to the image plane)
OSP_FB_ACCUM	accumulation buffer for progressive refinement
OSP_FB_VARIANCE	estimate of the current variance, see rendering

Table 3.31 – Framebuffer channels constants (of type OSPFrameBufferChannel), naming optional information the framebuffer can store. These values can be combined by bitwise OR when passed to ospNewFrameBuffer or ospClearFrameBuffer.

If a certain channel value is *not* specified, the given buffer channel will not be present. Note that ospray makes a very clear distinction between the *external* format of the framebuffer and the internal one: The external format is the format the user specifies in the format parameter; it specifies what color format OSPRay will eventually *return* the framebuffer to the application (when calling ospMapFrameBuffer): no matter what OSPRay uses internally, it will simply return a 2D array of pixels of that format, with possibly all kinds of reformatting, compression/decompression, etc, going on in-between the generation of the *internal* framebuffer and the mapping of the externally visible one.

In particular, OSP_FB_NONE is a perfectly valid pixel format for a framebuffer that an application will never map. For example, an application driving a display wall may well generate an intermediate framebuffer and eventually transfer its pixel to the individual displays using an OSPPixelOp pixel operation.

A framebuffer can be freed again using

```
void ospFreeFrameBuffer(OSPFrameBuffer);
```

Because OSPRay uses reference counting internally the framebuffer may not immediately be deleted at this time.

The application can map the given channel of a framebuffer – and thus access the stored pixel information – via

Note that only OSP_FB_COLOR or OSP_FB_DEPTH can be mapped. The origin of the screen coordinate system in OSPRay is the lower left corner (as in OpenGL), thus the first pixel addressed by the returned pointer is the lower left pixel of the image.

A previously mapped channel of a framebuffer can be unmapped by passing the received pointer mapped to

```
void ospUnmapFrameBuffer(const void *mapped, OSPFrameBuffer);
```

The individual channels of a framebuffer can be cleared with

```
void ospFrameBufferClear(OSPFrameBuffer, const uint32_t frameBufferChannels);
```

When selected, OSP_FB_COLOR will clear the color buffer to black (0, 0, 0, 0), OSP_FB_DEPTH will clear the depth buffer to inf, OSP_FB_ACCUM will clear the accumulation buffer to black, resets the accumulation counter accumID and also clears the variance buffer (if present) to inf.

Pixel Operation

A pixel operation are functions that are applied to every pixel that gets written into a framebuffer. Examples include post-processing, filtering, blending, tone mapping, or sending tiles to a display wall. To create a new pixel operation of given type type use

```
OSPPixelOp ospNewPixelOp(const char *type);
```

The call returns NULL if that type is not known, or else an OSPPixelOp handle to the created pixel operation.

To set a pixel operation to the given framebuffer use

```
void ospSetPixelOp(OSPFrameBuffer, OSPPixelOp);
```

3.7 Rendering

To render a frame into the given framebuffer with the given renderer use

The third parameter specifies what channel(s) of the framebuffer is written to⁴. What to render and how to render it depends on the renderer's parameters. If the framebuffer supports accumulation (i.e. it was created with OSP_FB_ACCUM) then successive calls to ospRenderFrame will progressively refine the rendered image. If additionally the framebuffer has an OSP_FB_VARIANCE channel then ospRenderFrame returns an estimate of the current variance of the rendered image, otherwise inf is returned. The estimated variance can be used by the application as a quality indicator and thus to decide whether to stop or to continue progressive rendering.

⁴ This is currently not implemented, i.e. all channels of the framebuffer are always updated

Chapter 4 Parallel Rendering with MPI

OSPRay has the ability to scale to multiple nodes in a cluster via MPI. This enables applications to take advantage of larger compute and memory resources when available.

4.1 Prerequisites for MPI Mode

In addition to the standard build requirements of OSPRay, you must have the following items available in your environment in order to build&run OSPRay in MPI mode:

- An MPI enabled multi-node environment, such as an HPC cluster
- An MPI implementation you can build against (i.e. Intel MPI, MVAPICH2, etc...)

4.2 Enabling the MPI module in your build

To build the MPI module the CMake variable OSPRAY_MODULE_MPI must be enabled, which can be done directly on the command line (with -D...) or through a configuration dialog (ccmake, cmake-gui), see also [Compiling OSPRay].

This will trigger CMake to go look for an MPI implementation in your environment. You can then inspect the CMake value of MPI_LIBRARY to make sure that CMake found your MPI build environment correctly.

This will result in an OSPRay module being built. To enable using it, applications will need to either link libospray_module_mpi, or call

```
ospLoadModule("mpi");
```

before initializing OSPRay.

4.3 Modes of using OSPRay's MPI features

OSPRay provides two ways of using MPI to scale up rendering: offload and distributed.

The "offload" rendering mode is where a single (not-distributed) calling application treats the OSPRay API the same as with local rendering. However, OSPRay uses multiple MPI connected nodes to evenly distribute frame rendering work, where each node contains a full copy of all scene data. This method is most effective for scenes which can fit into memory, but are very expensive to render: for example, path tracing with many samples-per-pixel is very compute heavy, making it a good situation to use the offload feature. This can be done

with any application which already uses OSPRay for local rendering without the need for any code changes.

The "distributed" rendering mode is where a MPI distributed application (such as a scientific simulation) uses OSPRay collectively to render frames. In this case, the API expects all calls (both created objects and parameters) to be the same on every application rank, except each rank can specify arbitrary geometries and volumes. Each renderer will have its own limitations on the topology of the data (i.e. overlapping data regions, concave data, etc.), but the API calls will only differ for scene objects. Thus all other calls (i.e. setting camera, creating framebuffer, rendering frame, etc.) will all be assumed to be identical, but only rendering a frame and committing the model must be in lock-step. This mode targets using all available aggregate memory for very large scenes and for "in-situ" visualization where the data is already distributed by a simulation app.

4.4 Running an application with the "offload" device

As an example, our sample viewer can be run as a single application which offloads rendering work to multiple MPI processes running on multiple machines.

The example apps are setup to be launched in two different setups. In either setup, the application must initialize OSPRay with the offload device. This can be done by creating an "mpi_offload" device and setting it as the current device (via the ospSetCurrentDevice() function), or passing either "--osp:mpi" or "--osp:mpi-offload" as a command line parameter to ospInit(). Note that passing a command line parameter will automatically call ospLoadModule("mpi") to load the MPI module, while the application will have to load the module explicitly if using ospNewDevice().

Option 1: single MPI launch

OSPRay is initialized with the ospInit() function call which takes command line arguments in and configures OSPRay based on what it finds. In this setup, the app is launched across all ranks, but workers will never return from ospInit(), essentially turning the application into a worker process for OSPRay. Here's an example of running the ospVolumeViewer data-replicated, using c1-c4 as compute nodes and localhost the process running the viewer itself:

```
% mpirun -perhost 1 -hosts localhost,c1,c2,c3,c4 ./ospExampleViewer [scene_file] --osp:mpi
```

Option 2: separate app/worker launches

The second option is to explicitly launch the app on rank 0 and worker ranks on the other nodes. This is done by running ospray_mpi_worker on worker nodes and the application on the display node. Here's the same example above using this syntax:

```
% mpirun -perhost 1 -hosts localhost ./ospExampleViewer [scene_file] --osp:mpi \
   : -hosts c1,c2,c3,c4 ./ospray_mpi_worker --osp:mpi
```

This method of launching the application and OSPRay worker separately works best for applications which do not immediately call ospInit() in their main() function, or for environments where application dependencies (such as GUI libraries) may not be available on compute nodes.

4.5 Running an application with the "distributed" device

Applications using the new distributed device should initialize OSPRay by creating (and setting current) an "mpi_distributed" device or pass "--osp:mpi-distributed" as a command line argument to ospInit(). Note that due to the semantic differences the distributed device gives the OSPRay API, it is not expected for applications which can already use the offload device to correctly use the distributed device without changes to the application.

Chapter 5 Examples

5.1 Tutorial

A minimal working example demonstrating how to use OSPRay can be found at apps/ospTutorial.cpp¹. On Linux build it in the build directory with

¹ A C99 version is available at apps/ospTu-

g++ ../apps/ospTutorial.cpp -I ../ospray/include -I .. ./libospray.so -Wl,-rpath,. -o ospTutorial

On Windows build it in the build_directory\\$Configuration with

cl ..\..\apps\ospTutorial.cpp /EHsc -I ..\..\ospray\include -I ..\.. ospray.lib

Running ospTutorial will create two images of two triangles, rendered with the Scientific Visualization renderer with full Ambient Occlusion. The first image firstFrame.ppm shows the result after one call to ospRenderFrame – jagged edges and noise in the shadow can be seen. Calling ospRenderFrame multiple times enables progressive refinement, resulting in antialiased edges and converged shadows, shown after ten frames in the second image accumulated-Frames.png.



Figure 5.1 – First frame.



Figure 5.2 - After accumulating ten frames.

Examples 42

5.2 Example Viewer

OSPRay also includes an exemplary viewer application ospExampleViewerSg, showcasing all features of OSPRay. The Example Viewer uses the ImGui library for user interface controls. The viewer is based on a prototype OSPRay scenegraph interface where its nodes are displayed in the GUI and can be manipulated interactively. For instance, simply run it as ospExampleViewerSg teapot.obj.

This application also functions as an OSPRay state debugger – invalid values will be shown in red up the hierarchy and won't change the viewer until corrected. You can also add new nodes where appropriate: for example, when "lights" is expanded right clicking on "lights" and typing in a light type, such as "point", will add it to the scene. Similarly, right clicking on "world" and creating an "Importer" node will add a new scene importer from a file. Changing the filename to an appropriate file will load the scene and propagate the resulting state.



Figure 5.3 – Screenshot of ospExample-ViewerSg

5.3 Demos

Several ready-to-run demos, models and data sets for OSPRay can be found at the OSPRay Demos and Examples page.

Examples 43

© 2013–2017 Intel Corporation

Intel, the Intel logo, Xeon, Intel Xeon Phi, and Intel Core are trademarks of Intel Corporation in the U.S. and/or other countries. Other names and brands may be claimed as the property of others.

Optimization Notice: Intel's compilers may or may not optimize to the same degree for non-Intel microprocessors for optimizations that are not unique to Intel microprocessors. These optimizations include SSE2, SSE3, and SSSE3 instruction sets and other optimizations. Intel does not guarantee the availability, functionality, or effectiveness of any optimization on microprocessors not manufactured by Intel. Microprocessor-dependent optimizations in this product are intended for use with Intel microprocessors. Certain optimizations not specific to Intel microarchitecture are reserved for Intel microprocessors. Please refer to the applicable product User and Reference Guides for more information regarding the specific instruction sets covered by this notice.

Notice Revision #20110804