■ NetApp

Antivirus configuration

ONTAP 9

NetApp August 10, 2023

This PDF was generated from https://docs.netapp.com/us-en/ontap/antivirus/index.html on August 10, 2023. Always check docs.netapp.com for the latest.

Table of Contents

Antivirus configuration	1
Antivirus configuration overview	1
About NetApp antivirus protection	1
Vscan server installation and configuration	6
Configure scanner pools	7
Configure on-access scanning	15
Configure on-demand scanning	19
Best practices for configuring the off-box antivirus functionality in clustered ONTAP	24
Enable virus scanning on an SVM	25
Reset the status of scanned files	26
View Vscan event log information	27
Troubleshoot connectivity issues and monitor performance activities	

Antivirus configuration

Antivirus configuration overview

Vscan is an antivirus scanning solution developed by NetApp that allows customers to protect their data from being compromised by viruses or other malicious code.

Vscan performs virus scans when clients access files over SMB. You can configure Vscan to scan on-demand or on a schedule. You can interact with Vscan using the ONTAP command-line interface (CLI) or ONTAP application programming interfaces (APIs).

Related information

Vscan partner solutions

About NetApp antivirus protection

About NetApp virus scanning

Vscan is an antivirus scanning solution developed by NetApp that allows customers to protect their data from being compromised by viruses or other malicious code. It combines partner-provided antivirus software with ONTAP features to give customers the flexibility they need to manage file scanning.

How virus scanning works

Storage systems offload scanning operations to external servers hosting antivirus software from third-party vendors.

Based on the active scanning mode, ONTAP sends scan requests when clients access files over SMB (on-access) or access files in specific locations, on a schedule or immediately (on-demand).

• You can use *on-access scanning* to check for viruses when clients open, read, rename, or close files over SMB. File operations are suspended until the external server reports the scan status of the file. If the file has already been scanned, ONTAP allows the file operation. Otherwise, it requests a scan from the server.

On-access scanning is not supported for NFS.


You can use on-demand scanning to check files for viruses immediately or on a schedule. We recommend
that on-demand scans run only in off-peak hours to avoid overloading existing AV infrastructure, which is
normally sized for on-access scanning. The external server updates the scan status of checked files, so
that file-access latency is reduced over SMB. If there were file modifications or software version updates, it
requests a new file scan from the external server.

You can use on-demand scanning for any path in the SVM namespace, even for volumes that are exported only through NFS.

You typically enable both on-access and on-demand scanning modes on an SVM. In either mode, the antivirus software takes remedial action on infected files based on your software settings.

The ONTAP Antivirus Connector, provided by NetApp and installed on the external server, handles

communication between the storage system and the antivirus software.




Virus scanning workflow

You must create a scanner pool and apply a scanner policy before you can enable scanning. You typically enable both on-access and on-demand scanning modes on an SVM.



You must have completed the CIFS configuration.



To create an on-demand task, there must be at least one on-access policy enabled. It can be the default policy or a user created on-access policy.

Antivirus architecture

The NetApp antivirus architecture consists of Vscan server software and associated settings.

Vscan server software

You must install this software on the Vscan server.

ONTAP Antivirus Connector

This is NetApp-provided software that handles scan request and response communication between the SVMs and antivirus software. It can run on a virtual machine, but for best performance use a physical machine. You can download this software from the NetApp Support Site (requires login).

· Antivirus software

This is partner-provided software that scans files for viruses or other malicious code. You specify the remedial actions to be taken on infected files when you configure the software.

Vscan software settings

You must configure these software settings on the Vscan server.

Scanner pool

This setting defines the Vscan servers and privileged users that can connect to SVMs. It also defines a scan request timeout period, after which the scan request is sent to an alternative Vscan server if one is available.



You should set the timeout period in the antivirus software on the Vscan server to five seconds less than the scanner-pool scan-request timeout period. This will avoid situations in which file access is delayed or denied altogether because the timeout period on the software is greater than the timeout period for the scan request.

Privileged user

This setting is a domain user account that a Vscan server uses to connect to the SVM. The account must exist in the list of privileged users in the scanner pool.

Scanner policy

This setting determines whether a scanner pool is active. Scanner policies are system-defined, so you cannot create custom scanner policies. Only these three policies are available:

- Primary specifies that the scanner pool is active.
- Secondary specifies that the scanner pool is active, only when none of the Vscan servers in the primary scanner pool are connected.
- Idle specifies that the scanner pool is inactive.

On-access policy

This setting defines the scope of an on-access scan. You can specify the maximum file size to scan, file extensions and paths to include in the scan, and file extensions and paths to exclude from the scan.

By default, only read-write volumes are scanned. You can specify filters that enable scanning of read-only volumes or that restrict scanning to files opened with execute access:

- ° scan-ro-volume enables scanning of read-only volumes.
- ° scan-execute-access restricts scanning to files opened with execute access.



"Execute access" is different from "execute permission." A given client will have "execute access" on an executable file only if the file was opened with "execute intent."

You can set the scan-mandatory option to off to specify that file access is allowed when no Vscan servers are available for virus scanning. Within on-access mode you can choose from these two mutually-exclusive options:

- Mandatory: With this option, Vscan tries to deliver the scan request to the server until the timeout period expires. If the scan request is not accepted by the server, then the client access request is denied.
- Non-Mandatory: With this option, Vscan always allows client access, whether or not a Vscan server was available for virus scanning.

On-demand task

This setting defines the scope of an on-demand scan. You can specify the maximum file size to scan, file extensions and paths to include in the scan, and file extensions and paths to exclude from the scan. Files in subdirectories are scanned by default.

You use a cron schedule to specify when the task runs. You can use the vserver vscan on-demand-task run command to run the task immediately.

Vscan file-operations profile (on-access scanning only)

The vscan-fileop-profile parameter for the vserver cifs share create command defines which SMB file operations trigger virus scanning. By default, the parameter is set to standard, which is NetApp best practice. You can adjust this parameter as necessary when you create or modify an SMB share:

- o no-scan specifies that virus scans are never triggered for the share.
- ° standard specifies that virus scans are triggered by open, close, and rename operations.
- ° strict specifies that virus scans are triggered by open, read, close, and rename operations.

The strict profile provides enhanced security for situations in which multiple clients access a file simultaneously. If one client closes a file after writing a virus to it, and the same file remains open on a second client, strict ensures that a read operation on the second client triggers a scan before the file is closed.

You should be careful to restrict the strict` profile to shares containing files that you anticipate will be accessed simultaneously. Since this profile generates more scan requests, it may impact performance.

• writes-only specifies that virus scans are triggered only when modified files are closed.

Since writes-only generates fewer scan requests, it typically improves performance.

If you use this profile, the scanner must be configured to delete or quarantine unrepairable infected files, so they cannot be accessed. If, for example, a client closes a file after writing a virus to it, and the file is not repaired, deleted, or quarantined, any client that accesses the file without writing to it will be infected.



If a client application performs a rename operation, the file is closed with the new name and is not scanned. If such operations pose a security concern in your environment, you should use the standard or strict profile.

Vscan partner solutions

NetApp collaborates with Trellix, Symantec, Trend Micro, and Sentinel One to deliver industry-leading anti-malware and anti-virus solutions that build upon ONTAP Vscan technology. These solutions help you scan files for malware and remediate any affected files.

As shown in the table below, interoperability details for Trellix, Symantec and Trend Micro are maintained on the NetApp Interoperability Matrix. Interoperability details for Trellix and Symantec can also be found on the partner websites. Interoperability details for Sentinel One and other new partners will be maintained by the partner on their websites.

Partner	Solution documentation	Interoperability details
Trellix (Formerly McAfee)	Trellix Product Documentation	 NetApp Interoperability Matrix Tool Supported platforms for Endpoint Security Storage Protection (trellix.com)
Symantec	Symantec Protection Engine 9.0.0	 NetApp Interoperability Matrix Tool Support Matrix for Partner Devices Certified with Symantec Protection Engine (SPE) for Network Attached Storage (NAS) 8.x (broadcom.com)
Trend Micro	Trend Micro ServerProtect for Storage 6.0 Getting Started Guide	NetApp Interoperability Matrix Tool
Sentinel One	Sentinel One support This link requires a user log-in. You can request access from Sentinel One.	

Vscan server installation and configuration

You must set up and configure one or more Vscan servers to enable antivirus scanning.

- To install and configure the antivirus software on the server, follow the instructions provided by your vendor.
- To install and configure the ONTAP Antivirus Connector, follow the instructions in the README.txt file available on the NetApp support site.



For disaster recovery and MetroCluster configurations, you must set up and configure separate Vscan servers for the primary/local and secondary/partner ONTAP clusters.

Antivirus software requirements

- For information about antivirus software requirements, see the vendor documentation.
- For information about the vendors, software, and versions supported by Vscan, see the NetApp Interoperability Matrix Tool (IMT).

ONTAP Antivirus Connector requirements

- You can download this software from the NetApp Support Site (requires login).
- For information about software version support, see the NetApp Interoperability Matrix Tool (IMT).

Vscan server configuration requirements

- You must install .NET 3.0 or later and you must enable SMB 2.0 on the Vscan server. For SMB servers with an export policy, you must add all Vscan servers to the policy.
- You can install different versions of Windows Server OS on different Vscan servers in a cluster. At a minimum, ONTAP Antivirus Connector requires Windows Server 2008.

Configure scanner pools

Configure scanner pools overview

A scanner pool defines the Vscan servers and privileged users that can connect to SVMs. A scanner policy determines whether a scanner pool is active.



If you use an export policy on an SMB server, you must add each Vscan server to the export policy.

Create a scanner pool on a single cluster

A scanner pool defines the Vscan servers and privileged users that can connect to SVMs. You can create a scanner pool for an individual SVM or for all the SVMs in a cluster.

What you'll need

- SVMs and Vscan servers must be in the same domain or in trusted domains.
- For scanner pools defined for an individual SVM, you must have configured ONTAP Antivirus Connector with the SVM management LIF or SVM data LIF.
- For scanner pools defined for all the SVMs in a cluster, you must have configured ONTAP Antivirus Connector with the cluster management LIF.
- The list of privileged users must include the domain user account the Vscan server uses to connect to the SVM.
- Once the scanner pool is configured, check the connection status to the servers.

Steps

1. Create a scanner pool:

vserver vscan scanner-pool create -vserver data_SVM|cluster_admin_SVM -scanner
-pool scanner pool -hostnames Vscan server hostnames -privileged-users

```
privileged users
```

- Specify a data SVM for a pool defined for an individual SVM, and specify a cluster admin SVM for a pool defined for all of the SVMs in a cluster.
- Specify an IP address or FQDN for each Vscan server host name.
- Specify the domain and user name for each privileged user. For a complete list of options, see the man page for the command.

The following command creates a scanner pool named SP on the vs1 SVM:

```
cluster1::> vserver vscan scanner-pool create -vserver vs1 -scanner-pool
SP -hostnames 1.1.1.1,vmwin204-27.fsct.nb -privileged-users
cifs\u1,cifs\u2
```

2. Verify that the scanner pool was created:

```
vserver vscan scanner-pool show -vserver data_SVM|cluster_admin_SVM -scanner
-pool scanner pool
```

For a complete list of options, see the man page for the command.

The following command displays the details for the SP scanner pool:

```
Cluster1::> vserver vscan scanner-pool show -vserver vs1 -scanner-pool

SP

Vserver: vs1

Scanner Pool: SP

Applied Policy: idle

Current Status: off

Cluster on Which Policy Is Applied: -

Scanner Pool Config Owner: vserver

List of IPs of Allowed Vscan Servers: 1.1.1.1, 10.72.204.27

List of Host Names of Allowed Vscan Servers: 1.1.1.1, vmwin204-

27.fsct.nb

List of Privileged Users: cifs\u1, cifs\u2
```

You can also use the vserver vscan scanner-pool show command to view all of the scanner pools on an SVM. For complete command syntax, see the man page for the command.

Create scanner pools in MetroCluster configurations

You must create primary and secondary scanner pools on each cluster in a MetroCluster configuration, corresponding to the primary and secondary SVMs on the cluster.

What you'll need


- SVMs and Vscan servers must be in the same domain or in trusted domains.
- For scanner pools defined for an individual SVM, you must have configured ONTAP Antivirus Connector with the SVM management LIF or SVM data LIF.
- For scanner pools defined for all the SVMs in a cluster, you must have configured ONTAP Antivirus Connector with the cluster management LIF.
- The list of privileged users must include the domain user account the Vscan server uses to connect to the SVM.
- Once the scanner pool is configured, check the connection status to the servers.

About this task

MetroCluster configurations protect data by implementing two physically separate mirrored clusters. Each cluster synchronously replicates the data and SVM configuration of the other. A primary SVM on the local cluster serves data when the cluster is online. A secondary SVM on the local cluster serves data when the remote cluster is offline.

This means that you must create primary and secondary scanner pools on each cluster in a MetroCluster configuration, The secondary pool becomes active when the cluster begins serving data from the secondary SVM. For Disaster Recovery (DR) the configuration is similar to MetroCluster.

This figure shows a typical MetroCluster/DR configuration.



Steps

1. Create a scanner pool:

vserver vscan scanner-pool create -vserver data_SVM|cluster_admin_SVM -scanner -pool scanner_pool -hostnames Vscan_server_hostnames -privileged-users privileged users

- Specify a data SVM for a pool defined for an individual SVM, and specify a cluster admin SVM for a pool defined for all the SVMs in a cluster.
- Specify an IP address or FQDN for each Vscan server host name.
- Specify the domain and user name for each privileged user.



You must create all scanner pools from the cluster containing the primary SVM.

For a complete list of options, see the man page for the command.

The following commands create primary and secondary scanner pools on each cluster in a MetroCluster configuration:

```
cluster1::> vserver vscan scanner-pool create -vserver cifssvm1 -
scanner-pool pool1_for_site1 -hostnames scan1 -privileged-users cifs
\u1,cifs\u2

cluster1::> vserver vscan scanner-pool create -vserver cifssvm1 -
scanner-pool pool1_for_site2 -hostnames scan1 -privileged-users cifs
\u1,cifs\u2

cluster1::> vserver vscan scanner-pool create -vserver cifssvm1 -
scanner-pool pool2_for_site1 -hostnames scan2 -privileged-users cifs
\u1,cifs\u2

cluster1::> vserver vscan scanner-pool create -vserver cifssvm1 -
scanner-pool pool2_for_site2 -hostnames scan2 -privileged-users cifs
\u1,cifs\u2
```

2. Verify that the scanner pools were created:

 $\label{lem:constraint} $$\operatorname{vserver} \ data_SVM | \ cluster_admin_SVM - scanner - pool \ scanner_pool \\$

For a complete list of options, see the man page for the command.

The following command displays the details for the scanner pool pool1:

You can also use the vserver vscan scanner-pool show command to view all of the scanner pools on an SVM. For complete command syntax, see the man page for the command.

Apply a scanner policy on a single cluster

A scanner policy determines whether a scanner pool is active. You must activate a scanner pool before the Vscan servers that it defines can connect to an SVM.

About this task

- · You can apply only one scanner policy to a scanner pool.
- If you created a scanner pool for all the SVMs in a cluster, you must apply a scanner policy on each SVM individually.

Steps

1. Apply a scanner policy:

```
vserver vscan scanner-pool apply-policy -vserver data_SVM -scanner-pool
scanner_pool -scanner-policy primary|secondary|idle -cluster
cluster_to_apply_policy_on
```

A scanner policy can have one of the following values:

- Primary specifies that the scanner pool is active.
- ° Secondary specifies that the scanner pool is active only if none of the Vscan servers in the primary scanner pool are connected.
- Idle specifies that the scanner pool is inactive.

The following example shows that the scanner pool named SP on the vs1 SVM is active:

```
cluster1::> vserver vscan scanner-pool apply-policy -vserver vs1
-scanner-pool SP -scanner-policy primary
```

2. Verify that the scanner pool is active:

```
vserver vscan scanner-pool show -vserver data_SVM|cluster_admin_SVM -scanner
-pool scanner_pool
```

For a complete list of options, see the man page for the command.

The following command displays the details for the SP scanner pool:

You can use the vserver vscan scanner-pool show-active command to view the active scanner pools on an SVM. For the complete command syntax, see the man page for the command.

Apply scanner policies in MetroCluster configurations

A scanner policy determines whether a scanner pool is active. You must apply a scanner policy to the primary and secondary scanner pools on each cluster in a MetroCluster configuration.

About this task

- You can apply only one scanner policy to a scanner pool.
- If you created a scanner pool for all the SVMs in a cluster, you must apply a scanner policy on each SVM individually.
- For disaster recovery and MetroCluster configurations, you must apply a scanner policy to every scanner pool in the local cluster and remote cluster.
- In the policy that you create for the local cluster, you must specify the local cluster in the cluster parameter. In the policy that you create for the remote cluster, you must specify the remote cluster in the cluster parameter. The remote cluster can then take over virus scanning operations in case of a disaster.

Steps

1. Apply a scanner policy:

```
vserver vscan scanner-pool apply-policy -vserver data_SVM -scanner-pool
scanner pool -scanner-policy primary|secondary|idle -cluster
```

```
cluster to apply policy on
```

A scanner policy can have one of the following values:

- ° Primary specifies that the scanner pool is active.
- Secondary specifies that the scanner pool is active only if none of the Vscan servers in the primary scanner pool are connected.
- ° Idle specifies that the scanner pool is inactive.



You must apply all scanner policies from the cluster containing the primary SVM.

The following commands apply scanner policies to the primary and secondary scanner pools on each cluster in a MetroCluster configuration:

```
cluster1::>vserver vscan scanner-pool apply-policy -vserver cifssvm1
-scanner-pool pool1_for_site1 -scanner-policy primary -cluster
cluster1

cluster1::>vserver vscan scanner-pool apply-policy -vserver cifssvm1
-scanner-pool pool2_for_site1 -scanner-policy secondary -cluster
cluster1

cluster1::>vserver vscan scanner-pool apply-policy -vserver cifssvm1
-scanner-pool pool1_for_site2 -scanner-policy primary -cluster
cluster2

cluster1::>vserver vscan scanner-pool apply-policy -vserver cifssvm1
-scanner-pool pool2_for_site2 -scanner-policy secondary -cluster
cluster2
```

2. Verify that the scanner pool is active:

```
vserver vscan scanner-pool show -vserver data_SVM|cluster_admin_SVM -scanner
-pool scanner pool
```

For a complete list of options, see the man page for the command.

The following command displays the details for the scanner pool pool1:

You can use the vserver vscan scanner-pool show-active command to view the active scanner pools on an SVM. For complete command syntax, see the man page for the command.

Commands for managing scanner pools

You can modify and delete scanner pools, and manage privileged users and Vscan servers for a scanner pool. You can also view summary information about the scanner pool.

If you want to	Enter the following command
Modify a scanner pool	vserver vscan scanner-pool modify
Delete a scanner pool	vserver vscan scanner-pool delete
Add privileged users to a scanner pool	vserver vscan scanner-pool privileged- users add
Delete privileged users from a scanner pool	vserver vscan scanner-pool privileged- users remove
Add Vscan servers to a scanner pool	vserver vscan scanner-pool servers add
Delete Vscan servers from a scanner pool	vserver vscan scanner-pool servers remove
View summary and details for a scanner pool	vserver vscan scanner-pool show
View privileged users for a scanner pool	vserver vscan scanner-pool privileged- users show

For more information about these commands, see the man pages.

Configure on-access scanning

Create an on-access policy

An on-access policy defines the scope of an on-access scan. You can create an on-access policy for an individual SVM or for all the SVMs in a cluster. If you created an on-access policy for all the SVMs in a cluster, you must enable the policy on each SVM individually.

About this task

- You can specify the maximum file size to scan, file extensions and paths to include in the scan, and file
 extensions and paths to exclude from the scan.
- You can set the scan-mandatory option to off to specify that file access is allowed when no Vscan servers are available for virus scanning.
- By default, ONTAP creates an on-access policy named "default_CIFS" and enables it for all the SVMs in a cluster.
- Any file that qualifies for scan exclusion based on the paths-to-exclude, file-ext-to-exclude, or max-file-size parameters is not considered for scanning, even if the scan-mandatory option is set to on. (Check this troubleshooting section for connectivity issues related to the scan-mandatory option.)
- By default, only read-write volumes are scanned. You can specify filters that enable scanning of read-only volumes or that restrict scanning to files opened with execute access.
- Virus scanning is not performed on an SMB share for which the continuously-available parameter is set to Yes.
- See the Antivirus architecture section for details about the Vscan file-operations profile.
- You can create a maximum of ten (10) on-access policies per SVM. However, you can enable only one on-access policy at a time.
 - You can exclude a maximum of one hundred (100) paths and file extensions from virus scanning in an on-access policy.
- · Some file exclusion recommendations:
 - Consider excluding large files (file size can be specified) from virus scanning because they can result in a slow response or scan request timeouts for CIFS users. The default file size for exclusion is 2GB.
 - Consider excluding file extensions such as .vhd and .tmp because files with these extensions might not be appropriate for scanning.
 - Consider excluding file paths such as the quarantine directory or paths in which only virtual hard drives or databases are stored.
 - Verify that all exclusions are specified in the same policy, because only one policy can be enabled at a time. NetApp highly recommends having the same set of exclusions specified in the antivirus engine.

Steps

1. Create an on-access policy:

vserver vscan on-access-policy create -vserver data_SVM|cluster_admin_SVM -policy-name policy_name -protocol CIFS -max-file-size

max_size_of_files_to_scan -filters [scan-ro-volume,][scan-execute-access]
-file-ext-to-include extensions_of_files_to_include -file-ext-to-exclude

extensions_of_files_to_exclude -scan-files-with-no-ext true|false -paths-to-exclude paths of files to exclude -scan-mandatory on|off

- Specify a data SVM for a policy defined for an individual SVM, a cluster admin SVM for a policy defined for all the SVMs in a cluster.
- The -file-ext-to-exclude setting overrides the -file-ext-to-include setting.
- Set -scan-files-with-no-ext to true to scan files without extensions. The following command creates an on-access policy named Policy1 on the vs1 SVM:

```
cluster1::> vserver vscan on-access-policy create -vserver vs1 -policy
-name Policy1 -protocol CIFS -filters scan-ro-volume -max-file-size 3GB
-file-ext-to-include "mp*","tx*" -file-ext-to-exclude "mp3","txt" -scan
-files-with-no-ext false -paths-to-exclude "\vol\a b\","\vol\a,b\"
```

2. Verify that the on-access policy has been created: vserver vscan on-access-policy show -instance data SVM|cluster admin SVM -policy-name policy name

For a complete list of options, see the man page for the command.

The following command displays the details for the Policy1 policy:

Enable an on-access policy

An on-access policy defines the scope of an on-access scan. You must enable an on-access policy on an SVM before its files can be scanned.

If you created an on-access policy for all the SVMs in a cluster, you must enable the policy on each SVM individually. You can enable only one on-access policy on an SVM at a time.

Steps

1. Enable an on-access policy:

```
vserver vscan on-access-policy enable -vserver data_SVM -policy-name
policy name
```

The following command enables an on-access policy named Policy1 on the vs1 SVM:

```
cluster1::> vserver vscan on-access-policy enable -vserver vs1 -policy
-name Policy1
```

2. Verify that the on-access policy is enabled:

```
vserver vscan on-access-policy show -instance data_SVM -policy-name
policy_name
```

For a complete list of options, see the man page for the command.

The following command displays the details for the Policy1 on-access policy:

```
cluster1::> vserver vscan on-access-policy show -instance vs1 -policy
-name Policy1

Vserver: vs1
Policy: Policy1
Policy Status: on
Policy Config Owner: vserver
File-Access Protocol: CIFS
Filters: scan-ro-volume
Mandatory Scan: on

Max File Size Allowed for Scanning: 3GB
File Paths Not to Scan: \vol\a b\, \vol\a,b\
File Extensions Not to Scan: mp3, txt
File Extensions to Scan: mp*, tx*
Scan Files with No Extension: false
```

Modify the Vscan file-operations profile for an SMB share

The *Vscan file-operations profile* for an SMB share defines the operations on the share that can trigger scanning. By default, the parameter is set to standard. You can adjust the parameter as necessary when you create or modify an SMB share.

See the Antivirus architecture section for details about the Vscan file-operations profile.



Virus scanning is not performed on an SMB share that has the continuously-available parameter set to Yes.

Step

1. Modify the value of the Vscan file-operations profile for an SMB share:

vserver cifs share modify -vserver data_SVM -share-name share -path share_path
-vscan-fileop-profile no-scan|standard|strict|writes-only

For a complete list of options, see the man page for the command.

The following command changes the Vscan file operations profile for an SMB share to strict:

```
cluster1::> vserver cifs share modify -vserver vs1 -share-name
SALES_SHARE -path /sales -vscan-fileop-profile strict
```

Commands for managing on-access policies

You can modify, disable, or delete an on-access policy. You can view a summary and details for the policy.

If you want to	Enter the following command
Create an on-access policy	vserver vscan on-access-policy create
Modify an on-access policy	vserver vscan on-access-policy modify
Enable an on-access policy	vserver vscan on-access-policy enable
Disable an on-access policy	vserver vscan on-access-policy disable
Delete an on-access policy	vserver vscan on-access-policy delete
View summary and details for an on-access policy	vserver vscan on-access-policy show
Add to the list of paths to exclude	vserver vscan on-access-policy paths- to-exclude add
Delete from the list of paths to exclude	vserver vscan on-access-policy paths- to-exclude remove
View the list of paths to exclude	vserver vscan on-access-policy paths- to-exclude show

Add to the list of file extensions to exclude	vserver vscan on-access-policy file- ext-to-exclude add
Delete from the list of file extensions to exclude	vserver vscan on-access-policy file- ext-to-exclude remove
View the list of file extensions to exclude	vserver vscan on-access-policy file- ext-to-exclude show
Add to the list of file extensions to include	vserver vscan on-access-policy file- ext-to-include add
Delete from the list of file extensions to include	vserver vscan on-access-policy file- ext-to-include remove
View the list of file extensions to include	vserver vscan on-access-policy file- ext-to-include show

For more information about these commands, see the man pages.

Configure on-demand scanning

Configure on-demand scanning overview

You can use on-demand scanning to check files for viruses immediately or on a schedule.

You might want to run scans only in off-peak hours, for example, or you might want to scan very large files that were excluded from an on-access scan. You can use a cron schedule to specify when the task runs.

About this topic

- You can assign a schedule when you create a task.
- Only one task can be scheduled at a time on an SVM.
- · On-demand scanning does not support scanning of symbolic links or stream files.



On-demand scanning does not support scanning of symbolic links or stream files.



To create an on-demand task, there must be at least one on-access policy enabled. It can be the default policy or a user created on-access policy.

Create an on-demand task

An on-demand task defines the scope of an on-demand scan. You can specify the maximum size of the files to be scanned, the extensions and paths of the files to be included in the scan, and the extensions and paths of the files to be excluded from the scan. Files in subdirectories are scanned by default.

About this task

- A maximum of ten (10) on-demand tasks can exist for each SVM, but only one can be active.
- An on-demand task creates a report, which has information regarding the statistics related to the scans. This report is accessible with a command or by downloading the report file created by the task at the location defined.

Steps

1. Create an on-demand task:

```
vserver vscan on-demand-task create -vserver data_SVM -task-name task_name -scan-paths paths_of_files_to_scan -report-directory report_directory_path -report-expiry-time expiration_time_for_report -schedule cron_schedule -max -file-size max_size_of_files_to_scan -paths-to-exclude paths_of_files_to_exclude -file-ext-to-exclude extensions_of_files_to_exclude -file-ext-to-include extensions_of_files_to_include -scan-files-with-no-ext true|false -directory-recursion true|false
```

- The -file-ext-to-exclude setting overrides the -file-ext-to-include setting.
- Set -scan-files-with-no-ext to true to scan files without extensions.

For a complete list of options, see the man page for the command.

The following command creates an on-demand task named Task1 on the vs1SVM:

```
cluster1::> vserver vscan on-demand-task create -vserver vs1 -task-name Task1 -scan-paths "/vol1/","/vol2/cifs/" -report-directory "/report" -schedule daily -max-file-size 5GB -paths-to-exclude "/vol1/cold-files/" -file-ext-to-include "vmdk?","mp*" -file-ext-to-exclude "mp3","mp4" -scan-files-with-no-ext false [Job 126]: Vscan On-Demand job is queued. Use the "job show -id 126" command to view the status.
```



You can use the job show command to view the status of the job. You can use the job pause and job resume commands to pause and restart the job, or the job stop command to end the job.

2. Verify that the on-demand task has been created:

```
vserver vscan on-demand-task show -instance data SVM -task-name task name
```

For a complete list of options, see the man page for the command.

The following command displays the details for the Task1 task:

```
cluster1::> vserver vscan on-demand-task show -instance vs1 -task-name
Task1
                           Vserver: vs1
                         Task Name: Task1
                List of Scan Paths: /vol1/, /vol2/cifs/
             Report Directory Path: /report
                      Job Schedule: daily
Max File Size Allowed for Scanning: 5GB
            File Paths Not to Scan: /vol1/cold-files/
       File Extensions Not to Scan: mp3, mp4
           File Extensions to Scan: vmdk?, mp*
      Scan Files with No Extension: false
           Request Service Timeout: 5m
                    Cross Junction: true
               Directory Recursion: true
                     Scan Priority: low
                  Report Log Level: info
        Expiration Time for Report: -
```

After you finish

You must enable scanning on the SVM before the task is scheduled to run.

Schedule an on-demand task

You can create a task without assigning a schedule and use the vserver vscan ondemand-task schedule command to assign a schedule; or add a schedule while creating the task.

About this task

The schedule assigned with the vserver vscan on-demand-task schedule command overrides a schedule already assigned with the vserver vscan on-demand-task create command.

Steps

1. Schedule an on-demand task:

```
{\tt vserver\ vscan\ on-demand-task\ schedule\ -vserver\ data\_SVM\ -task-name\ task\_name\ -schedule\ cron\_schedule}
```

The following command schedules an on-access task named Task2 on the vs2 SVM:

```
cluster1::> vserver vscan on-demand-task schedule -vserver vs2 -task
-name Task2 -schedule daily
[Job 142]: Vscan On-Demand job is queued. Use the "job show -id 142"
command to view the status.
```



You can use the job show command to view the status of the job. You can use the job pause and job resume commands to pause and restart the job, or the job stop command to end the job.

2. Verify that the on-demand task has been scheduled:

```
vserver vscan on-demand-task show -instance data_SVM -task-name task_name For a complete list of options, see the man page for the command.
```

The following command displays the details for the Task 2 task:

```
cluster1::> vserver vscan on-demand-task show -instance vs2 -task-name
Task2
                           Vserver: vs2
                         Task Name: Task2
                List of Scan Paths: /vol1/, /vol2/cifs/
             Report Directory Path: /report
                      Job Schedule: daily
Max File Size Allowed for Scanning: 5GB
            File Paths Not to Scan: /vol1/cold-files/
       File Extensions Not to Scan: mp3, mp4
           File Extensions to Scan: vmdk, mp*
      Scan Files with No Extension: false
           Request Service Timeout: 5m
                    Cross Junction: true
               Directory Recursion: true
                     Scan Priority: low
                  Report Log Level: info
```

After you finish

You must enable scanning on the SVM before the task is scheduled to run.

Run an on-demand task immediately

You can run an on-demand task immediately, whether or not you have assigned a schedule.

What you'll need

You must have enabled scanning on the SVM.

Step

1. Run an on-demand task immediately:

```
vserver vscan on-demand-task run -vserver data SVM -task-name task name
```

The following command runs an on-access task named Task1 on the vs1 SVM:

```
cluster1::> vserver vscan on-demand-task run -vserver vs1 -task-name
Task1
```

[Job 161]: Vscan On-Demand job is queued. Use the "job show -id 161" command to view the status.



You can use the job show command to view the status of the job. You can use the job pause and job resume commands to pause and restart the job, or the job stop command to end the job.

Commands for managing on-demand tasks

You can modify, delete, or unschedule an on-demand task. You can view a summary and details for the task, and manage reports for the task.

If you want to	Enter the following command
Create an on-demand task	vserver vscan on-demand-task create
Modify an on-demand task	vserver vscan on-demand-task modify
Delete an on-demand task	vserver vscan on-demand-task delete
Run an on-demand task	vserver vscan on-demand-task run
Schedule an on-demand task	vserver vscan on-demand-task schedule
Unschedule an on-demand task	vserver vscan on-demand-task unschedule
View summary and details for an on-demand task	vserver vscan on-demand-task show
View on-demand reports	vserver vscan on-demand-task report show
Delete on-demand reports	vserver vscan on-demand-task report delete

Best practices for configuring the off-box antivirus functionality in clustered ONTAP

Consider the following recommendations for configuring the off-box functionality in clustered ONTAP.

- Restrict privileged users to virus-scanning operations. Normal users should be discouraged from using
 privileged user credentials. This restriction can be achieved by turning off login rights for privileged users
 on Active Directory.
- Privileged users are not required to be part of any user group that has a large number of rights in the
 domain, such as the administrators group or the backup operators group. Privileged users must be
 validated only by the storage system so that they are allowed to create Vscan server connections and
 access files for virus scanning.
- Use the computers running Vscan servers only for virus-scanning purposes. To discourage general use, disable the Windows terminal services and other remote access provisions on these machines and grant the right to install new software on these machines only to administrators.
- Dedicate Vscan servers to virus scanning and do not use them for other operations, such as backups. You
 might decide to run the Vscan server as a virtual machine (VM). If this is the case, ensure that the
 resources allocated to the VM are not shared and are enough to perform virus scanning. Consult
 Symantec for guidance on antivirus engine requirements.
- Provide adequate CPU, memory, and disk capacity to the Vscan server to avoid resource bottlenecks.
 Most Vscan servers are designed to use multiple CPU core servers and to distribute the load across the CPUs. Consult Symantec for guidance on antivirus engine requirements.
- NetApp recommends using a dedicated network with a private VLAN for the connection from the SVM to
 the Vscan server so that the scan traffic is not affected by other client network traffic. Create a separate
 NIC that is dedicated to the antivirus VLAN on the Vscan server and to the data LIF on the SVM. This step
 simplifies administration and troubleshooting if network issues arise. The AV traffic should be segregated
 using a private network. The AV server should be configured to communicate with domain controller (DC)
 and clustered ONTAP in one of the following ways:
 - The DC should communicate to the AV servers through the private network that is used to segregate the traffic.
 - The DC and AV server should communicate through a different network (not the private network mentioned previously), which is not the same as the CIFS client network.

For Kerberos authentication to work for the AV communication, create a DNS entry for the private LIFs and a service principal name on the DC corresponding to the DNS entry created for the private LIF. Use this name when adding a LIF to the AV Connector. The DNS should be able to return a unique name for each private LIF connected to the AV Connector.



IMPORTANT: If the LIF for Vscan traffic is configured on a different port than the LIF for client traffic, the Vscan LIF might fail over to another node in case of a port failure. The change will make the Vscan server not reachable from the new node and the scan notifications for file operations on the node will fail. Ensure that the Vscan server is reachable through at least one LIF on a node so that it can process scan requests for file operations performed on that node.

• Connect the NetApp storage system and the Vscan server by using at least a 1GbE network.

- For an environment with multiple Vscan servers, connect all servers that have similar high-performing network connections. Connecting the Vscan servers improves performance by allowing load sharing.
- For remote sites and branch offices, NetApp recommends using a local Vscan server rather than a remote Vscan server because the former is a perfect candidate for high latency. If cost is a factor, use a laptop or PC for moderate virus protection. You can schedule periodic complete file system scans by sharing the volumes or qtrees and scanning them from any system in the remote site.
- Use multiple Vscan servers to scan the data on the SVM for load-balancing and redundancy purposes. The
 amount of CIFS workload and resulting antivirus traffic vary per SVM. Monitor CIFS and virus-scanning
 latencies on the storage controller. Trend the results over time. If CIFS latencies and virus-scanning
 latencies increase due to CPU or application bottlenecks on the Vscan servers beyond trend thresholds,
 CIFS clients might experience long wait times. Add additional Vscan servers to distribute the load.
- Install the latest version of Antivirus Connector. For detailed information about supportability, see the NetApp Interoperability Matrix Tool (IMT).
- Keep antivirus engines and definitions up to date. Consult Symantec for recommendations on update frequency.
- In a multi-tenancy environment, a scanner pool (pool of Vscan servers) can be shared with multiple SVMs provided that the Vscan servers and the SVMs are part of the same domain or of a trusted domain.
- The AV software policy for infected files should be set to delete or quarantine, which is the default value set by most AV vendors. In case the vscan-fileop-profile is set to write_only, and if an infected file is found, the file remains in the share and can be opened since opening a file will not trigger a scan. The AV scan is triggered only after the file is closed.
- The scan-engine timeout value should be lesser than the scanner-pool request-timeout. If it is set to a higher value, access to files might be delayed and may eventually time out. To avoid this, configure the scan-engine timeout to 5 seconds lesser than the scanner-pool request-timeout value. See the scan engine vendor's documentation for instructions on how to change the scan-engine timeout settings. The scanner-pool timeout can be changed by using the following command in advanced mode and by providing the appropriate value for the request-timeout parameter: vserver vscan scanner-pool modify
- For an environment that is sized for on-access scanning workload and requiring the use of on-demand scanning, it is recommended to schedule the on-demand scan job in off-peak hours to avoid additional load on the existing AV infrastructure.

Enable virus scanning on an SVM

You must enable virus scanning on an SVM before an on-access or on-demand scan can run.

Steps

1. Enable virus scanning on an SVM:

vserver vscan enable -vserver data_SVM



You can use the vserver vscan disable command to disable virus scanning, if necessary.

The following command enables virus scanning on the vs1 SVM:

```
cluster1::> vserver vscan enable -vserver vs1
```

2. Verify that virus scanning is enabled on the SVM:

```
vserver vscan show -vserver data_SVM
```

For a complete list of options, see the man page for the command.

The following command displays the Vscan status of the vs1 SVM:

Reset the status of scanned files

Occasionally, you might want to reset the scan status of successfully scanned files on an SVM by using the vserver vscan reset command to discard the cached information for the files. You might want to use this command to restart the virus scanning processing in case of a misconfigured scan, for example.

About this task

After you run the vserver vscan reset command, all eligible files will be scanned the next time they are accessed.



This command can affect performance adversely, depending on the number and size of the files to be rescanned.

What you'll need

Advanced privileges are required for this task.

Steps

1. Change to advanced privilege level:

```
set -privilege advanced
```

2. Reset the status of scanned files:

```
vserver vscan reset -vserver data SVM
```

The following command resets the status of scanned files on the vs1 SVM:

```
cluster1::> vserver vscan reset -vserver vs1
```

View Vscan event log information

You can use the vserver vscan show-events command to view event log information about infected files, updates to Vscan servers, and the like. You can view event information for the cluster or for given nodes, SVMs, or Vscan servers.

What you'll need

Advanced privileges are required for this task.

Steps

1. Change to advanced privilege level:

```
set -privilege advanced
```

2. View Vscan event log information:

```
vserver vscan show-events
```

For a complete list of options, see the man page for the command.

The following command displays event log information for the cluster cluster1:

cluster1::	*> vserver vscan	show-events		
Vserver	Node	Server	Event Type	Event Time
vs1	Cluster-01	192.168.1.1	file-infected	9/5/2014
11:37:38				
vs1	Cluster-01	192.168.1.1	scanner-updated	9/5/2014
11:37:08				
vs1	Cluster-01	192.168.1.1	scanner-connected	9/5/2014
11:34:55				
3 entries	were displayed.			

Troubleshoot connectivity issues and monitor performance activities

Potential connectivity issues involving the scan-mandatory option

You can use the vserver vscan connection-status show commands to view information about Vscan server connections that you might find helpful in troubleshooting connectivity issues.

By default, the scan-mandatory option for on-access scanning denies file access when a Vscan server connection is not available for scanning. Although this option offers important safety features, it can lead to

problems in a few situations.

- Before enabling client access, you must ensure that at least one Vscan server is connected to an SVM on each node that has a LIF. If you need to connect servers to SVMs after enabling client access, you must turn off the scan-mandatory option on the SVM to ensure that file access is not denied because a Vscan server connection is not available. You can turn the option back on after the server has been connected.
- If a target LIF hosts all the Vscan server connections for an SVM, the connection between the server and the SVM will be lost if the LIF is migrated. To ensure that file access is not denied because a Vscan server connection is not available, you must turn off the scan-mandatory option before migrating the LIF. You can turn the option back on after the LIF has been migrated.

Each SVM should have at least two Vscan servers assigned to it. It is a best practice to connect Vscan servers to the storage system over a different network from the one used for client access.

Commands for viewing Vscan server connection status

You can use the vserver vscan connection-status show commands to view summary and detailed information about Vscan server connection status.

If you want to	Enter the following command
View a summary of Vscan server connections	vserver vscan connection-status show
View details for Vscan server connections	vserver vscan connection-status show- all
View details for connected Vscan servers	vserver vscan connection-status show- connected
View details for available Vscan servers that are not connected	vserver vscan connection-status show- not-connected

For more information about these commands, see the man pages.

Troubleshoot virus scanning

For common virus scanning issues, there are possible causes and ways to resolve them. Virus scanning is also known as Vscan.

Issue	How to resolve it
The Vscan servers are not able to connect to the clustered ONTAP storage system.	Check whether the scanner pool configuration specifies the Vscan server IP address. Check also if the allowed privileged users in the scanner pool list are active. To check the scanner pool, run the vserver vscan scanner-pool show command on the storage system command prompt. If the Vscan servers still cannot connect, there might be an issue with the network.

Clients observe high latency	It is probably time to add more Vscan servers to the scanner pool.
Too many scans are triggered	Modify the value of the vscan-fileop-profile parameter to restrict the number of file operations monitored for virus scanning.
Some files are not being scanned.	Check the on-access policy. It is possible that the path for these files has been added to the path-exclusion list or that their size exceeds the configured value for exclusions. To check the on-access policy, run the vserver vscan on-access-policy show command on the storage system command prompt.
File access is denied.	Check whether the scan-mandatory setting is specified in the policy configuration. This setting denies data access if no Vscan servers are connected. Modify the setting as appropriate.

Monitor status and performance activities

You can monitor the critical aspects of the Vscan module, such as the Vscan server connection status, the health of the Vscan servers, and the number of files that have been scanned. This information helps you diagnose issues related to the Vscan server.

View Vscan server connection information

You can view the connection status of Vscan servers to manage the connections that are already in use and the connections that are available for use. Various commands display information about the connection status of Vscan servers.

Command	Information displayed
vserver vscan connection-status show	Summary of the connection status
vserver vscan connection-status show-all	Detailed information about the connection status
vserver vscan connection-status show- not-connected	Status of the connections that are available but not connected
vserver vscan connection-status show- connected	Information about the connected Vscan server

For more information about these commands, see the man pages.

View Vscan server statistics

You can view Vscan server—specific statistics to monitor performance and diagnose issues related to virus scanning. You must collect a data sample before you can use the statistics show command to display the Vscan server statistics. To complete a data sample, complete the following step:

Step

1. Run the statistics start command and the optional statistics stop command.

View statistics for Vscan server requests and latencies

You can use ONTAP offbox_vscan counters on a per-SVM basis to monitor the rate of Vscan server requests that are dispatched and received per second and the server latencies across all Vscan servers. To view these statistics, complete the following step:

Step

1. Run the statistics show object offbox vscan -instance SVM command with the following counters:

Counter	Information displayed
scan_request_dispatched_rate	Number of virus-scanning requests sent from ONTAP to the Vscan servers per second
scan_noti_received_rate	Number of virus-scanning requests received back by ONTAP from the Vscan servers per second
dispatch_latency	Latency within ONTAP to identify an available Vscan server and send the request to that Vscan server
scan_latency	Round-trip latency from ONTAP to the Vscan server, including the time for the scan to run

Example of statistics generated from an ONTAP offbox vscan counter

View statistics for individual Vscan server requests and latencies

You can use ONTAP offbox_vscan_server counters on a per-SVM, per-off-box Vscan server, and per-node basis to monitor the rate of dispatched Vscan server requests and the server latency on each Vscan server individually. To collect this information, complete the following step:

Step

1. Run the statistics show -object offbox_vscan -instance SVM:servername:nodename command with the following counters:

Counter	Information displayed
scan_request_dispatched_rate	Number of virus-scanning requests sent from ONTAP
scan_latency	Round-trip latency from ONTAP to the Vscan server, including the time for the scan to run to the Vscan servers per second

Example of statistics generated from an ONTAP offbox_vscan_server counter

View statistics for Vscan server utilization

You can also use ONTAP offbox_vscan_server counters to collect Vscan server—side utilization statistics. These statistics are tracked on a per-SVM, per—off-box Vscan server, and per-node basis. They include CPU utilization on the Vscan server, queue depth for scanning operations on the Vscan server (both current and maximum), used memory and used network. These statistics are forwarded by the Antivirus Connector to the statistics counters within ONTAP. They are based on data that is polled every 20 seconds and must be collected multiple times for accuracy; otherwise, the values seen in the statistics reflect only the last polling. CPU utilization and queues are particularly important to monitor and analyze. A high value for an average queue can indicate that the Vscan server has a bottleneck. To collect utilization statistics for the Vscan server on a per-SVM, per—off-box Vscan server, and per-node basis, complete the following step:

Step

1. Collect utilization statistics for the Vscan server

Run the statistics show -object offbox_vscan_server -instance SVM:servername:nodename command with the following offbox vscan server counters:

Counter	Information displayed
scanner_stats_pct_cpu_used	CPU utilization on the Vscan server
scanner_stats_pct_input_queue_avg	Average queue of scan requests on the Vscan server
scanner_stats_pct_input_queue_hiwatermark	Peak queue of scan requests on the Vscan server
scanner_stats_pct_mem_used	Memory used on the Vscan server
scanner_stats_pct_network_used	Network used on the Vscan server

Example of utilization statistics for the Vscan server

Copyright information

Copyright © 2023 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.