Dispersion formulas (for metal)

All quantities (except dimensionless numbers) are expressed in units of eV. In this case, the angular frequency ω is expressed by the vacuum wavelength $\lambda[\mu m]$ as

$$\omega[\text{eV}] = \frac{hc}{e} \times 10^6 \frac{1}{\lambda [\mu m]}.$$

The refractive index n and extinction coefficient k is given by

$$n = \text{Re}\sqrt{\varepsilon},$$
$$k = \text{Im}\sqrt{\varepsilon}.$$

Where arepsilon is the dielectric function given by one of the following formulas.

1: Drude-Lorentz model

$$\varepsilon(\omega) = \varepsilon_b - \frac{f_0 \omega_p^2}{\omega(\omega + i\Gamma_0)} - \sum_{j=1}^5 \frac{f_j \omega_p^2}{\omega^2 - \omega_j^2 + i\omega\Gamma_j}.$$

In this case, coefficients are defined by

$$\{C_n\} = \{\varepsilon_b, f_0, \Gamma_0, \omega_p, f_1, \Gamma_1, \omega_1, f_2, \Gamma_2, \omega_2, \cdots\}.$$

2: Brendel-Bormann model

$$\varepsilon(\omega) = \varepsilon_b - \frac{f_0 \omega_p^2}{\omega(\omega + \mathrm{i}\Gamma_0)} + \mathrm{i}\frac{\sqrt{\pi}}{2\sqrt{2}} \sum_{j=1}^5 \left[\frac{f_j \omega_p^2}{\sqrt{\omega(\omega + \mathrm{i}\Gamma_j)}\sigma_j} \left\{ w \left(\frac{\sqrt{\omega(\omega + \mathrm{i}\Gamma_j)} - \omega_j^2}{\sqrt{2}\sigma_j} \right) + w \left(\frac{\sqrt{\omega(\omega + \mathrm{i}\Gamma_j)} + \omega_j^2}{\sqrt{2}\sigma_j} \right) \right\} \right],$$

where w(z) is the error integral of the complex argument,

$$w(z) = e^{-z^2} \operatorname{erfc}(-iz) \quad (\operatorname{Im}[z] > 0),$$

with erfc(z) is the complementary error function,

$$\operatorname{erfc}(z) = \frac{2}{\sqrt{\pi}} \int_{z}^{\infty} \exp(-t^{2}) dt.$$

In this case, coefficients are defined by

$$\{\mathcal{C}_n\} = \{\varepsilon_b, f_0, \Gamma_0, \omega_p, f_1, \Gamma_1, \omega_1, \sigma_1, f_2, \Gamma_2, \omega_2, \sigma_2, \cdots\}.$$