

SC

Service Connector

Configuration and Operation Guide

SC_4_Operation_E (Version V1.1)

This document describes topics related to the SC configuration, operation and troubleshooting.

This document is a spiritual ownership of STABILIT Informatik AG, and must not be used or copied without a written allowance of this company. Unauthorized usage is illegal in terms of Chapter 23 / 5 UWG / Swiss law.

The information in this document is subject to change without notice and should not be construed as a commitment by STABILIT Informatik AG.

Copyright © 2011 by STABILIT Informatik AG All rights reserved.

All other logos, product names are trademarks of their respective owners.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.

See the License for the specific language governing permissions and limitations under the License.

This Document has been created with Microsoft Word 2003 (11) with template file C:\STABILIT\STANDARD\TEMPLATES\S_REP_E.DOT and printed at 15 April 2011 12:08.

Identification

Project:	SC			
Title:	Service Connector			
Subtitle:	Configuration and Operation Guide			
Version:	V1.1			
Reference:	SC_4_Operation_E			
Classification:	Public			
Keywords:	Configuration, Operation, Troubleshooting			
Comment:	This document describes topics related to the SC configuration, operation			
	and troubleshooting.			
Author(s):	STABILIT Informatik AG			
	Jan Trnka, Daniel Schmutz, Joël Traber			
Approval				
(Reviewed by):	Signature Jan Trnka			
	SIGNAVATO			
Audience:	Project team, development team			
Distribution:	Public			
Filename	c:\stabilit\projects\eurex\sc\documents\sc_4_operation_e.doc			

Revision History

Date	Version	Author	Description			
11.02.2011	V1.0	Jan Trnka	Initial version			
13.04.2011	V1.1	Jan Trnka	Corrections based on external review.			
15.04.2011	V1.2	Joël Traber	Added format of function scVersion,			
			serviceConfiguration to inspectCommand.			

Table of Contents

1 PR	EFACE	
1.1	Purpose & Scope of this Document	
1.2	Definitions & Abbreviations	
1.3	External References	5
1.4	Typographical Conventions	5
1.5	Outstanding Issues	5
	NCEPTS	
2.1	Session Service	
2.2	Publishing Service	
2.3	File Service	
2.4	HTTP Redirection Service	
2.5	SC Cascading	
2.6	Message Caching	
2.7	Message Fan-Out	
2.8	SC Console	
2.9	Web GUI	
2.10	Restrictions	
2.10	ϵ	
2.10		
2.10		
2.10	0.4 Virus and Intrusion Protection	
3 NE	TWORK	16
3 NE	Connection Topology	
3.1	1 60	
3.1.		
3.1.	•	
3.1.	5 Double Cascade	12
4 INS	STALLATION, UPDATE, REMOVAL	13
4.1	Installation	
4.2	Update	
4.3	Removal	
5 CO	NFIGURATION	14
5.1	SC Properties	
5.2	Logging	
6 OP	ERATIONS	22
6.1	Starting SC	22
6.2	Stopping SC	22
6.3	Other console operations	22
6.4	Monitoring SC with the Web GUI	
6.5	Monitoring SC with jconsole or jvisualvm	
	-	
7 TR	OUBLESHOOTING	27
7.1	General	27
7.2	The most often situations	27
8 GL	OSSARY	28

Tables

Table 1 Abbreviations & Definitions	.4
Table 2 External references	.5
Table 3 Typographical conventions	5

Figures

Figure 1 Example of a connection (simplified)	10
Figure 2 Example of a cascaded connection (simplified)	10

1 Preface

1.1 Purpose & Scope of this Document

This document describes issues related to the configuration, operation and troubleshooting of the Service Connector. Good understanding of network communication and the Service Connector concepts is prerequisite to this reading.

The SC message protocol is described in [1].

This document is particularly important to the operation & support staff..

1.2 Definitions & Abbreviations

Item / Term	Definition / Description	
DMZ	Demilitarized Zone (Network segment between two firewalls)	
DNS	Domain Name Server	
DOS	Denial Of Service	
GUI	Graphical User Interface	
HTML	Hypertext Mark-up Language	
HTTP	Hypertext Transport Protocol	
HTTPS	HTTP over SSL, encrypted and authenticated transport protocol	
IE	Internet Explorer – Microsoft Web Browser	
J2EE	Java 2 Platform Enterprise Edition	
Java	Programming language and run-time environment from SUN	
JDK	Java Development Kit	
Linux	Unix-like operating system, open source	
Log4j	Standard logging tool used in Java	
OpenVMS	HP Operating system	
OSI	Open System Interconnection reference model	
	http://en.wikipedia.org/wiki/OSI model	
RPC	Remote Procedure Call	
SCMP	SC Message Protocol	
SOA	Service Oriented Architecture	
SOAP	Simple Object Access Protocol	
SSL	Secure Socket Layer – secure communication protocol with	
	encryption and authentication	
SC	Service Connector	
TCP/IP	Transmission Control Protocol / Internet Protocol	
URL	Uniform Resource Locator	
Web Service	software designed to support interoperable machine-to-machine	
	interaction over a network	
Web-GUI	Graphical User Interface running in Web-Browser built with Web	
	components. Also called Thin-Client.	
Windows	Microsoft operating system family	
XML	Extensible Mark-up Language	
XSD	XML Schema Definition	
XSLT	Extensible Style Sheet Language Transformation	

Table 1 Abbreviations & Definitions

1.3 External References

References	Item / Reference to other Document
[1]	SC_1_SCMP-V1.1_E

Table 2 External references

1.4 Typographical Conventions

Convention	Meaning
text in italics	USP feature or functionality or USP related comments
text in Courier font	code example
[phrase]	In syntax diagrams, indicates that the enclosed values are optional
{ phrase1 phrase2 }	In syntax diagrams, indicates that multiple possibilities exist.
•••	In syntax diagrams, indicates a repetition of the previous expression

Table 3 Typographical conventions

The terminology used in this document may be somewhat different to other sources. The chapter Glossary includes a list of often used terms with the explanation of their meaning in this document.

1.5 Outstanding Issues

Following issues are outstanding at the time of the document release:

1.

2 Concepts

Service Connector is a message oriented middleware connecting applications providing services to other applications consuming the services. It fits into an overall service oriented architecture.


Service Connector supports following service types

2.1 Session Service

Session service allows statefull message exchange between requesting client application and server application implementing the service. All actions are initiated by the client. When the

client starts the session, SC allocates a server instance for this session. The server must be ready at this time. Multiple server instances serving the same service can be pre-started. Serving multiple sessions or multiple services within one server instance is possible only for multisession servers.

Clients and servers are <u>not</u> connected directly to each other. The client and the server are only the logical communication end-points. The SC acts like a message broker and is never a direct executor of the service. Clients and servers may be distributed across any number of nodes in the network.




All services are independent on each other. Clients and servers may be distributed across any number of nodes in the network. The server application may request another service and so play the client role.

2.2 Publishing Service

Publishing service allows a server to send messages to many clients. In order to receive a published message, the client must subscribe to a service. The subscription mask allows fine granular definition of the client interest.

Clients and servers are <u>not</u> connected directly to each other. The application server which implements the service designates the contents of each message with a message mask and sends it to SC. When the message mask matches the client subscription mask, SC will deliver the message to the client. Multiple clients may subscribe for the same service at the same time and may get the same message. The publishing server does not know which client did will receive its messages and when. Sequence order of the published messages is preserved by SC.



Multiple server instances may publish their messages to the same service. (Not allowed when large messages are published!) All services are independent on each other. Clients and servers may be distributed across any number of nodes in the network. The server application may request another service and so play the client role.

Service

2.3 File Service

File service allows file exchange between client application and a web server. All actions are initiated by the client. The client can upload to a service or download file from a service or get

a list of files in this service. Client and the Web Server are $\underline{\text{not}}$ connected directly to each other. The web server must define one $\underline{\text{flat}}$ directory for each service. Sub-directory structure is not supported. The same directory may be used by different services.

All services are independent on each other. Clients and web servers may be distributed across any number of nodes in the network.

PHP is required on the Web Server in order to support file services.

The provided PHP upload script may be adapted e.g. for sending notification mail after file upload.

2.4 HTTP Redirection Service

SC HTTP redirection service allows redirection of http traffic through the SC infrastructure to a designated target URL (web server). This is possible without a session or subscription context. It can be used by any application also by a browser. SC receives the http requests on a dedicated port and passes it to the configured server.

It does not work like a HTTP proxy.

Client and the Web Server are <u>not</u> connected directly to each other. Clients and targets (web servers) may be distributed across any number of nodes in the network. The requested target URL must be resolved (by DNS or other means) by the underlying network infrastructure. SC does not provide any name resolution.

Multiple http redirection services may be defined to different targets, each one listening on a different TCP/IP port.

2.5 SC Cascading

Multiple SCs may be running in a network. Any SC service may be defined as cascaded. This means that the message traffic for such service is redirected to another SC.

Cascading is fully transparent to the client. Clients can use services at any cascade level. Servers are allowed on the bottom level only.

Major benefits of cascading are:

- Improved security by using cascaded SC in a DMZ as a single access point for all local clients.
- Reduced communication costs by sharing infrastructure (VPN tunnel) by multiple clients
- Much lower outbound network traffic by utilizing message fanout.
- Improved performance by utilizing SC cache near to the clients.
- Routing of services into other network segments.


Service

2.6 Message Caching

For session services SC implements caching of message sent from servers to clients. The

cached message is available to all clients sending a request for it. Each service has its own cache and each cached message has an absolute expiration date and time. The cache is loaded by the first client requesting the messages. All subsequent clients will get the message from the cache, bypassing the server processing. Security is not affected because message exchange is possible only in a scope of a valid session.

The definition, which message should be cached, how it is identified and how long it is valid, is matter of agreement between the communicating parties.




SC caching can be enabled or disabled per SC instance. In cascaded configurations caching is supported on cascaded session service. This allows caching near to the message consumer.

2.7 Message Fan-Out

For publishing services SC implements message fan-out in cascaded configurations. Message published by a server is distributed to the clients on the most upper cascade

level. Between the SC nodes the message is transported only once. This allows efficient distribution of a message to large number of clients within a very short time.

The efficient usage of the fan-out is dependent on the design and structure of the subscription mask. It must contain items reflecting the cascade hierarchy.



2.8 SC Console

SC console is a tool which allows sending of simple management commands to SC from the command line. It may be used in scripts embedded into other management tools.

2.9 Web GUI

Web-GUI is a simple monitoring instrument showing the current SC activity. It can be disabled in the configuration. It utilizes http and can be used from any remote node having access to SC.

2.10 Restrictions

2.10.1 Load balancing

The SC does not provide any load balancing features. Established communication session will not be redirected to another server or service node during its life time.

2.10.2 Failover

The SC does not provide any failover features. Aborted communication must be re-established by the communicating partners. The client application must find out a service which is ready.

2.10.3 Security

The SC does not implement any security feature. The environment where SC is used must provide all required authentication, authorization, encryption, tunneling etc. features. Message transport over https is not supported.

The IP address of the all nodes on the network path between the client and the server is available to the server when client starts a new session or the client subscribes. This can be used to authenticate and authorize the client when VPN tunnel is used.

2.10.4 Virus and Intrusion Protection

The entire network where SC is used is assumed to be safe and secure. No virus protection is embedded in SC. Screening firewall can be used on any segment of the network. It is recommended to use SC within a DMZ.

SC is not designed to withstand network attacks like DOS or SYNC flood, or any other.

3 Network

Clients and servers are not connected directly to each other. They are both connected to the SC. The Java API provided with SC and the communication between cascaded SCs uses a connection pool in order to save network resources.

Connection pool is established for each two communication end points. There is no fix allocation of a connection to a certain session or subscription within the pool. Each request may use a different connection. Connections are created on demand and closed when they are idle for longer time. Connection pool can be configured to use TCP/IP or HTTP protocol. Using HTTP adds an extra overhead to SCMP but may be simpler to configure in foreign networks. SCMP over HTTP will pass a screening firewall placed between the end-points.

Sending of keep alive messages can be configured for each connection pool. This is required whenever a firewall is configured on this network segment.




Figure 1 Example of a connection (simplified)

Cascaded SCs are connected hierarchically.




Figure 2 Example of a cascaded connection (simplified)

3.1 Connection Topology

Client application, server application and the SC may reside on the same node or on separate nodes. The connection can either utilize HTTP protocol or direct TCP/IP communication. No assumption about the physical network topology is made. Multiple firewalls can be located on the path between the communicating partners. In order to demonstrate SC features, following connection topologies are shown:

- 1. Client ⇔ SC ⇔ Server
- 2. Client ⇔ SC ⇔ SC ⇔ Server
- 3. Client \Leftrightarrow SC \Leftrightarrow SC \Leftrightarrow Server
- = Direct connection
- = Single cascade
- = Double cascade


Other advanced cascaded topologies are possible.

3.1.1 Direct connection

This setup is suitable for applications with individual (mobile) clients connected directly to the service provider. In order to achieve higher application availability and scalability the server infrastructure can have redundant components.

The client can choose between connection to SC1 or 2 depending on their availability. Services X1 and X2 are identical and provided by servers 1 and 2. In case server 1 is not available service X2 can be used. Clients can use both X1 and X2 service and so distribute the load across all available servers. The logic to choose the access point and the appropriate service name is quite simple and must be implemented in the client.

The separation of SC nodes and the server nodes allows simple relocation of the services within the server site LAN and also allows scale-up the service performance by adding additional servers.




3.1.2 Single cascade

This setup is suitable for client applications running in enterprise environments. The clients are <u>not</u> connected directly to the service provider, but use an SC proxy placed within the enterprise DMZ as the local access point. In this way the enterprise security polices can be enforced. Utilization of the message cache in SC proxy can massively speed up the application. In order to achieve higher application availability SC proxy can be redundant. SC proxy can also be used to provide specific local services.

The client can choose between connection to SC proxy 1 or 2 depending on their availability. The logic to choose the access point and the appropriate service name is quite simple and must be implemented in the client.

Services X1 and X2 are identical and provided by server 1 and 2. In case server 1 is not available service X2 can be used. The network infrastructure must allow access between SC proxy 1, 2 and SC1 and 2.

The separation of SC nodes and the server nodes allows simple relocation of the services within the server site LAN and also allows scale-up the service performance by adding additional servers.




3.1.3 Double cascade

This setup is suitable for service providers wrapping the original service with some added value. The clients are <u>not</u> connected to the original service provider, but use an LAN SC proxy of the added value provider. Specific local services can be implemented here. The SC Proxy placed in the DMZ ensures the security polices and isolates the logical network segments. Utilization of message cache in the LAN SC proxy can massively speed up the application. In order to achieve higher application availability SC proxies can be redundant.

The client can choose between connection to LAN SC proxy 1 or 2 depending on their availability. The logic to choose the access point and the appropriate service name is quite simple and must be implemented in the client.

Services X1 and X2 are identical and provided by server 1 and 2. In case server 1 is not available service X2 can be used. The network infrastructure must allow access between SC proxy 1, 2 and SC1 and 2.

The separation of SC nodes and the server nodes allows simple relocation of the services within the server site LAN and also allows scale-up the service performance by adding additional servers.



4

Installation, Update, Removal

SC is Open Source software under Apache License 2. It is available as a complete source code in the SVN repository http://www.stabilit.ch/svn/repos/sc and as a kit on http://www.stabilit.ch/download/sc/

Kit Structure

The kit is available in two flavors:

- sc-bin_V9.9-999.zip kit containing only binaries
- sc-src_V9.9-999.zip kit containing binaries and additional resources required for development

The structure of the kit is described in the *readme.txt* file included in both zip-files.

4.1 Installation

For pre-requisites and products required by the specific SC version please see the *readme.txt* file included in the kit. These are usually:

- Java 1.6.18 or later
- Apache 2.0 or later (on node running file services)
- PHP 4.0 or later (on node running file services)

The installation is done by extracting the kit file into a directory of your choice. After the installation a verification procedure described in *readme.txt* file included in both zip-files.

4.2 Update

If you made changes to the SC configuration, then preserve these files before upgrade. The upgrade is simply done by extracting the kit file into a directory of the previous installation.

Version compatibility

If you install new SC version you may see get error message of type "Incompatible SC version nr." This may happen when you clients or server has a higher version (is newer) then the SC (is older). The opposite situation (SC version is higher than the client/ server) is valid and the software will run without change.

For description of the compatibility issues please read SC_0_SCMP_E.PDF Chapter: SCMP header Attributes - scVersion.

4.3 Removal

You must stop SC before you want to remove the software.

If you made changes to the SC configuration you must find out where you put the:

- log directory
- root.pidPath
- root.dumpPath
- cache.diskPath

and then delete all these directories.

Then you can delete the directory where did you extract the SC kit file.

5

Configuration

The SC is configured by property files in the conf/ directory. These are:

sc.properties
 sc-specific.properties
 log4j-sc.properties
 log4j-console.properties
 log4j-demo-client.properties
 log4j-demo-server.properties
 logging properties for sc-console
 logging properties for demo-client
 logging properties for demo-server

5.1 SC Properties

The SC is configured with a single configuration file sc.properties. Additional configurations may be included within this file.

The most important concepts used within the property file are described within the property file itself. They are:

- Multiple definitions of the same property but different value
- Include of specific configurations
- Usage of environment variables declared externally
- Usage of Java system properties within the property file

The meaning of the specific properties is explained in the configuration file itself.

The properties are grouped into 6 blocks:

- 1. Root = general parameters
- 2. Cache = caching parameters
- 3. Web = Web-GUI parameters
- 4. Listeners and their configuration
 - Listeners have symbolic names and configuration parameters references these names.
- Remote nodes and their configuration
 Remote nodes have symbolic names and configuration parameters references these names.
- 6. Services and their configuration

The block sequence is just a logical order. It is fully free.

```
# Exception of this rule:
        For list properties (values separated by comma) the subsequent values
        will be appended!
        Properties which must not be overwritten must be placed before inlude.
        Properties which may be overwritten must be placed after include.
# Instructions for use of external parameters and java system properties.
       # External parameters can be passes on the command line like
    -Dparameter=c:/temp
# OS Environment variables can be passes on the command in the same way like
    -Dparameter=%OS_VARIABLE%
# Within this file the parameter value can be used as ${sys:parameter}
# E.g. log path defined as OS environment variable LOG_DIR can be passed
# on the command line as -Dlogdir=%LOG_DIR% and then used in this file as:
               root.pidPath=${sys:logdir}
# Java system properties can be used with the same syntax ${sys:property}
# E.g. java system property file.separator can be used in this file as:
        fs=${sys:file.separator}
# For list of available java system properties see:
# http://download.oracle.com/javase/tutorial/essential/environment/sysprop.html
# variables
fs=${sys:file.separator}
# general parameters
# writePID (OPTIONAL, default=false) defines if a pid-file should be written or not.
# pid-file is created at SC startup to signal a running SC. It contains the SC PID. The
# file is deleted on exit.
root.writePID=true
# pidPath (MANDATORY if writePID=true) defines directory where the pid file is written to.
\# It can be relative or absolute path. Relative path begins with . or ..
root.pidPath=..${fs}logs${fs}sc
# dumpPath (MANDATORY) defines directory where the dump file is written to.
\# It can be relative or absolute path. Relative path begins with . or ..
root.dumpPath=..${fs}logs${fs}sc
# commandValidationEnabled (OPTIONAL, default=true) defines if header attributes in
# incomming SCMP requests are validated or not. Disabling validation has only minimal
# impact on performance and is usefull for testing (it disables also the version check).
# ** ATTENTION ** TURNING OFF VALIDATION IS NOT RECOMMENDED IN PRODUCTIVE ENVIRONMENT
root.commandValidationEnabled=true
\# operationTimeoutMultiplier (OPTIONAL, default=0.8) defines factor applied to oti
# in SCMP request. This will cause oti expiration on SC before oti expiration on the
# requester.
root.operationTimeoutMultiplier=0.8
# echoIntervalMultiplier (OPTIONAL, default=1.2) defines factor applid to eci
#in SCMP request. This will ensure session timeout expiration on SC before session
#timeout expiration on the requester
root.echoIntervalMultiplier=1.2
# connectionTimeoutMillis (OPTIONAL, default=5000) defines the maximum time SC will
# wait when it creates a new connection. SC creates connection to server, to another SC,
# to a web-server or to Tomcat.
root.connectionTimeoutMillis=10000
# subscriptionTimeoutMillis (OPTIONAL, default=10000) defines the maximum time
# between subsequent client requests for new publications. If this timeout expires,
# client subscription is deleted.
# This parameter is analogous to echoInterval in session services.
```

```
#root.subscriptionTimeoutMillis=10000
# keepAliveOTIMillis (OPTIONAL, default=2000) defines the maximum time
# for receiving response to keepalive message. If this timeout expires,
# the connection is closed.
#root.keepAliveOTIMillis=2000
# serverAbortOTIMillis (OPTIONAL, default=10000) defines the maximum time
# for receiving response to abort session message sent to the server.
# If this timeout expires, server registration is deleted.
#root.serverAbortOTIMillis=10000
# cache parameters
# enabled (OPTIONAL, default=true) enables or disables caching in SC
cache.enabled=true
# diskPath (MANDATORY if cache.enabled = true) defines location on disk where
# cache will write temporary files holding the data.
\# It can be relative or absolute path. Relative path begins with . or ..
cache.diskPath=..${fs}cache
# maxElementsInMemory (OPTIONAL, default=10000, 0 = no limit) defines maximum
# number of elements (messages or parts) in memory.
#cache.maxElementsInMemory=10000
# maxElementsOnDisk (OPTIONAL, default=1000000, 0 = no limit) defines maximum
# number of elements (messages or parts) on disk.
#cache.maxElementsOnDisk=1000000
# expirationCheckIntervalSeconds (OPTIONAL, default=300) defines interval in seconds
# SC will check cache for expired messages and clean them up.
cache.expirationCheckIntervalSeconds=60
# web parameters
# xslTransformationCache (OPTIONAL, default=false) enables or disables caching of
# xsl transformations done in web-qui. During development of the qui it is usefull
# to turn this on, otherwise browser must be restarted all the time.
#web.xslTransformationCache.enabled=false
# pageHeaderPrefix (OPTIONAL, default="") allows to define text displyed
# in page header and title. This is usefull to distinguish SC instances running
\# at the same time
#web.pageHeaderPrefix=P01
# scDownloadService (OPTIONAL, default="") allows to define service used for
# downloading of files via SC mgmt GUI
web.scDownloadService=file-1
# scUploadService (OPTIONAL, default="") allows to define service used for
# uloading of files via SC mgmt GUI
web.scUploadService=file-1
# colorSchema (OPTIONAL, default="") defines color schema used for the mgmt GUI
# Is useful o distinguish multiple running SCs
# possible values = (blue, green, yellow, brown, red)
#web.colorSchema=blue
# include customer specific configuration
include = sc-specific.properties
# SC listeners
```

listeners (MANDATORY) defines symbolic names for listeners. Each listener must be

```
# configred later in this file. This is list property!
listeners=sc-http, sc-tcp, mgmt-http, http-proxy
# http listener for SCMP messaging
# port (MANDATORY) on which the listener listens
sc-http.port=7000
\# interfaces (OPTIONAL) list of interfaces the listener should be included
# if missing, all interfaces will be included. This is list property!
#sc-http.interfaces=localhost
# connectionType (MANDATORY, allowed values = netty.http, netty.tcp, netty.web, netty-
proxy.http)
# the connection type (protocoll) used by this listener
sc-http.connectionType=netty.http
# tcp listener for SCMP messaging
sc-tcp.port=9000
sc-tcp.connectionType=netty.tcp
# listener for SC Mgmt-Gui
mgmt-http.port=81
mgmt-http.connectionType=netty.web
# credentials for SC Mgmt-Gui
mgmt-http.username=admin
mgmt-http.password=admin
# listener for http proxy, traffic is redirected to one remote host
http-proxy.port=8080
\verb|http-proxy.connectionType=netty-proxy.http|\\
http-proxy.remoteNode=apache
# remoteNodes (MANDATORY for cascading and file services or for http-proxy listener)
# defines symbolic names for remote nodes.
# Each host must be configred later in this file. This is list property!
remoteNodes=sc1, sc2, apache, fileServer
# remote SC connected via tcp (cascaded services)
# type (MANDATORY allowed values = cascadedSC, webServer, fileServer) defines
# the type of the remote host
sc1.type=cascadedSC
# port (MANDATORY) defines where the remote node listens
sc1.port=7001
# host (MANDATORY) defines the adress of the remote host
sc1.host=localhost
# connectionType (MANDATORY) defines the connection type (see above)
scl.connectionType=netty.http
# maxConnectionPoolSize (OPTIONAL, default = 100) defines number of connections to this host
sc1.maxConnectionPoolSize=20
# keepAliveIntervalSeconds (OPTIONAL, default = 60) defines interval for sending keepalive
messages
sc1.keepAliveIntervalSeconds=10
# remote SC connected via http (cascaded services)
sc2.type=cascadedSC
sc2.host=localhost
sc2.port=9001
sc2.connectionType=netty.tcp
sc2.maxConnectionPoolSize=20
sc2.keepAliveIntervalSeconds=10
# Web-Server for http-proxy traffic
apache.type=webServer
apache.host=www.stabilit.ch
apache.port=80
apache.connectionType=netty.http
apache.keepAliveIntervalSeconds=0
apache.maxConnectionPoolSize=20
```

Web-Server for file services

```
fileServer.type=fileServer
fileServer.host=localhost
fileServer.port=80
fileServer.connectionType=netty.http
fileServer.keepAliveIntervalSeconds=0
fileServer.maxConnectionPoolSize=20
# maxSessions (OPTIONAL, default = 10) defines maximal number of internal sessions used for
this file service
fileServer.maxSessions=10
# serviceNames (MANDATORY) defines names of services.
# Each service must be configred later in this file. This is list property!
\verb|serviceNames| = \verb|session-1|, \verb|session-2|, \verb|publish-1|, \verb|publish-2|, \verb|file-1|, \verb|sc1-session-1|, \verb|sc2-session-2|, \verb|sc1-session-2|, sc1-session-2|, sc1
publish-1,sc2-publish-2
# local services
# type (MANDATORY, allowed values = session, publish, file)
session-1.type=session
# enabled (OPTIONAL, default=enabled) enables or disables session creation
session-1.enabled=true
session-2.type=session
session-2.enabled=true
publish-1.type=publish
publish-1.enabled=true
publish-2.type=publish
publish-2.enabled=true
# file services
file-1.type=file
file-1.enabled=true
# remoteNode (MANDATORY) defines the remote host on which a Web-Server must be running
file-1.remoteNode=fileServer
# path (MANDATORY) defines the url path used for this service.
\ensuremath{\sharp} The path is added to the host address when the http request is constructed
file-1.path=sc/file-1/
# uploadScript (MANDATORY) name of the script residing on the web-server that handles file
file-1.uploadScript=scupload.php
 # uploadScript (MANDATORY) name of the script residing on the web-server that handles file list
file-1.listScript=sclist.php
# cascaded services
sc1-session-1.type=session
sc1-session-1.enabled=true
# remoteNode (MANDATORY) defines the remote SC to which the service is cascaded
sc1-session-1.remoteNode=sc1
sc2-session-2.type=session
sc2-session-2.enabled=true
sc2-session-2.remoteNode=sc2
sc1-publish-1.type=publish
sc1-publish-1.enabled=true
sc1-publish-1.remoteNode=sc1
sc1-publish-1.noDataIntervalSeconds=10
sc2-publish-2.type=publish
sc2-publish-2.enabled=true
sc2-publish-2.remoteNode=sc2
sc2-publish-2.noDataIntervalSeconds=10
```

5.2 Logging

Standard open source package log4j is used for SC logging. It is configured with a single configuration file log4j-sc.properties.

For concepts of log4j please read http://logging.apache.org/log4j/ The complete log4j manual is available as http://www.qos.ch/shop/products/log4jManual The most important configurations within the property file belongs to:

- Usage of log levels
- Definition of appenders
- Usage of environment variables declared externally
- Usage of Java system properties within the property file

There are 5 loggers configured for logging:

1. Default logger

This is a hierarchical logger used to produce regular log output to console and file. All errors will appear here.

2. connectionLogger

This is specific logger used to log connection problems. It has only TRACE or DEBUG level

3. messageLogger

This is specific logger used to log messages. It has only TRACE or DEBUG level.

4. sessionLogger

This is specific logger used to log session events. It has only TRACE level.

5. subscriptionLogger

This is specific logger used to log subscription events. It has only TRACE level.

6. cacheLogger

This is specific logger used to cache events. It has only TRACE level.

7. performanceLogger

This is specific logger used to log messages. It has only TRACE level.

```
#/*-
         Copyright © 2010 STABILIT Informatik AG, Switzerland
    Licensed under the Apache License, Version 2.0 (the "License");
    you may not use this file except in compliance with the License.
    You may obtain a copy of the License at
    http://www.apache.org/licenses/LICENSE-2.0
    Unless required by applicable law or agreed to in writing, software
    distributed under the License is distributed on an "AS IS" BASIS,
    WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
    See the License for the specific language governing permissions and
 * limitations under the License.
# Usage of log levels inside the service connector:
 Log levels: ALL, TRACE, DEBUG, INFO, WARN, ERROR, FATAL, OFF
  FATAL -
             fatal error, the execution cannot continue. The only possible action
               after this error is System.exit(1);
               The cause must be investigated and corrected before restart.
  ERROR -
               serious error which can be recovered. The execution may continue
               but error cause must be investigated and corrected.
  WARN -
               expected error that has been successfully recovered.
               Signal to take a corrective action in the future.
               This is the production set-up for maximum performance.
  INFO -
               Highly important event, documenting a significant activity.
               This is the production set-up for normal performance producing
               reasonable (not too high) amount of output.
  DEBUG -
               Importance event, used to document regular activity.
               Can be enabled for trouleshooting.
  TRACE -
               Event used to track down problem in a particular area.
               Must be selectively enabled for a particular class or branch
 Read log4j documentation at: http://logging.apache.org/log4j/1.2/manual.html
  Instructions for use of external parameters and java system properties.
   ______
  External parameters can be passes on the command line like
     -Dparameter=c:/temp
```

```
OS Environment variables can be passes on the command in the same way like
     -Dparameter=%OS_VARIABLE%
\# Within this file the parameter value can be used as \{parameter\}
# E.g. log path defined as OS environment variable LOG_DIR can be passed
# on the command line as -Dlogdir=%LOG_DIR% and then used in this file as:
                root.pidPath=${logdir}
# Java system properties can be used with the same syntax ${property}
# E.g. java system property file.separator can be used in this file as:
         fs=${file.separator}
# For list of available java system properties see:
# http://download.oracle.com/javase/tutorial/essential/environment/sysprop.html
fs=${file.separator}
logPath=..${fs}logs${fs}sc
\# It can be relative or absolute path. Relative path begins with . or ..
# All logging output sent to standard out and a file
# WARN is production set-up
log4j.rootLogger=INFO, console, generalLog
\verb|log4j.appender.console=| org.apache.log4j.ConsoleAppender|
log4j.appender.console.layout=org.apache.log4j.PatternLayout
log4j.appender.console.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p (%c:%L)
# generalLog
log4j.additivity.generalLog=false
log4j.appender.generalLog=org.apache.log4j.DailyRollingFileAppender
log4j.appender.generalLog.DatePattern='.'yyyy-MM-dd
log4j.appender.generalLog.File=${logPath}$${fs}sc.log
\verb|log4j.appender.generalLog.layout=| org.apache.log4j.PatternLayout|
log4j.appender.generalLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p
(%c:%L) - %m%n
# connections
# DEBUG level for connection creation and deletion
# TRACE level for read buffer, write buffer, send keepalive
log4j.logger.ConnectionLogger=DEBUG, connectionLog
log4j.additivity.ConnectionLogger=false
log4j.appender.connectionLog=org.apache.log4j.DailyRollingFileAppender
log4j.appender.connectionLog.DatePattern='.'yyyy-MM-dd
log4j.appender.connectionLog.File=${logPath}${fs}connection.log
log4j.appender.connectionLog.layout=org.apache.log4j.PatternLayout
log4j.appender.connectionLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p -
%m%n
# messages
# DEBUG important message attributes
# TRACE all message attributes
log4j.logger.MessageLogger=DEBUG, messageLog
log4j.additivity.MessageLogger=false
\verb|log4j.appender.messageLog=org.apache.log4j.DailyRollingFileAppender|\\
log4j.appender.messageLog.DatePattern='.'yyyy-MM-dd
log4j.appender.messageLog.File=${logPath}${fs}message.log
log4j.appender.messageLog.layout=org.apache.log4j.PatternLayout
log4j.appender.messageLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} %m%n
# sessions
# TRACE level for session creation, deletion and abort
log4j.logger.SessionLogger=TRACE, sessionLog
log4j.additivity.SessionLogger=false
\verb|log4j.appender.sessionLog=| org.apache.log4j.DailyRollingFileAppender| \\
log4j.appender.sessionLog.DatePattern='.'yyyy-MM-dd
log4j.appender.sessionLog.File=${logPath}${fs}session.log
\verb|log4j.appender.sessionLog.layout=org.apache.log4j.PatternLayout|
log4j.appender.sessionLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p -
8m8n
# subscriptions
# TRACE level for subscribe, change subscription and unsubscribe
log4j.logger.SubscriptionLogger=TRACE, subscriptionLog
log4j.additivity.SubscriptionLogger=false
\verb|log4j.appender.subscriptionLog=org.apache.log4j.DailyRollingFileAppender|
```

```
log4j.appender.subscriptionLog.DatePattern='.'yyyy-MM-dd
\verb|log4j.appender.subscriptionLog.layout=org.apache.log4j.PatternLayout|
log4j.appender.subscriptionLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p
- %m%n
# performance
# TRACE level for begin and end points
log4j.logger.PerformanceLogger=OFF, performanceLog
log4j.additivity.PerformanceLogger=false
log4j.appender.performanceLog=org.apache.log4j.DailyRollingFileAppender
log4j.appender.performanceLog.DatePattern='.'yyyy-MM-dd
\verb|log4j.appender.performanceLog.File=\$\{logPath\}\$\{fs\}performance.log|\\
log4j.appender.performanceLog.layout=org.apache.log4j.PatternLayout
log4j.appender.performanceLog.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss.SSSZ} [%t] %-5p -
%m%n
# cache
# TRACE level for begin and end points
log4j.logger.CacheLogger=TRACE, cacheLog
{\tt log4j.additivity.CacheLogger=false}
log4j.appender.cacheLog=org.apache.log4j.DailyRollingFileAppender
log4j.appender.cacheLog.DatePattern='.'yyyy-MM-dd
log4j.appender.cacheLog.File=${logPath}${fs}cache.log
\verb|log4j.appender.cacheLog.layout=| org.apache.log4j.PatternLayout|
\label{log4} \verb|log4j.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSSZ\} \ [\$t] \ \&-5p\ -\ \&m\&n \ Log4f.appender.cacheLog.layout.ConversionPattern= &d\{yyyy-MM-dd\ HH: mm:ss.SSZZ\} \ [\$t] \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \
```

6 Operations

This chapter describes the normal SC operations done by the operators.

Don't make changes to the scripts coming from the SC kit. Otherwise you will lose them after the next software update. It is recommended to wrap the scripts or to write your own scripts.

6.1 Starting SC

The Service connector is started with the script bin/start-sc.bat on Windows or start-sc.sh on unix or linux platforms.

It is possible to declare environment variables which are passed to SC where they can be used for configuration. The script shows an example how to do this. The property files in conf/contain the description how to use the environment variables and java system properties inside the configuration files.

On Windows 32 and Windows 64 SC can be started as Windows service. The directories *bin/win32* and *bin/win64* contain the necessary tools and guide.

On unix or linux platforms SC can be started as a deamon. The directories *bin/unix* contains the necessary tools and guide.

6.2 Stopping SC

The Service connector is stopped with the script bin/stop-sc.bat on Windows or stop-sc.sh on unix or linux platforms. The script invokes the sc-console which in turn sends a *kill* message to the SC.

SC not configured to listen on TCP port cannot be stopped by the sc-console!

Even if sc-console can connect to remote SC, stopping SC is possible only from the local node where SC is running.

6.3 Other console operations

The sc-console can be used to manage services and to get information about the SC. SC not configured to listen on TCP port cannot communicate with the sc-console. The syntax is:

```
java -jar sc-console.jar -h <host> -p <port> <sc-command>
```

The possible sc-commands are:

- enable?serviceName=abc
 - Enables services. Service must be enabled in order to accept new sessions or subscriptions.
- disable?serviceName=abc
 Disables services. Disables service will reject new sessions or subscriptions.
- state?serviceName=abc
 Shows state (enabled / disabled) of the services.

- sessions?serviceName=abc
 - Shows number of allocated and free sessions for this service
- inspectCache?serviceName=abc&cacheId=700
 Shows the state of the message cache.
- serviceConfiguration?serviceName=abc
 Returns the configuration of given service name. No regex allowed here.
- clearCache

Clears the message cache

- scVersion

Returns the version of the SC the client is communicating to.

- dump

Creates a dump file in the log directory containing information valuable for troubleshooting.

kill
 Terminates the SC.

For serviceName value regular expression can be used (exception: serviceConfiguration). E.g tate?serviceName = .*

Will display state of all services.

6.4 Monitoring SC with the Web GUI

By default the mgmt-port is enabled and configured on port 81. Entering the URL http://localhost:81/ in your browser will connect with the SC.

Login

The login screen is displayed when a user connects the Browser to SC.



The credentials are defined in the configuration file.

Home

The home page shows the summary of the runtime environment and is refreshed periodically.



The display has several sections:

- The header shows the actual version number and the node name on which SC is running. Actual menu is shown in the navigation line.
- There is a menu structure in the left colum
- The status show if SC is running or not. When the GUI loses connection to the SC the green point will be red.
- The runtime box shows summary of the most important runtime parameters.
- The statistic shows an overall SC statistic.
- The System Info areas shows information related to the runtime environment. The link on the configuration file will display its content.

Services The service form shows all configured services.

List of services						
Service State	Service Name	Service Type	Servers	Message Queue	Allocated Sessions / Subscriptions	Available Sessions
Enabled	file-1	FILE_SERVICE		-		+:
Enabled	my-session-1	SESSION_SERVICE	0	-	0	0
Enabled	publish-1	PUBLISH_SERVICE	0	0	0	0
<u>Enabled</u>	publish-2	PUBLISH_SERVICE	0	0	0	0
Enabled	sc1-publish-1	CASCADED_PUBLISH_SERVICE		0		*:
Enabled	sc1-session-1	CASCADED_SESSION_SERVICE	-	-	×-	-
Enabled	sc2-publish-2	CASCADED_PUBLISH_SERVICE	2	0	<u> </u>	2
Enabled	sc2-session-2	CASCADED_SESSION_SERVICE			-	-
<u>Enabled</u>	session-1	SESSION_SERVICE				
Enabled	session-2	SESSION_SERVICE	0	= 1	0	0

The link on service state allows enabling or disabling the service interactively. When services are active, counters become links to a drill down and will display detailed information on sessions and servers.

Sessions The session form shows all active sessions.

	List of sessions					
Service	Service Session ID IP Adresslist Session Timeout (s) Server					
session-1	37883714-c2b3-454a-a170-1a3cb825a286	10.0.0.125/127.0.0.1	12.0	localhost:9002		

The link on service will display service details, the link on server the server details

Subscriptions The subscription form shows all active subscriptions.

	List of subscriptions						
Service	Service Subscription ID Subscription Mask IP Addresslist Subscription Timeout (ms) No Data Interval (s) Server						
publish-1	4a9e3367-aee5-4062- a8a9-24b5b7e92cd0	0000121ABCDEFGHIJKLMNO X	10.0.0.125/127.0.0.1	60000.0	100	localhost:9001	

The link on service will display service details, the link on server the server details

Servers

The server form shows all active servers.

List of servers					
Host	Port	Server Key	Server Type	Max Sessions	Max Connections
localhost	9001	sc2	CASCADED_SC	-	20
localhost	7001	sc1	CASCADED_SC	-	20
localhost	9002	session-1_localhost/3386	STATEFUL_SERVER	100	10
localhost	80	fileServer	FILE_SERVER	10	20
localhost	9001	publish-1_localhost/3421	STATEFUL_SERVER	10	5

Listeners

The listener form shows all active listeners.

List of listeners					
Host	Port	Name	Connection Type	Interfaces	Remote Node
127.0.0.1	7000	sc-http	netty.http	127.0.0.1 10.0.0.125 10.0.10.1	**
127.0.0.1	81	mgmt-http	netty.web	127.0.0.1 10.0.0.125 10.0.10.1	5.5
127.0.0.1	9000	sc-tcp	netty.tcp	127.0.0.1 10.0.0.125 10.0.10.1	*
127.0.0.1	8080	http-proxy	netty-proxy.http	127.0.0.1 10.0.0.125 10.0.10.1	<u>apache</u>

The link on remote node will display node details

Cache

The cache form shows the state of the cache.

		Cache manager configu	ation		
Status	Disk Path	Disk Path maxElementsInMemory		maxElementsOnDisk	
ENABLED	\cache	\cache 10000		100000	
		List of caches			
Service Name	Composite Size	Element Size	Memory Store Size	Disk Store Size	
my-session-1	0	0	0	0	
sc2-session-2	0	0	0	0	
sc1-session-1	0	0	0	0	
session-1	0	0	0	0	
session-2	0	0	0	0	

Maintenance

The maintenance form allows performing maintenance actions.



Logs

The log form shows the logs and allows their view.

Log files ≤< 2011-03-11			
Logger Name	Appender Name	File	
CacheLogger	cacheLog	\logs\sc\cache.log (1033)	
ConnectionLogger	connectionLog	\logs\sc\connection.log (6276)	
root	generalLog	<u>\logs\sc\sc.log</u> (9350)	
MessageLogger	messageLog	<u>\logs\sc\message.log</u> (920)	
PerformanceLogger	performanceLog	\logs\sc\performance.log (0)	
SessionLogger	sessionLog	\logs\sc\session.log (458)	
SubscriptionLogger	subscriptionLog		

The link left of the date allows browsing previous days. The link on the log file will display its content.

6.5 Monitoring SC with jconsole or jvisualvm

Note: jconsole or jvisualvm can be used only when JDK 1.6.0 or later is installed. Remote monitoring is allowed, e.g. SC and jconsole may be on different nodes.

The script example/jconsole.bat and jvisualvm.bat show how to start jconsole or jvisualvm. When SC is running on your desktop, you can directly select the SC from the local process list. If SC is running on remote node you need to know the node, port of the node and will see SC in the remote process list. The script bin/start-sc.sh shows how to define JMX remote port.

The most interesting parameters are:

- Heap Memory Usage
- Number of Threads
- CPU usage
- VM Summary

With jconsole or jvisualvm it is also possible to set the log level at run-time.

7

Troubleshooting

7.1 General

If you encounter a problem, please work systematically through the following checklist:

- 1) Connect to SC with the Web-GUI and check that it is responding. You can also use the console and get state of the services with *state?serviceName=*.* command.
- 2) Look for ERRORs in sc.log

If you find suspicious log entries:

- 1) Use the Web-GUI and create a dump file
- 2) Upload log files and the dump file as a zip-file to the Web Server
- 3) Send a description of the issue and the zip-file to <u>info@stabilit.ch</u>

Note:

We understand the user frustration in a case of an error. However we need a precise description of the problem. In order to increase the chance to find and correct the error soon, please do:

- Keep cool, handle the incident <u>without</u> emotions.
- Work systematically. Do not jump from one topic to other.
- Communicate precisely, use common terminology.
- Write down what you have done, later you will not remember the exact steps.
- Do not continue if not absolutely necessary. Other errors may subsequently happen.
- Do not repeat the case. It will be more difficult to trace down the problem origin.
- Save all material, logs, notes, screen shots in one place.

7.2 The most often situations

SC does not start.

Start SC manually from the command line and see the displayed error. If there is lot of output before SC crashes see the error in the log file.

SC cannot be stopped with the script (stop-sc.bat / stop-sc.sh).

The SC has been started listening on TCP port other than the one used in the stop-sc.bat script. Find out in the sc configuration which TCP port is in use (also nestat utility can be helpful) and edit the stop-sc.bat script accordingly.

8 Glossary

Client

Piece of an application consuming services and initiating actions.

Client node

Client node is physical network node (computer) on which the client application resides.

Server

Piece of an application providing services to clients.

Server node

Server node is physical network node (computer) on which the server application resides.

Service

Abstract unit of work provided by the server and delivered to the client in order to implement a specific functionality. SC supports session, publishing and file services.

Session

Temporary allocation of a dedicated server to a client. Session ensures information flow between a client and the allocated server. SC supports request/response sessions and subscription sessions.

Call

A call represents a pair of a request and response.

Command

A command dispatches specific actions on a server according to the incoming request.

Request

Data structure created by the Client or SC in order to initiate an information exchange. It may contain one or more messages.

Response

Data structure created by the Server or SC in order to deliver the requested information. It may contain one or more messages.

Message

Basic transport instrument to exchange information between client, SC and the server. It belongs to a request or to a response.

Message Part

Message part is a piece of a large message. Large message is broken into parts.

Message payload

Message payload is part of the transported message containing the application data. SC does not inspect, transform or interpret the payload. It is the responsibility of the communicating partners to define the format, syntax and semantic of the payload.

Message transport format

Format of messages transported messages between client, SC and the server. It consists of a header and a payload.

Composite

Data structure prepared to hold all message parts of a large message

Registry

Common list of known objects that ensures their uniqueness, organized in a way to find them easily.

Requester

Piece of code in SC or client initiating the information exchange

Responder

Piece of code in SC or server delivering the requested information

Connection

Network communication between client and SC or SC and the server

Endpoint

Network communication part on SC or server

SCMP => SC Message Protocol

Is a publically presented protocol used for communication between client, SC and the server. In the OSI layer model, message transport protocol is immediately <u>above</u> the application protocol layer 7.

RR => Request / Response

This is basic communication style. The client requests an execution of a (remote) service and gets back the results in form of a response. The execution may be blocking - clients waits for the response, or non-blocking (asynchronous) – the clients does not wait for the response. Sometimes it is also called Remote Procedure Call = RPC.

SP => Subscribe / Publish

This is another popular communication style. The client tells the server what he is interested in and gets the data from the server later when a event arise. The execution is always non-blocking (asynchronous) – the client does not wait for the data receipt. This is because the event occurs on the server.

Index

A	Body • 27
attack	Cache • 8
DOS • 9	Fan-Out • 8
Virus • 9	Payload • 27
С	Monitoring • 23
Cache • 25	P
Cascading • 7, 10	Pre-Requisites • 13
double • 12	Properties
single • 11	File • 14
Client • 27	Logging • 18
Н	Meaning • 14
HTTP • 10	R
Redirection • 7	Removing • 13
I	S
Installing • 13	SC-Console • 8, 22
IP address • 9	Server • 27
IP Keep alive • 10	Servers • 24
J	Service • 27
jconsole • 25	File • 7
jvisualvm • 25	Publish • 6
K	Session • 6
Kit	Services • 24
Structure • 13	Session • 27
L	Subscriptions • 24
Listeners • 24	T
Logger • 19	TCP • 10
Login • 23	U
M	Updating • 13
Maintenance • 25	V
Message • 27	VPN • 9