■ NetApp

Revert an ONTAP cluster

ONTAP 9

aherbin May 26, 2021

This PDF was generated from https://docs.netapp.com/us-en/ontap/revert/task_reverting_an_ontap_cluster.html on May 31, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Revert an ONTAP	cluster					1
NOVOIL ALL ON IAL	Ciustoi	 	 	 	 	

Revert an ONTAP cluster

To take the cluster offline to revert to an earlier ONTAP release, you must disable storage failover and the data LIFs, address reversion preconditions, revert the cluster and file system configurations on a node, and then repeat the process for each additional node in the cluster.

You must have completed the revert verifications and pre-checks.

Reverting a cluster requires you to take the cluster offline for the duration of the reversion.

1. Set the privilege level from admin to advanced, entering **y** when prompted to continue: set -privilege advanced

The advanced prompt (*>) appears.

2. Verify that the target ONTAP software is installed: system image show

The following example shows that version 9.1 is installed as the alternate image on both nodes:

```
cluster1::*> system image show
              Is Is
                                     Install
       Image Default Current Version
Node
                                     Date
node0
       image1 true true 9.2
                                     MM/DD/YYYY TIME
       image2 false false 9.1 MM/DD/YYYY TIME
node1
       image1 true true 9.2
                                     MM/DD/YYYY TIME
       image2 false false 9.1
                                     MM/DD/YYYY TIME
4 entries were displayed.
```

- 3. Disable all of the data LIFs in the cluster: network interface modify {-role data} -status -admin down
- 4. If the cluster consists of only two nodes, disable cluster HA: cluster ha modify -configured false
- 5. Disable storage failover for the nodes in the HA pair from either node: storage failover modify -node nodename -enabled false

You only need to disable storage failover once for the HA pair. When you disable storage failover for a node, storage failover is also disabled on the node's partner.

6. Log in to the node that you want to revert.

To revert a node, you must be logged in to the cluster through the node's node management LIF.

7. Set the node's target ONTAP software image to be the default image: system image modify -node nodename -image target_image -isdefault true

8. Verify that the target ONTAP software image is set as the default image for the node that you are reverting: system image show

The following example shows that version 9.1 is set as the default image on node0:

```
cluster1::*> system image show
            Is Is
                                Install
     Image Default Current Version
Node
                                Date
       ______
node0
      image1 false true 9.2 MM/DD/YYYY TIME
      image2 true false 9.1
                                MM/DD/YYYY TIME
node1
      image1 true true 9.2
                               MM/DD/YYYY TIME
      image2 false false 9.1 MM/DD/YYYY TIME
4 entries were displayed.
```

- 9. If the cluster consists of only two nodes, verify that the node does not hold epsilon:
 - a. Check whether the node currently holds epsilon: cluster show -node nodename

The following example shows that the node holds epsilon:

- b. If the node holds epsilon, mark epsilon as false on the node so that epsilon can be transferred to the node's partner: cluster modify -node nodenameA -epsilon false
- c. Transfer epsilon to the node's partner by marking epsilon true on the partner node: cluster modify -node nodenameB -epsilon true
- 10. Verify that the node is ready for reversion: system node revert-to -node nodename -check -only true -version 9.x

The check-only parameter identifies any preconditions that must be addressed before reverting, such as the following examples:

- Disabling storage failover
- Disabling the Snapshot policy
- Deleting Snapshot copies that were created after upgrading to the later version of ONTAP
- 11. Verify that all of the preconditions have been addressed: system node revert-to -node nodename -check-only true -version 9.x

12. Revert the cluster configuration of the node: system node revert-to -node nodename -version 9.x

The -version option refers to the target release. For example, if the software you installed and verified is ONTAP 9.1, the correct value of the -version option is 9.1.

The cluster configuration is reverted, and then you are logged out of the clustershell.

13. Log back in to the clustershell, and then switch to the nodeshell: run -node nodename

After logging on the clustershell again, it might take a few minutes before it is ready to accept the nodeshell command. So, if the command fails, wait a few minutes and try it again.

14. Revert the file system configuration of the node: revert to 9.x

This command verifies that the node's file system configuration is ready to be reverted, and then reverts it. If any preconditions are identified, you must address them and then rerun the revert to command.



Using a system console to monitor the revert process displays greater details than seen in nodeshell.

When the command finishes, the LOADER prompt is displayed.

15. Enter yes at prompt to revert.

If AUTOBOOT is true, the node will reboot to ONTAP. If AUTOBOOT is false, the node will halt.

16. After the node has rebooted, confirm that the new software is running: system node image show

In the following example, image1 is the new ONTAP version and is set as the current version on node0:

	_	tem node Is	Is		Install
Iode	Image	Default	Current	Version	Date
iode0					
	image1	true	true	X.X.X	MM/DD/YYYY TIME
	image2	false	false	Y.Y.Y	MM/DD/YYYY TIME
ode1					
	image1	true	false	X.X.X	MM/DD/YYYY TIME
	image2	false	true	Y.Y.Y	MM/DD/YYYY TIME

17. Verify that the revert status is complete for each node: system node upgrade-revert show -node nodename

The status should be listed as complete.

If the revert is not successful, contact technical support immediately.

- 18. Repeat [step-5] through [step-17] on the other node in the HA pair.
- 19. If the cluster consists of only two nodes, reenable cluster HA: cluster ha modify -configured true
- 20. Reenable storage failover on both nodes if it was previously disabled: storage failover modify -node nodename -enabled true
- 21. Repeat [step-6] through [step-18] for each additional HA pair and both the clusters in MetroCluster Configuration.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.