

Author: Guanzhou (Jose) Hu 胡冠洲 @ UW-Madison

This note is a reading note of the book: <u>Operating Systems: Three Easy Pieces (OSTEP)</u> v1.01 by Prof. Remzi Arpaci-Dusseau and Prof. Andrea Arpaci-Dusseau. Figures included in this note are from this book unless otherwise stated.

Operating Systems

Introduction to OS

Virtualizing the CPU: Processes & Scheduling

Abstraction of Process

Machine State

Process Status

Process Data Structures

Process APIs

Time-Sharing of the CPU

Privilege Modes

Hardware Interrupts

Context Switch & Scheduler

Scheduling Policies

Basic Policies

Multi-Level Feedback Queue (MLFQ)

Lottery Scheduling

Completely Fair Scheduler (CFS)

Virtualizing the Memory: Memory Management

Concurrency: Multi-Tasking & Synchronization

Multi-CPU Scheduling

Persistence: Storage Devices & File Systems

Advanced/Related Topics

Introduction to OS

An <u>Operating System (OS)</u> is a body of software sitting in between *software applications* and a <u>Von Neumann</u> <u>computer architecture</u>. An OS connects applications to physical hardware. It makes **abstractions** of the underlying hardware and provides an easy-to-use *interface* for running portable software on physical hardware.

An OS does this through three general techniques:

- 1. **Virtualization**: taking a physical resource (processor, memory, storage, ...) and transforms it into a more general, portable, and easy-to-use virtual interface for user applications to use
- 2. **Concurrency**: acting as a resource manager which supports multiple user applications to run concurrently and coordinates among running applications, ensuring correct, fair, and efficient sharing of resources
- 3. **Persistence**: data can be easily lost on volatile devices such as DRAM. An OS allows users to talk to external devices including persistent storage drives through *Input/Output* (I/O)

Abstraction is a great idea in both computer architecture and operating systems. It hides implementation complexity about the underlying layer and exposes a unified model of how to use the underlying layer to the upper layer. Check out the first section of <u>this note</u>.

In the layers of abstractions, we call the operations supported by the lower-layer as **mechanisms**, and the algorithms/decisions made by the higher-layer on how to use the mechanisms to achieve a goal as **policies** (or *disciplines*).

A modern operating system also pursues some other goals apart from the above stated. They are:

- Performance: minimize the overheads brought by the OS
- Security: protect against bad behavior; provide isolation
- Reliability: properly recover on fail-stops
- Connectivity: networking support; connect with the Internet
- Energy-efficiency, Mobility, ...

Generally, the most essential part of an OS is the **kernel**, which is the collection of code that implements the above-mentioned core functionalities. The kernel is a piece of static code (hence not a dynamic running entity). A monolithic OS consists of the kernel and some upper-level system applications that provide a friendly UI.

Virtualizing the CPU: Processes & Scheduling

One of the most important abstractions an OS provides is the **process**: a running instance of a program. We typically want to run many processes at the same time (e.g., a desktop environment, several browser windows, a music player, and a task monitor), more than the number of available CPU cores (and probably other physical resources as well). The OS must be able to *virtualize* a physical resource and let multiple processes share the limited resource. This section focuses on sharing the CPU, which is the most fundamental resource required to kick off any process.

Abstraction of Process

A process is simply an *instance* running on a processor (the dynamic instance, doing actual work) of a piece of *program* (the static code + data, residing on persistent storage). There can be multiple processes running the same piece of program code.

Machine State

Running a process instance of a program requires the OS to remember the *machine state* of the process, which typically consists of the following information:

- Address space: memory space that a process can address, typically also virtualized, which contains at least:
 - Code: compiled machine code of the program
 - Data: any initial static data/space the program needs
 - Stack: space reserved for the run-time function stack of the process
 - Heap: space reserved for any new run-time data

FIGURE

- **Registers context**: CPU registers' values; particularly special ones include:
 - o Program counter (PC, or instruction pointer): which instruction of the program to execute next
 - Stack pointer (SP) & Frame pointer (FP): for managing the function stack
- **I/O information**: states related to storage or network, for example:
 - List of currently open files (say in the form of *file descriptors*)

Process Status

A process can be in one of the following states at any given time:

- (optional) *Initial*: being created and hasn't finished initialization yet
- Ready: is ready to be scheduled onto a CPU to run, but not scheduled at this moment
- Running: scheduled on a CPU and executing instructions
- *Blocked*: waiting for some event to happen, e.g., waiting for disk I/O completion or waiting for another process to finish, hence not ready to be scheduled at this moment
- (optional) Terminated: has exited/been killed but its information data structures have not been cleaned up yet




Figure 4.2: Process: State Transitions (extended)

Process Data Structures

The OS must have some data structures to hold the information of each process. We call the metadata structure of a process the **process control block** (PCB, or *process descriptor*). This structure must include the machine state of the process, the status of the process, and any other necessary information related to the process. For example, the xv6 OS has the following PCB struct:

```
struct context {
2
         int eip;
3
        int esp;
4
        int ebx;
5
        int ecx;
        int edx;
6
         int esi;
8
         int edi;
9
         int ebp;
10
    };
11
12
    enum proc_state { UNUSED, EMBRYO, SLEEPING,
13
                        RUNNABLE, RUNNING, ZOMBIE };
14
    /** The PCB structure. */
15
16
    struct proc {
17
        char *mem;
                                       // Start of process memory
```

```
18
        uint sz;
                                   // Size of process memory
19
        char *kstack;
                                   // Bottom of kernel stack
20
        enum proc state state;
                                   // Process state
21
        int pid;
                                   // Process ID
22
        struct proc *parent;
                                 // Parent process
        void *chan;
23
                                   // If !zero, sleeping on chan
                                   // If !zero, has been killed
24
        int killed;
        struct file *ofile[NOFILE]; // Open files
25
26
       struct inode *cwd;
                                  // Current directory
                                  // Register values context
27
        struct context context;
28
        struct trapframe *tf;
                                  // Trap frame of current interrupt
29
    };
```

The collection of PCBs is the **process list** (or *task list*), the first essential data structure we meet in an OS. It can be implemented as just a fixed-sized array of PCB slots as in xv6, but can also take other forms such as a linked list or a hash table.

Process APIs

These interfaces are available on any modern OS to enable processes:

• create - initialize the above mentioned states, load the program from persistent storage in some executable format, and get the process running at the entry point of its code; the process then runs until completion and exits (, or possibly runs indefinitely)




Figure 4.1: Loading: From Program To Process

- destroy forcefully destroy (kill, halt) a process in the middle of its execution
- wait let a process wait for the termination of another process
- status retrieve the status information of a process

• other control signals like suspending & resuming, ...

Application programming interface (API) means the set of interfaces a lower-layer system/library provides to upper-layer programs. The APIs that an OS provides to user programs are called **system calls** (*syscalls*). Everything a user program wants to do that might require system-level privileges, such as creating processes, accessing shared resources, and communicating with other processes, are typically done through invoking system calls.

In UNIX systems, process creation is done through a pair of fork() + exec() syscalls.

- Initialization of a process is done through fork() ing an existing process: create an exact duplicate
 - The original process is the *parent* process and the created duplicate is the *child* process
 - There is a special init process created by the OS at the end of the booting process, and several basic user processes, e.g., the command-line shell or the desktop GUI, are forked from the init processes.
 They then fork other processes, for example when the user opens a calculator from the shell, forming a tree of processes
- Executable loading is done through <code>exec()</code> ing an executable file: replace the code and data section with that executable and start executing it from its entry

See Chapter 5, Figure 5.3 for a fork+exec+wait example, Section 5.4 for an introduction to UNIX shell terminologies, and Section 5.5. for control signals handling.

Time-Sharing of the CPU

To virtualize the CPU and coordinate multiple processes, the virtualization must be both *performant* (no excessive overhead) and *controlled* (OS controls which one runs at which time; bad processes cannot simply run forever and take over the machine). OS balances these two goals with the following two techniques:

- (Limited) Direct Execution (LDE): just run the user program directly on the CPU; OS is not simulating processor hardware; but the OS must be able to re-gain control in some way to do the coordination
- **Time-Sharing**: divide time into small slots, schedule a process to run for a few slots and switch to another one, constantly switching back and forth among ready processes

The OS needs to solve several problems to enable the combination of these two techniques.

Privilege Modes

If we just let a process run all possible instructions directly, it will have dominant control over the machine. Hence, the processor lists a set of sensitive instructions as *privileged* instructions, which can only be run in high privilege mode. A user process normally runs in **user mode**, with restricted permissions. When it invokes a syscall (mentioned in the section above), it switches to **kernel mode** to execute the registered syscall handler containing privileged instructions. After the handler has done its work, it returns the process back to user mode.

Examples of privileged instructions in x86 (can only be called in "ring-0" mode, as opposed least-privileged "ring-3" mode) include:

- HALT stop execution
- I/O port instructions
- Turning off interrupts
- ..

The switching between modes is enabled through a mechanism called **trap**. The special trap instruction simultaneously jumps into somewhere in kernel mode (identified by a *trap number*) and raises the privilege level to kernel mode. This also includes changing the stack pointer to the *kernel stack* reserved for this process, and saving the process's user registers into the kernel stack.

To let the hardware know where is the corresponding handler code for a given trap number, the OS registers the address of a *trap table*: trap no. \rightarrow trap handler addresses into a special hardware register.

This trapping mechanism provides protection since a user process cannot do arbitrary system-level actions, but rather must request a particular action via a number.

Trapping into kernel from software through a syscall is sometimes called a software interrupt.

We often use *trap* to name an active syscall made by the program. We use *exception* (or *fault*) to name a passive fall-through into kernel if the program misbehaves (e.g., tries to directly call a privileged instruction) or encounters an error (e.g., runs out-of-memory, OOM).

Hardware Interrupts

Another big issue is that the OS must be able to re-gain control in the middle of the user-level execution of a process, and achieve a switch between processes. We need help from a special hardware component - the *timer*.

A process can trap/fault into kernel, so does a hardware device. The behavior of a hardware device sending a signal to the processor to pause it current user code execution and to run a specified handler is called an **interrupt**. The handler is often called an *interrupt service routine* (ISR). Similar to traps, there is an *interrupt table* from interrupting device no. \rightarrow interrupt handler addresses (sometimes the software trap table is just embedded in the interrupt table).

One particularly important type of interrupt is the **timer interrupt**, issued by the timer every configured interval (e.g., 10ms). The ISR for timer interrupt is the place where the OS re-gains control on deciding which process to schedule for the next time slot.

Examples of other hardware interrupts include:

- Keystroke of a specific key from a keyboard device
- Mouse movement/click; other peripheral devices
- ..

Interrupts need to be *disabled* (meaning not obeying incoming interrupts) during the handling of a trap/interrupt, so that every interrupt is handled to its completion.

Also see <u>double fault</u> and <u>triple fault</u> for how the architecture reacts to faults happened inside trap handlers/ISRs.

Context Switch & Scheduler

We have defined the context of a process as the set of important registers values. Switching from process A to process B is a **context switch** procedure:

- 1. Save the current registers values (the context of A) into A's PCB
- 2. Restore the saved register values (the context) of B from B's PCB
- 3. Jump to where B was left off most likely B is in its kernel stack right after the switch, because the last time B was scheduled out, it must be in the scheduler routine

The timer interrupt ISR typically calls the **scheduler**: a routine that chooses which process to run for the next time slot, possibly using its knowledge of what were scheduled in the history, based on a scheduling policy. It then performs a context switch to switch to the target process. The entire picture looks like:

OS @ boot (kernel mode)	Hardware	
initialize trap table start interrupt timer	remember addresses of syscall handler timer handler start timer interrupt CPU in X ms	
OS @ run (kernel mode)	Hardware	Program (user mode)
Handle the trap Call switch() routine save regs(A) → proc_t(A) restore regs(B) ← proc_t(B) switch to k-stack(B) return-from-trap (into B)	timer interrupt save regs(A) \rightarrow k-stack(A) move to kernel mode jump to trap handler	Process A
	restore regs(B) ← k-stack(B) move to user mode jump to B's PC	Process B

Figure 6.3: Limited Direct Execution Protocol (Timer Interrupt)

Note the difference between *user registers* (those at user-level execution of the program) and *kernel registers* (those actually stored in the context). At a timer interrupt, the user registers are already stored into the process's kernel stack and the registers have been switched to the set for kernel execution (PC pointing to the handler code, SP pointing to kernel stack, etc.). Hence, the context saved for a process is actually the set of its kernel registers, and the user registers are recovered by the "return-from-trap" operation.

Context switch is not free and there is observable *overhead* (saving/restoring registers, making caches/TLBs/branch predictors cold, etc.). We should not ignore this overhead when developing scheduling policies.

Scheduling Policies

With the trap/interrupt mechanism and the context switch mechanism in hand, it is now time to develop scheduling policies for the scheduler to decide which process runs next. Determining the *workload* - here the processes running in the system and their characteristics - is critical to building policies. A policy can be more find-tuned if we know more about the workload.

Basic Policies

Let's first (unrealistically) assume that our workloads are:


- All jobs only use the CPU (so a single resource w/o blocking) and perform no I/O
- The run-time of each job is known

We look at these metrics to compare across policies:

- Turnaround time $T_{\rm turnaround} = T_{\rm completion} T_{\rm arrival}$ for each job, then averaged over jobs; if with the assumption of "jobs arrive at the same time", $T_{\rm arrival}$ will be 0 for everyone
- Response time $T_{\rm response} = T_{\rm firstrun} T_{\rm arrival}$ for each job; it measures how "promptive" an interactive job (say the shell) would be
- Fairness: we often need to *tradeoff* between turnaround time and fairness


Some basic, classic policies are:

• First-In-First-Out (FIFO, or First-Come-First-Serve, FCFS)




FIFO is intuitive but can often leads to the *convoy effect*: where a number of relatively short jobs get queued after a long job, yielding poor overall turnaround time. FIFO may work well in some cases such as caching, but not for CPU scheduling.

• Shortest-Job-First (SJF)




SJF is optimal on turnaround time if all jobs arrive at the same time, each job runs until completion, and their durations are known; however, in reality, this is rarely the case, and suppose A comes a little bit earlier than B & C in the above example, it encounters the same problem as in FIFO.

• Shortest-Time-to-Completion-First (STCF, or Preemptive-Shortest-Job-First, PSJF)




STCF is a *preemptive* policy - it can **preempt** a job in the middle if another one with shorter TtoC arrives. (Accordingly, FIFO and SJF schedulers are *non-preemptive*.) STCF is optimal given our current assumption and the turnaround time metric.

Round-Robin (RR)



Above-mentioned policies are not really taking advantage of the time-sharing mechanisms. RR divides time into small slots (*scheduling quantum*) and then switches to the next job in the run queue in a determined order. RR is a **time-slicing** scheduling policy. The time slice length should be chosen carefully: short enough to be responsive, and long enough to *amortize* the cost of context switches.

RR is quite fair and responsive, but one of the worst on turnaround time. With RR, we can also take I/O into consideration: when job A blocks itself on doing a disk I/O, the scheduler schedules B for the next slot, *overlapping* these two jobs.



Multi-Level Feedback Queue (MLFQ)

The biggest problem of the above basic policies is that they assume job durations are known beforehand (*priori* knowledge). However, this is hardly true in any real systems. Good scheduling policies tend to learn something from jobs' past behavior (*history*) and make decisions accordingly. One of the best-known approaches is **Multi-Level**Feedback Queue (MLFQ). It tries to trade-off between optimizing turnaround time and minimizing response time. In other words, it well mixes *interactive* or *I/O-intensive* jobs with long-running *CPU-intensive* jobs.

MLFQ has a number of distinct *queues*, each assigned a different **priority** level. A job is in a single queue at any given time.

- If priority(A) > priority(B), i.e., A is in a higher level than B, A runs;
- If priority(A) = priority(B), i.e., for jobs in the same level, they run in RR.




Figure 8.1: MLFQ Example

The key lies in how MLFQ dynamically sets priorities for jobs. MLFQ first assumes that a job might be short-running & interactive, hence giving it highest priority. Then, every time it runs till the end of a time slice without blocking itself on e.g. I/O, we reduce its priority level by 1, moving it to the queue one level down.

- When a job enters, it is placed at the highest priority (the topmost queue);
- If a job uses up an entire time slice without relinquishing the CPU, it moves down one queue;
- If a job gives up the CPU before the time slice is up, it stays in the same priority level queue.




Figure 8.4: A Mixed I/O-intensive and CPU-intensive Workload

There are still a few problems. There might be *starvation* if there are quite a few interactive jobs that a long-running job might have no chance to run. A program could *game* the scheduler by issuing an I/O at the very end of every time slice. The behavior of a job might also change over time. Hence, we add several rules:

- *Priority boost*: after some time period *S*, move all the jobs in the system to the topmost queue;
- *Gaming tolerance*: once a job uses up its time allotment at a given level (regardless of how many times it has given up the CPU), it moves down one queue.

Smarter MLFQ implementations tune these parameters instead of setting them as a default constant: adjusting #priority levels (#queues), lower levels have longer time slice quanta, using math formula (e.g., decaying) to calculate quanta and allotment, etc. OS implementations, such as FreeBSD, Solaris, and Windows NT, use some form of MLFQ as the base scheduler.

Lottery Scheduling

We also examine a different type of scheduler known as **fair-share** scheduler. Instead of minimizing turnaround time, it tries to guarantee that each job obtain a certain percentage of CPU time - a *proportional share*. **Lottery Scheduling** is a good example of such scheduler, see <u>the paper</u>.

Lottery scheduling assigns each job a number of *tickets*. At each scheduling decision point, it uses *randomness* to decide who wins the next slot. Say A has 75 tickets, B has 25, and C has 100, so the total amount of tickets is 200. The systems picks a random number between 0~199 and walks a running sum: if 75 > num, A wins, else if 75+25=100 > num > 75, B wins, otherwise C wins.

There are a few extra ticket mechanisms that might be useful:

- *Ticket currency*: a group/user can allocate tickets among their own child jobs in whatever scale they form a hierarchy of currencies and the eventual proportions are multiplied (Figure 3 of the paper)
- *Ticket transfer*: a process can temporarily transfer tickets to another process to boost its share, e.g., when a client sends a request to a server process and wants it to finish the request quickly
- *Ticket inflation*: in a *cooperative* (*trusted*) scenario, a process can simply inflate its number of tickets to reflect the need of more CPU share, without even communicating with any shared state in kernel

Stride scheduling avoids using randomness but instead divides the #tickets by a large number to get the stride value of each process. Whenever a process finishes a slot, increment its pass value by its stride. Pick the process with smallest pass value to run next. The strength of lottery scheduling (using randomness) is that it does not need any global state.

Completely Fair Scheduler (CFS)

Linux adopts a scalable, weighted-RR, fair-share scheduler named the **Completely Fair Scheduler** (CFS), see here. It tries to be efficient and scalable by spending very little time making scheduling decisions. CFS accounts *virtual runtime* (vruntime) for every job.

- Each job's vruntime increases at the same rate with physical time; always pick the process with the lowest vruntime;
- Parameter sched_latency (e.g., 48ms) decides the length of a whole round; CFS divides this value by the number of processes to determine the time slice length for each process;
- CFS never assigns time slice lengths shorter than parameter min_granularity, so it won't go wrong if there
 are too many processes;
- Each process has a *nice* value from -20 to +19, positive niceness implies lower priority (so smaller weight); there is a mapping from niceness to weight value (in a log-scale manner, just like the dB unit of loudness); CFS then weights time slices across *n* processes:

$$\begin{aligned} \texttt{time_slice}_k &= \frac{\texttt{weight}_k}{\sum_{i=1}^n \texttt{weight}_i} \cdot \texttt{sched_latency} \: \text{if} > \texttt{min_granularity} \: \text{else min_granularity} \\ & \texttt{vruntime}_k \; + = \; \frac{\texttt{weight}_{\text{default}} = 1024}{\texttt{weight}_k} \cdot \texttt{physical_runtime}_k \end{aligned}$$

CFS uses a *red-black tree* to keep track of all ready processes for efficiency. When a process goes to sleep, it is removed from the tree. CFS also has many advanced features including heuristics and scheduling across groups and multiple CPUs.

Virtualizing the Memory: Memory Management

TODO

Caching and memory hierarchy?

Concurrency: Multi-Tasking & Synchronization

TODO

Multi-CPU Scheduling

(Chapter 10)

TODO

Persistence: Storage Devices & File Systems

TODO

Advanced/Related Topics

TODO a list of notes, blogs, and books

Implementation (xv6, Phillip, Hux)

I've made a brief OS history tree in XMind which is <u>available here</u>.