ARM Assembly

```
01:
       mystery1
02: STMFD
               SP!, {R4-R8}
                               #function prologue Store multiple instruction decrement before
03: LDRB
               R3, [R0]
                               #Loads arg1 into register R3. arg1 is most likely a pointer.
               R3, #0x2D
04: CMP
                               #Compare R3's values to 45
               loc B348
                              #If R3 is equal to 45 go to loc_B348 on line 57.
05: BEQ
               R3, #0x2B
06: CMP
                               #Compare R3 to 43
07: MOV
               R6, #0
                               #Put 0 into R6
08: LDREQB
               R3, [R0,#1]!
                               #Load R0+1 into R3 and then update R0 to R0+1 if R3 equals 43
09:
       loc B2AC
10: CMP
                               #Compare R3 to 48
               R3, #0x30
                               #If R3 is not equal to 48 go to loc B2C8 on line 18
11: BNE
               loc B2C8
12: ADD
               R3, R0, #1
                               # R3 = R0 + 1
       loc_B2B8
13:
14: MOV
               R0, R3
                               #R0=R3
15: LDRB
               R2, [R3], #1
                               #R2=R3, R3=R3+1
16: CMP
               R2, #0x30
               loc B2B8
17: BEQ
                               #Loop back to line 13 while R2 == 48
18:
       loc B2C8
19: MOV
               R12, #0
                               \#R12 = 0
               R4, #0
20: MOV
                               \#R4 = 0
21: MOV
               R5, #0
                               \#R5 = 0
22: MOV
               R8, #0xA
                               \#R8 = 10
23: B
               loc_B2E4
                               #Branch to loc_B2E4 on line 27
24:
       loc B2DC
25: ADDS
               R4,R2,R7
                               # R4 = R2+R7
26: ADC
            R5, R3, R7, ASR#31 #R5 = R3 +(R7>>31) with carry
27:
       loc B2E4
28: LDRB
               R7, [R0, R12]
                               # R7 = R0+R12. R0 is bp and R12 is offset
29: ADD
               R12, R12, #1
                               #R12 = R12+1
30: UMULL
               R2, R3, R4, R8 # R4xR8. Least significant 32 bits R2 and most significant 32 bits R3.
31: SUBS
               R7, R7, #0x30
                              # R7 = R7 - 48
32: BMI
               loc B318
                               #branch to loc_B318 on line 43 if R7 is negative
               R7, #9
33: CMP
                               #Compare R7 to 9
34: MLA
               R3, R8, R5, R3
                               \#R3 = R8xR5 + R3
35: BGT
               loc B318
                               # branch to loc B318 on line 43 if R7 greater than 9
36: CMP
               R12, #0xB
                               #Compares R12 to 11
                               #Branch to loc_B2DC on line 24 if R12!=11
37: BNE
               loc_B2DC
38:
       loc B30C
39: MOV
                               \#R0 = 0
               RO, #0
40:
       loc B310
41: LDMFD
               SP!, {R4-R8}
                               #function epilogue put from stack back into R4 and R8. IA mode
42: BX
               LR
                               # return
43:
       loc B318
               R2, R4, R6
44: SUBS
                               # R2 = R4-R6
45: SBC
           R3, R5, R6, ASR#31 \# R3 = R5-(R6>>31) with carry
```

```
R2, #0x80000000 #Compare R2 with #0x80000000
46: CMP
47: SBCS
               R0, R3, #0
                              \#R0 = R3 - 0
               loc B30c
                              #Branch to loc B30C on line 38 if R2 greater than or equal 0x80000000
48: BGE
49: CMP
               R6,#0
                              #Compare R6 to 0
               loc B33C
                              #Branch to loc B33C on line 53 if 6 equals 0
50: BEQ
51: RSBS
               R4, R4, #0
                              \#R4 = 0-R4
                              \#R5 = 0-R5
52: RSC
               R5, R5, #0
53: loc_B33C
                              # Store the value into R4 into R1(our second argument a pointer)
54: STR
               R4, [R1]
55: MOV
               RO, #1
                              # R0 = 1
56: B
               loc_B310
                              #Branch to loc_B310 on line 40.
57:
       loc B348
58: LDRB
               R3, [R0,#1]!
                              #Load R0+1 into R3 and then update R0 to R0+1
59: MOV
               R6, #1
                              #Put 1 into R6
               loc B2Ac
60: B
                              #Branch to loc B2Ac on line 09.
       ; End of function mystery1
61:
```

Mode

This code is in ARM mode since all the instructions are 32 bits.

Types

```
R0 type char * when argument. When function returns R0 is a boolean
R1 type int *
R2 type int
R3 type char (one byte) then later is a variable that is a char *
int64 t sum; //R5:R4
R6 type Boolean
R7 type int signed
R8 type int
R12 type int
                                     Function Prototype
```

```
C Code
atoi(char *arg1, int * arg2)
{
        char ch = arg1[0];
        bool neg;
        if(ch== '-')//check if the number is negative
```

mystery1(char * arg1, int * arg2)

```
ch = arg1[1];
          arg1++;
          neg = true;
        else{ //if not negative
          neg = false;
          if(ch== '+'){ ch=arg1[1]; arg1++;} //if plus in front move over to next digit.
        if(ch=='0') //go through this until you reach a number that is not 0
          char * chp = arg1+1;
          int cur_dig;
          do{
           arg1 = chp;
           cur_dig = *chp;
           chp++;
          } while(cur_dig=='0')
        }
        int i =0;
        int num = 0;
        //R5 is here in case R4 overflows from multiplication for 10 digit numbers greater than 2<sup>31</sup>-1
        int ten = 10;
        LOOP:
        int digit = arg[i];
        i += 1;
        int64_t sum= num*ten;
        digit = digit - '0';
        if(digit>=0)
          //R3= ten*R3+R5 instruction there only incase of 10 digit numbers greater than 2^31-1
          if(digit <= 9)
         {
            if(i!=11)
            {
                num = sum+digit; //add the digit to the end of the number
                //the R5 = R3+(digit>>31) instruction is only there in case there is a ten digit value that is
not 32 bit.
                goto LOOP; //loop
           else{ //max number of digits a 32 bit value can have is 10. If there are 11 or more fail.
                goto fail;
```

{

```
}
          }
        }
          sum = num - neg; //this is here in case the value is -2,147,483,648
          if(sum >= \#0x80000000) // if R2 is greater than the highest signed 32 bit value fail. 2^{31}-1 is the
greatest signed 32 bit value.
            fail: bool ret = false;
            return ret;
          }
          if(!neg)
            num = -num;
            //R5 = -R5 is not really necessary ARM is doing this since we were working with 64 bits.
          arg2 = #
          bool ret = true;
          return ret;
}
```

Explanation

This function is atoi. It takes a string and accepts a pointer to an integer. The output is a Boolean where 0 is failing and 1 is passing. If there is a minus sign, the value is assumed negative. If it is blank or have a plus sign, that means the value will be positive. If there are any 0's before the number, those are omitted. Then while there is a digit between 0 and 9, multiply the current number by ten and then add the digit to the running total. If there is more than 10 digits (greater than 32 bits), return 0 since we cannot have a number with that many digits. Also, if the value is not between [-2³¹, 2³¹-1], return 0 as well. Afterwards return 1 and have the second parameter of the function point to the integer. If the value was negative, set the negative sign on the integer.