# Protocol: Quantifying species abundance using 16S Sanger Sequencing and CASEU

# Jack Reddan, Kapil Amarnath

# May 25, 2022

# Contents

1	Cul	lture Collection			
	1.1	Overview			
	1.2				
	1.3	Method			
2	gDNA Isolation				
	2.1	Overview			
	2.2	Materials			
	2.3	Method			
3	16S rDNA Amplification				
	3.1				
	3.2	Materials			
	3.3	Method			
4	16S rDNA Purification				
	4.1	Overview			
	4.2	Materials			
	4.3	Method			
5	Sanger Sequencing				
		Overview			
	5.2	Materials			
	5.3	Method			
6	Species Abundances with CASEU				
	-	Overview			
		Materials			
		Method			

A PCR			
	A.1 Master Mix Recipe	7	
	A.2 Thermocycler Program	7	
	Genewiz B.1 Sample Mix Recipe	<b>7</b>	
_	CASEU C.1 Installation	<b>7</b> 7	

### 1 Culture Collection

#### 1.1 Overview

This section describes collecting cultures for which you wish to quantify species abundances. In addition to any experimental mixtures, pure cultures of community members are needed for the analysis.

#### 1.2 Materials

- Pure and mixed liquid cultures
- 2-mL microcentrifuge tubes

#### 1.3 Method

- 1. In a 2-mL microcentrifuge tube, Collect 1 ODmL of liquid culture for all mixtures and pure cultures. Spin-down and remove supernatant.
- 2. Either store pellets at  $-20^{\circ}$ C, or continue to gDNA Isolation.

### 2 gDNA Isolation

#### 2.1 Overview

This section describes how to isolate gDNA to be used for 16S rDNA amplification. These steps are for the QIAGEN DNeasy Blood & Tissue Kit. If you happen use a different kit, please follow its instructions, and then proceed to 16S rDNA Amplification.

### 2.2 Materials

- QIAGEN DNeasy Blood & Tissue kit
- 100% ethanol
- Cell pellets from cultures collected in Culture Collection

#### 2.3 Method

Follow the subsequent instruction in parallel for all samples to be processed.

- 1. Resuspend pellet in 180  $\mu$ L of buffer ATL, and add 20  $\mu$ L of Proteinase K. Mix thoroughly by vortexing. Incubate at 56°C for 1 hour, and vortex every 15 minutes.
- 2. Vortex for 15s, then add 200  $\mu$ L of buffer AL and mix thoroughly by vortexing. Immediately add 200  $\mu$ L of 100% ethanol and, again, mix thoroughly by vortexing.

- 3. Pipet the mixture from step 2 into a DNeasy Mini spin column placed in a 2-mL collection tube. Centrifuge at  $\geq 6,000 \times g$  for 1 min. Afterwards, discard flow-through and collection tube.
- 4. Place DNeasy Mini spin column into a new 2-mL collection tube and add 500  $\mu$ L of buffer AW1. Centrifuge at  $\geq$  6,000 x g for 1 min. Afterwards, discard flow-through and collection tube.
- 5. Place DNeasy Mini spin column into a new 2-mL collection tube and add 500  $\mu$ L of buffer AW2. Centrifuge at 20,000 x g for 3 min. Afterwards, discard flow-through and collection tube.
- 6. Place DNeasy Mini spin column into a clean 1.5-mL microcentrifuge tube. Add 200  $\mu$ L of buffer AE and incubate at room tempurature for 1 min. Centrifuge at  $\geq$  6,000 x g for 1 min to elute.
- 7. Check gDNA concentration on the nano spectrophotometer. Then store at -20°C or continue to 16S rDNA Amplification.

## 3 16S rDNA Amplification

#### 3.1 Overview

This section describes how to amplify the 16S rDNA using Phusion polymerase for Sanger sequencing. If you are using a different polymerase, please follow its specific instructions and proceed to Sanger Sequencing.

#### 3.2 Materials

- Phusion polymerase
- 5X High Fidelity (HF) reaction buffer
- dNTPs
- 27F forward and 1492R reverse primers
- gDNA template from gDNA Isolation

#### 3.3 Method

Follow the subsequent instruction in parallel for all gDNA samples collected in gDNA Isolation.

1. Mix the  $ddH_2O$ , dNTPs, forward/reverse primers, 5X HF buffer, and polymerase according to Appendix A for N+1 reactions, where N is the number of gDNA samples to be processed.

- 2. Pipet 38  $\mu$ L of the PCR master mix into 200- $\mu$ L PCR tubes. Then add 2  $\mu$ L of template gDNA, at a concentration of 100 ng/ $\mu$ L, to the mix for each sample.
- 3. Place reactions into the thermocycler and run the PCR program specified in Appendix A.
- 4. Once the run is complete, check for synthesis of the desired product using gel electrophoresis. If the proper product was amplified, either store the reaction at  $-20^{\circ}$  C or proceed to 16S rDNA Purification

### 4 16S rDNA Purification

### 4.1 Overview

This section describes how to purify the 16S rDNA amplification using the QIAGEN QIAquick PCR Purification Kit. If you are using a different purification kit, please follow its instructions and continue to Sanger Sequencing.

#### 4.2 Materials

- 16S rDNA PCR amplicon samples
- QIAquick PCR Purification Kit

### 4.3 Method

Follow the subsequent instructions in parallel for all PCR amplicons synthesized in 16S rDNA Amplification.

- 1. Add 5 volumes of buffer PB to 1 volume of PCR sample and mix by pipet.
- 2. Place a QIAquick spin column in a provided 2-mL collection tube. Then apply the sample to the column and centrifuge at  $\geq$  17,900 x g for 60 s. Discard the flow-through.
- 3. Add 750  $\mu L$  of buffer PE to the column and centrifuge at  $\geq$  17,900 x g for 60 s. Discard the flow-through.
- 4. Centrifuge the column at  $\geq$  17,900 x g for 60 s, then transfer the column to a clean 1.5-mL microcentrifuge tube.
- 5. To elute, add 30  $\mu$ L of buffer EB to the center of the column. Let stand for 1 min 60 s, and then centrifuge at  $\geq$  17,900 x g for 60 s.
- 6. Check the concentration of the purified product on the nano spectrophotometer. Then either store at  $-20^{\circ}$ C or proceed to Sanger Sequencing.

## 5 Sanger Sequencing

#### 5.1 Overview

This section describes how to prepare the purified 16S rDNA samples obtained from 16S rDNA Purification for Sanger sequencing by Genewiz. If you are using a different sequencing platform or provider, please follow the relevant instructions, as they most certainly will differ from what is listed here, and continue to Species Abundances with CASEU

#### 5.2 Materials

- Purified PCR 16S rDNA amplicons
- 27F forward primer
- 8-tube PCR strip

#### 5.3 Method

Follow the subsequent instructions in parallel for all PCR amplicons purified in 16S rDNA Purification.

- 1. Dilute an aliquot of the 16S rDNA amplicon to a concentration of 3 ng/ $\mu$ L.
- 2. Add the amplicon dilution, 27F forward primer, and ddH<sub>2</sub>O to a PCR tube following the recipe in Appendix B.
- 3. Label tubes using the tube number with the prefix HL (e.g. HL1, HL2, ...HLN), noting what each tube contains.
- 4. Submit a Genewiz Sanger sequencing order online and print the order form. Place both the PCR tubes and order form in a clear, sealable plastic bag and deposit in the Genewiz drop-box.

- 6 Species Abundances with CASEU
- 6.1 Overview
- 6.2 Materials
- 6.3 Method
- A PCR
- A.1 Master Mix Recipe
- A.2 Thermocycler Program
- B Genewiz
- B.1 Sample Mix Recipe
- C CASEU
- C.1 Installation
- C.2 Example Script

References