Simple VLBI simulator documentation

Dr. Jack F. Radcliffe

1 Introduction

This simple simulator is designed to allow measurement sets to be created that can replicate VLBI arrays at low frequencies and can include custom arrays. It was borne out of initial simulations to look at the effect of primary beam attenuation on wide-field VLBI arrays but has been now developed as a tool to assist with the production of simple VLBI data sets and mosaics.

2 Installation instructions

2.1 Prerequisites

The majority of the work in getting this package installed is the various packages that are required for it to function. As a result, we recommend using singularity as the various packages require some shared environments which can clash with each other. These singularity images are available here.

If you decide not to use singularity, or want to build optimised images based on your computer architecture, then the packages you will need are the following:

- simms https://github.com/ratt-ru/simms. This package is used to generate custom empty measurement sets. YOu can also get this installed as part of the stimela package.
- CASA https://casa.nrao.edu. We recommend the modular version of CASA as you have more control over the packages that are installed with pip.
- python v3.10+ you will need the pandas, astropy, numpy, scipy and matplotlib packages which you can install using pip or conda (depending on how you installed python).
- wsclean with the Image Domain Gridder https://wsclean.readthedocs.io/en/latest/. This is required if you are needing to simulate the primary beam effects and other direction-dependent effects.

2.2 Installation

Installation should be fairly simple and requires just a git clone of this repository (which you may have already done!). Nothing else is needed!

3 Quick start guide

The simulator is pretty simple to use and just needs to have the two input files (simulator_inputs.txt and simulator_advanced_inputs.txt) edited to select the array of your choice. You can copy the input files to whatever directory you want as long as they are specified when you run the simulator. The various inputs in this file and descriptions are described in Section 3.1. The simulator comprises three different steps that are controlled by a bash script per step. To make these scripts, we can use the following syntax on the command line,

```
singularity exec <path_to_casa_image> python <path_to_git_repository>/
wf_vlbi_simulator.py <path_to_inputs>/simulator_inputs.txt <path_to_inputs>/
simulator_advanced_inputs.txt <step_number>
```

The step number corresponds to the part of the simulation you want to perform and the number corresponds to the following,

- 1. make ms generates a measurement set, inputs noise and optionally imports a model.
- 2. **single pointing** s image of a single pointing including primary beam attenuation. If a mosaic is not needed, sensitivity maps are made.
- 3. **mosaic** produces measurement sets corresponding to a mosaic defined in the input file. Makes images of each measurement set.
- 4. **make image** combines the mosaic pointing into a single mosaic and generates sensitivity maps.

3.1 Input files

The simulator takes two input files, the simulator_inputs.txt file, which you will need to edit, while the simulator_advanced_inputs.txt file is probably ok being left as default (unless you want to make exact, large data size measurement sets). The simulator_inputs.txt file comprises a range of parameters that you need to set and the following subsections will describe these.

3.1.1 Software and paths

• CASA_exec, wsclean_exec, stimela_exec, and rms_exec - the full executable commands on how to open CASA, wsclean, stimela/simms and the rms-finding software. These must be the full command i.e., if you are using singularity then the CASA command in the input file may look something like,

CASA_exec = singularity exec /idia/software/containers/casa-6.3.simg python

- output path set this to put all outputs into this folder
- repo path path to the github repository and must include the wf vlbi simulator part.
- prefix string to append to the start of all output file names. Will be set the 'sim' is left empty.

3.1.2 HPC options

The simulator is designed to be usable on both your local computer and any high-performance computing architecture which uses Slurm or PBS Pro as its job manager. For the following inputs, leaving a parameter blank means that the parameter will not be specified to the job manager (and may be set as the default value on the cluster).

- job_manager defines the job manager software (options are slurm or pbspro). If this is set to bash then the codes can be run on your local machine.
- partition selects the partition of the cluster to use.
- walltime maximum time requested on the cluster to run the job.
- nodes number of nodes requested.
- cpus number of CPUs per node required.
- mpiprocs number of tasks per node (normally good to set to the same as the number of CPUs).
- nodetype defines the type of node to use (not used in Slurm)

• max_jobs - for the steps that use multiple jobs (e.g., the mosaic step), this specifies the maximum number of jobs to be submitted at once. Setting this to -1 means that there is no maximum limit.

documentation in progress